cisco.

Workload Optimization Manager 3.8.0 Full Documentation

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS REFERENCED IN THIS DOCUMENTATION ARE SUBJECT TO CHANGE WITHOUT NOTICE. EXCEPT AS MAY OTHERWISE BE AGREED BY CISCO IN WRITING, ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS DOCUMENTATION ARE PRESENTED WITHOUT WARRANTY OF ANY KIND. EXPRESS OR IMPLIED.

The Cisco End User License Agreement and any product specific license terms govern your use of any Cisco software, including this product documentation, and are located at: http://www.cisco.com/go/eula. Cisco product warranty information is available at http://www.cisco.com/go/warranty. US Federal Communications Commission Notices are found here http://www.cisco.com/c/en/us/products/us-fcc-notice.html.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any products and features described in this document as in development or available at a future date remain in varying stages of development and will be offered on a when-and if-available basis. Any such product or feature roadmaps are subject to change at the sole discretion of Cisco, and Cisco will have no liability for delay in the delivery or failure to deliver any products or feature roadmap items that may be set forth in this document.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

The documentation set for this product strives to use bias-free language. For the purposes of this documentation set, bias-free is defined as language that does not imply discrimination based on age, disability, gender, racial identity, ethnic identity, sexual orientation, socioeconomic status, and intersectionality. Exceptions may be present in the documentation due to language that is hardcoded in the user interfaces of the product software, language used based on RFP documentation, or language that is used by a referenced third-party product.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com go trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)

© 2023 Cisco Systems, Inc. All rights reserved.



Contents

Documentation Overview	19
Release Notes	20
What's New	21
Feature Updates and Notices	25
Versioning Explanation	26
Configuration Requirements	27
Known Issues	29
REST API Notes	32
REST API Changes	32
API Deprecation History	33
API Deprecation Contract	35
Installation	38
Minimum Requirements	38
Installing on a Virtual Machine Image	39
OVA: Installing the vCenter Image for On-prem Environments	40
VHD: Installing the Microsoft Hyper-V Image	41
Deploying the Workload Optimization Manager Components	42
General Configuration Tasks	46
(Required) Synchronizing Time	46
(Important) Verifying your MariaDB Version	48
(Optional) Increasing Available Disk Space	51
(Optional) Enforcing Secure Access via LDAP	53
(Optional) Adding a Certificate for Securing the Workload Optimization Manager Ul	56
(Optional) Adding Additional CA Certificates for Probes	59
(Optional) Modifying the Certificates for Cluster Manager	61
(Optional) Enabling the Reporting Add-on	63
(Optional) Enabling the Data Exporter	63
(Optional) Changing the IP Address of the Platform Node	67
(Optional) Enabling and Disabling Probe Components	68
(Optional) Disabling Component Health Monitoring	71
(Optional) Overriding Default Ports	72
License Installation and First-time Login	73
Single Sign-On Authentication	73
Setting Up SAML Authentication	74
Setting Up OpenID Authentication	77
Disabling Single Sign-On	82
Updating Workload Optimization Manager to a New Version	83



Checking Before Updating	83
External DBs and Workload Optimization Manager Updates	84
Offline Update	87
Reference: What Are the Typical Settings for an IdP?	90
Reference: FIPS Cipher Suites	91
Reference: Step-wise Platform Deployment	92
Reference: Step-wise Offline Update	95
Reference: Working with YAML Files	97
Product Overview	100
How Workload Optimization Manager Works	100
The Desired State	101
The Market and Virtual Currency	101
Risk Index	102
The Workload Optimization Manager Supply Chain	103
Workload Optimization Manager Targets	104
Sustainability Features	105
Getting Started	108
Logging In to Workload Optimization Manager	108
The Home Page	109
APPLICATION View	109
ON-PREM View	110
CLOUD View	111
Configuring Targets	114
Configuring Targets - Enhanced View	118
Supply Chain of Entities	123
Working With a Scoped View	124
Scoping the Workload Optimization Manager Session	124
Overview Charts	
Details View	128
Scope Policies	130
List of Entities	132
Navigating With the Supply Chain	133
Viewing Cluster Headroom	134
Target Configuration	135
Adding and Removing Targets	137
Applications and Databases Targets	137
Apache Tomcat	138
Application Insights	141
Cisco AppDynamics	1/13



Datadog	14/
Dynatrace	150
IBM WebSphere	154
Instana	156
JBoss	
JVM Application	162
MySQL	165
New Relic	168
Oracle	172
Oracle WebLogic	175
SQL Server	177
Cloud Native Targets	180
Fabric Targets	185
Cisco UCS Manager	185
HPE OneView	188
Guest OS Processes Targets	191
WMI	191
SNMP	195
Hyperconverged Targets	199
Cisco HyperFlex	200
Nutanix	202
Hypervisor Targets	205
IBM PowerVM	206
Microsoft Hyper-V	210
vCenter Server	215
Orchestrator Targets	222
ActionScript Server	222
Flexera One	229
ServiceNow	233
Private Cloud	234
Virtual Machine Manager	234
Public Cloud	238
Amazon Web Services	238
AWS Billing	254
Google Cloud Platform	255
GCP Billing	266
Microsoft Azure	268
Azure Billing	288
Microsoft Enterprise Agreement	293
Storage Targets	297



EMC VMAX	298
EMC XtremIO	300
EMC ScaleIO	301
EMC VPLEX	303
HPE 3PAR	304
IBM FlashSystem	307
NetApp	311
Pure Storage	317
Virtual Desktop Infrastructure Targets	319
Horizon	319
Port Configuration	321
User Interface Reference	324
Entity Types - Applications	324
Business Application	
Business Transaction	
Service	
Application Component	332
Application Topology	
Entity Types - Container Platform	
Kubernetes Service	
Container	
Container Spec	
Workload Controller	351
Container Pod	
Namespace	364
Container Cluster	367
Virtual Machine (Kubernetes Node)	
Kubernetes CPU Metrics	
Entity Types - Cloud Infrastructure	
Virtual Machine (Cloud)	
App Component Spec	
Virtual Machine Spec	
Database Server (Cloud)	
Volume (Cloud)	
Database (Cloud)	
Zone	
Region	
Entity Types - On-prem Infrastructure	
Virtual Machine (On-prem)	
Database Server (On-prem)	468



Volume (On-prem)	470
Virtual Data Center (Private Cloud)	472
Business User	475
Desktop Pool	478
View Pod	480
Host	482
Chassis	488
Data Center	489
Storage	491
Logical Pool	498
Disk Array	500
Storage Controller	504
IO Module	506
Switch	506
Workload Optimization Manager Actions	508
Working With Action Center	509
Action Details	515
Actions by Entity Type	518
Action Categories	525
Action Types	526
Action Acceptance Modes	529
Plans: Looking to the Future	530
Plan Management	531
Setting Up Plan Scenarios	531
Plan Scenarios and Types	537
Configuring Nightly Plans	596
Park: Stop or Start Cloud Resources	597
Place: Reserve Workload Resources	603
Creating a Reservation	605
Managing Reservations	607
Dashboards: Focused Views	608
Built-in Dashboards	608
Creating and Editing Custom Dashboards	612
Creating and Editing Chart Widgets	614
Chart Types	616
Creating Groups	669
Working With Policies	672
Placement Policies	673
Automation Policies	677
Parking Policies	700



Working With Schedules	703
Managing Calendar Schedules	704
Managing Parking Schedules	707
Templates: Resource Allocations for New Entities	709
Creating Templates	709
VM Template Settings	710
Host Template Settings	711
HCI Host Template Settings	713
Storage Template Settings	715
Billing and Costs	716
Reserved Instance Settings	716
Price Adjustments	717
Currency Settings	722
Administrative Tasks	722
Managing User Accounts	723
Maintenance Options	731
License Configuration	732
Email Settings	733
API Reference	735
API Guide Revision History	735
API Guide Revision History	736
API Change History	736
Getting Started with the Workload Optimization Manager REST API	740
Workload Optimization Manager REST API Swagger Documentation	742
Workload Optimization Manager Markets	743
The Real-Time Market	743
Plan Markets	744
Running Plans	745
Workload Placement Policies	748
Calculating Reservations and Workload Placement	749
Workload Optimization Manager REST API Endpoints	753
Actions Endpoint	753
Admin Endpoint	771
Businessunits Endpoint	775
Clients Endpoint	787
Entities Endpoint	791
Groups Endpoint	819
Licenses Endpoint	854
Logs Requests	854
Markets Endpoint	855



Notifications Endpoint	876
Parking Endpoint	878
Policies Endpoint	881
Price Lists Utility Requests	883
Price Lists Requests	883
Reservations Endpoint	884
Reserved Instances Endpoint	892
Roles Requests	894
Scenarios Endpoint	895
Schedules Endpoint	941
Search Endpoint	955
Settings Endpoint	963
Settings Policies Endpoint	967
Statistics Endpoint	973
Supplychains Endpoint	993
Tags Endpoint	996
Targets Endpoint	1000
Templates Endpoint	1010
Topology Definitions Endpoint	1020
Workflows Endpoint	1024
Workload Optimization Manager Cookbook	1025
Authenticating With the API	1026
Plan Results Cookbook	1028
Creating a Static Group	1035
Creating a Dynamic Group	1041
Reference: Internal Workload Optimization Manager API Requests	1046
Reference: Scenario Peak-of-Peak Full Scenario Input DTO	1047
Reference: Tables	1066
Reference: DTO Index	1071
ActionApiDTO	1071
ActionApilnputDTO	
ActionDetailsApiDTO	1077
ActionExecutionApiDTO	1078
ActionExecutionAuditApiDTO	1078
ActionExecutionCharacteristicApiDTO	1079
ActionExecutionCharacteristicInputApiDTO	1079
ActionExecutionInputApiDto	
ActionResourceImpactStatApiInputDTO	1080
ActionResourceImpactStatInput	1081
ActionScheduleApiDTO	1082



ActionScopesApiInputDTO	1083
ActionScopesResourceImpactStatApiInputDTO	1084
ActiveDirectoryApiDTO	1084
ActiveDirectoryGroupApiDTO	1085
AddObjectApiDTO	1085
AggregateCommodityFieldApiDTO	1086
AggregatedHealthResponseDTO	1087
AutomatedEntityDefinitionData	1088
BaseApiDTO	1088
BaseCommodityApiDTO	1088
BaseGroupApiDTO	1089
BasicActionApiDTO	1090
BillingFamilyApiDTO	1090
BooleanConditionApiDTO	1091
BooleanFieldValueApiDTO	1091
BulkActionRequestApiDTO	1091
BulkActionRequestInputDTO	1092
BusinessUnitApiDTO	1092
BusinessUnitApilnputDTO	1094
BusinessUnitPriceAdjustmentApiDTO	1095
BusinessUnitRelatedApiDTO	1095
BusinessUserEntityAspectApiDTO	1096
BusinessUserSessionApiDTO	1096
ChangePasswordApiDTO	1096
ClientInputDTO.	1097
ClientNetworkSitesMetadataApiDTO	1097
ClientNetworkTokenApiDTO	1097
ClientNetworkTokenInputDTO	1098
ClientNetworkTokensMetadataApiDTO	1098
ClientServiceApiDTO	1099
CloudAspectApiDTO	1099
CloudCommitmentAspectApiDTO.	1101
CloudCommitmentCapacityApiDTO	1102
CloudCommitmentScopeDTO	1102
CloudFamilyReferenceApiDTO	1102
CloudProvisionActionDetailsApiDTO	1103
CloudResizeActionDetailsApiDTO	1103
CloudServicePriceAdjustmentApiDTO	1104
CloudServicePricingModelApiDTO	1105
CloudSuspendActionDetailsApiDTO	1106



CommodityFieldApiDTO	1106
ComputeTierAspectApiDTO	1107
ConditionApiDTO	1108
ConfigChangesApiDTO	1108
ConstraintApiDTO	1109
ConstraintApilnputDTO	1110
ContainerPlatformContextAspectApiDTO	1110
CostInputApiDTO	1111
CpuModelApiDTO	1111
CriteriaOptionApiDTO	1112
DBEntityAspectApiDTO	
DatabaseServerEntityAspectApiDTO	1114
DatabaseServerTierAspectApiDTO	1116
DatabaseTierAspectApiDTO	1116
DemandEntityInfoDTO	1117
DemandReservationApiDTO	1117
DemandReservationApilnputDTO.	1119
DemandReservationParametersDTO	1120
DeploymentParametersDTO	1120
DeploymentProfileApiDTO	1121
DeploymentProfileParamApiDTO	1121
DeploymentProfileProviderApiDTO	1122
DeploymentProfileTargetApiDTO	1122
DesktopPoolEntityAspectApiDTO	1122
DetailDataApiDTO	1123
DiscoveredEntityApiDTO	1124
EntityActionsApiDTO	1124
EntityAspect	1125
EntityCountRequestApiDTO	1125
EntityDetailsApiDTO	1125
EntityMetadataRequestApiDTO	1126
EntityPriceDTO	1126
EntityQueryApiDTO	1126
EntityStatsApiDTO	1127
EntityUptimeApiDTO	1128
EnumFieldValueApiDTO	1128
ExecutorInfoApiDTO	1128
ExecutorScheduleApiDTO	1129
ExecutorUserApiDTO	1129
FailedResourceApiDTO	1129



FieldApiDTO	1130
FieldValueApiDTO	1130
FieldValueTypeApiDTO	1131
FilterApiDTO	1131
GroupApiDTO	1132
GroupCountRequestApiDTO	1134
GroupMetadataRequestApiDTO	1135
GroupQueryApiDTO	1135
HealthCategoryResponseDTO	1135
HttpProxyDTO	1136
HttpServletResponse.	1137
IEntityDefinitionData	1137
IManualConnectionsData	1138
IncludedCouponsApiDTO	1138
InclusionConditionApiDTO	1138
InputFieldApiDTO	1138
InstanceTypeFilterApiDTO	1140
InstanceTypeIdsApiDTO	1140
IntegerConditionApiDTO	1141
IntegerFieldValueApiDTO	1141
LicenseApiDTO	1142
Link	1143
LoadChangesApiDTO	1143
Locale	1144
LogEntryApiDTO	1145
LoggingApiDTO	1147
Manual Dynamic Connections	1147
ManualEntityDefinitionData	1147
Manual Group Connections	1147
ManualStaticConnections	1148
MarketApiDTO	1148
MasterImageEntityAspectApiDTO	1149
MaxUtilizationApiDTO	1150
MemberFieldApiDTO	1150
MigrateObjectApiDTO	1151
MultiTextFieldValueApiDTO	1152
NameValueInputDTO	1152
NumberConditionApiDTO	1153
NumberFieldValueApiDTO	1153
OAuthDataApiDTO	1153



OnDemandCostFilterApiDTO	1154
OnPremResizeActionDetailsApiDTO	1154
OrderByApiDTO	.1155
PMDiskAspectApiDTO	1156
PMDiskGroupAspectApiDTO	1156
PMEntityAspectApiDTO	1156
PaginationApiDTO	1158
ParkableEntityApiDTO	.1159
ParkableEntityEnforcementPauseApiDTO	1161
ParkableEntityEnforcementPauseInputDTO	.1161
ParkableEntityGroupApiDTO	1161
ParkableEntityInputDTO	1162
ParkableEntityScheduleApiDTO	1162
ParkableEntityUUIDSetDTO.	.1163
ParkingEntitySchedulerApiDTO	1163
ParkingItemApiDTO	1164
ParkingPolicyApiDTO	1164
PatchedTargetDataApiDTO	1165
PatchedTargetFieldApiDTO	.1165
PeakBaselineApiDTO	1166
PlacementInfoDTO	.1166
PlacementOptionApiDTO	1166
PlacementOptionApiInputDTO	1167
PlacementParametersDTO	1168
PlanDestinationApiDTO	.1168
PolicyApiDTO	.1169
PolicyApiInputDTO	.1171
PortChannelApiDTO	.1172
PortsAspectApiDTO	.1173
PriceAdjustmentDTO	1173
PrimitiveFieldApiDTO	1173
PrintWriter	1174
ProbeApiDTO	1174
ProbePropertyApiDTO	1175
ProbePropertyNameValuePairApiDTO	1175
ProductCapabilityDTO	1175
ProductVersionDTO	1176
PurchaseProfileDTO	1178
QueryInputApiDTO	.1178
RIBuyActionDetailsApiDTO	1179



RIPurchaseProfilesSettingApiDTO	1179
RangeApiDTO	1180
RangeInputApiDTO	1180
RateCardApiDTO	1181
RateCardInfoApiDTO	1181
RateCardRelatedApiDTO	1182
RateCardValidationApiDTO	1182
Recommendation	1182
ReconfigureActionDetailsApiDTO	1183
RecurrenceApiDTO	1184
RegionAspectApiDTO	1184
RelatedActionApiDTO	1185
RelatedEntityFieldApiDTO	1185
RelatedGroupFieldApiDTO	1186
RelievePressureObjectApiDTO	1186
RemoveConstraintApiDTO	1187
RemoveObjectApiDTO	1187
ReplaceObjectApiDTO	1188
RequestHeader	1188
ReservationConstraintApiDTO.	1189
ReservationFailureInfoDTO.	1189
ReservationInvalidInfoApiDTO	1190
ReservedInstanceApiDTO	1190
ReservedInstancePurchaseSettingsDTO	1193
ResizeActionDetailsApiDTO.	1193
ResourceApiDTO	1194
ResourceGroupApiDTO	1194
RoleApiDTO.	1195
SAMLIdpApiDTO	1195
STEntityAspectApiDTO	1196
ScenarioApiDTO	1198
ScheduleApiDTO	1199
ScheduleEntityResponseApiDTO	1200
ScheduleItemApiDTO	1201
ScheduleTimeSpansApiDTO	1201
ScopeUuidsApilnputDTO	1202
SearchAllQueryApiDTO	1202
SearchCountRecordApiDTO	
SearchQueryRecordApiDTO	1203
SelectAllApiDTO	1203



SelectEntityApiDTO	1204
SelectGroupApiDTO	1205
ServiceEntityApiDTO	1205
ServletOutputStream	1207
SettingActivePolicyApiDTO	1208
SettingApiDTOSerializable	1208
SettingApiDTOString	1210
SettingApiDTO	1212
SettingOptionApiDTO	1214
SettingsManagerApiDTO	
SettingsPolicyApiDTO	1214
SkippedActionApiDTO	1215
StatApiDTO	1216
StatApilnputDTO	1217
StatCommoditySourceApiDTO	1218
StatFilterApiDTO	1218
StatHistUtilizationApiDTO	1219
StatPeriodApiInputDTO	1219
StatScopesApilnputDTO	1220
StatSnapshotApiDTO	1220
StatValueApiDTO	1221
StringSettingApiDTO	1221
SupplyChainStatsApilnputDTO	1222
SupplychainApiDTO	1223
SupplychainEntryDTO	1223
TagApiDTO	1224
TargetApiDTO	1224
TargetErrorDetailsApiDTO	1226
TargetHealthApiDTO	1227
TargetHealthSummaryApiDTO	1228
TargetOperationStageApiDTO	1228
TargetOperationStageStatusApiDTO	1229
TargetThirdPartyErrorDetailsApiDTO	1229
TelemetryDTO	1230
TemplateApiDTO	1230
TemplateApiInputDTO	1232
TemplatePriceAdjustmentDTO	1233
TextConditionApiDTO	1234
TextFieldValueApiDTO	1235
TimeBasedTopologyChangesApiDTO	1235



	TimeSpanApiDTO	1235
	TimeSpanGroupApiDTO	1236
	TopologyChangesApiDTO	1236
	TopologyDataDefinitionApiDTO	1237
	UnplacementDetailsApiDTO	1237
	UnplacementReasonApiDTO	1238
	UserApiDTO	1239
	UtilizationApiDTO	1240
	VMEntityAspectApiDTO	1240
	VirtualDiskApiDTO	1242
	VirtualDisksAspectApiDTO	1244
	VirtualVolumeEntityAspectApiDTO	1244
	WebhookApiDTO	1245
	WeekDayTimeSpansApiDTO	1246
	WhereApiDTO	1247
	WidgetApiDTO	1247
	WidgetElementApiDTO	1248
	WidgetsetApiDTO	1249
	WorkflowApiDTO	1250
	WorkflowAspect	1251
	WorkflowOperationRequestApiDTO	1251
	WorkflowOperationResponseApiDTO	1251
	WorkloadControllerAspectApiDTO	1252
Re	ference: Entity Statistics	1252
	ApplicationComponent Statistics	1252
	BusinessApplication Statistics	1253
	BusinessTransaction Statistics	1253
	BusinessUser Statistics	1253
	Chassis Statistics	1254
	ContainerPlatformCluster Statistics	1254
	ContainerPod Statistics	1254
	ContainerSpec Statistics	1255
	Container Statistics	1255
	DataCenter Statistics	1256
	DatabaseServer Statistics	1258
	Database Statistics	1258
	DesktopPool Statistics	1259
	DiskArray Statistics	1259
	IOModule Statistics	1259
	LogicalPool Statistics	1260



Namespace Statistics	1260
PhysicalMachine Statistics	1261
Service Statistics	1263
StorageController Statistics	1263
StorageTier Statistics	1263
Storage Statistics	1263
Switch Statistics	1264
ViewPod Statistics	1264
VirtualDataCenter Statistics	1265
VirtualMachine Statistics	1265
VirtualVolume Statistics	1266
WorkloadController Statistics	1267
Integration - Embedded Reporting	1268
Enabling Embedded Reporting	1268
Navigating to the Embedded Reports Page	1273
(Optional) Report Editing	1274
Embedded Reports Storage Requirement Estimates	1275
Custom Reports	1276
Importing Reports	1277
Creating Reports	1277
Exploring SQL Queries	1278
Schema Tables	1278
action_group Table	1278
cloud_service_cost Table	1278
completed_action Table	1279
entity Table	1280
entity_cost Table	1282
entity_savings Table	1282
entity_types_with_cost Table	1283
file Table	1283
historical_entity_attrs Table	1284
metric Table	1287
pending_action Table	1290
pending_action_stats Table	1291
run_health_checks Table	1291
scope Table	1292
scope_to Table	1294
scope_to_types Table	1294
topology_stats Table	1294
wasted_file Table	1294



JSON Data Objects	1295
ActionCommodity JSON	1295
ActionEntity JSON	1295
ActionImpactedCost JSON	1296
ActionImpactedCosts JSON	1296
ActionImpactedEntity JSON	1296
BuyRiInfo JSON	1297
CommodityChange JSON	1297
CommodityPercentileChange JSON	1298
DeleteInfo JSON	1298
entity.attrs JSON	1298
EntitySettings JSON	1300
group.attrs JSON	1300
ImpactedMetric JSON	1300
MoveChange JSON	1301
Target JSON	1301
action.attrs JSON	1301
Enums	1302
AttachmentState Enum	1302
OSType Enum	1302
action_category Enum	1302
action_mode Enum	1303
action_state Enum	1303
action_type Enum	1303
attr_type Enum	1304
cost_category Enum	1304
cost_source Enum	1304
entity_state Enum	1304
entity_type Enum	1304
environment_type Enum	1306
file_type Enum	1306
metric_type Enum	1307
savings_type Enum	1312
severity Enum	1312
terminal_state Enum	1312
Configuring an External TimescaleDB	1312
Creating an External TimescaleDB	1313
Manual Provisioning of Users and Databases	1313
Automatic Provisioning of Users and Databases	1317
Reference: Working with YAML Files	1318



Documentation Overview

Documentation for this product release includes the following general topics.

- Release Notes (on page 20) Describes new features, improvements, deprecated/removed features, fixes, and known issues
- Installation (on page 38) Helps you install Workload Optimization Manager in your on-prem environment
- Product Overview (on page 100) Provides an overview of the platform and its underlying architecture
- Getting Started (on page 108) Describes login steps, the Home Page, actions, and policies
- <u>Target Configuration (on page 135)</u> Provides a list of targets that the product can monitor, and describes how to configure each target properly
- <u>User Interface Reference (on page 324)</u> Provides a list entities discovered from targets, and describes how to configure plans, charts, and administrative settings
- <u>API Reference (on page 735)</u> Helps you use the REST API as you script interactions with the product
- <u>Integration Embedded Reporting (on page 1268)</u> Describes how to set up Embedded Reporting, an add-on that stores a history of your managed environment and presents this history via dashboards and reports



Release Notes

Release Date: September 8, 2023

These release notes describe the following for Workload Optimization Manager 3.8.0:

- New features
- Deprecated or removed features
- Improvements
- Fixes
- Known issues
- REST API changes

For any questions, contact your support representative.

Configuring Kubernetes Targets for Workload Optimization Manager

To set up a Kubernetes target for Workload Optimization Manager, you deploy the Kubeturbo pod with specific configuration resources. These resources require your version of Workload Optimization Manager, mapped to a TURBONOMIC_SERVER_VERSION. Use the following table to map your version of Workload Optimization Manager:

Workload Optimization Manager Version	TURBONOMIC_SERVER_VERSION number
3.8.0	8.10.0
3.7.7	8.9.7
3.7.6	8.9.6
3.7.5	8.9.5
3.7.4	8.9.4
3.7.3	8.9.3
3.7.2	8.9.2
3.7.1	8.9.1
3.7.0	8.9.0
3.6.6	8.8.6
3.6.5	8.8.5
3.6.4	8.8.4



Workload Optimization Manager Version	TURBONOMIC_SERVER_VERSION number
3.6.3	8.8.3
3.6.2	8.8.2
3.6.1	8.8.1
3.6.0	8.8.0
3.5.6	8.7.6
3.5.5	8.7.5
3.5.4	8.7.4
3.5.3	8.7.3
3.5.2	8.7.2
3.5.1	8.7.1
3.5.0	8.7.0

For information about Kubeturbo, see the Kubeturbo GitHub repository at https://github.com/turbonomic/kubeturbo. For more information about Kubernetes targets, see Target Configuration (on page 135).

What's New

Workload Optimization Manager is powered by our next-generation architecture, allowing the core platform to scale with large application and infrastructure environments in a single-instance deployment. This eliminates complexity and provides scale-on-demand capabilities, while continuing to assure application performance and health.

Version 3.8.0

NOTE:

Frequent changes to the product or third-party targets require that some features are updated, deprecated, removed, or no longer supported. For more information about these features, see <u>Feature Updates and Notices (on page 25)</u>.

Application Performance Management

Support for Datadog Targets

This release introduces support for the Datadog target. This integration provides insights into application performance while optimizing resource allocation, ensuring that applications receive the necessary resources while minimizing waste, resulting in improved operational efficiency and cost savings. Workload Optimization Manager discovers the Business Application, Business Transaction, Service, Application Component, and Virtual Machine and its related commodities for Tomcat and Standalone Java applications.

In addition, the Datadog target supports containers and related entities for Azure Kubernetes Service (AKS), Amazon Elastic Kubernetes Service (EKS), and Google Kubernetes Engine (GKE), including discovery and stitching when the kubeturbo target is added.

For details, see Datadog (on page 147).

Enable the Datadog probe before adding the target. To enable the probe, set the following in the charts vlalphal xl cr.yaml resource:

spec:
 datadog:
 enabled: true



■ Collection of Tags from APM Targets

Workload Optimization Manager can now collect tags from Datadog, Dynatrace, and New Relic targets. You can use these tags to search for, filter, or group entities discovered from these targets.

To collect tags, select **Collect Tag Information** in the target configuration pages for any of the supported targets. To view the collected tags, set the scope to a particular entity and then check the **Related Tag Information** chart.

For details, see Datadog (on page 147), Dynatrace (on page 150), and New Relic (on page 168).

Service Level Indicator (SLI) Data For Instana Entities

SLI data is now available in the Entity Information and Response Time charts for Instana Business Applications, Business Transactions, and Services.

■ Discovery of SQL Server Clusters

When you add SQL Server as a target, Workload Optimization Manager can now discover SQL Server clusters from the target, and represent the instances in those clusters as individual Database Server entities in the supply chain.

Workload Optimization Manager also creates a group for each cluster. When you set the scope to a group and click Database Server in the supply chain, the user interface displays a list of instances in the cluster, and indicates which instance is currently active and which ones are idle (redundant). Workload Optimization Manager only monitors resources for the active instance.

For details, see <u>SQL Server (on page 177)</u>.

Server Configuration Filter

For SQL Database Servers discovered from SQL or APM targets, the Server Configuration filter is now available when you search for servers or create server groups. This filter returns a list of standalone or clustered servers.

NOTE:

The filter supports two options: clustered and standalone. However, currently only SQL Server databases support both scenarios. For all non-SQL databases, including database servers like Oracle and MySQL, we recommend using the filter in the standalone mode by default. This means Workload Optimization Manager will recognize and treat the database as a standalone configuration.

Container Resource Management

■ Execution of SLO-driven Scale Actions

For Kubernetes environments, SLO-driven scale actions are now run via Workload Controllers. These actions adjust the number of replicas that are associated with horizontally scalable Kubernetes Services to comply with SLOs for your applications. A single scale action represents the replicas that are currently needed to meet SLOs.

For more information, see Workload Controller Scale Actions (on page 356).

On-prem Resource Management

■ Support for IBM® Power Systems

Initial feature support for managing IBM® Power Systems is now available. For IBM Power 8, 9, and 10 environments using Hardware Management Console (HMC) versions 9 or 10, Workload Optimization Manager will discover and continuously decide on the optimal logical partition (LPAR) processing unit allocation and virtual processor capacity based on historical demand collected from the HMC. IBM Power Systems and LPARs are represented as Hosts and Virtual Machines and are visible across all HMC targets in the Workload Optimization Manager UI. Recommended LPAR resize PU and VP actions will better inform IBM Power users on the optimal LPAR size. The recommended actions can leverage existing Workload Optimization Manager workflow capabilities for external approval and execution.

For details, see IBM PowerVM (on page 206).

Enable the PowerVM probe before adding the target. To enable the probe, set the following in the charts_vlalpha1_xl_cr.yaml resource:

```
spec:
  powervm:
   enabled: true
```



NOTE:

Features such as Virtual I/O Server (VIOS) LPAR optimization, move actions, planning, and full stack visibility are being considered for future releases.

Sustainability Features for On-prem Environments

Workload Optimization Manager now tracks the energy consumption and carbon footprint of on-prem hosts and VMs to help you put your sustainability goals into action.

This release introduces the following key features:

- Sustainability data is now available when you set the scope to hosts or VMs discovered via VMware vCenter targets, and then view the Energy and Carbon Footprint charts.
- To calculate carbon footprint, Workload Optimization Manager uses industry standards that take into account energy consumption, data center efficiency, and carbon intensity data. You can create Data Center policies to adjust the calculations according to the requirements of your data centers. After you adjust the calculations, Workload Optimization Manager can accurately report your organization's carbon footprint.
- If you have enabled the Embedded Reporting add-on, use the sustainability dashboards to gain insight into how you can reduce your energy consumption and carbon footprint.

For details, see Sustainability Features (on page 105).

Discovery of Hardware Compatible Versions for vCenter Environments

For vCenter environments, Workload Optimization Manager now discovers the hardware versions that are compatible with VMs to ensure that these VMs can start after they move to a new host through vMotion. This improvement also prevents VMs from moving to a host with an incompatible hardware version.

To view compatible hardware versions, set the scope to a vCenter VM or host and then check the 'Hardware Compatibility Version' field in the Entity Information chart.

■ Execution of vCenter Rightsize Actions Together

If a VMware vCenter entity has several pending rightsize actions, they execute together when they are automated, manually accepted simultaneously, or approved before entering an execution schedule window. Executing rightsize actions together prevents multiple restarts of a single VM when there are multiple pending actions, allowing for more changes within an execution window. This feature was enabled by default starting in version 3.6.6 and applies to all VMware vCenter rightsize actions.

Cloud Resource Management

Support for Azure Dedicated SQL Pools

Workload Optimization Manager now discovers <u>dedicated SQL pools</u> used in Azure Synapse Analytics, and represents them as Database entities in the supply chain. If there are no connections to a SQL pool for at least one hour, Workload Optimization Manager will recommend suspending the pool as a cost-saving measure.

For details, see Database (Cloud) (on page 431).

Workload Optimization Manager requires a new set of permissions to discover dedicated SQL pools and execute suspend actions. For details, see Azure Service Principal and Subscription Permissions (on page 275).

Parking Policies for Cloud Workloads

You can now create parking policies to enforce parking actions dynamically and at scale. For example, you can create a parking policy at the cloud provider level so that all existing and newly discovered parkable entities from a specific cloud provider are parked uniformly.

For details, see Parking Policies (on page 700).

Parking Actions for AWS RDS Instances

This release introduces 'parking' actions for AWS RDS instances to help you reduce your cloud expenses. With these actions, you can stop instances for a period of time and then start them when you need them. You can enforce parking actions on demand or according to a schedule.

NOTE:

AWS RDS instances are represented as Database Server entities in Workload Optimization Manager.

For details, see Park: Stop or Start Cloud Resources (on page 597).



Workload Optimization Manager requires the rds: StopDBInstance and rds: StartDBInstance permissions to stop and start instances. For the full list of permissions, see AWS Permissions (on page 242).

■ Usage Of AWS Billing Data for Discount Calculations

Workload Optimization Manager now uses billing data from AWS to calculate your discount coverage and utilization. With this improvement, the calculated values that display in the Discount Coverage and Discount Utilization charts should now closely match the coverage and utilization data reported by AWS.

Discounts include Reserved Instances (RIs) and Savings Plans for both non-government and GovCloud workloads.

NOTE:

After you update to this version, it could take up to 24 hours for charts to populate with discount data.

■ Enhancements to Cloud Savings and Investments

Workload Optimization Manager now uses cost snapshots and daily billing reports from your cloud providers to calculate top-down savings and investments associated with scale and delete actions. With this enhancement, savings and investments charts can now accurately report the impact of actions on your cloud expenses. In addition, the charts can now break down savings and investments by account, region, and other meaningful categories.

For details, see Cumulative Savings and Investments Charts (on page 653).

NOTE:

To view savings and investments before version 3.7.3, add the legacy savings and investments charts to your dashboards.

■ 'Buy Reservations' Actions Based on Azure MCA Pricing

Workload Optimization Manager can now recommend actions to buy Azure reservations based on MCA pricing, both for the real-time environment and for plans.

User Interface Management

New View of the Target Configuration Page

A new Target Configuration user experience is now enabled by default. This new view includes the following improvements:

- You can easily view targets in a tabular form with improved search, sort, and filtering capabilities.
- Targets with health issues are easily identified, alongside details such as who changed the target configuration and when it was changed.
- The Target Details page for some target integrations communicate the stages of validation and discovery, as well as any encountered error conditions to aid in troubleshooting your target configurations. Related targets are also shown where applicable.
- The target view no longer requires a manual refresh after adding or changing a target and is more dynamic than the previous view.

The option to use the older view is still available; however, this will be deprecated in a future release.

For details, see Configuring Targets - Enhanced View (on page 118).

Action Center Improvements

Action Center provides a comprehensive view of the actions that Workload Optimization Manager recommends to assure performance and improve infrastructure efficiency. To provide easy access to Action Center and the details for individual actions, we are introducing the following improvements:

- A new **Action** button is now available on the main menu of the user interface. This opens a dedicated Action Center page with a unique URL, which you can bookmark and share with interested parties.
- Action Center is now the default view for actions. Check out Action Center in entity views and plan results, and launch it conveniently from action-focused charts, such as the Pending Actions, Top Utilized, and Potential Savings charts.
 For a list of Action Center features, see Working with Action Center (on page 509).
- The Action Details page for a specific action now has a unique URL (or deep link), so you can easily share the page with interested parties. To get the URL, click the 'share' icon at the top-right section of the page and then copy the URL displayed in the address bar of the new tab. For details, see Action Details (on page 515).
- From Action Center, you can select up to 75 actions and then click **Print Action Details** to open a new printable view
 of the action details. This prints the action details for all of the selected actions at once.



Feature Updates and Notices

Frequent changes to the product or third-party targets require that some features are updated, deprecated, removed, or no longer supported. See the following sections for more information about these features.

Updates

The updates listed here will be made in the noted version. Consider the details and recommended actions that are provided.

Feature	Status	Details and Recommended Action
Legacy savings and investments charts	Added to version 3.7.5	When we released the enhanced savings and investments charts in version 3.7.3, we announced that legacy savings and investments data is not available in the enhanced charts, but can be extracted from the platform using a script.
		Starting in version 3.7.5, legacy data is available in the legacy savings and investments charts. The charts are titled 'Legacy' so you can distinguish them from the enhanced charts.
Sustainability features	Documentation updated in version 3.7.4	When we released the first set of <u>sustainability features (on page 105)</u> in version 3.7.2, the documentation incorrectly listed three targets that fully support these features – HPE OneView, Cisco UCS Manager, and VMware vCenter.
		Currently, only VMware vCenter fully supports these features. The documentation has been updated accordingly.
Azure permissions	Updated in version 3.7.1	Permissions were updated to more accurately reflect the minimum permissions for discovering workloads and executing actions. For example, permissions with wildcards (*) were replaced with the exact permissions.
		For details, see <u>Azure Service Principal and Subscription Permissions (on page 275)</u> .
Rate of Resize setting	Updated in version	The Rate of Resize default value has changed from 2 to 3.
in on-prem VM 3.7.1 policies	3.7.1	If you have changed your default setting to 1 or want to keep the current default setting of 2, create a new policy scoped to all on-prem VMs and configure the Rate of Resize to your desired setting.

Notices

Features are labeled based on the following definitions:

- Deprecated The feature is still supported but no longer developed or enhanced. The feature is not recommended for use and might become obsolete. Cisco might remove it in a subsequent release of the product.
- Removed The feature is no longer available in the product.
- Unsupported The feature is no longer supported in the product.

NOTE:

When a specific release or version of an integration partner technology reaches end-of-life (EOL) or its end of support date, Workload Optimization Manager no longer provides support for that version. Workload Optimization Manager follows integration partners' official EOL timeline for version support. Targeting a non-supported version, or one that is no longer supported by the vendor, is at your own risk.

The changes listed here will be made in the noted version. Consider the details and recommended actions that are provided.

Feature	Status	Details and Recommended Action
SAAS deploymentMode	Removed in version 3.7.7	Use the "HYBRID_SAAS" deploymentMode instead. For details, see ProductCapabilityDTO (on page 1175).



Feature	Status	Details and Recommended Action
"Use hypervisor VMEM for Resize" setting in on-prem VM policies	Removed in version 3.7.4	This setting is replaced by the Collect Virtual Machine Metrics option in the target configuration pages for APM targets.
MySQL 5.7	To be unsupported in a future release	MySQL version 5.7 will reach EOL on October 21, 2023 and will no longer be supported after that date. Workload Optimization Manager plans to support MySQL 8.0 in a future release as an optional alternative database server for MariaDB.
		MySQL version 5.6 reached EOL on February 5, 2021. Because it is no longer supported, references to MySQL 5.6 were removed from the documentation in version 3.7.0.
		For details, see <u>EOL MySQL</u> .
Billing Breakdown and Estimated Cost	Removed in version 3.7.1	The charts have been removed from the product and can no longer be added to dashboards.
Breakdown charts		If you have added these charts to your dashboards, delete them immediately and start using the replacement chart, Workload Cost Breakdown.
Microsoft Enterprise Agreement target	Deprecated in version 3.6.6	Deprecation impacts customers who previously added, or plan to add, a Microsoft Enterprise Agreement target to manage Azure non-government subscriptions.
		For details, see Microsoft Enterprise Agreement (on page 293).
VMware vCenter versions 6.0, 6.5, and 6.7	Unsupported since version 3.6.3	Update your VMware vCenter version to 7.0 or 8.0, which are fully supported.
Tbmigrate, the Classic-To-XL Migration Tool	Unsupported since version 3.3.0	If you need to migrate from a Classic installation to one of the 3.x version families, contact your support representative.

Versioning Explanation

Workload Optimization Manager versioning uses V-R-M elements (Version, Release, Modification) in the version number to express the status of a release.

Numbered Element	Example	Description
V - Version number	3 .X.X	 Changes to platform architecture or significant changes to data models
R - Release number	X. 1 .X	■ Major feature changes
M - Modification number is 0 (zero)	X.X. 0	 A quarterly release All Early Access (EA) features from previous bi-weekly releases are now GA No new Early Access (EA) features in this release
M - Modification number is greater than zero (1 or higher)	X.X.3	 A bi-weekly release Can include new Early Access (EA) features Includes fixed issues



Numbered Element	Example	Description
		NOTE: For API developers, the X.X.1 release can include final implementations of deprecated API features. These final implementations can make API changes that are not compatible with an earlier version.

Configuration Requirements

For this release of Workload Optimization Manager, you must satisfy the following configuration requirements.

Dynatrace Targets

Starting with Workload Optimization Manager version 3.4.2, the API token that you use when you configure a Dynatrace target must access specific scopes of the Dynatrace API V1 and V2.

If you are updating to Workload Optimization Manager version 3.4.2 or later, from a version that is earlier than 3.4.2, you must generate a new API token for the Dynatrace target configuration. Then, you must enter that token in the target configuration, and validate the target.

Workload Optimization Manager uses the API token to authenticate its calls to the Dynatrace API. This token must have permission to run GET methods using the Dynatrace API, both Version 1 and Version 2. Generate a new generic access token with these scopes:

Workload Optimization Manager Functions	Required Permissions	
Monitoring	■ API V1 scopes	
	 Access problem and event feed, metrics, and topology API V2 scopes 	
	Read entitiesRead metrics	

NOTE:

If the target still fails to validate after you update the access token, take note of your configuration settings, delete the target, and configure the target again. Be sure to use the new API token that you generated.

Workload Optimization Manager Updates and Operator Version

Workload Optimization Manager deploys as a cloud-native application on a Kubernetes cluster. This cluster can be preconfigured on a VM that you deploy, or you can deploy Workload Optimization Manager to a Kubernetes cluster in your environment. In either case, Workload Optimization Manager uses an Operator to manage the application deployment.

For different versions of Workload Optimization Manager, the version of Operator you use changes as follows:

Product Version	Operator Version
3.8.0	42.39
3.7.7	42.38
3.7.6	42.37
3.7.5	42.36
3.7.4	42.35
3.7.3	42.34



Product Version	Operator Version
3.7.2	42.33
3.7.1	42.32
3.7.0	42.31
3.6.6	42.30
3.6.5	42.29
3.6.4	42.28
3.6.3	42.27
3.6.2	42.25
3.6.1	42.24
3.5.6 - 3.6.0	42.23
3.5.5	42.22
3.5.4	42.21
3.5.3	42.20
3.5.2	42.19
3.5.1	42.18
3.4.6 - 3.5.0	42.17
3.4.4 - 3.4.5	42.16
3.4.3	42.15
3.4.2	42.14
3.4.1	42.13
3.4.0	42.12

When you update Workload Optimization Manager, always include the matching version of Operator in the update. Online or offline updates that were completed according to the <u>latest installation instructions (on page 83)</u> automatically include the latest Operator.

If you installed Workload Optimization Manager on a Kubernetes cluster, you might need to manually update the Operator version.

After you update the Operator version, and you verify that the pod is running and ready, edit your Custom Resource declaration to update Workload Optimization Manager to the version that matches your Operator version.

For more information, contact your support representative.

Supported MariaDB Version for OVA and VHD Installations

For its default historical database on Open Virtual Appliance (OVA) and Virtual Hard Disk (VHD) installations, Workload Optimization Manager currently supports MariaDB version 10.5.20. This support includes comprehensive testing and quality control for Workload Optimization Manager usage of the historical database.

IMPORTANT:

Because of a known issue, you must never use MariaDB versions 10.5.14, 10.5.15, 10.6.7, 10.7.3, or 10.8.2.

If you are running Workload Optimization Manager installed as an OVA or VHD image, and are using the database that is included in that installation, then you must use version 10.5.20. For versions of Workload Optimization Manager that you installed as an OVA or VHD before version 3.5.6, you must now update to MariaDB version 10.5.20if not already done.



For more information, see Verifying Your MariaDB Version (on page 48).

SQL Server Modes for External Databases

If you deploy Workload Optimization Manager to work with an external database instead of the included historical database, then you must specify the correct SQL Server modes for the database. Configure the database as {{ERROR_FOR_DIVISION_BY_ZERO,NO_AUTO_CREATE_USER,NO_ENGINE_SUBSTITUTION}}.

In particular, the SQL Server modes should not include ONLY FULL GROUP BY, NO ZERO IN DATE, or NO ZERO DATE.

Transport Layer Security Requirements

By default, Workload Optimization Manager requires Transport Layer Security (TLS) version 1.2 to establish secure communications with targets. Most targets have TLS 1.2 enabled; however, some targets do not enable TLS or they enabled an earlier version. In that case, you see handshake errors when Workload Optimization Manager tries to connect with the target service. When you go to the Target Configuration view, you see a Validation Failed status for such targets.

NetApp filers often do not enable TLS and the supported version is TLS 1.0, which causes the NetApp target to fail validation.

If target validation fails because of TLS support, you see validation errors with the following strings:

- No appropriate protocol
 - Ensure that you enable the latest version of TLS that your target technology supports. If you still encounter issues, contact Cisco Technical Support.
- Certificates do not conform to algorithm constraints

Refer to the documentation for your target technology (such as the NetApp documentation) for instructions to generate a certification key with a length of 1024 or greater on your target server. If you still encounter issues, contact Cisco Technical Support.

Known Issues

■ Known Issue:

"Upgrade issues from Workload Optimization Manager version 3.3.2 or earlier to version 3.7.2 or later"

If you upgrade from Workload Optimization Manager version 3.3.2 or earlier to version 3.7.2 or later, you might see issues such as the Workload Optimization Manager UI forcing you to reset the administrator password and seeing no targets on the Targets page.

These issues occur because the data stored in the consul is lost during the upgrade. To avoid this issue, first upgrade Workload Optimization Manager to a version before 3.7.2, then upgrade again to your preferred version.

For example, if you are running 3.2.1 and want to upgrade to 3.7.5, you can upgrade to 3.7.1 first, then upgrade to 3.7.5.

Known Issue:

"When updating to Workload Optimization Manager version 3.7.3 or later from OVAs that run older versions of Kubernetes, you might encounter an error."

When updating to Workload Optimization Manager version 3.7.3 or later from OVAs that run older versions of Kubernetes, you might encounter the following error: /opt/local/bin/t8c-license-service.sh >>>> ERROR - Pre requirement check: FAILED. The License Service cannot be installed since it is not supported in older versions of Kubernetes. The upgrade of other Workload Optimization Manager components and the normal use of Workload Optimization Manager are not affected.

This error affects Kubernetes versions earlier than 1.19. To check your Kubernetes version, run the following command: kubectl version.

If you encounter this error and need assistance, contact your support representative.

Known Issue:

"The Top VM and Top Host widgets on the PowerVM dashboard may display incorrectly."



The Top VM and Top Host widgets on the PowerVM dashboard might encounter an issue related to temporary groups, which are ad-hoc groups created in the following scenarios:

- When you click on any of the nodes or entity donuts in the supply chain
- When you select entities in the search and scope the selection

To work around this issue, you can do one of the following:

- Edit the Top VM or Top Host widget to add the power commodities.
- Reopen the PowerVM group.
- Edit the URL to remove the ?entityType= query string parameter.

Known Issue:

"For vCenter Server environments, Workload Optimization Manager does not recognize DRS rules for VM restart dependencies that are based on VM-VM Dependency rules."

For vCenter Server environments, Workload Optimization Manager does not recognize DRS rules for VM restart dependencies that are based on VM-VM Dependency rules.

You may be able to achieve a similar effect by expressing dependencies via the VM-Host rule, or cluster affinity or anti-affinity rules.

Known Issue:

"For AppDynamics environments, the platform cannot discover Database Servers if the target authentication uses oAuth for credentials."

For AppDynamics environments, Workload Optimization Manager cannot discover Database Servers if the target authentication uses <code>oAuth</code> for credentials.

Known Issue:

"Changes to a policy do not immediately show up in the user interface view of the affected scope."

When you set the scope of the Workload Optimization Manager view to a group, you can then view the automation policies that impact the given group. If you edit a policy for that group (in Settings: Policies), and then scope the view to that group again, the policy changes do not appear in the display for that group.

The display should update within ten minutes, after the next round of incremental discovery. If the condition persists, log out of your session and log in again to update the display.

Known Issue:

"Optimized Improvements for plans do not include hosts to provision."

For cases where actions indicate provisioning new hosts, the Optimized Improvements chart does not include the hosts to provision in the After Plan section.

Known Issue:

"The Optimal Improvements chart can show incorrect data for hosts to be suspended."

In cases where actions recommend that you suspend hosts, the Optimal Improvements chart should indicate no utilization on the hosts to be suspended. Under some circumstances, the chart can show utilization on these hosts. The result is incorrectly low values for utilization on the other hosts in the current scope.

■ Known Issue:

"For Workload Optimization Manager deployments where the database uses a custom (non-3306) port for MariaDB or MySQL, the Parking feature cannot start."

For Workload Optimization Manager deployments where the database uses a custom (non-3306) port for MariaDB or MySQL, the Parking feature cannot start. In these cases, suspend should be disabled from the charts_vlalphal_xl_cr.yaml resource as follows:

spec:



suspend:

enabled: false

Known Issue:

"ThoughtSpot Liveboard queries that take more than 10 minutes to complete result in a query timeout message."

ThoughtSpot Liveboard queries that take more than 10 minutes to complete result in a query timeout message.

Known Issue:

"New Relic has ended support for monitoring integration with Microsoft SQL Server 2012."

Workload Optimization Manager no longer supports monitoring and stitching of Microsoft SQL 2012 discovered through New Relic. We recommend that you upgrade your Microsoft SQL instance to a version New Relic supports.

■ Known Issue:

"For Azure, billing information for RIs can show costs as NA."

In Azure environments, if you configure a Microsoft Enterprise Agreement target, costs for RIs can show in the user interface as NA. For example, a VM that shows 100% RI coverage can show the Reserved Compute Cost as NA. This occurs because of a known gap in the data provided by the Microsoft EA API that the target probe uses to collect data.

Known Issue:

"Cloud VMs might scale to very large instance types even if there are smaller instance types available for scaling."

When a cloud VM with a specific disk count and disk type applies a policy that enables 'instance store aware scaling', Workload Optimization Manager might recommend scaling the VM to a very large instance type, even if there are smaller, less expensive instance types that can adequately meet the VM's resource requirements.

To avoid this issue, disable instance store aware scaling and restrict the VM to its current instance family. For example, if an AWS VM is currently running the i3.2xlarge instance type, specify the i3 instance family as a scaling constraint for the VM.

■ Known Issue:

"For New Relic MySQL, DB Cache Hit Rate values are incorrect."

For New Relic MySQL 8, DB Cache Hit Rate values are incorrect in Workload Optimization Manager. Because the percentage of queries that are retrieved from the cache (db.qCacheHitRatio) is not supported in New Relic MySQL version 8.0 and higher, the DB Cache Hit Rate values are no longer displayed in Workload Optimization Manager.

For more information, see the New Relic documentation.

Known Issue:

"The user interface shows incomplete Azure billed costs and metrics because of an issue with the Azure API."

When attempting to discover Azure billing targets configured with partitioned cost exports on the first day of any month, Workload Optimization Manager is unable to find the directory containing the export files within a customer's Azure Storage account. The export files exist, but the Azure API does not return the correct storage location of that day's cost export files. As a result, the Workload Optimization Manager user interface may not reflect any billed cost that Azure exported on the first of the month, and the metrics dependent on that billed cost. The billed cost, including costs for the first day of the month, will start appearing on the second day of the month. Note that the billed cost is not limited to expenses incurred on the first day of the month.

Known Issue:

"In a Nutanix environment, a Replace Hosts plan can fail to place VMs."



You can configure a Replace Hosts plan on a Nutanix cluster to replace the hosts with HCl templates. However, the plan will fail to create the HCl hosts, and will result in unplaced VMs.

Known Issue:

"Hardware Refresh to replace hosts with HCI templates can fail to place workloads."

When running a Hardware Replace plan, the plan can fail to place workloads onto HCl hosts. The plan correctly places workloads if the plan scope is in a hyperconverged environment. If the scope is *not* in a hyperconverged environment, then you must scope the plan to an entire cluster, and you must configure the plan to replace all the hosts in the cluster with HCl templates.

■ Known Issue:

"For Kubernetes, in some environments analysis cannot execute Scale Node actions."

For Kubernetes OCP 4.x and AKS environments, Workload Optimization Manager can generate and execute Scale Node actions. However, if the environment includes other Kubernetes distributions that don't support execution of Scale Node actions (EKS, AKS, and OCP), then Workload Optimization Manager can disable execution of *all* Scale Node actions in the environment.

Known Issue:

"For Kubernetes environments with nodes running Linux with cgroup v2 enabled, you must use Kubernetes version 1.23.2 or later."

For Kubernetes environments with nodes running Linux with cgroup v2 enabled, an issue in earlier versions of Kubernetes prevents Workload Optimization Manager from collecting CPU utilization data for the affected nodes. To collect CPU utilization from the cgroup v2 nodes, you must run Kubernetes version 1.23.2 or later.

Known Issue:

"With Executed Actions charts, some data is missing for actions on entities that have been removed from the environment."

When you view Executed Actions charts or export data from them, some data is missing for actions on entities that have been removed from the environment. For example, assume an action was executed on a storage volume, and that volume has later been removed from the environment. In that case, the exported data for that action will not include values that describe the removed volume.

REST API Notes

This section describes issues that result in changes to the REST API. It is a running list of changes that accumulates until the next release of the API Guide. When we release a new version of the guide, it will include these changes. At that time, this list will start with new changes to the API.

Because the API is a full reflection of the Workload Optimization Manager product, some changes to the product necessarily cause changes in the API. This can include bug fixes and improvements to the product. For example, we might add new commodities that you can get for a given entity type, or a bug fix might change the data that is returned by an API request. We strive to make these changes backward-compatible whenever possible.

In some instances, we must make changes that are not backward-compatible. In this case, we deprecate the change for a period of time that should be sufficient for you to understand the change and implement an alternative in your scripts.

REST API Changes

For this release (version 3.8.0), there are no new API changes to report. API changes from the previous version family are incorporated in the new API Guide.



API Deprecation History

The following endpoints, requests, DTOs, and/or parameters have been deprecated in the Workload Optimization Manager API. The changes were finalized and removed from the API in the listed release.

NOTE

See the instructions for alternative usage for deprecated items.

3.7.1

Endpoints	None
Requests	None
Request Parameters	None
DTOs	■ DTO: ScenarioChangeApiDTO Instruction: Use the loadChanges or configChanges parameters in the ScenarioApiDTO.
DTO Parameters	■ DTO: ScenarioApiDTO Parameter Name: changes Instruction: Use the loadChanges or configChanges parameters.

3.6.1

Endpoints	None
Requests	■ GET /search/market/ Instruction: Use GET /markets. ■ GET /search/target/ Instruction: Use GET /targets. ■ GET /groups/ <groupid>/actions/<actionid> Instruction: Do not use this call (not implemented). ■ GET, POST /target/<targetid>/stats Instruction: Do not use this call (not implemented). ■ GET /businessunits/<busunitid>/stats Instruction: Use GET /entities/<entityid>/stats or GET /stats/ <entityid>/stats. These calls use the business unit entity ID. ■ POST /businessunits/<busunitid>/stats</busunitid></entityid></entityid></busunitid></targetid></actionid></groupid>
	<pre>Instruction: Use POST /stats/<entityid>/stats or POST /stats.</entityid></pre>
Request Parameters	None
DTOs	None
DTO Parameters	None
ENUM Values	 entityType:VMSpec Instruction: Use VirtualMachineSpec. entityTypes:VMSpec Instruction: Use VirtualMachineSpec. entityTypeFilter:VMSpec Instruction: Use VirtualMachineSpec.



	<pre>providerEntityType:VMSpec</pre>
	Instruction: Use VirtualMachineSpec.
	<pre>relatedEntityType:VMSpec</pre>
	Instruction: Use VirtualMachineSpec.
	■ providerType:VMSpec
	Instruction: Use VirtualMachineSpec.

3.5.1

Endpoints	None
Requests	■ DELETE /entities/ <entityid>/tags/<tagkey></tagkey></entityid>
	<pre>Instruction: Use DELETE /entities/<entityid>/tags?key=<tagkey>.</tagkey></entityid></pre> <pre> DELETE /groups/<groupid>/tags/<tagkey></tagkey></groupid></pre>
	<pre>Instruction: Use DELETE /groups/<groupid>/tags?key=<tagkey>.</tagkey></groupid></pre>
Request Parameters	None
DTOs	■ LicenseApiInputDTO
	Instruction: Use LicenseApiDTO.
DTO Parameters	■ DTO: HttpProxyDTO
	Parameter Name: portNumber
	Instruction: Use proxyPortNumber.
	■ DTO: LogEntryApiDTO
	Parameter Name: reasonCommodity
	Instruction: Use the array, reasonCommodities.

3.4.1

Behavior Changes:

■ Pagination of Returned Data from /search requests:

For searches, the API paginates the returned data. Starting with version 3.4.1, the default pagination limit is 100 entries, and the maximum pagination limit is 500. If you do not specify a pagination limit, then the API returns pages set to the default limit of 100. If you make no settings, and your search results include more than 100 entries, the results will be paginated. Your scripts should always check for a pagination cursor when processing search results.

You can change these settings in the $charts_vlalphal_xl_cr.yaml$ resource. Find the entries for:

- apiPaginationDefaultLimit
- apiPaginationMaxLimit

Endpoints	None
Requests	None



ented in
ontod in
ented in

API Deprecation Contract

The following endpoints, requests, DTOs, and parameters are deprecated in the Workload Optimization Manager API. The changes will be finalized and removed from the API in the listed release.

NOTE:

See the instructions for alternative usage for deprecated items.



3.8.1

Endpoints	None
Requests	None
Request Parameters	None
DTOs	None
DTO Parameters	■ DTO: StatApiInputDTO
	Parameter Name: costPrice
	<pre>Instruction: Use the dedicated cost endpoints in /entities, /groups, and / markets instead.</pre>
	NOTE: These are marked "In Development" currently but will reach GA soon.
	<pre>- /entities/{entity_Uuid}/cost - /groups/{group_Uuid}/cost - /markets/{market_Uuid}/cost</pre>

3.9.1

Endpoints	■ GET /tags/{tagKey}/entities
	Instruction: Use GET /tags/entities. This endpoint better supports searches for certain special characters, such as a slash (/), within tag names.
Requests	None
Request Parameters	None
DTOs	None
DTO Parameters	None

3.10.1

Endpoints	None
Requests	None
Request Parameters	 Request: GET /search Parameter Name: entity_types Instruction: This parameter was previously deprecated and is scheduled for removal in 8.12.1. The mandatory types or group_type parameters are the preferred parameters to specify an object or group type in a search request.
DTOs	BusinessUnitRelatedApiDTO Instruction: This DTO was used with the /pricelists endpoints from Workload Optimization Manager Classic, which was never implemented in Workload Optimization Manager 8.x and was deleted in version 8.9.3. This DTO was never implemented or used in Workload Optimization Manager, but it is referenced in the BusinessUnitApiDTO DTO. Because the DTO was never implemented, no alternative is required.
DTO Parameters	■ DTO: ActionApiDTO



Parameter: actionState

Enums: RECOMMENDED and PENDING_ACCEPT are removed as possible values for the actionState parameter. The parameter is otherwise unchanged.

Instruction: Both these action states are replaced by the READY action state.



Installation

This guide gives you information you need to install Workload Optimization Manager in your virtual environment, install your license, and get started managing your resources.

If you have any questions, contact Cisco support.

Minimum Requirements

License Requirements

To run Workload Optimization Manager on your environment, you must install the appropriate license. Licenses enable different sets of Workload Optimization Manager features, and they support a specified number of workloads in your environment.

User Interface Requirements

To display the Workload Optimization Manager user interface, you must log into the platform with a browser that can display HTML5 pages. Workload Optimization Manager currently supports the following browsers:

- Apple Safari
- Google Chrome
- Microsoft Edge
- Mozilla Firefox

Network Addressing Requirements

Workload Optimization Manager requires static IP addressing. Static IP setup is covered as a step when installing the Workload Optimization Manager VM image.

Compute and Storage Requirements

The requirements for running a Workload Optimization Manager instance depend on the size of the environment you are managing. Workload Optimization Manager keeps a real-time representation of your environment in memory. The greater the number of entities to manage, and the more extensive the relationships between them, the more resources you need for the VM that runs Workload Optimization Manager. And as the VM requirements increase, so do the requirements for the physical machine that hosts the VM.

The requirements listed here are recommendations that you should keep in mind as you plan your Workload Optimization Manager deployment. After deploying, if you find that you need to change memory capacity, CPU capacity, or both for the VM, you can shut it down, make changes, and then power it up again to use the new capacity.



The machine that hosts the Workload Optimization Manager platform must support the SSE4.2 instruction set. Support for this instruction set was introduced at different times for different chip manufacturers:

- Intel: November 2008
- AMD: October 2011

The machine you use to host Workload Optimization Manager should be newer than these dates. On a Linux system, you can run the following command to check for this support:

cat /proc/cpuinfo | grep sse4

For more information, see the glossary entry at http://www.cpu-world.com/Glossary/S/SSE4.html.

In most cases you can run Workload Optimization Manager on a host that meets the following minimum requirements:

Supported VM Image Technology		Storage Requirements	Memory	CPUs
VMware	vCenter versions 7.0 and 8.0	1.25 TB or greater	■ Default: 128 GB	8 vCPUs
Microsoft	Hyper-V Server 2012 R2 or later	NOTE: Can be thin provisioned depending on the storage requirements.	■ For 10,000 VMs or less, 64 GB	

Cisco provides a VM image (an OVA or VHD file) which is preconfigured with two hard drives. A minimum of 1.25 TB is necessary to ensure that the drives have the proper amount of space for storage.

Installing on a Virtual Machine Image

You can get a download of the Workload Optimization Manager platform as a:

- VMware Open Virtual Appliance (OVA) 1.0 image
- Microsoft Hyper-V image

NOTE

For minimum requirements, we recommend 128 GB of memory for the VM that hosts Workload Optimization Manager. However, if you plan to manage a smaller environment (10,000 VMs or less), you can install on a VM that provides 64 GB of memory. (See Minimum Requirements (on page 38)).

If you plan to install a VM with 64 GB of memory, then you must modify the default for VM memory. (See <u>Deploy the Workload Optimization Manager VM (on page 40)</u>).

You will install the platform in two main steps:

- Install the Workload Optimization Manager VM image on your network.
 This installs and starts up the VM that will host your instance of the Workload Optimization Manager platform.
- 2. Deploy the Workload Optimization Manager components on the VM.

About the Workload Optimization Manager VM Image

Workload Optimization Manager installs as a VM that runs the CentOS Linux OS. For each new version, we deliver a VM image (Open Virtual Appliance (OVA) or Virtual Hard Disk (VHD)) that you install to run the product. Typically you install this image once, and for subsequent updates to Workload Optimization Manager you will execute product updates on that installed VM. This means two things:

- Product updates patch new components of the Workload Optimization Manager application stack onto the same CentOS
 platform that you got when you originally installed the VM image. Product updates do not affect the underlying OS.
- Over time, you might learn of important security patches for the CentOS distribution. It is your responsibility to keep the OS
 up to date. You can install these patches on your Workload Optimization Manager VM whenever necessary.



We currently release the VM image with the CentOS Linux OS. We have found it to meet overall security requirements. We intend to continue with CentOS for as long as that platform remains viable and secure.

OVA: Installing the vCenter Image for On-prem Environments

The first step to installing Workload Optimization Manager is to deploy the VM that will host the platform.

For vCenter Server environments, we deliver an OVA image for each quarterly release. If you want to run Workload Optimization Manager on vCenter Server, you can install the Quarterly Release, and then update to a later point release if necessary.

NOTE

For minimum requirements, we recommend 128 GB of memory for the VM that hosts Workload Optimization Manager. However, if you plan to manage a smaller environment (10,000 VMs or less), you can install on a VM that provides 64 GB of memory. (See Minimum Requirements (on page 38)).

If you plan to install a VM with 64 GB of memory, then you must modify the default for VM memory. (See <u>Deploy the Workload Optimization Manager VM (on page 40)</u>).

To install the Workload Optimization Manager OVA:

1. Download the Workload Optimization Manager installation package.

Navigate to the Workload Optimization Manager Software Download page (https://software.cisco.com/download/home/286328879/type/286317011/release) for links to the latest OVA image.

The installation package includes the cisco cwom-<version>-<XXXXXXXXXXXXXXXX.ova file

where <version> is the Workload Optimization Manager version number and <XXXXXXXXXXXXXXXXX is the timestamp.

For example: cisco_cwom-3.0.0-20190916164429000.ova

The OVA file deploys as a VM with the Workload Optimization Manager components ready for installation.

2. Import the OVA file into your datacenter.

Use the vCenter Server client to import the OVA into your environment.

Deploy the Workload Optimization Manager VM.

Configure the VM that was deployed from the OVA file.

If you want to deploy a VM with 64 GB of memory, manually modify the default value for Memory:

- a. Right-click the VM and choose Edit Settings.
- b. Type 64 for Memory.
- c. Click **OK** to save the settings
- d. Power on the VM.
- Open the remote console.

For the Workload Optimization Manager VM that you just deployed:

- a. Choose the Summary tab.
- b. Click Launch Remote Console.
- 5. Set up the Workload Optimization Manager System Administrator account.
 - a. In the remote console, log in with the following default credentials:
 - Username: turbo

Do not use the account name, root.

Password: vmturbo

Then, you will be prompted to enter a new password.

b. Enter your new password.

The new password must comply with the strong password policy (a mixture of upper- and lower-case letters, numbers, and a symbol). Only you will know this new password.



Be sure to save the changes account credentials in a safe place. For security reasons, this is the only account that can access and configure the Workload Optimization Manager VM.

- c. Enter your new password again to verify it.
- 6. Update the root password.

The platform uses the root account for certain processes, such as rolling up log messages in /var/log/messages. To ensure the account credentials are current, you must change the password:

- Open a SuperUser session.
 - In the remote console, enter su -
 - At the password prompt, enter the default password: vmturbo
- Reset a new password.

After you log in as root with the default password, the system prompts you for a New password. This new password must comply with the strong password policy (a mixture of upper- and lower-case letters, numbers, and a symbol). Only you will know this new password.

NOTE:

Be sure to save the root account credentials in a safe place.

c. Exit the SuperUser session.

Enter exit.

7. Perform other necessary configuration steps, and then install the Workload Optimization Manager components.

To perform the required and important configuration steps for the Workload Optimization Manager instance, see General Configuration Tasks (on page 46).

To install the Workload Optimization Manager components, see <u>Deploying the Workload Optimization Manager Components</u> (on page 92).

VHD: Installing the Microsoft Hyper-V Image

The first step to installing Workload Optimization Manager is to deploy the VM that will host the platform.

For Hyper-V environments, we deliver a Hyper-V image for each quarterly release. If you want to run Workload Optimization Manager on a Hyper-V VM, you can install the Quarterly Release, and then update to a later point release if necessary.

NOTE:

For minimum requirements, Cisco recommends 128 GB of memory for the VM that hosts Workload Optimization Manager. However, if you plan to manage a smaller environment (10,000 VMs or less), you can install on a VM that provides 64 GB of memory. (See <u>Minimum Requirements (on page 38)</u>).

If you plan to install a VM with 64 GB of memory, then you must modify the default for VM memory. (See <u>Deploy the Workload Optimization Manager VM (on page 40)</u>).

To install Workload Optimization Manager:

- 1. Download the Workload Optimization Manager installation package.
 - Navigate to the Workload Optimization Manager Software Download page (https://software.cisco.com/download/home/286328879/type/286317011/release) for links to the latest Hyper-V image.
- 2. Expand the .zip file and copy the contents, which includes the Virtual Machine image, to your Hyper-V server (either to your cluster shared volume or to a local hard drive).
- 3. Use the Import Virtual Machine Wizard in the Hyper-V Manager to import the Virtual Machine into your environment.
- 4. Make sure your virtual network adapter is connected to the correct virtual network.
- 5. Ensure the Workload Optimization Manager instance will have sufficient memory.
 - Cisco recommends that you use static memory for your Workload Optimization Manager instance. However, you can specify static or dynamic memory for the instance. By default, the installation sets static memory to 128 GB.
- 6. Start the Workload Optimization Manager appliance and record its IP address.



- Set up the Workload Optimization Manager System Administrator account.
 - a. Log into the VM's Hyper-V console with the following default credentials:
 - Username: turbo

Do not use the account name, root.

■ Password: vmturbo

Then, you will be prompted to enter a new password.

b. Enter your new password.

The new password must comply with the strong password policy (a mixture of upper- and lower-case letters, numbers, and a symbol). Only you will know this new password.

NOTE:

Be sure to save the changed account credentials in a safe place. For security reasons, this is the only account that can access and configure the Workload Optimization Manager VM.

- Enter your new password again to verify it.
- Update the root password.

The platform uses the root account for certain processes, such as rolling up log messages in /var/log/messages. To ensure the account credentials are current, you must change the password:

- a. Open a SuperUser session.
 - In the remote console, enter su -
 - At the password prompt, enter the default password: vmturbo
- Reset a new password.

After you log in as root with the default password, the system prompts you for a New password. This new password must comply with the strong password policy (a mixture of upper- and lower-case letters, numbers, and a symbol). Only you will know this new password.

NOTE:

Be sure to save the root account credentials in a safe place.

c. Exit the SuperUser session.

Enter exit.

9. Enable the NIC for the installed VM.

The Workload Optimization Manager instance configuration includes one NIC, but it is not enabled or connected to a network. Display the NIC in the Hyper-V Manager and enable it.

10. Perform other necessary configuration steps, and then install the Workload Optimization Manager components.

To perform the required and important configuration steps for the Workload Optimization Manager instance, see <u>General Configuration Tasks (on page 46)</u>.

To install the Workload Optimization Manager components, see <u>Deploying the Workload Optimization Manager Components</u> (on page 92).

Deploying the Workload Optimization Manager Components

After you install the Workload Optimization Manager VM that will host the platform, you can install the platform components.

First, gather the information you will need to run the installation:

Network Time Source for Time Synchronization (optional)

You can perform this step during installation, or at a later date. If you want to synchronize the VM's clock now, you will be prompted for the Network Time Source. For more information about synchronizing the VM's clock, see Synchronizing Time (on page 46).

Your updated root password



The installation script requires that you have updated the root password for the VM. If you followed the instructions in OVA: Installing the vCenter Image (on page 40) or in VHD: Installing the vCenter Image (on page 41), then you should have already performed this step.

When you are ready with the necessary information, you can run the installation script.

The IBM License Service, which collects license usage information that is used to create usage snapshots and reports, is installed automatically as part of the t8cinstall.sh script. For more information, see "Tracking License Usage with IBM License Service" in the *Installation Guide*.

This following steps describe the default installation process. If you want to customize your installation, then you should consider taking the steps in <u>Stepwise Platform Deployment (on page 92)</u>. For example, to change the Kubernetes host name for the deployment, you must perform a stepwise installation.

NOTE:

Starting with Workload Optimization Manager version 3.5.5, IBM Container Registry is used for all Workload Optimization Manager images for online upgrades and new installs. Ensure you have access to https://icr.io before continuing.

All OVA installs use Kubernetes v1.24.6. Docker commands no longer work. You can use crictl and ctr commands instead. For more information, see the following resources:

- Container runtime changes in Kubernetes 1.24 and beyond on the Kubernetes documentation site
- Mapping from dockercli to crictl on the Kubernetes documentation site
- crictl command reference and information on GitHub
- ctr command reference and information on GitHub
- 1. Start up the installation script.
 - Start a secure session (SSH) on your Workload Optimization Manager VM as the turbo user.
 - Run the installation script.

```
sudo /opt/local/bin/t8cInstall.sh
```

2. Verify that you have configured a static IP address for the Workload Optimization Manager VM.

After the components start up, you will type this static IP address into a web browser to access the login page for the Workload Optimization Manager user interface.

As a first step, the script prompts you with:

```
Have you run the ipsetup script to setup networking yet? [y/n] n
```

If you have not configured a static IP for the platform VM, enter n to exit the installation script now, and configure a static IP. If you have already configured a static IP for the platform VM, enter y to continue the installation. The script output displays the IP address that it recognizes for the VM, for example:

```
Old IP Address: 10.0.2.15

New IP Address: 10.10.123.123
```

Because of dependencies between Workload Optimization Manager and the Kubernetes installation, it is not recommended to change the IP address after the Workload Optimization Manager installation. For a production installation of Workload Optimization Manager, the VM must run with a static IP. For a testing or evaluation installation, you can use DHCP. However, if you plan to later use such an installation in a production environment, be sure to configure a static IP.

If you followed the instructions in OVA: Installing the vCenter Image (on page 40) or in VHD: Installing the vCenter Image (on page 41), then you already ran the ipsetup script to configure a static IP.

3. Wait while the script performs the installation.

As the installation process continues, the script:

- Configures the platform environment with the necessary certificates
- Configures the Kubernetes cluster on the VM

This can take a few tries before it succeeds. For each try that does not succeed, you will see messages similar to:



To further debug and diagnose cluster problems, use 'kubectl cluster-info dump'.

When the connection succeeds, the script advances to the next steps.

- Establishes local storage for the platform
- Creates the kubernetes namespace for the platform as turbonomic
- Configures authorization to access the required Kubernetes secrets
- Initializes the MariaDB database server to manage historical data for the platform

The script creates two accounts on the MariaDB that have full privileges:

- root@localhost
 - This account does not use a password. To connect via this account the user must be system root.
- mysql@localhost

This account does not use a password. To connect via this account the user must be system mysql.

NOTE:

For security reasons, Cisco recommends that you configure passwords for these accounts. You can connect with these accounts via sudo. For example, sudo mysql. After you connect, you can then set passwords to these accounts. For more information, see the MariaDB Knowledgebase at https://mariadb.com/kb.

- Installs the Timescale database for Embedded Reports and the Data Exporter
- Deploys and starts up the platform components

As the deployment begins, the script prints out the following:

After it deploys the components, it waits for the components to start up:

```
The installation process is complete, waiting for all the components to start up.

** The script will wait for as long as 30 minutes. **
```

If the components all start up within 30 minutes, then the installation is complete and successful.

If the components do not all start up within 30 minutes, the script displays the following and then exits:

```
One or more of your deployments has not started up yet.

** Please give your environment another 30 minutes to stablize. **

To check the status of your components, execute the following command:

kubectl get pods

If some components are still not ready, contact your support representative

Deployments not ready:
```

The script then displays the formatted result of the kubectl get pods command. This shows you the current status of the pods in the Workload Optimization Manager platform.

If the script exits before the components all start up, we recommend that you give the platform another 30 minutes. To periodically check the component status, run the <code>kubectl get pods</code> command. If the components do not all start up after another 30 minutes, contact your support representative.

If the installation is successful and the components are all started up, the script displays a message similar to the following, where it gives the VM's static IP address:



You can move on to the next steps.

4. Save a copy of the platform's Master Key secret.

The installation procedure creates a Master Key secret in the Kubernetes cluster. Workload Optimization Manager uses this secret to provide access for the platform components. You should save the key data to a safe location. If for some reason the key data gets corrupted or is otherwise unusable, Workload Optimization Manager will fail to operate. If this happens, you can contact your support representative and use this saved data to recover your platform.

To save the data:

List the platform secrets.

```
kubectl get secrets
```

The results should include the Master Key secret.

```
master-key-secret Opaque 1 57d
```

b. Display the Master Key data.

Once you find the Master Key name, you can then display the key data.

```
kubectl get secret master-key-secret -o yaml
```

The output is similar to the following example:

```
apiVersion: v1
data:
  primary_key_256.out: AfnJWutxNHAduaIOdAii3DRA2fMa6lzX4rWetZxxZvc=
kind: Secret
metadata:
  creationTimestamp: "2021-06-30T02:59:19Z"
  managedFields:
  - apiVersion: v1
    fieldsType: FieldsV1
    fieldsV1:
      f:data:
        .: {}
        f:primary_key_256.out: {}
      f:type: {}
    manager: kubectl-create
    operation: Update
    time: "2021-06-30T02:59:19Z"
  name: master-key-secret
  namespace: turbonomic
  resourceVersion: "1072"
  uid: a314b2ba-2061-4b41-b844-56caf2c3728d
type: Opaque
```

The important key data to save is the primary_key... data. In the above example, you should save the line:

```
primary_key_256.out: AfnJWutxNHAduaIOdAii3DRA2fMa61zX4rWetZxxZvc=
```

c. Save the data to a safe place.

Write this data to a file and save it in a safe backup location. If you ever need to recover the Master Key, your support representative will use this data to perform the recovery.

5. Log in to the Workload Optimization Manager user interface and set the administrator user account password.



Workload Optimization Manager includes a default user account named administrator which has an ADMINISTRATOR role. As you log in for the first time, you must set your own password for that account. You can create or delete other accounts with the ADMINISTRATOR role, but your installation of Workload Optimization Manager must always have at least one account with that role.

In the login page, enter the information as required, and make a note of it.

- Use the default credential for USERNAME: administrator.
- Type a password for PASSWORD.

The new password must comply with the strong password policy (a mixture of upper- and lower-case letters, numbers, and a symbol). Only you will know this new password.

- Type the password again to verify it for REPEAT PASSWORD.
- Click Create Account.

This is the account you will use to access the Workload Optimization Manager user interface with administrator permissions. Be sure to save the user interface administrator account credentials in a safe place.

NOTE:

The initial login is always for the default user account named administrator which has an ADMINISTRATOR role.

6. After you have logged in as administrator, you can create other user accounts, and you can give them various roles. For more information about user accounts and roles, see Managing User Accounts (on page 723).

NOTE:

For security reasons, you can create a different account with an ADMINISTRATOR role to serve as the main administrator of your Workload Optimization Manager installation, and then delete the default administrator account. But remember, you must always have at least one user account with administrator privileges.

General Configuration Tasks

After you install the Workload Optimization Manager instance, you should perform the following configuration tasks:

- (Required) Synchronize the system clock and configure your time servers
- (Important) Verify your MariaDB version
- (Optional) Increase available disk space
- (Optional) Enforce secure access via LDAP
- (Optional) Enforce secure access via trusted certificate
- (Optional) Enable secure access for probes
- (Optional) Modify the certificates for Cluster Manager
- (Optional) Enable embedded reports
- (Optional) Enable the Data Exporter
- (Optional) Change the IP address of the platform node
- (Optional) Enable and disable probe components
- (Optional) Disable component health monitoring

(Required) Synchronizing Time

It is important that you synchronize the clock on the Workload Optimization Manager instance with the other devices on the same network. By default, the Workload Optimization Manager server is configured to synchronize with any one of the following time servers:

- 0.centos.pool.ntp.org
- 1.centos.pool.ntp.org
- 2.centos.pool.ntp.org
- 3.centos.pool.ntp.org



To synchronize with these servers, your installation of Workload Optimization Manager must have access to the internet. If your environment restricts internet access, then you have to configure synchronization with a time server on your network.

In all cases, you should verify that the Workload Optimization Manager clock is properly synchronized. To check the system clock:

1. Open an SSH terminal session to your Workload Optimization Manager instance.

Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Username: [your_private_password]
- Verify your time settings.

Run the date command.

The output is similar to the following example:

```
Thu Feb 2 14:25:45 UTC 2019
```

Run the timedatectl command.

The output is similar to the following example:

```
Local time: Fri 2019-12-06 21:09:26 UTC
Universal time: Fri 2019-12-06 21:09:26 UTC
RTC time: Fri 2019-12-06 21:09:27
Time zone: UTC (UTC, +0000)
NTP enabled: yes
NTP synchronized: yes
RTC in local TZ: no
DST active: n/a
```

This tells you whether you have NTP enabled, and whether it is currently synchronized, along with other time synchronization information.

If the output is correct and your environment has access to the internet, you can assume the system clock is synchronized.

If the output is incorrect, or if you need to configure synchronization with a time server on your network, you must configure chrony on the server instance.

To set up chrony on your Workload Optimization Manager instance:

- 1. Open an SSH terminal session to your Workload Optimization Manager instance.
- 2. Open the chrony configuration file.

```
sudo vi /etc/chrony.conf
```

3. Specify the time servers that you want to use in your environment.

The chrony file includes the following statements to configure time servers:

```
server 0.centos.pool.ntp.org iburst
server 1.centos.pool.ntp.org iburst
server 2.centos.pool.ntp.org iburst
server 3.centos.pool.ntp.org iburst
```

Enter statements for the servers you want to use. Then delete or comment out the statements that you do not want to use. Specify a time server via the following command syntax:

```
server <My_Time_Server_Name > iburst
```

Save the file.



5. Restart the chrony service.

```
sudo systemctl restart chronyd
```

6. Verify that your time is correct.

Run the date command.

The output is similar to the following example:

```
Fri Dec 6 21:09:26 UTC 2019
```

To verify the time has been synchronized, run the timedatectl command.

The output is similar to the following example:

```
Local time: Fri 2019-12-06 21:09:26 UTC
Universal time: Fri 2019-12-06 21:09:26 UTC

RTC time: Fri 2019-12-06 21:09:27

Time zone: UTC (UTC, +0000)

NTP enabled: yes

RTC in local TZ: no

DST active: n/a
```

To verify the time, compare the date output with the output from a known UTC time server.

If the output is correct you can assume the system clock is synchronized.

If the output is incorrect, contact your support representative.

(Important) Verifying your MariaDB Version

For its default historical database, Workload Optimization Manager currently supports MariaDB version 10.5.20. This support includes comprehensive testing and quality control for Workload Optimization Manager usage of the historical database.

If you are running Workload Optimization Manager installed as a VM image (OVA or VHD), and using the database that is included in that image installation, then you must use version 10.5.20. If you are updating your version of Workload Optimization Manager (instead of installing it for the first time), ensure that you are using the correct version of MariaDB with your installation.

IMPORTANT:

It is a requirement that you run MariaDB version 10.5.20 or later. Workload Optimization Manager can operate with other versions of MariaDB; however, it is fully tested to operate with MariaDB version 10.5.20.

Because of a known issue, you must never use MariaDB versions 10.5.14, 10.5.15, 10.6.7, 10.7.3, or 10.8.2.

Workload Optimization Manager also supports MySQL 5.7.x, deployed as a custom installation.

When you initially installed Workload Optimization Manager, that installation included MariaDB running a specific version. As you update your Workload Optimization Manager version, the MariaDB version remains the same. The first release of Workload Optimization Manager that included MariaDB 10.5.20 is 3.5.6. If you initially installed an earlier version, and did not update your MariaDB to 10.5.20, then you must do it now.

- For VM image installations, it is possible to configure the installation to use a remote database (external to the VM). For such deployments, you must manage the database versioning yourself. If you are using a remote MariaDB instance, use version 10.5.20. For a remote MySQL, use version 5.7.x.
- For installations on a Kubernetes cluster (not deployed as a Workload Optimization Manager VM image), if you are using MariaDB use version 10.5.20; however, MariaDB 10.2 for Azure DB Services is tolerated. You can find a download package at: https://archive.mariadb.org/mariadb-10.5.20/yum/centos7-amd64. For MySQL, use version 5.7.x. For such deployments, you must manage the database versioning yourself.



Checking your MariaDB Version

Check the version of MariaDB running on your Workload Optimization Manager OVA. If you used the update script to update Workload Optimization Manager to version 3.1.5 or later, use these steps to update your MariaDB.

1. Open an SSH terminal session to your Workload Optimization Manager instance.

Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Password: [your_private_password]
- Check the MariaDB version.

```
mysql -u root --password=my_pwd -e "SHOW VARIABLES LIKE 'version';"
```

The output is similar to the following example:

Variable_name	Value	
	10.5.20-MariaDB	Ċ

If the version is earlier than 10.5.20-MariaDB, then you must update your database.

If your version is equal to or greater than 10.5.20-MariaDB do not complete the update steps.

Updating your MariaDB

If you are using Workload Optimization Manager installed as a VM image, and you are using the default MariaDB that was installed with that image, you must run MariaDB version 10.5.20.

To update your MariaDB on your Workload Optimization Manager VM:

Open an SSH terminal session to your Workload Optimization Manager instance.

Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Password: [your_private_password]
- 2. Ensure that the VM is mounted on the Workload Optimization Manager update ISO image.

NOTE

When you complete a Workload Optimization Manager update, the system automatically unmounts the ISO image. To update MariaDB, your Workload Optimization Manager instance must be mounted on the same ISO image that you used to update it to version 3.1.5 or later.

For more information, see Offline Update (on page 87).



Run the MariaDB update script.

Before you run the script, you need to know the MariaDB password. By default, this password is vmturbo.

a. Make the script executable.

NOTE:

If you complete offline updates and ran the offline upgrade script, the updated mariadbUpgrade.sh is copied from the ISO image to the /opt/local/bin directory with the executable flag enabled. You can skip this step and run the script.

```
sudo chmod +x /opt/local/bin/mariadbUpgrade.sh
```

b. Run the database update script.

```
sudo /opt/local/bin/mariadbUpgrade.sh
```

The script updates the version of MariaDB. It also increases size limits for the allowed packets, and buffer and log sizes for the innodb. The script output includes the following (where Total Memory and buffer pool size can vary depending on your VM configuration):

```
Update the mariadb configuration

Total Memory: 128773 MB

Changing Innodb buffer pool size to: 9216 MB

Changing max allowed packets to: 1G

Changing innodb log file size to: 10G
```

Verify the updated MariaDB version.

When the script completes, you are running version 10.5.20. To verify, run:

```
mysql -u root --password=my_pwd -e "SHOW VARIABLES LIKE 'version';"
```

The output is similar to the following example:

Variable_name	+ Value +	
version	10.5.20-MariaDB	

Scale up the Workload Optimization Manager platform's pods.

To update the database, the script scales down your platform pods. When it completes, the script displays the following prompt:

After you verify that the correct version of MariaDB is running, scale up the platform.

```
kubectl scale deployment --replicas=1 t8c-operator -n turbonomic
```



(Optional) Increasing Available Disk Space

A standard installation of Workload Optimization Manager on a VM image includes a MariaDB database server for historical data. If you enable Embedded Reports, the platform also uses TimescaleDB Postgres database to manage the reports data. For various reasons, you might find that the default storage capacity for your database services is not sufficient. In that case, you need to increase the available storage capacity.

A common reason to increase this capacity is to accommodate estimated needs for Embedded Reports. The storage requirements for Embedded Reports can change over time as your environment changes, or as you increase the number of targets you configure your your Workload Optimization Manager installation. For information about estimating Embedded Reports requirements, see Embedded Reports Storage Requirement Estimates (on page 1275).


A summary of the steps you will perform is:

- Add a new disk to the VM
- Rescan the scsi devices
- Create a new LVM partition
- Create a physical volume (pv)
- Add the pv to the existing volume group (vg)
- Extend the logical volume (lv)
- Extend the file system to use the new lv
- To increase storage for Embedded Reports, increase the XFS quota

To increase space for MariaDB, you do not need to perform this step.

Logical Volume Management for Workload Optimization Manager Storage

The platform uses Logical Volume Management (LVM) to manage the VM disks. To increase database storage, you should add a new disk to the VM, and then use it to extend the LVM logical volume, /dev/turbo/var_lib_mysql. This logical volume serves both the historical database and the Embedded Reports database.



Increasing Storage

To increase the storage space available to your databases:

1. Add a new disk to the VM.

Use the steps for your VM datacenter to add a new disk to the VM. Workload Optimization Manager installs as a VMware or a Hyper-V VM. Refer to the documentation for your hypervisor for the steps to add a new disk.



2. Open an SSH terminal session to your Workload Optimization Manager instance.

Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Password: [your_private_password]
- 3. Rescan the scsi devices.

To make sure the new disk is available, rescan the scsi devices and then list your block devices.

```
echo "- - -" > /sys/class/scsi_disk//0\:0\:0\:0\device/rescan
```

To check for the new disk, run the command:

lsblk

The new disk should appear with a name similar to /dev/sdc. If you don't see the new disk, try this alternative to force a rescan:

■ Check the number of scsi host devices that are on your VM.

```
ls /sys/class/scsi_host
```

You should see a list of devices, such as host0, host1, host2... hostn

Scan each device.

For each device run the command (where <hostn> is a numbered host device such as host0 or host1):

```
echo "- - -" > /sys/class/scsi_host/host0/scan
```

List the block devices.

Run lsblk again to list the block devices.

4. Create a new LVM partition.

Assuming the new disk is named /dev/sdc1, run the command:

```
cfdisk /dev/sdc1
```

Then run the operations:

- new
- primary
- confirm size
- change type to 8E
- write
- quit
- 5. Create the Physical Volume (pv).

Assuming the new disk is named /dev/sdc1, run the command:

```
pvcreate /dev/sdc1
```

Add the new pv to the existing Volume Group.

Assuming the new disk is named /dev/sdc1, run the command:

```
vgextend /dev/turbo /dev/sdc1
```



7. Extend the Logical Volume (lv) to use the free space in the new pv.

First list the physical extents (PE) that are available. Run the command:

```
vgdisplay
```

The output is similar to the following example:

```
Free PE / Size 128000 / 500.00 GiB
```

In this example, 128000 is the amount to extend the lv. For this example, run the command:

```
lvextend -l +128000 /dev/turbo/var_lib_mysql
```

Extend the XFS file system to use all the current lv space.

Before you extend the XFS, view the free disk space and record the number. To verify that you have increased the available space, you will compare this value to the free space after you have extended XFS. Run the command:

```
df -h
```

Then extend the XFS capacity:

```
xfs_growfs /dev/turbo/var_lib_mysql
```

Then list the updated free disk space and compare it to your original number:

```
df -h
```

9. If you are increasing capacity for Embedded Reports, extend the XFS quota for the TimescaleDB.

To increase space for MariaDB, you do not need to perform this step.

To increase capacity for the Timescale DB, you need to increase the quota for that process by the amount you want. The quota name is Postgresql.

For example, assume you added a 400 GB volume, and the current Postgresql quota is 400 GB. In that case, you could increase the quota to 800 GB. Following this example, run the command:

```
xfs_quota -x -c 'limit -p bhard=800g Postgresql' /var/lib/dbs
```

To see the current quotas set for /var/lib/dbs, run the command:

```
xfs_quota -xc 'report -pbih' /var/lib/dbs
```

(Optional) Enforcing Secure Access via LDAP

If your company policy requires secure access, you can use a certificate with your LDAP service to set up secure access for your users. For example, you can configure Active Directory (AD) accounts to manage *External Authentication* for users or user groups. The user interface to enable AD includes a **Secure** option, which enforces certificate-based security. For more information, see <u>Managing User Accounts</u> (on page 723).

If your LDAP service uses a Certificate Authority (CA), then the certificate signed by that CA should support this feature as it is. Simply turn on the **Secure** option when you are setting up your AD connection.

If your LDAP service uses a self-signed certificate, then you must install that certificate on the Workload Optimization Manager authorization pod. The steps you will perform include:

- Get the certificate from your LDAP server
- Import the certificate to the platform's TrustStore
- Add the certificate to the Workload Optimization Manager platform's authorization pod
- Enable the TrustStore in the Workload Optimization Manager platform's Operator chart



Installing a Self-signed Certificate

To set up secure access:

Open an SSH terminal session to your Workload Optimization Manager instance.

Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Password: [your_private_password]
- 2. Download your LDAP Server certificate to the Workload Optimization Manager instance.

Acquire a certificate from your LDAP administrator, and download it to the Workload Optimization Manager platform. For example, you can download it to the file / tmp/ldapserver.crt.

Import the .crt file to the Workload Optimization Manager TrustStore by using the keytool utility.

NOTE:

This step modifies the cacerts file on the Workload Optimization Manager platform.

a. Install the keytool utility in /usr/bin/keytool.

```
sudo yum install java-1.8.0-openjdk
```

b. If an alias for an LDAP certificate already exists, delete that certificate. For example, assuming the alias ldapcert1, run the following command:

```
keytool -delete -alias ldapcert1 -keystore cacerts -storepass changeit
```

c. Import your new certificate to the TrustStore.

```
keytool -import -alias ldapcert1 -file /tmp/ldapserver.crt -keystore cacerts \
    -deststoretype jks -storepass changeit -noprompt
```

Create an auth secret from the cacerts file.

```
base64 cacerts > auth-secrets.yaml
```

Open the secrets file for editing.

```
vi auth-secrets.yaml
```

- 6. Edit the file to make it a valid yaml file.
 - a. Indent every line of the certificate by four spaces.

When you created the file, you concatenated the contents of the certificate. The first step is to indent the certificate by four spaces. For example, in a vi editor, execute the following command:

```
:%s/^/ /g
```

b. Add data fields to the secrets file.

Add the following text to the top of the file:

```
apiVersion: v1
kind: Secret
metadata:
   name: auth-secret
data:
   cacerts: |
```

c. Save your changes.

The output is similar to the following example:



apiVersion: v1 kind: Secret metadata: name: auth-secret

data:

cacerts:

/u3+7QAAAAIAAABAAAAAgAFY2VydDEAAAF5H2lEigAFWC41MDkAAAYQMIIGDDCCBPSgAwIBAgIT MRcwFQYKCZImiZPyLGQBGRYHdm10dXJibzEUMBIGCgmSJomT8ixkARkWBGNvcnAxFjAUBgNVBAMT DWNvcnAtREVMTDEtQ0EwHhcNMjEwNDA4MDM00TEyWhcNMjIwNDA4MDM00TEyWjAhMR8wHQYDVQQD ExzkzWxsMS5jb3JwLnztdHVyYm8uY29tMIIBIjANBgkqhkiG9w0BAQEFAAOCAQ8AMIIBCgKCAQEA sCXuh2MTrFERyU/aKgdbgyjLezNuwF6nmZveZUhDaJDpfLHJlzhwfyYRTGfSSusVo4polJS4WqPZ T3Zk8f2IaX04RpfpQErq5N3uY/BxFkATWLMDiquSd0Di798k2diYXAxXvzMmfmIkBBYJta9oztum $\verb"uXyh/42dXOGznQ5fFuxosgAksZ6CnXGDKrTBlb0bHpST1z1Pdg+fJ+f9Tq7Iff0YdVbuedFTwsik" and the statement of the s$ Z0JgDCIRrmmsOJphiHdBqJ6ZLdbSeEzBIbboiQs81pAELw7V0ZZUfKV6y8+zMTACGwpVPJSFv7LX $\verb|R1W1TWcqhXVAOmroe2WcU8KJE6XZTBxp7z7dzwIDAQABo4IDADCCAvwwLwYJKwYBBAGCNxQCBCIe| \\$ ${\tt IABEAG8AbQBhAGkAbgBDAG8AbgB0AHIAbwBsAGwAZQByMB0GA1UdJQQWMBQGCCsGAQUFBwMCBggrader} \\ {\tt IABEAG8AbgBDAG8AbgBAGABAGABAGABAGABAGA$ BgEFBQcDATAOBgNVHQ8BAf8EBAMCBaAweAYJKoZIhvcNAQkPBGswaTAOBggqhkiG9w0DAgICAIAw CWCGSAFlAwQBBTAHBgUrDgMCBzAKBggqhkiG9w0DBzBCBgNVHREEOzA5oB8GCSsGAQQBgjcZAaAS BBDswjlHut/nQZ0uK2aUglGbghZkZWxsMS5jb3JwLnZtdHVyYm8uY29tMB0GA1UdDgQWBBR6M7Hb BiirpjIXO3PXXScB8LkmRDAfBqNVHSMEGDAWqBRjs913el7SuKUDMlrHHRhBkENqaDCB0OYDVR0f BIHJMIHGMIHDOIHAOIG9hoG6bGRhcDovLy9DTj1jb3JwLURFTEwxLUNBLENOPWR1bGwxLENOPUNE UCxDTj1QdWJsaWMlMjBLZXklMjBTZXJ2aWNlcyxDTj1TZXJ2aWNlcyxDTj1Db25maWdlcmF0aW9u $\verb|LERDPWNvcnAsREM9dm10dXjibyxEQz1jb20/Y2VydGlmaWNhdGVSZXZvY2F0aW9uTGlzdD9iYXNl| \\$ P29iamVjdENsYXNzPWNSTERpc3RyaWJ1dGlvblBvaW50MIHHBggrBgEFBQcBAQSBujCBtzCBtAYI KwYBBQUHMAKGgadsZGFwOi8vL0NOPWNvcnAtREVMTDEtQ0EsQ049QU1BLENOPVB1YmxpYyUyMEt1 eSUyMFNlcnZpY2VzLENOPVNlcnZpY2VzLENOPUNvbmZpZ3VyYXRpb24sREM9Y29ycCxEQz12bXR1cmJvLERDPWNvbT9jQUNlcnRpZmljYXRlP2Jhc2U/b2JqZWN0Q2xhc3M9Y2VydGlmaWNhdGlvbkF1 C9mUxL0G5Tudr0VlyEnLH2wtj10CGsIi54+aPGYiElXijThEe1WTHaO2hklRLdNrM8KxUp3tUNb/ cP4d+EYt297wVWgxpl9MStiND8+7M2+65daoEu5IOLtq4lC7YlCSXay19N5HdiGBHV5L07PTZ261 qDzShSb0ZWtG7++5VkqveVEIfs3hUYdaItz0Zu6sym90aUcvn5wohV1GPPqGDvVCg5Kf50hsZfmy ${\tt ltNlaqiiqLMnYVMa93CkpFFjoP9gmGFJky0yTfh6G8HuqbI7guddDsUqMQTT3uv3EBwSYeImOya7}$ Zye5C4NnsAfnx8kOwXdsVERC

Apply this secrets file to the platform environment.

```
kubectl apply -f auth-secrets.yaml
```

- Update the platform's Operator Chart to use the cacerts certificate that you created in the secrets file.
 - Open the chart file for editing.

/opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml

Add the certification secret as an authorization spec for the component options.

In the chart file, find the spec: section. Within that section, find the auth: subsection.

This should be the second subsection in spec:, after global:. If there is no auth: subsection, you can add it to spec:.



c. Add the certification secret to the file:

You will add the secret's path to a javaComponentOptions: statement within the auth: subsection. Add the path as a -D option. The auth: subsection should be similar to the following example, with auth indented by two spaces and javaComponentOptions indented by four spaces:

```
# Pass in the JAVA_OPTS to the auth POD to set up additional options such as
# a trustStore for AD Certificate(s) for LDAPS (Secure LDAP)
auth:
   javaComponentOptions: "-Djavax.net.ssl.trustStore=/home/turbonomic/data/helper_dir/cacerts"
```

d. Apply your Operator Chart changes to the Workload Optimization Manager platform.

```
kubectl apply -f \
/opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```

This restarts the authorization component so it can use the new setting.

(Optional) Adding a Certificate for Securing the Workload Optimization Manager UI

If your company policy requires SSL connections that use a trusted certificate, Workload Optimization Manager installs a trusted certificate from a known certificate authority.

Requesting a Certificate

The first step is to acquire a certificate. The following steps describe how to generate a certificate request.

Open a Secure Shell terminal session.

Open an SSH terminal session on your Workload Optimization Manager instance. Log in as turbo, and use the password that you created for the administration account during installation.

For more information, see Set up the Workload Optimization Manager System Administrator account (on page 40).

2. Change to the directory where you want to store the private key file.

If your shell session is on your Workload Optimization Manager instance, use the /opt/turbonomic directory.

```
cd /opt/turbonomic
```

Create and save the private key file.

For this example, the private key file is named myPrivate.key.

```
openssl genrsa -out myPrivate.key 2048
```

You need this file later. If you are in a session on your Workload Optimization Manager instance, copy the file to your local machine.

4. Create a file to contain the information that generates the signed certificate request (CSR).

```
vi certsignreq.cfg
```

5. Add the request data to the certsignreq.cfg file.

In the file, insert the following code. For any fields marked by angle brackets (for example <city>), provide the indicated value. For example, your country, city, company, and so on.

```
[req]

ts = 2048

prompt = no
```



```
default_md = sha256
req_extensions = req_ext
distinguished_name = dn

[dn]
C=<country, 2 letter code>
L=<city>
O=<company>
OU=<organizational unit name>
CN=<FQDN>
emailAddress=<email address>

[req_ext]
subjectAltName = @alt_names

[alt_names]
DNS.1 = <FQDN>
DNS.2 = <server's short name>
DNS.3 = <server's IP address>
```

For the CN field, specify the fully qualified domain name of the Workload Optimization Manager instance.

Alternative names are other ways to access the Workload Optimization Manager instance. In the <code>[alt_names]</code> section, the value for the <code>DNS.1</code> field is required. For <code>DNS.1</code>, specify the fully qualified domain name of the Workload Optimization Manager instance. Values for the <code>DNS.2</code> and <code>DNS.3</code> are optional. You can add more <code>DNS.x</code> fields if needed.

For example:



```
ts = 2048
prompt = no
default_md = sha256
req_extensions = req_ext
distinguished_name = dn
[dn]
C=US
ST=New York
L=White Plains
0=Turbonomic
OU=Educational Services
CN=demo.turbonomic.com
emailAddress= <first.lastname> @turbonomic.com
[req_ext]
subjectAltName = @alt_names
[alt_names]
DNS.1 = demo.turbonomic.com
DNS.2 = demo
DNS.3 = my.ip.add.ress
```

6. Write and guit the file.

Press Esc, type :wq!, and press Enter.



Generate the certificate request file.

In this example, the file is named myRequest.csr.

```
openssl req -new -sha256 -nodes -out myRequest.csr -key \
  myPrivate.key -config certsignreq.cfg
```

8. Send the generated request file to your certificate authority.

If you generated the file on your Workload Optimization Manager instance, transfer the file to your local machine. The path to the certificate request file on your remote machine is /opt/turbonomic/myRequest.csr.

Your certificate authority uses this file to create the certificate for you. If your certificate authority gives you an encoding choice between DER and Base 64, choose **Base 64**.

9. When you receive the certificate, save it to disk.

If you did not receive the certificate encoded in Base 64, you must convert it from DER to Base 64.

In this example, the certificate is named MyCertificate.crt.

```
openssl x509 -inform der -in MyCertificate.der -out MyCertificate.crt
```

Installing the Signed Certificate in Workload Optimization Manager

After you obtain the signed certificate, you can install it on your Workload Optimization Manager instance. You use the private key and certificate files that you obtained when requesting the signed certificate:

- myPrivate.key
- MyCertificate.crt

To install the signed certificate:

- 1. Open an SSH terminal session on your Workload Optimization Manager instance.
- 2. Add the key and certificate data to your Workload Optimization Manager charts.yaml file.

```
/ {\tt opt/turbonomic/kubernetes/operator/deploy/crds/charts\_vlalphal\_xl\_cr.yaml}
```

Find the section for global parameters. Under the global parameters, create the ingress: secrets section, and then create entries for certificate, key, and name.

Your global parameters should be similar to the following example:

```
global:
ingress:
secrets:
- certificate: |
----BEGIN CERTIFICATE----
SAMPLE PUBLIC KEY
----END CERTIFICATE----
key: |
----BEGIN RSA PRIVATE KEY----
SAMPLE PRIVATE KEY
----END RSA PRIVATE KEY----
name: nginx-ingressgateway-certs
```

For the fields you added:

- certificate: holds the content of your MyCertificate.crt file. Open that file to copy its contents and paste them here.
- key: holds the content of your myPrivate.key file. Open that file to copy its contents and paste them here.
- name: Is required and the name must be nginx-ingressgateway-certs.



3. Apply the changes that you made to the CR file.

```
kubectl apply -f \
  kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```

4. Restart the nginx pod.

To require a certificate for HTTPS access, you must restart the nginx pod.

Get the full name of the pod.

```
kubectl get pods -n turbonomic
```

In the output, look for the entry for nginx. You should find an entry similar to:

```
nginx-5b775f498-sm2mm 1/1 Running
```

b. Restart the pod.

```
kubectl delete pod nginx-<UID>
```

Where <UID> is the generated ID for the pod instance.

After the nginx pod restarts Workload Optimization Manager requires a certificate for HTTPS access.

(Optional) Adding Additional CA Certificates for Probes

If your target requires SSL connections that use a trusted certificate, Workload Optimization Manager installs a trusted certificate on the associated probe component.

The Workload Optimization Manager platform includes various probe components that it uses to connect to targets and discover their data. This procedure assumes setup for one component, the Dynatrace probe. You can use the same steps for other probes, providing a different Kubernetes Secret Name for each.

To install a certificate on a probe component, you must know the Kubernetes secret name for the probe. This table lists the probes that you can configure, plus their secret names. To configure secure access for any probes not listed here, contact your support representative.

Probe	K8s Secret Name
mediation-appinsights	appinsights
mediation-aws mediation-awsbilling mediation-awscost	aws
mediation-azure mediation-azurecost mediation-azuresp mediation-azurevolumes	azure
mediation-azurebilling	azurebilling
mediation-azureea	azureea
mediation-dynatrace	dynatrace
mediation-newrelic	newrelic

Installing the Signed Certificate on the Probe Component

This procedure assumes that you already have a valid .crt file. If you do not have the certificate file, ask your networking team to generate one for you.



After you obtain the signed certificate (MyCertificate.crt), install it on your probe instance.

1. Copy the certificate from your local machine to the Workload Optimization Manager instance.

Use SmartCloud Provisioning to copy the MyCertificate.crt from your local machine to the /tmp directory on the instance.

- 2. Open an SSH terminal session on your Workload Optimization Manager instance, that uses the turbo user account.
- 3. Obtain the truststore from the probe component.

Obtain the ID for the pod that runs the probe.

```
kubectl get pods
```

This lists the pods running in the Workload Optimization Manager platform, including their IDs. Record the ID of the pod that you want to configure.

To get the CA truststore, run the following command, where <Probe-Pod-Id> is the ID you recorded:

```
kubectl cp <Probe-Pod-Id>:etc/pki/ca-trust/extracted/java/cacerts cacerts
```

Import the certificate into the pod's keystore.

As part of this step, you ensure that the certificate is in Base64 format and you create a yaml file that uses the K8s Secret Name for the probe. While still in the bash session, run the following commands:

- chmod 775 cacerts
- keytool -import -alias probe_certificate -file \
 <MyCertificate.crt> -keystore cacerts -deststoretype jks \
 -storepass changeit -no-prompt

Where <MyCertificate.crt> is the name of the certificate that you acquired.

base64 cacerts > <Secret_Name>-secrets.yaml

Where <Secret_Name>-secrets.yaml is the yaml file that you create that uses the K8s Secret Name for the probe.

For example, assume that you are enabling SSL for the Dynatrace probe. In that case, the secret name is dynatrace, and you would create the yaml file dynatrace-secrets.yaml.

- 5. Update the <Secret_Name>-secrets.yaml file you created.
 - a. While still in the bash session on the Workload Optimization Manager server, open the yaml file created in the previous step in a vi editor session.

```
vi <Secret_Name>-secrets.yaml
```

b. Align the base64 data to the yaml format.

Type: to enter the command mode. For the command, type the following, where the white space token is four space characters.

```
:%s/^/ /g
```

Press RETURN, then save and exit the vi editor.

c. Add the following content to the file above your Base64 data.



xxxxxxxxxxxxxxxxxxxxxxxx

Your Base64 data should be in the cacerts section in place of the xxx characters in the example above.

6. Apply the yaml file to the Workload Optimization Manager platform.

Run the following command, where <Secret_Name>-secrets.yaml is yaml you created.

```
kubectl apply -f <Secret_Name>-secrets.yaml
```

- For each probe that you configure with an SSL certificate, add an entry in the chart_v1alpha1_cl_cr.yaml file.
 - a. With a shell session running on the Workload Optimization Manager platform, open the following file in a text editor.

```
vi /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalpha1_xl_cr.yaml
```

- b. Search the file for the entry for the probe that you are configuring. Use the probe names listed in the table above. For example, if you are configuring the Dynatrace probe, find the entry for mediation-dynatrace. If the entry does not exist in the file, you can add it to the spec: section at the same level as global:, with the probe entry that is indented by two spaces and javaComponentOptions indented by four spaces.
- c. Underneath the probe entry, add the following entry for javaComponentOptions.

```
javaComponentOptions: -Djavax.net.ssl.trustStore=/etc/targets/cacerts
```

For example, if you are configuring the Dynatrace probe, the entry should be:

```
mediation-dynatrace:
    javaComponentOptions: -Djavax.net.ssl.trustStore=/etc/targets/cacerts
    resources:
    limits:
        memory: 2Gi
```

- d. Save and exit the chart_v1alpha1_cl_cr.yaml file.
- e. Apply the changed file to your Workload Optimization Manager platform.

kubectl apply -f /opt/turbonomic/kubernetes/operator/deploy/crds/charts_v1alpha1_x1_cr.yaml

(Optional) Modifying the Certificates for Cluster Manager

For installations behind a firewall, to upload diagnostics from the clustermgr component, you must modify its certificates.

These steps to modify the certificates on clustermgr assume that you have already generated the certificates that you want to add to the cluster manager.

Open an SSH terminal session on your Workload Optimization Manager instance.

Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Username: [your_private_password]
- 2. Get the full name of the clustermgr pod.

```
kubectl get pods -n turbonomic | grep clustermgr
```

The output is similar to the following example:

```
clustermgr-5f487f58f-tf84b 0/1 Running 52 2d4h
```

In this example, clustermgr-5f487f58f-tf84b is the full name of the pod, and 5f487f58f-tf84b is the POD_ID.

3. Save a copy of the pod's current ca-bundle.crt file to /tmp.

Run the following command, where < POD_ID> is the ID you get from the pod's full name.



```
kubectl cp \
clustermgr-<POD_ID>:etc/pki/ca-trust/extracted/pem/tls-ca-bundle.pem \
/tmp/ca-bundle.crt
```

4. Add your certificates to the bundle.

Repeat this command for each certificate, where <MY_CERT> is your certificate file.

```
cat <MY_CERT> >> /tmp/ca-bundle.crt
```

5. Create a Kubernetes secret for the modified certificates.

```
kubectl create secret generic clustermgr-secret --from-file=/tmp/ca-bundle.crt
```

Open the cr.yaml file for editing.

For example:

```
vi /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```

Modify the cr.yaml file to use this secret.

Add the following to the file:

```
clustermgr:
  env:
    - name: component_type
     value: clustermgr
    - name: instance_id
      valueFrom:
        fieldRef:
          fieldPath: metadata.name
    - name: instance_ip
      valueFrom:
        fieldRef:
          fieldPath: status.podIP
    - name: serverHttpPort
      value: "8080"
    - name: kafkaServers
      value: kafka:9092
    - name: kafkaNamespace
      valueFrom:
        fieldRef:
          apiVersion: v1
          fieldPath: metadata.namespace
    - name: CURL_CA_BUNDLE
      value: /home/turbonomic/data/ca-bundle.crt
```

8. Save your changes and apply the cr.yaml file.

```
kubectl apply -f \
/opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```

If you watch the log with grep <code>^clustermgr</code>, then you will see the appropriate curl command run whenever you send diagnostics.

You can also check the .crt file in the cluster manager pod by using the following commands, where <POD_ID> is the ID you got from the pod's full name:

```
kubectl exec -it clustermgr-<POD_ID> bash
```



vi /home/turbonomic/data/ca-bundle.crt

(Optional) Enabling the Reporting Add-on

The Workload Optimization Manager platform includes a reporting add-on that you can choose to enable when you install the platform. Use the reporting add-on to understand trends in application resource management and to share insights with stakeholders through reports and dashboards.

The reporting add-on runs as its own component within the Workload Optimization Manager platform. This architecture enhances performance and reduces storage requirements. It stores a history of your managed environment and then presents selective snapshots of this history through a set of standard dashboards and reports. You can create your own dashboards and reports to focus on other areas of concern.

For more information, see Integration - Embedded Reporting (on page 1268).

(Optional) Enabling the Data Exporter

To support Data Export, Workload Optimization Manager provides an extractor component that can stream data to a standard format. You can load that data into search and analytics services such as Elasticsearch.

To enable the Data Exporter, you must:

- Enable the extractor component.
 - The extractor is a component that runs as part your Workload Optimization Manager installation. The extractor is not enabled by default.
- Deploy a connector that delivers the extractor's stream to your data service.

The extractor publishes Workload Optimization Manager data as Kafka topics. The connector enables your data service to consume the data topic. This document includes a deployment file for a sample Elasticsearch connector.

Enabling the Extractor Component

The first step to enabling the Data Exporter is to enable the extractor component.

NOTE:

If you have enabled Embedded Reporting, then the extractor component is already enabled (set to true).

It is possible to enable the Data Exporter without enabling Embedded Reports, just as it is possible to enable Embedded Reports without enabling the Data Exporter.

Open an SSH terminal session to your Workload Optimization Manager instance.

Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Password: [your_private_password]
- 2. Open the cr.yaml file to enable the extractor component.

vi /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml

Edit the entry for the extractor component.

Search for the extractor entry in the cr.yaml file.

```
extractor:
    enabled: false
```

Change the entry to true.

Edit the entry for the extractor properties.

Search for the properties: extractor entry in the cr.yaml file.



```
properties:
    extractor:
    enableDataExtraction: false
```

Change the entry to true.

5. Save and apply your changes to the platform.

```
kubectl apply -f \
/opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```

6. Verify that the extractor component is running.

Give the platform enough time to restart the components. Then run the command:

```
kubectl get pods -n turbonomic
```

You should see output similar to the following:

```
NAME READY STATUS RESTARTS ... extractor-5f41dd61c4-4d61q 1/1 Running 0 ...
```

Look for an entry for the extractor component. If the entry is present, then the extractor component is installed and running.

Deploying a Connector

The extractor publishes Workload Optimization Manager data as Kafka topics. To load this data into a search and analysis service, you must deploy a connector to that service. For example, you must deploy an Easticsearch connector to load the data into Elasticsearch. You deploy the connector in the same Kubernetes node that runs the Workload Optimization Manager platform. Create a Kubernetes Deployment that declares the pods you need for the connector.

To deploy the connector, create a deployment yaml file on the same host that is running the extractor component, and run the command:

```
kubectl create -f <MyConnectorDeployment.yaml>
```

Where <MyConnectorDeployment.yaml> is the name of the deployment file.

Assume that the name of the deployed pod is es-kafka-connect. To verify that the connector is running, run the command:

```
kubectl get pods -n turbonomic
```

The output is similar to the following example:

```
NAME READY STATUS RESTARTS
...
es-kafka-connect-5f41dd61c4-4d61q 1/1 Running 0
...
```

After you deploy the connector, wait for a cycle of Workload Optimization Manager analysis (approximately ten minutes). Then you will see the entities and actions from your Workload Optimization Manager environment, loaded as JSON in your data service.



Connector Deployment Example

The following example is a sample deployment of a connector to Elasticsearch that uses Kibana with Elasticsearch to display data dashboards. In this example, you have the following set up:

- Elasticsearch is deployed to a VM on the network where you are running Workload Optimization Manager. The Elasticsearch host is visible from the Workload Optimization Manager Kubernetes node. You specify this host address in the connector deployment.
- An Elasticsearch index is set up to load the Workload Optimization Manager data. You specify this index in the connector deployment.

The following listing is a deployment that uses a Logstash image to collect the extractor data and pipe it to the Elasticsearch host. The deployment also sets up storage volumes, configures the input from the extractor, and configures output to the Elasticsearch instance. As you go over the listing, pay attention to the following:

The location of the Elasticsearch host and the login credentials.

```
env:
    - name: ES_HOSTS
    value: "<UrlToMyElasticsearchHost>"
    - name: ES_USER
    value: "<MyElasticsearchUser>"
    - name: ES_PASSWORD
    valueFrom:
        secretKeyRef:
        name: <MyES_KeyName>
        key: <MyES_Key>
...
```

Logstash will use the following environment variables:

- ES_HOSTS: to identify where to pipe the exported data.
- ES_USER: to identify the user account on Elasticsearch.
- ES_PASSWORD: for the account login. This connector example assumes that you have stored the Elasticsearch
 password as a Kubernetes Secret.
- The name of the Kafka topic.

```
..
logstash.conf: |
input {
   kafka {
    topics => ["turbonomic.exporter"]
```

The Logstash input configuration expects a single topic named turbonomic.exporter.

■ The Logstash output configuration is to the Elasticsearch server that is identified by the ES_HOSTS environment variable. You specify your own Elasticsearch index in place of <MyElasticsearchIndex>.

```
output {
    elasticsearch {
        index => "<MyElasticsearchIndex>"
        hosts => [ "${ES_HOSTS}" ]
    }
}
```

Sample Listing: Elasticsearch Connector



This listing is a sample of a deployment file that can work to create an Elasticsearch connector for the Data Exporter. You need to change some settings, such as username and password. You also might need to specify ports and other settings to make the connector comply with your specific environment.

```
apiVersion: apps/v1
kind: Deployment
metadata:
  name: elasticsearch-kafka-connect
    app.kubernetes.io/name: elasticsearch-kafka-connect
spec:
  replicas: 1
  selector:
    matchLabels:
      app.kubernetes.io/name: elasticsearch-kafka-connect
  template:
    metadata:
      labels:
        app.kubernetes.io/name: elasticsearch-kafka-connect
    spec:
      containers:
      - name: logstash
        image: docker.elastic.co/logstash/logstash:7.10.1
        ports:
          - containerPort: 25826
        env:
          - name: ES_HOSTS
            value: "<UrlToMyElasticsearchHost>"
          - name: ES_USER
            value: "<MyElasticsearchUser>"
          - name: ES_PASSWORD
            valueFrom:
              secretKeyRef:
                name: <MyES_KeyName>
                key: <MyES_Key>
        resources:
          limits:
            memory: 4Gi
        volumeMounts:
          - name: config-volume
            mountPath: /usr/share/logstash/config
          - name: logstash-pipeline-volume
            mountPath: /usr/share/logstash/pipeline
      volumes:
      - name: config-volume
        configMap:
          name: logstash-configmap
          items:
            - key: logstash.yml
              path: logstash.yml
      - name: logstash-pipeline-volume
        configMap:
          name: logstash-configmap
          items:
            - key: logstash.conf
```



```
path: logstash.conf
apiVersion: v1
kind: ConfigMap
metadata:
 name: logstash-configmap
data:
  logstash.yml: |
    http.host: "0.0.0.0"
    path.config: /usr/share/logstash/pipeline
  logstash.conf:
    input {
      kafka {
        topics => ["turbonomic.exporter"]
        bootstrap_servers => "kafka:9092"
        client_id => "logstash"
        group_id => "logstash"
        codec => "json"
        type => "json"
        session_timeout_ms => "60000"
                                         # Rebalancing if consumer is found dead
        request_timeout_ms => "70000"
                                         # Resend request after 70 seconds
    }
    filter {
    output {
      elasticsearch {
        index => "<MyElasticsearchIndex>"
        hosts => [ "${ES_HOSTS}" ]
        user => "${ES_USER}"
        password => "${ES_PASSWORD}"
apiVersion: v1
kind: Service
metadata:
    app: elasticsearch-kafka-connect
  name: elasticsearch-kafka-connect
spec:
 ports:
    - name: "25826"
      port: 25826
      targetPort: 25826
  selector:
    app: elasticsearch-kafka-connect
```

(Optional) Changing the IP Address of the Platform Node

For standard installations of Workload Optimization Manager (installed as a VM image), you might need to change the platform's IP address. For example, if you must move the VM then you might need to assign it a different address. If you must change the IP address of the platform, you can use the supplied scripts.



Change the IP address of your Workload Optimization Manager installation as seldom as possible. Changing the IP address is a sensitive action that can impact unforeseen dependencies.

Use these steps to change the IP address only for Workload Optimization Manager version 3.0.0 or later. If you must change your IP address and you cannot update to version 3.0.0 or later, contact your support representative.

To change the IP address of the Workload Optimization Manager VM:

Get your information ready.

Identify the current IP address for your platform and the new IP address you use.

Know the credentials to open a shell session on the VM and run commands.

2. Create a full snapshot of the VM.

It is important to make a full snapshot of your installation before you try to modify its IP address.

3. Change the VM's IP address.

The Workload Optimization Manager VM includes the ipsetup script to complete this task.

a. Open an SSH terminal session to your Workload Optimization Manager VM.

Use the following credentials:

- Username: turbo
- Password: Give the password that you assigned to the turbo account when you first installed the platform.
- b. Once the session is open, run the ipsetup script:

```
sudo /opt/local/bin/ipsetup
```

When the script runs, it requests the following inputs.

NOTE:

Provide values for these fields; otherwise, the installation can fail or your VM can be unreachable.

- Required: Do you want to use DHCP or set a static IP...
 - Choose static
- Required: Please enter the IP Address for this machine
- Required: Please enter the network mask for this machine
- Required: Please enter the Gateway address for this machine
- Required: Enter DNS Server(s) IP Address for this machine

Make a note of the IP address that you provide.

c. Propagate your IP change through to the Kubernetes cluster on the VM.

```
sudo /opt/local/bin/kubeNodeIPChange.sh
```

d. Verify that the change is successful.

Log in to the Workload Optimization Manager user interface for the newly located installation, and ensure that it displays correctly. Review the Supply Chain, your groups, and your policies. Also ensure that charts show data correctly.

When you are sure that the change is successful, you can remove the snapshot that you made of the VM in its old location.

(Optional) Enabling and Disabling Probe Components

In Workload Optimization Manager, a probe is a platform component that connects to a target. It discovers the target's entities and loads them into the Workload Optimization Manager supply chain, and it can run actions on the devices in the target environment. Workload Optimization Manager includes many probe components that you can use to connect Workload Optimization Manager with your environment.



When you first install Workload Optimization Manager, it enables a certain set of probes by default. Each probe uses resources in your Workload Optimization Manager installation. If probes are not needed, you should consider disabling them. On the other hand, if there are disabled probes that you do need, you must enable them to put them into service.

NOTE:

As Workload Optimization Manager evolves, the set of delivered probes change. Also, from one version to the next, the set of probes that are enabled by default can change. When you update to a new version, the update does not change your probe configuration. An update to a newer version does not automatically enable any new probes in your deployment. If you want to take advantage of new probes in an update, then you must enable them manually.

Viewing the Current List of Available Probes

As you update your version of Workload Optimization Manager, more probes can come available with the update. However, the update does not modify your current configuration of enabled or disabled probes. This means that any new probes that come with an update will not be available to you by default.

To enable any new probes, you must first know the internal name for the probe. To get a list of probes that are available to your current version, you can view the contents of the values.yaml file.

Open an SSH terminal session on your Workload Optimization Manager instance.

Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Username: [your_private_password]
- 2. Display the list of available probes.

```
cat /opt/turbonomic/kubernetes/operator/helm-charts/xl/values.yaml
```

The output is similar to the following example:

```
customdata:
   enabled: false
dynatrace:
   enabled: false
gcp:
   enabled: false
hpe3par:
   enabled: false
...
```

This list gives the internal names of the probes. If you want to add a new probe to your list of configured probes, you must use the internal name, and set enabled: true.

Viewing the Current List of Configured Probes

Your current installation of Workload Optimization Manager has a certain set of available probes. Some of these will be enabled, and it is likely that some probes are disabled. To View the current configuration of probes that are available, open the cr.yaml file for your Workload Optimization Manager installation and review the probe entries:

1. In the same SSH session, open the cr.yaml file for editing. For example:

```
vi /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```

2. Search for the list of probes that are configured for your current installation.

The output is similar to the following example:

```
actionscript:
   enabled: true
appdynamics:
   enabled: true
appinsights:
```



```
enabled: true
aws:
  enabled: true
azure:
  enabled: true
dynatrace:
  enabled: true
hpe3par:
  enabled: true
horizon:
  enabled: false
hyperflex:
  enabled: false
```

This list identifies all the probes that are configured for your installation, and shows whether they are enabled (true) or disabled (false).

NOTE:

This list of probes is not identical to the list of probe pods that are running in your installation. Some probes use multiple pods. Probe pod names use the following convention, where {ProbeName} is the probe internal name (in the lists above), and {NameExtension} is an optional extension to that name in case there are multiple pods for this probe:

```
mediation-{ProbeName}{NameExtension}
```

For example, if you run kubectl get pods -n turbonomic, the results can show the following for the vcenter probe:

```
NAME READY STATUS RESTARTS mediation-vcenter-5bc4f5fbd4-nzm4j 1/1 Running 0 mediation-vcenterbrowsing-5c5987f66c-bfjq4 1/1 Running 0
```

Enabling/Disabling Probes

To enable or disable probes that you want in Workload Optimization Manager, you edit the cr.yaml file to add new probes and to change the values of the enabled: properties. Then you apply those changes to reload the platform components.

- 1. Log in to an SSH terminal session for your Workload Optimization Manager instance and display the list of available probes.
- 2. In the SSH session, open the cr.yaml file for editing. For example:

```
vi /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```

Edit the probe entries.

To enable or disable currently configured probes, find the probes to edit and change the settings to enable or disable them.

To add new probes to the list, copy the probe entry you want from the output when you used cat to view the available probes. Then paste that entry into the cr.yaml file and set enabled: true.

4. Save and apply your changes to the platform.

NOTE:

During the online or offline upgrade process, you should not use kubectl to apply these changes now.

After you save your changes, apply the changes:

```
kubectl apply -f \
/opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```

5. Verify that the probes have installed correctly and all the Workload Optimization Manager pods have started.



```
kubectl get pods -n turbonomic
```

Review the list for the mediation pods that implement your probes. All pods should display READY and STATUS states similar to:

```
NAME READY STATUS RESTARTS [...] 1/1 Running 0
```

6. View the new probe configuration in the user interface.

Refresh your browser and go to the Target Management page. You will now see the target categories and types to match your configuration changes.

(Optional) Disabling Component Health Monitoring

The Notification Center includes component health information to notify you of Workload Optimization Manager component issues and the steps you can take to resolve these issues. To open Notification Center, click the information icon on the main menu.

If you would rather use your own tools to monitor the Workload Optimization Manager component status, you can disable the feature in the CRD file.

To disable component health monitoring:

Open an SSH terminal session on your Workload Optimization Manager instance.

Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Username: [your_private_password]
- 2. Open the following cr.yaml file in a text editor:

/opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalpha1_xl_cr.yaml

3. Add the following to the CRD file:

```
properties:
    global:
     featureFlags:
        componentHealth: false
```

- 4. When you are done editing the cr.yaml file, save and apply your changes.
 - Save your changes and quit the text editor.
 - To apply the changes, run the following command in your SSH terminal session:

```
kubectl apply -f \
/opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```

5. Delete the api and Cluster Manager pods.

Deleting these pods triggers them to restart, which loads the changes you made.

- Close the Workload Optimization Manager UI if it is open in your browser.
- To get the full pod names, run the command:

```
kubectl get pods
```

Find the entries for the pods that begin with api and clustermgr. For example, assume that the entries are:

```
...
api-7df7b8c8c7-6rqgg
...
```



```
clustermgr-7c6579745d-m8dwc
```

. . .

Run the following command to delete the pods that use the api and clustermgr pod names:

```
kubectl delete pods api-7df7b8c8c7-6rqgg clustermgr-7c6579745d-m8dwc
```

NOTE:

The pod names change when deleted and started again so always get the latest pods before you run the delete command.

The pods are deleted and re-created.

6. Verify the deletion and recreation of the pods.

To verify that the pods are re-created and running, run the command:

```
kubectl get pods
```

After all of the pods start, the READY column should read 1/1, 2/2, and so on and the STATUS column should read Running for each pod.

The output is similar to the following example:

```
clustermgr-7c6579745d-m8dwc 1/1 Running 1 (2d16h ago) 3d15h api-7df7b8c8c7-6rqgg 1/1 Running 1 (2d16h ago) 3d15h
```

(Optional) Overriding Default Ports

MariaDB or MySQL database server uses port 3306 by default. Postgres database (for Embedded Reporting) uses port 5432 by default. Use the following sample configurations to override the default ports.

Sample configuration for MariaDB with IP address used for the database server with custom port (non-3306):

```
global:
```

```
repository: icr.io/cpopen/turbonomic
tag: 8.9.1
externalIP: 10.10.10.10
externalDbIP: 10.10.10.11
externalDbPort: 3307
```

Sample configuration for MariaDB with a fully qualified domain name used for the database server with custom port (non-3306):

global:

```
repository: icr.io/cpopen/turbonomic tag: 8.9.1 externalIP: 10.10.10.10 externalDBName: MyDatabaseServer.com externalDbPort: 3307
```

Sample configuration for Postgres database (for Embedded Reporting) with custom port (non-5432):

```
global:
```

```
repository: icr.io/cpopen/turbonomic tag: 8.9.1 externalDbIP: 10.10.10.30 externalTimescaleDBIP: 10.10.10.31
```



externalTimescaleDBPort: 5434

License Installation and First-time Login

Before you begin, make sure you have your full or trial license key file that was sent to you in a separate email. Save the license file on your local machine so you can upload it to your Workload Optimization Manager installation.

To use Workload Optimization Manager for the first time, perform the following steps:

- 1. Type the IP address of your installed Workload Optimization Manager instance in a Web browser to connect to it.
- 2. Log in to Workload Optimization Manager.
 - Use the default credential for USERNAME: administrator.
 - Type a password for **PASSWORD**.
 - Type the password again to verify it for **REPEAT PASSWORD**.
 - Click CONFIGURE.
- 3. Continue setting up your Workload Optimization Manager installation.

Click LET'S GO.

4. Open the Enter License fly-out.

Click IMPORT LICENSE.

- 5. Upload your license key file.
 - In the Enter License fly-out, you can upload the license in one of the following ways:
 - Drag and drop the license key file into the Enter License fly-out.
 - Browse to the license key file.

Be sure to upload only .xml, .lic, or .jwt files.

b. Click SAVE.

Single Sign-On Authentication

If your company policy supports Single Sign-On (SSO) authentication, you can configure Workload Optimization Manager to support SSO authentication via either Security Assertion Markup Language (SAML) 2.0 or OpenID Connect 1.0.

At a high-level, to do this you will:

- Create external groups or at least one external user for SSO. See Managing User Accounts (on page 723).
- Configure Workload Optimization Manager to use SSO authentication.

You will configure one of:

- SSO via a SAML Identity Provider (IdP). See Setting Up SAML Authentication (on page 74).
- SSO via an OpenID Identity Provider. See Setting Up OpenID Authentication (on page 77).

This section describes how to configure Workload Optimization Manager to use either SAML or OpenID to support SSO.

When SSO is enabled, users will provide their SSO credentials to log in to the Workload Optimization Manager instance. Once SSO is enabled, users cannot give local or Active Directory (AD) credentials for to login. The Identity Provider (IdP) will perform the authentication.

Prerequisites

Before you begin, make sure the IdP is set up for SSO. You can use a proprietary or public IdP. For examples of settings for a public Okta IdP, see What Are the Typical Settings for an IdP? (on page 90).



Setting Up SAML Authentication

Security Assertion Markup Language (SAML) is an XML-based open standard for exchanging authentication and authorization data between parties. To configure Workload Optimization Manager to authenticate via SAML:

1. (Required) Create external groups or at least one external user for SSO.

IMPORTANT:

When SSO is enabled, Workload Optimization Manager only permits logins via the SSO IdP. Whenever you navigate to your Workload Optimization Manager installation, it redirects you to the SSO Identity Provider (IdP) for authentication before displaying the Workload Optimization Manager user interface.

Before you enable SSO for your Workload Optimization Manager installation, you must configure at least one SSO user with Workload Optimization Manager administrator privileges. If you do not, then once you enable SSO you will not be able to configure any SSO users in Workload Optimization Manager. To authorize an SSO user as an administrator, use **EXTERNAL AUTHENTICATION** to do one of the following:

■ Configure a single SSO user with administrator authorization.

Add an external user. The username must match an account that is managed by the IdP.

Configure an SSO user group with administrator authorization.

Add an external group. The group name must match a user group on the IdP, and that group must have at least one member.

For information about creating external groups or external users for SSO, see Managing User Accounts (on page 723).

(Required) Ensure that chrony is configured and the system time on your Workload Optimization Manager instance is correct.

For instructions, see Synchronizing Time (on page 46).

3. Obtain the metadata from your IdP.

You will use this metadata to configure SSO in the Workload Optimization Manager CR file located at:

/opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml

To get the metadata:

- a. Contact your security administrator to obtain the metadata from IdP.
- b. Save the metadata file in a directory on your local machine.

```
/tmp/MySamlMetadata.txt
```

c. Compare your metadata to the sample provided in <u>Example of IdP Metadata (on page 76).</u>

Cat out the file you just saved. It should be similar to the provided sample.

4. Obtain a certificate from IdP.

Contact your security administrator to obtain a certificate from IdP.

Update the CR file with your SAML configuration.

You now have the data that you need to configure SSO via SAML. You will edit the cr.yaml file that configures your Workload Optimization Manager node, and then deploy or restart the node.

Display the contents of your downloaded SAML metadata.

For example, assuming you saved the file to this location on your local machine, run the command:

```
cat /tmp/MySamlMetadata.txt
```

Open the CR file for editing.

In a shell, cd to the deploy/crds directory in the Workload Optimization Manager VM:

```
cd /opt/turbonomic/kubernetes/operator/deploy/crds
```

Then open the CR file for editing. For example, to open the file in VI:



```
vi charts_vlalphal_xl_cr.yaml
```

As you edit this file, you will refer to the metadata that you obtained from your IdP.

■ In the CR file, navigate to the entry for the API component.

In the CR file search for or scroll to the entry:

```
apiVersion: charts.helm.k8s.io/v1alpha1
```

You will make changes to this component spec, under spec:properties:api:

■ Turn on the SAML feature.

For the first API property, set the following:

```
samlEnabled: true
```

Set the SSO endpoint.

In the SAML metadata, find the entry for md:SingleSignOnService. Within that element, find the Location attribute. The value of Location is the SSO endpoint. Using the sample metadata we have provided, you would make the following setting in your CR file:

```
samlWebSsoEndpoint: https://dev-771202.oktapreview.com/app/ibmdev771202_turbo2_1/exkexl6xc9Mhzqi
C30h7/sso/saml
```

Set the SAML entity ID.

In the SAML metadata, find the entry for md: EntityDescriptor. Within that element, find the entityID attribute. Using the sample metadata we have provided, you would make the following setting in your CR file:

```
samlEntityId: http://www.okta.com/exkexl6xc9MhzqiC30h7
```

Set the SAML registration.

Set the following property:

```
samlRegistrationId: simplesamlphp
```

■ Set the SAML SP entity ID

Set the following property:

```
samlSpEntityId: turbo
```

■ Enter the SAML certificate.

In the metadata that you got from your IdP, find the entry for <ds:X509Certificate>. Copy the contents of this tag - copy the characters that are between <ds:X509Certificate> and </ds:X509Certificate>.

Create an entry for the certificate in the API properties section of the CR file. On a new line, enter:

```
samlIdpCertificate: |
```

Then open a new line after the entry you just created, and paste the certificate content that you copied from your metadata file.

The finished API section of the CR file is similar to the following example:

```
apiVersion: charts.helm.k8s.io/vlalpha1
kind: X1
metadata:
  name: x1-release
spec:
  properties:
   api:
    samlEnabled: true
```



samlWebSsoEndpoint: https://dev-771202.oktapreview.com/app/ibmdev771202_turbo2_1/exkex16xc9Mhz giC30h7/sso/saml samlEntityId: http://www.okta.com/exkfdsn6oy5xywqCO0h7

samlRegistrationId: simplesamlphp samlSpEntityId: turbo samlIdpCertificate: | ----BEGIN CERTIFICATE----

MIIDpDCCAoygAwIBAgIGAWMnhv7cMA0GCSqGSIb3DQEBCwUAMIGSMQswCQYDVQQGEwJVUzETMBEG A1UECAwKQ2FsaWZvcm5pYTEWMBQGA1UEBwwNU2FuIEZyYW5jaXNjbzENMAsGA1UECgwET2t0YTEU MBIGA1UECwwLU1NPUHJvdmlkZXIxEzARBgNVBAMMCmRldi03NzEyMDIxHDAaBgkqhkiG9w0BCQEW DWluZm9Ab2t0YS5jb20wHhcNMTqwNTAzMTk0MTI4WhcNMjqwNTAzMTk0MjI4WjCBkjELMAkGA1UE BhMCVVMxEzARBgNVBAgMCkNhbGlmb3JuaWExFjAUBgNVBAcMDVNhbiBGcmFuY21zY28xDTALBgNV ${\tt BAoMBE9rdGExFDASBgNVBAsMC1NTT1Byb3ZpZGVyMRMwEQYDVQQDDApkZXYtNzcxMjAyMRwwGgYJ}$ KoZIhvcNAQkBFg1pbmZvQG9rdGEuY29tMIIBIjANBgkqhkiG9w0BAQEFAAOCAQ8AMIIBCgKCAQEA ugxQGqHAXpjVQZwsO9n818bFCoEevH3AZbz7568XuQm6MK6h7/O9wB4C5oUYddemt5t2Kc8GRhf3 BDXX5MVZ8G9AUpG1MSqe1CLV2J96rMnwMIJsKeRXr01LYxv/J4kjnktpOC389wmcy2fE4RbPoJne P4u2b32c2/V7xsJ7UEjPPSD4i8l2QG6qsUkkx3AyNsjo89PekMfm+Iu/dFKXkdjwXZXPxaL0HrNW PTpzek8NS5M5rvF8yaD+eE1zS0I/HicHbPOVvLal0JZyN/f4bp0XJkxZJz6jF5DvBkwIs8/Lz5GK nn4XW9Cqjk3equSCJPo5o1Msj8v1LrJYVarqhwIDAQABMA0GCSqGSIb3DQEBCwUAA4IBAQC26kYe LgqjIkF5rvxB2QzTgcd0LVzXOuiVVTZr8Sh57l4jJqbDoIgvaQQrxRSQzD/X+hcmhuwdp9s8zPHS JagtUJXiypwNtrzbf6M7ltrWB9sdNrqc99d1gOVRr0Kt5pLTaLe5kkq7dRaQoOIVIJhX9wgynaAK HF/SL3mHUytjXggs88AAQa8JH9hEpwG2srN8EsizX6xwQ/p92hM2oLvK5CSMwTx4VBuGod70EOwp $6 \\ TaluRLQh6 \\ jCCOCWRuZbbz2T3/sOX+sibC4rLIlwfyTkcUopF/bTSdWwknoRskK4dBekFcvN9N+COMPACTED \\ for the first of the following properties of th$ p/qaHYcQd6i2vyor888DLHDPXhSKWhpG

- ----END CERTIFICATE---
- Save your changes to the CR file. Apply the modified cr.yaml file.

Execute the command:

7.

kubectl apply -f /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml

- 8. Restart the API component to load the new spec.
 - Open an SSH terminal session to your Workload Optimization Manager instance.
 - Restart the API component.

```
kubectl delete pod api-<API_POD_ID>
```

To auto-fill the pod ID, type api- and then press TAB.

- Verify that the configuration is successful. 9.
 - a. Navigate to the Workload Optimization Manager User Interface.

You will be automatically redirected to your IdP for authentication.

- Log in with the username that is a member of the external group or external user that you previously configured.
- Verify that the system time on your Workload Optimization Manager instance is correct.
 - If the time is not synchronized, this might cause an HTTP Status 401 -authentication failed exception in the browser.
- If the configuration is not successful, look for an HTTP Status 500 exception in the product log. If this exception exists, review your CR file for invalid entries.

Example of IdP Metadata

This section provides an example of IdP metadata which may be useful when you are examining the optional attributes in your metadata.



If your metadata includes optional attribute tags that are not listed in the example, remove those optional attribute tags since they are not supported.

```
<?xml version="1.0" encoding="UTF-8"?>
         <md:EntityDescriptor xmlns:md="urn:oasis:names:tc:SAML:2.0:metadata"</pre>
         entityID="http://www.okta.com/exkex16xc9MhzqiC30h7">
         <md:IDPSSODescriptor WantAuthnRequestsSigned="false"</pre>
         protocolSupportEnumeration="urn:oasis:names:tc:SAML:2.0:protocol">
         <md:KeyDescriptor use="signing">
         <ds:KeyInfo xmlns:ds="http://www.w3.org/2000/09/xmldsig#">
         <ds:X509Data>
         <ds:X509Certificate>
         MIIDpDCCAoygAwIBAgIGAWMnhv7cMA0GCSqGSIb3DQEBCwUAMIGSMQswCQYDVQQGEwJVUzETMBEG
         A1UECAwKQ2FsaWZvcm5pYTEWMBQGA1UEBwwNU2FuIEZyYW5jaXNjbzENMAsGA1UECqwET2t0YTEU
         MBIGA1UECwwLU1NPUHJvdmlkZXIxEzARBqNVBAMMCmRldi03NzEyMDIxHDAaBqkqhkiG9w0BCQEW
         DWluZm9Ab2t0YS5jb20wHhcNMTgwNTAzMTk0MTI4WhcNMjgwNTAzMTk0Mj14WjCBkjELMAkGA1UE
         BhMCVVMxEzARBgNVBAgMCkNhbGlmb3JuaWExFjAUBgNVBAcMDVNhbiBGcmFuY21zY28xDTALBgNV
         BAOMBE9rdGExFDASBgNVBAsMC1NTT1Byb3ZpZGVyMRMwEQYDVQQDDApkZXYtNzcxMjAyMRwwGgYJ
         KoZIhvcNAQkBFg1pbmZvQG9rdGEuY29tMIIBIjANBgkqhkiG9w0BAQEFAAOCAQ8AMIIBCgKCAQEA
         ugxQGqHAXpjVQZwsO9n818bFCoEevH3AZbz7568XuQm6MK6h7/O9wB4C5oUYddemt5t2Kc8GRhf3
         BDXX5MVZ8G9AUpG1MSqe1CLV2J96rMnwMIJsKeRXr01LYxv/J4kjnktpOC389wmcy2fE4RbPoJne
         P4u2b32c2/V7xsJ7UEjPPSD4i8l2QG6qsUkkx3AyNsjo89PekMfm+Iu/dFKXkdjwXZXPxaL0HrNW
         PTpzek8NS5M5rvF8yaD+eE1zS0I/HicHbPOVvLal0JZyN/f4bp0XJkxZJz6jF5DvBkwIs8/Lz5GK
         nn4XW9Cqjk3equSCJPo5o1Msj8v1LrJYVarqhwIDAQABMA0GCSqGSIb3DQEBCwUAA4IBAQC26kYe
         LqqjIkF5rvxB2QzTqcd0LVzXOuiVVTZr8Sh5714jJqbDoIqvaQQrxRSQzD/X+hcmhuwdp9s8zPHS
         JagtUJXiypwNtrzbf6M7ltrWB9sdNrqc99d1gOVRr0Kt5pLTaLe5kkq7dRaQoOIVIJhX9wgynaAK
         HF/SL3mHUytjXggs88AAQa8JH9hEpwG2srN8EsizX6xwQ/p92hM2oLvK5CSMwTx4VBuGod70EOwp
         6TaluRLQh6jCCOCWRuZbbz2T3/sOX+sibC4rLIlwfyTkcUopF/bTSdWwknoRskK4dBekFcvN9N+C
         p/qaHYcQd6i2vyor888DLHDPXhSKWhpG
         </ds:X509Certificate>
         </ds:X509Data>
         </ds:KeyInfo>
         </md:KeyDescriptor>
         <md:NameIDFormat>urn:oasis:names:tc:SAML:1.1:nameid-format:unspecified</md:NameIDFormat>
         <md:NameIDFormat>urn:oasis:names:tc:SAML:1.1:nameid-format:emailAddress</md:NameIDFormat>
         <md:SingleSignOnService Binding="urn:oasis:names:tc:SAML:2.0:bindings:HTTP-POST"</pre>
         Location="https://dev-771202.oktapreview.com/app/ibmdev771202_turbo2_1/exkex16xc9MhzqiC30h7/sso/
saml"/>
         <md:SingleSignOnService Binding="urn:oasis:names:tc:SAML:2.0:bindings:HTTP-Redirect"</pre>
         Location="https://dev-771202.oktapreview.com/app/ibmdev771202_turbo2_1/exkex16xc9MhzqiC30h7/sso/
saml"/>
         </md:IDPSSODescriptor>
         </md:EntityDescriptor>
```

Setting Up OpenID Authentication

According to the OpenID Foundation, "OpenID Connect 1.0 is a simple identity layer on top of the OAuth 2.0 protocol". OpenID Connect enables clients to verify user identity via a given authentication server. Workload Optimization Manager supports OpenID authentication through the following providers:

- Google
- IBM-MCM
- Okta



Logging in to Workload Optimization Manager with OpenID

When you configure OpenID in Workload Optimization Manager, the platform registers the OpenID clients that you specify. To log in through of these OpenID clients, you manually navigate to a URL that tells Workload Optimization Manager which client to use. It then redirects to the OpenID login screen for that given client.

The URL that you provide is in the form:

https://<hostname>/vmturbo/oauth2/login/code/<openIdClients>

Where:

- <hostname> is the host address for your installation of Workload Optimization Manager
- <openIdClients> is the is the client name of the OpenID provider you want to use
 You specify this as the openIdClients property when you configure OpenID in Workload Optimization Manager.

NOTE:

This URL must also be set in the Authorized direct URIs section of your provider's OpenID configuration.

For example, assume your Workload Optimization Manager host address is 10.10.12.34, and you configured an Okta OpenID client. In that case, when the Workload Optimization Manager login screen appears, you would navigate to:

```
https://10.10.12.34/vmturbo/oauth2/login/code/okta
```

After you navigate to that URL, the browser redirects to the OpenID login screen, where you can enter credentials for a single user or a user group.

NOTE:

To authenticate a user group, the group must be configured on the OpenID provider, and also on Workload Optimization Manager. The group name must be identical in both configurations.

On the OpenID provider, the client that you are using should include groups scope values that give specific names for user groups. Contact your OpenID administrator to get the group names. Then, on Workload Optimization Manager you should create user groups that use the same names.

For example, assume the OpenID ID token includes the following groups claim:

```
{
   "sub": "1234567890",
   "name": "My_User_Name",
   "iat": "12121212",
   "groups": "My_Special_User_Group"
}
```

To use the group My_Special_User_Group for authentication, you must create a user group in Workload Optimization Manager with the name My_Special_User_Group. Any members of that group will then get the role you have assigned to that user group.

Configuring OpenID on Workload Optimization Manager

To configure Workload Optimization Manager to authenticate via OpenID:

 (Required) Ensure that chrony is configured and the system time on your Workload Optimization Manager instance is correct.

For instructions, see Synchronizing Time (on page 46).

2. Obtain the necessary data from your OpenID provider.

Contact your security administrator to obtain the data from the provider. You will use this data to configure SSO in the Workload Optimization Manager CR file located at:

/opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml



The data you need and the properties you declare in the CR file will differ depending on the OpenID provider you want to use:

■ Google:

CR Fields:	Description:
openIdClients	google
	The name of the OpenID client you are using to perform authentication.
openIdClientId	The OAuth2 Client Identifier for the OpenID client that you are using.
openIdClientSecret	The OAuth2 Client Secret for the OpenID client that you are using.

■ IBM-MCM:

CR Fields:	Description:	
openIdClients	ibm	
	The name of the OpenID client you are using to perform authentication.	
openIdClientAuthentication	post	
	The client authentication method.	
openIdUserAuthentication	form	
	The user authentication method.	
openIdClientId	The OAuth2 Client Identifier for the OpenID client that you are using.	
openIdClientSecret	The OAuth2 Client Secret for the OpenID client that you are using.	
openIdAccessTokenUri	The URI the login process will use to get an Access Token.	
openIdUserAuthorizationUri	The URI to the Authorization Endpoint for OpenID Connect.	
openIdUserInfoUri	The URI to the OpenID Connect UserInfo endpoint.	
openIdJwkSetUri	The URI to get the JSON Web Key set that can verify the Access Token.	
openIdExternalGroupTag	The name of a custom group to use for authentication.	

Okta:

CR Fields:	Description:
openIdClients	okta
	The name of the OpenID client you are using to perform authentication.
openIdClientId	The OAuth2 Client Identifier for the OpenID client that you are using.
openIdClientSecret	The OAuth2 Client Secret for the OpenID client that you are using.
openIdAccessTokenUri	The URI the login process will use to get an Access Token.
openIdUserAuthorizationUri	The URI to the Authorization Endpoint for OpenID Connect.
openIdUserInfoUri	The URI to the OpenID Connect UserInfo endpoint.
openIdJwkSetUri	The URI to get the JSON Web Key set that can verify the Access Token.

3. Update the Workload Optimization Manager CR file with your configuration data.

You now have the data that you need to configure SSO via OpenID. You will edit the ${\tt cr.yaml}$ file that configures your Workload Optimization Manager node, and then deploy or restart the node.

Open the CR file for editing.



cd /opt/turbonomic/kubernetes/operator/deploy/crds

Then open the CR file for editing. For example, to open the file in VI:

```
vi charts_vlalphal_xl_cr.yaml
```

As you edit this file, you will refer to the data that you obtained from your authentication provider.

■ In the CR file, navigate to the entry for the API component.

In the CR file search for or scroll to the entry:

```
apiVersion: charts.helm.k8s.io/vlalpha1
```

You will make changes to this component spec, under spec:properties:api:

■ Turn on the OpenID feature.

For the first API property, set the following:

```
openIdEnabled: true
```

The output is similar to the following example:

```
apiVersion: charts.helm.k8s.io/vlalpha1
kind: Xl
metadata:
  name: xl-release
spec:
  properties:
   api:
    openIdEnabled: true
```

- Enter the relevant OpenId data for your authentication provider. The CR file should be similar to these examples, depending on which provider you use.
 - Google:

```
apiVersion: charts.helm.k8s.io/vlalpha1
kind: Xl
metadata:
  name: xl-release
spec:
  properties:
    api:
        openIdEnabled: true
        openIdClients: google
        openIdClientId: xxxx-4vinrdgllag5p84jjebc6xxxxxxx5u.apps.googleusercontent.com
        openIdClientSecret: xxxxxhGcdFEjQa-xxxxxxxxx
```

- IBM-MCM:

```
apiVersion: charts.helm.k8s.io/vlalphal
kind: Xl
metadata:
  name: xl-release
spec:
  properties:
  api:
    openIdEnabled: true
```



```
openIdClients: ibm
  openIdClientAuthentication: post
  openIdUserAuthentication: form
  openIdClientId: turbonomic-mcm-demo
  openIdClientSecret: "xxxxxxvZ2ZscDhtOFVxxxxxxxU3d6cXR4cTZhb2xxxxxxRTOK"
    openIdAccessTokenUri: https://icp-console.apps.blue-13.dev.multicloudops.io/idprovider/
v1/auth/token
    openIdUserAuthorizationUri: https://icp-console.apps.blue-13.dev.multicloudops.io/idprovider/v1/auth/authorize
    openIdUserInfoUri: https://icp-console.apps.blue-13.dev.multicloudops.io/v1/auth/userI
nfo
    openIdJwkSetUri: https://icp-console.apps.blue-13.dev.multicloudops.io/oidc/endpoint/OP/
jwk
```

Okta

```
apiVersion: charts.helm.k8s.io/vlalpha1
kind: X1
metadata:
  name: xl-release
spec:
  properties:
  api:
    openIdEnabled: true
    openIdClients: okta
    openIdClientId: xxxxxxxxxhlxhQnSKxxxx
    openIdClientSecret: xxxxxxxxxtlhVCIRUnhq4xxxxxxxDdhLdqx0
    openIdAccessTokenUri: https://vmturbo.okta.com/oauth2/v1/token
    openIdUserInfoUri: https://vmturbo.okta.com/oauth2/v1/authorize
    openIdJwkSetUri: https://vmturbo.okta.com/oauth2/v1/userinfo
    openIdJwkSetUri: https://vmturbo.okta.com/oauth2/v1/keys
```

- 4. Save your changes to the CR file.
- 5. Apply the modified cr.yaml file.

kubectl apply -f /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml

- 6. Restart the API component to load the new spec.
 - a. Open an SSH terminal session to your Workload Optimization Manager instance.
 - b. Restart the API component.

```
kubectl delete pod api-<API_POD_ID>
```

To auto-fill the pod ID, type api- and then press TAB.

- 7. Verify that the configuration is successful.
 - a. Navigate to the Workload Optimization Manager User Interface.

You will be automatically redirected to your authentication provider for authentication.

- b. Log in with the username that is a member of the external group or external user that you previously configured.
- c. Verify that the system time on your Workload Optimization Manager instance is correct.
 - If the time is not synchronized, this might cause an ${\tt HTTP}$ Status 401 -authentication failed exception in the browser.
- d. If the configuration is not successful, look for an HTTP Status 500 exception in the product log. If this exception exists, review your CR file for invalid entries.



Disabling Single Sign-On

If for some reason you no longer want to use SSO, you can disable it for your Workload Optimization Manager installation. To disable Single Sign-On, perform these steps:

- 1. Update the SSO configuration to disable it.
 - a. Open an SSH terminal session to your Workload Optimization Manager instance.
 - b. Open the CR file for editing.

In a shell, cd to the deploy/crds directory in the Workload Optimization Manager VM:

```
cd /opt/turbonomic/kubernetes/operator/deploy/crds
```

Then open the CR file for editing. For example, to open the file in VI:

```
vi charts_vlalpha1_xl_cr.yaml
```

c. In the CR file, navigate to the entry for the API component.

In the CR file search for or scroll to the entry:

```
apiVersion: charts.helm.k8s.io/vlalpha1
```

You will make changes to this component spec, under spec:properties:api:

Turn off the SSO feature.

The entry to set to false is different depending on whether you use SAML or OpenID authentication:

SAML Authentication:

Find the samlEnabled: property to false. It should appear as follows:

```
samlEnabled: false
```

OpenID Authentication:

Find the openIdEnabled: property to false. It should appear as follows:

```
openIdEnabled: false
```

- e. Save your changes to the CR file.
- 2. Apply the modified cr.yaml file.

```
kubectl apply -f /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```

3. Restart the API component.

In the same SSH terminal session that you opened to edit the CR file:

a. Use sudo as root.

```
sudo bash
```

Restart your API component.

```
kubectl delete pod api-<API_POD_ID>
```

NOTE:

To auto-fill the pod ID, type api- and then press TAB.

- 4. Verify that the configuration is successful.
 - a. Navigate to the Workload Optimization Manager User Interface.

You will no longer be redirected to your IdP for authentication. You will be redirected to the default Workload Optimization Manager login screen.

Log in with a local account or an Active Directory (AD) account.



Updating Workload Optimization Manager to a New Version

When a new version is available, it is important to properly update your existing installed instance. When you first installed Workload Optimization Manager, you put into place sophisticated data collection and analysis processes, and your database retains performance data from across your virtual environment. Workload Optimization Manager uses this historical data for right-sizing, projecting trends, and other analysis. This means that the database is important to Workload Optimization Manager and becomes more so over time. Properly updating your installation of Workload Optimization Manager preserves the database for continued use.

OVA updates

Before you begin the update procedure:

Review What's New (on page 21) and Release Notes (on page 20) to see what is new for this release.

NOTE:

As Workload Optimization Manager evolves, the set of delivered probes change. Also, from one version to the next, the set of probes that are enabled by default can change. When you update to a new version, the update does not change your probe configuration. An update to a newer version does not automatically enable any new probes in your deployment. If you want to take advantage of new probes in an update, then you must enable them manually.

- Make sure you have the email that Cisco sent to you with links to the Workload Optimization Manager OVA file and to the ISO image.
- For on-prem installations, make sure that the physical machine hosting the VM meets the minimum requirements (see Minimum Requirements (on page 38)).
- Ensure you are running the correct version of the historical database.

For its default historical database, Workload Optimization Manager currently supports MariaDB version 10.5.20. This support includes comprehensive testing and quality control for Workload Optimization Manager usage of the historical database

For more information, see Verifying your MariaDB Version (on page 48).

■ Execute the upgrade-precheck.sh script.

You can use this script to make sure that your current installation of Workload Optimization Manager is ready to update. We strongly recommend that you run this script before going on to update your installation (see Checking Before Updating (on page 83))

Execute an offline update, via a downloaded ISO image (see Offline Update (on page 87)).

Checking Before Updating

Before you perform an update of your Workload Optimization Manager instance, you should execute the script, upgrade-precheck.sh. This script inspects your installation to check for the following:

- Sufficient free disk space
- For online updates, access to required endpoints (icr.io, github.com, etc.)
- The MariaDB service is running

Note that this check is for the default installation of the MariaDB service, only. For example, the script does not check an external installation of MySQL or MariaDB, if that is the historical database you have configured. In that case, the script will indicate that your MariaDB service is not running. For an external database deployment, this is a normal result.

- The Kubernetes service is running
- The necessary Kubernetes certificates are valid

If the certificates are not valid, you can run the kubeNodeCertUpdate.sh script to correct the issue. This script should be located on your installation at /opt/local/bin. For more information, contact your support representative.

- Root password is not set to expire
- Time sync is enabled, and current if running



All Workload Optimization Manager pods are running

To execute this script:

- 1. Download the latest version of the script.
 - a. Log in to the Workload Optimization Manager VM.

Use SSH to log in to the Workload Optimization Manager VM using the turbo account and password.

b. Change to the scripts directory.

```
cd /opt/local/bin
```

- c. Get the latest version of the script.
 - i. Navigate to the following Cisco web page:

https://software.cisco.com/download/home/286328879/type.

- ii. Under Select a Software Type, click Workload Optimization Manager.
- iii. From the menu on the left, select the desired Workload Optimization Manager version.
- iv. Click the download button for the following file:

```
upgrade-precheck-X.X.X.zip
```

- v. When prompted, login using your Cisco account.
- vi. After the download completes, unzip the downloaded file.
- d. Make the script executable.

```
chmod +x upgrade-precheck.sh
```

2. Run the script.

```
./upgrade-precheck.sh
```

As the script executes, it identifies any issues that you should address before you run an update.

External DBs and Workload Optimization Manager Updates

If you have deployed Workload Optimization Manager with an external database server, for some updates you might need to manually create a new database and user for that deployment. This is important if your external database server is multi-tenant, or if your deployment does not grant administrative privileges to Workload Optimization Manager.

NOTE:

If your external database server is multi-tenant, or if your database server does not grant administrative privileges to Workload Optimization Manager, then you must continue with this configuration requirement.

Azure database services are multi-tenant. If you deployed an external database on Azure, this configuration requirement applies to you.

If you deployed your database server in a way that grants Workload Optimization Manager privileges to create new databases and new users, then a product update will automatically create the required database. This configuration requirement does not apply to you and you do not need to take any action.

For some Workload Optimization Manager updates, the updated version includes new databases on the historical database server. If you are updating to one of these versions, then you must *first* create the new database, and a user account with privileges to access that database.

This table lists the Workload Optimization Manager versions that required new databases. If you are updating from a version earlier than one of these, you must create the indicated new databases. For example, if you are updating from version 3.0.1 to 3.0.5, then you must create the api database.



Workload Optimization Manager Version	New Databases	Notes
3.0.5	api	If you are updating from a version earlier than 3.0.5, you must create a new database named api, and a user account named api.

NOTE:

If you have already updated to one of these versions of Workload Optimization Manager, and you did not perform the steps to update your external DB, please contact your support representative.

To create the databases and users, you will:

- Manually create each required database
 - This includes creating the database in your DB instance, creating a user to access the database, and granting privileges to the user.
- Manually add the each required database to your cr.yaml file
 - The cr.yaml file declares entries for each component database. Each entry names the component, and gives the user and password that the component can use to access that database. You must add a new entry for each new database.

To create a new database:

- Connect to your external DB using a global account.
 - The account must have privileges to create databases and users. If you have specified dbRootUsername in the cr.yaml file, you can use that account.
- 2. Create the database, where <New_Database > matches the database name in the table above:

```
create database <New_Database>;
```

For example, to create a new api database, execute:

```
create database api;
```

Create the account that Workload Optimization Manager will use to access the database where <New_Database>
matches the database name in the table above:

```
create user '<New_Database>'@'%' identified by 'vmturbo';
```

For example, to create a user for the api database, execute:

```
create user 'api'@'%' identified by 'vmturbo';
```

NOTE:

The value vmturbo is the default password that Workload Optimization Manager uses for all component database accounts. If you have manually created accounts with different credentials, you can do so for this database as well.

4. Set the user account privileges for the new user account, where <New_Database> matches the database name in the table above:

```
GRANT SELECT, INSERT, UPDATE, DELETE, CREATE, DROP, REFERENCES, INDEX, ALTER, CREATE TEMPORARY T
ABLES, LOCK TABLES, EXECUTE, CREATE VIEW, SHOW VIEW, CREATE ROUTINE, ALTER ROUTINE, EVENT, TRIGGER
ON <New_Database>.* TO '<New_Database>'@'%';
```

For example, to set account privileges for the api user, execute:

GRANT SELECT, INSERT, UPDATE, DELETE, CREATE, DROP, REFERENCES, INDEX, ALTER, CREATE TEMPORARY TABLES, LOCK TABLES, EXECUTE, CREATE VIEW, SHOW VIEW, CREATE ROUTINE, ALTER ROUTINE, EVENT, TRIGGER ON api.*

TO 'api'@'%';



5. Flush privileges to make the privileges take effect.

```
flush privileges;
```

Now that the new database is created in your external DB service, you must declare access to it the Workload Optimization Manager cr.yaml resource.

Open the .cr file for editing. The location of the file depends on the type of Workload Optimization Manager installation you
are configuring.

VM Image installation of Workload Optimization Manager	Workload Optimization Manager on a Kubernetes node or node cluster
Open a SSH terminal session on your Workload Optimization Manager instance	Open the following file for editing:
Log in with the System Administrator that you set up when you installed Workload Optimization Manager:	deploy/crds/charts_vlalpha1_xl_cr.yaml
■ Username: turbo	
<pre>Password: [your_private_password]</pre>	
Then edit the file:	
<pre>/opt/turbonomic/kubernetes/operator/deploy/crd s/charts_vlalphal_xl_cr.yaml</pre>	

Add the credentials for the matching pod to access the new database.

Add the entry to the properties: section of the cryaml file, where $<\!vmturbo>$ is the password that you assigned to that user account, $<\!yourDB>$ is the qualified name of your external DB or your multi-tenant DB partition, and $<\!New_Database>$ is the name of your new database. Declare the following in the entry you add:

```
<New_Database>:
    <New_Database>DbUsername: <New_Database>@<yourDB>
    <New_Database>DbPassword: <vmturbo>
```

For example, if you added the api database, the resulting cr.yaml file should be similar to:

```
properties:
    global:
      enableSecureDBConnection: true
      sqlDialect: MYSQL
      dbRootPassword: yourAdminPassword
      dbRootUsername: xladmin@yourDB
      #dbUserPassword:
      #dbUsername:
    action-orchestrator:
      actionDbUsername: action@yourDB
      actionDbPassword: yourPassword
    auth:
      authDbUsername: auth@yourDB
      authDbPassword: yourPassword
    clustermgr:
      clustermgrDbUsername: clustermgr@yourDB
      clustermgrDbPassword: yourPassword
    cost:
      costDbUsername: cost@yourDB
      costDbPassword: yourPassword
      groupComponentDbUsername: group_component@yourDB
```



```
groupComponentDbPassword: yourPassword
history:
 historyDbUsername: history@yourDB
 historyDbPassword: yourPassword
plan-orchestrator:
  planDbUsername: plan@yourDB
  planDbPassword: yourPassword
topology-processor:
  topologyProcessorDbUsername: topology_processor@yourDB
  topologyProcessorDbPassword: yourPassword
repository:
  repositoryDbUsername: repository@yourDB
  repositoryDbPassword: yourPassword
  marketDbUsername: market@yourDB
  marketDbPassword: yourPassword
api:
  apiDbUsername: api@yourDB
  apiDbPassword: yourPassword
```

After you have done this, you can update to the latest version of Workload Optimization Manager.

NOTE:

Upgrading applies changes to the version information in this file.

Offline Update

To perform an offline update of your Workload Optimization Manager installation:

1. Save a snapshot of your current Workload Optimization Manager VM.

Before updating, shut down (not power off) the Workload Optimization Manager VM.

```
sudo init 0
```

Then, perform a snapshot (or clone the VM). This provides a reliable restore point you can turn to in the event that trouble occurs during the update. After you have the snapshot, bring the VM back online.

2. Optionally, enable new probes in your environment.

NOTE:

As Workload Optimization Manager evolves, the set of delivered probes change. Also, from one version to the next, the set of probes that are enabled by default can change. When you update to a new version, the update does not change your probe configuration. An update to a newer version does not automatically enable any new probes in your deployment. If you want to take advantage of new probes in an update, then you must enable them manually.

For steps to enable new probes in your updated version, see <u>Enabling and Disabling Probe Components (on page 68)</u>. Use these steps to edit the platform's cr.yaml file.

NOTE:

During the online or offline upgrade process, you should not apply these changes at this time.

- 3. Download the ISO image.
 - a. Navigate to the following Cisco web page:
 - https://software.cisco.com/download/home/286328879/type.
 - b. Under Select a Software Type, click Workload Optimization Manager.
 - c. From the menu on the left, select the desired Workload Optimization Manager version.
 - d. Click the download button for update64_package-X.X.X.iso.
 - e. When prompted, login using your Cisco account.



4. Save the ISO image to a location that is available to the VM that runs Workload Optimization Manager. Then mount the image as a CD drive.

For example, if you run the Workload Optimization Manager VM in vCenter Server do the following:

- a. In vCenter, navigate to the Workload Optimization Manager VM.
- b. Right-click the VM and choose **Edit Settings**.
- c. In the CD/DVD Drive drop-down menu, select **Datastore ISO**, then browse to the Workload Optimization Manager update ISO image and choose it.
- d. Ensure that **Connect at power on** is selected.
- 5. Open an SSH terminal session to your Workload Optimization Manager instance.

After you make a snapshot or clone of your current Workload Optimization Manager VM, open an SSH session. Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Username: [your private password]
- 6. Get the isoUpdate.sh script for your update version.
 - a. Navigate to the following Cisco web page:

https://software.cisco.com/download/home/286328879/type.

- b. Under Select a Software Type, click Workload Optimization Manager.
- c. From the menu on the left, select the desired Workload Optimization Manager version.
- d. Click the download button for isoUpdate-X.X.X.zip.
- e. When prompted, login using your Cisco account.
- f. After the download completes, unzip the downloaded file.
- 7. Upload the script to your Workload Optimization Manager instance.

Execute a file transfer from your local machine to the Workload Optimization Manager server. Save the script to /opt/local/bin/ on the VM that runs Workload Optimization Manager.

8. Make the script executable.

chmod +x /opt/local/bin/isoUpdate.sh

9. Execute the offline installation.

/opt/local/bin/isoUpdate.sh

As the script executes, it:

- Backs up the old scripts in your installation.
- Updates the configuration and code assets in your installation.
- Updates the platform to the new version.
- Updates custom resources.
- Updates the MariaDB configuration (but this does not update the MariaDB version).
- If you have enabled Embedded Reports or Data Export, installs the Embedded Reports and Data Export database (Postgres and TimescaleDB).
- Scales down the t8c-operator and the Workload Optimization Manager components.
- Executes the final updates for this version.
- Scales up the t8c-operator, which then restarts the Workload Optimization Manager components.

After the script is finished updating your platform, you should give it enough time for all the components to start up again.

10. Verify that the Workload Optimization Manager application installed correctly.

```
kubectl get pods -n turbonomic
```

After all of the pods start, the READY column should read 1/1, 2/2, and so on and the STATUS column should read Running for each pod.

The output is similar to the following example:



NAME	READY	STATUS	RESTARTS
action-orchestrator-b6454c9c8-mf185	1/1	Running	0
api-7887c66f4b-shndq	1/1	Running	0
arangodb-7f646fc5fc-zhcwf	1/1	Running	0
auth-5b86976bc8-vxwz4	1/1	Running	0
clustermgr-85548678d9-r5wb8	1/1	Running	0
consul-7f684d8cb8-6r677	1/1	Running	0
cost-5f46dd66c4-6d6cb	1/1	Running	0
extractor-5f41dd61c4-4d61q	1/1	Running	0
group-5bfdfbc6f8-96bsp	1/1	Running	0
history-5fc7fbc855-6zslq	1/1	Running	0
kafka-74cc77db94-dfrbl	1/1	Running	0
market-5f54699447-z4wkm	1/1	Running	0
mediation-actionscript-57b4fc6df-4lzfv	1/1	Running	0
mediation-appdynamics-6d65f8766f-kb441	1/1	Running	0
mediation-hpe3par-d7c475c4c-v8ftc	1/1	Running	0
mediation-hyperv-6bd8c94df5-4dbzx	1/1	Running	0
mediation-netapp-7f8fc955d9-4kkdl	1/1	Running	0
mediation-oneview-7dbd7b54cf-7rfqp	1/1	Running	0
mediation-pure-58c4bd8cd9-8n256	1/1	Running	0
mediation-ucs-6f4bb9889-9rnqk	1/1	Running	0
mediation-vcenter-5bc4f5fbd4-nzm4j	1/1	Running	0
mediation-vcenterbrowsing-5c5987f66c-bfjq4	1/1	Running	0
mediation-vmax-6c59969b89-28t9j	1/1	Running	0
mediation-vmm-9c4878cf9-rfxnl	1/1	Running	0
nginx-5b775f498-sm2mm	1/1	Running	0
plan-orchestrator-6dffc4c9b6-p5t5n	1/1	Running	0
reporting-b44fbdfb4-8fjv5	1/1	Running	0
repository-6d555bb4bf-fxldh	1/1	Running	0
rsyslog-fd694878c-5tb2c	1/1	Running	0
t8c-operator-558bcc758d-5h8mp	1/1	Running	0
topology-processor-b646b786b-9skp7	1/1	Running	0
zookeeper-5f65b5bf69-nnmbt	1/1	Running	0

11. Verify that you are running the correct version of MariaDB.

For this version of the product, Workload Optimization Manager supports MariaDB version 10.5.20. Even after updating to this Workload Optimization Manager version, it is possible that your installation is running an earlier version of MariaDB. While still in the SSH session, check the MariaDB version.

```
mysql -u root --password=my_pwd -e "SHOW VARIABLES LIKE 'version';"
```

The output is similar to the following example:

+-		+
	Variable_name	Value
+-	+	+
	version	10.5.20-MariaDB
4.		

If the MariaDB version is earlier than 10.5.20, you should update your MariaDB. For complete instructions and information, see <u>Verifying your MariaDB Version</u> (on page 48).

12. Clear your browser data and refresh your browser.



After clearing the browser data and refreshing your browser, you have full access to Workload Optimization Manager features. However, features that rely on current analysis data will not be available until after a full market cycle — usually 10 minutes. For example, the Pending Actions charts will not show any actions until after a full market cycle.

13. Notify other users to clear their browser data and refresh their Workload Optimization Manager browser sessions.

Reference: What Are the Typical Settings for an IdP?

NOTE:

The process described here is applicable only to the OVA deployment model.

Before you begin configuring Single Sign-On (SSO), you need to make sure the IdP is set up for SSO.

Here are typical settings for a public Okta IdP which may be useful when you set up your IdP.

SAML Settings: GENERAL		
Setting	Example	
Single Sign On URL (where <hostname> is the host that Workload Optimization Manager runs on, and <samlregistrationid> is the Registration ID that you got from your SSO provider)</samlregistrationid></hostname>	https:// <hostname>/vmturbo/saml2/sso/<samlregistrationid></samlregistrationid></hostname>	
Recipient URL (where <hostname> is the host that Workload Optimization Manager runs on, and <samlregistrationid> is the Registration ID that you got from your SSO provider)</samlregistrationid></hostname>	https:// <hostname>/vmturbo/saml2/sso/<samlregistrationid></samlregistrationid></hostname>	
Destination URL (where <hostname> is the host that Workload Optimization Manager runs on, and <samlregistrationid> is the Registration ID that you got from your SSO provider)</samlregistrationid></hostname>	https:// <hostname>/vmturbo/saml2/sso/<samlregistrationid></samlregistrationid></hostname>	
Audience Restriction	urn:test:turbo:markharm	
Default Relay State		
Name ID Format	Unspecified	
Application username	The username for the account that is managed by Okta	
Response	Signed	
Assertion Signature	Signed	
Signature Algorithm	RSA_SHA256	
Digital Algorithm	SHA256	
Assertion Encryption	Unencrypted	
SAML Single Logout	Enabled	
Single Logout URL (where <hostname> is the host that Workload Optimization Manager runs on)</hostname>	https:// <hostname>/vmturbo/rest/logout</hostname>	



SAML Settings: GENERAL	
Setting	Example
SP Issuer	turbo
Signature Certificate	Example.cer (CN=apollo)
authnContextClassRef	PasswordProtectedTransport
Honor Force Authentication	Yes
SAML Issuer ID	http://www.okta.com/\$(org.externalKey)

Reference: FIPS Cipher Suites

NOTE:

The process described here is applicable only to the OVA deployment model.

The Federal Information Processing Standard (FIPS) is in place to ensure the cryptographic strength of secure connections. By default, Workload Optimization Manager ships with a FIPS-compliant cipher suite already enabled. The suite comprises the following ciphers:

- TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA
- TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256
- TLS ECDHE RSA WITH AES 128 GCM SHA256
- TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA
- TLS ECDHE RSA WITH AES 256 CBC SHA384
- TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384
- TLS ECDHE RSA WITH ARIA 128 GCM SHA256
- TLS_ECDHE_RSA_WITH_ARIA_256_GCM_SHA384

Modifying the Cipher Suite

If necessary, you can modify the cipher suite to comply with your internal policies.

1. Open an SSH terminal session on your Workload Optimization Manager instance.

Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Password: [your_private_password]
- 2. In the SSH session, open the cr.yaml file for editing. For example:

vi /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml

3. Edit the cipher suite.

Search for the list of ciphers in the file. Change the list as your policies require, and then save the file.

4. Apply your changes to the platform.

```
kubectl apply -f \
/opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```



Reference: Step-wise Platform Deployment

NOTE:

The process described here is applicable only to the OVA deployment model.

After you have installed the Workload Optimization Manager VM that will host the platform, you can install the platform components, as follows:

Optionally, configure Single Sign-On Authentication (SSO) for this installation.

If you plan to use SSO to authenticate your Workload Optimization Manager users, you can configure it now. To configure SSO you will edit the charts_vlalphal_xl_cr.yaml file. You can edit it now, before you complete the installation, or you can edit it later and restart the affected components. For more information, see <u>Single Sign-On Authentication (on page 73)</u>.

Deploy Workload Optimization Manager Kubernetes nodes.

When you deploy Workload Optimization Manager on Kubernetes, you deploy one Kubernetes node as a VM that will host pods to run the Workload Optimization Manager components. The script to deploy and initialize the Kubernetes node also deploys the Kubernetes pods that make up the Workload Optimization Manager application.

Start a secure session (SSH) on your Workload Optimization Manager VM as the turbo user and perform the following steps:

a. Initialize the Kubernetes node and deploy the pods.

```
sudo /opt/local/bin/t8cInstall.sh
```

The script should take up to 20 minutes to complete.

b. Verify that the deployment succeeded.

At the end of the script output, in the summary section, verify that no errors are reported. If any errors are reported, contact Workload Optimization Manager Support.

c. Verify that the Workload Optimization Manager application installed correctly.

```
kubectl get pods -n turbonomic
```

To verify the installation of the application, run the command:

```
kubectl get pods -n turbonomic
```

After all of the pods start, the READY column should read 1/1, 2/2, and so on and the STATUS column should read Running for each pod.

The output is similar to the following example:

NAME RE	SADY STATUS	RESTARTS
action-orchestrator-b6454c9c8-mfl85 1/	1 Runnir	ng 0
api-7887c66f4b-shndq 1/	1 Runnir	ng 0
arangodb-7f646fc5fc-zhcwf 1/	1 Runnir	ng 0
auth-5b86976bc8-vxwz4 1/	1 Runnir	ng 0
clustermgr-85548678d9-r5wb8 1/	1 Runnir	ng 0
consul-7f684d8cb8-6r677 1/	1 Runnir	ng 0
cost-5f46dd66c4-6d6cb 1/	1 Runnir	ng 0
extractor-5f41dd61c4-4d61q 1/	1 Runnir	ng 0
group-5bfdfbc6f8-96bsp 1/	1 Runnir	ng 0
history-5fc7fbc855-6zslq 1/	1 Runnir	ng 0
kafka-74cc77db94-dfrbl 1/	1 Runnir	ng 0
market-5f54699447-z4wkm 1/	1 Runnir	ng 0
mediation-actionscript-57b4fc6df-4lzfv 1/	1 Runnir	ng 0
mediation-appdynamics-6d65f8766f-kb44l 1/	1 Runnir	ng 0
mediation-hpe3par-d7c475c4c-v8ftc 1/	1 Runnir	ng 0
mediation-hyperv-6bd8c94df5-4dbzx 1/	1 Runnir	ng 0



mediation-netapp-7f8fc955d9-4kkdl		Running	0
mediation-oneview-7dbd7b54cf-7rfqp	1/1	Running	0
mediation-pure-58c4bd8cd9-8n256	1/1	Running	0
mediation-ucs-6f4bb9889-9rnqk	1/1	Running	0
mediation-vcenter-5bc4f5fbd4-nzm4j	1/1	Running	0
mediation-vcenterbrowsing-5c5987f66c-bfjq4	1/1	Running	0
mediation-vmax-6c59969b89-28t9j	1/1	Running	0
mediation-vmm-9c4878cf9-rfxnl	1/1	Running	0
nginx-5b775f498-sm2mm	1/1	Running	0
plan-orchestrator-6dffc4c9b6-p5t5n	1/1	Running	0
reporting-b44fbdfb4-8fjv5	1/1	Running	0
repository-6d555bb4bf-fxldh	1/1	Running	0
rsyslog-fd694878c-5tb2c	1/1	Running	0
t8c-operator-558bcc758d-5h8mp	1/1	Running	0
topology-processor-b646b786b-9skp7	1/1	Running	0
zookeeper-5f65b5bf69-nnmbt	1/1	Running	0

d. Synchronize the system clock.

To ensure correct display of data, and to support Single Sign-On (SSO) authentication, you need to synchronize the system clock.

For information, see Synchronizing Time (on page 46) and Single Sign-On Authentication (on page 73).

e. Verify that the Load Balancer has installed correctly.

```
kubectl get services -n turbonomic | grep LoadBalancer
```

The output is similar to the following example:

```
nginx LoadBalancer 10.10.10.10 10.10.10.11 443:32669/TCP,80:32716/TCP 17h
```

f. Configure mediation.

The installation script automatically enables a default set of mediation probes. After installation completes, you can change the set of enabled mediation probes (see Enabling Probe Components (on page 68)).

For Workload Optimization Manager to manage your IT environment, it must attach to targets in your environment so it can perform discovery and execute actions. The combination of the processes of discovery and action execution is *mediation*. This release of Workload Optimization Manager supports mediation through the following targets. If you need to use additional targets that are not in this list, contact Workload Optimization Manager Support.

Applications and Databases

- Apache Tomcat 7.x, 8.x, and 8.5.x
- AppDynamics 4.1+
- Applnsights
- Datadog
- Dynatrace 1.1+
- IBM WebSphere Application Server 8.5+
- Instana release-242 or later
- JBoss Application Server 6.3+
- JVM 6.0+
- SQL Server 2012, 2014, 2016, 2017, 2019, and 2022
- MySQL 5.7.x
- NewRelic
- Oracle 11g R2, 12c, 18c, and 19c
- Oracle WebLogic 12c

Cloud Native

- Kubernetes, including any compliant k8s distribution (Rancher, Tanzu, open source, etc.)
- Cloud-hosted k8s services (AKS, EKS, GKE, IBM, Cisco IKS, ROKS, ROSA, etc.)
- Red Hat OpenShift 3.11 and higher (OCP 4.x)

Fabric and Network

- Cisco UCS Manager 3.1+
- HPE OneView 3.00.04

Guest OS Processes

- SNMP
- WMI: Windows versions 8 / 8.1, 10, 2008 R2, 2012 / 2012 R2, 2016, 2019 and 7

Hyperconverged

- Cisco HyperFlex 3.5
- Nutanix Community Edition
- VMware vSAN

Hypervisors

- IBM PowerVM 8, 9, 10
- Microsoft Hyper-V 2008 R2, Hyper-V 2012/2012 R2, Hyper-V 2016, Hyper-V 2019
- VMware vCenter 7.0 and 8.0

Orchestrator

- ActionScript
- Flexera One
- ServiceNow

Private Cloud

 Microsoft System Center 2012/2012 R2 Virtual Machine Manager, System Center 2016 Virtual Machine Manager, and System Center Virtual Machine Manager 2019

Public Cloud

- Amazon AWS
- Amazon AWS Billing
- Google Cloud Platform (GCP)
- GCP Billing
- Microsoft Azure Service Principal
- Azure Billing
- Microsoft Enterprise Agreement

Storage

- EMC ScaleIO 2.x and 3.x
- EMC VMAX using SMI-S 8.1+
- EMC VPLEX Local Architecture with 1:1 mapping of virtual volumes and LUNs
- EMC XtremIO XMS 4.0+
- HPE 3PAR InForm OS 3.2.2+, 3PAR SMI-S, 3PAR WSAPI
- IBM FlashSystem running on Spectrum Virtualize 8.3.1.2 or later (8.4.2.0 or later recommended)
- NetApp Cluster Mode using ONTAP 8.0+ (excluding AFF and SolidFire)
- Pure Storage F-series and M-series arrays running Purity 5.3.6 (Pure API 1.6)

Virtual Desktop Infrastructure

VMware Horizon

For information about these targets, see <u>Target Configuration (on page 135)</u>.



IMPORTANT:

You should wait until all the platform components have started up, are running, and are fully ready before your first login. If you try to add a license or add a target to the platform before the components are all ready, the platform can fail to initialize correctly. After the components start up, in your Web browser, type the static IP address of your Workload Optimization Manager VM. Your browser redirects the login page for Workload Optimization Manager users.

Log in to the Workload Optimization Manager user interface and set the administrator user account password.

Workload Optimization Manager includes a default user account named administrator which has an ADMINISTRATOR role. As you log in for the first time, you must set your own password for that account. You can create or delete other accounts with the ADMINISTRATOR role, but your installation of Workload Optimization Manager must always have at least one account with that role.

In the login page, enter the information as required, and make a note of it.

- Use the default credential for **USERNAME**: administrator.
- Type a password for PASSWORD.

The new password must comply with the strong password policy (a mixture of upper- and lower-case letters, numbers, and a symbol). Only you will know this new password.

- Type the password again to verify it for REPEAT PASSWORD.
- Click Create Account.

This is the account you will use to access the Workload Optimization Manager user interface with administrator permissions. Be sure to save the user interface administrator account credentials in a safe place.

NOTE:

The initial login is always for the default user account named administrator which has an ADMINISTRATOR role.

4. After you have logged in as administrator, you can create other user accounts, and you can give them various roles. For more information about user accounts and roles, see Managing User Accounts (on page 723).

NOTE

For security reasons, you can create a different account with an ADMINISTRATOR role to serve as the main administrator of your Workload Optimization Manager installation, and then delete the default administrator account. But remember, you must always have at least one user account with administrator privileges.

Reference: Step-wise Offline Update

NOTE:

The process described here is applicable only to the OVA deployment model.

Complete the following steps to perform a stepwise offline update of your Workload Optimization Manager installation.

Save a snapshot of your current Workload Optimization Manager VM.

Before updating, shut down (not power off) the Workload Optimization Manager VM.

```
sudo init 0
```

Then, perform a snapshot (or clone the VM). This provides a reliable restore point you can turn to in the event that trouble occurs during the update. After you have the snapshot, bring the VM back online.

2. Download and attach the ISO image to the VM that runs Workload Optimization Manager.

Refer to the email you received from Cisco for links to the Workload Optimization Manager OVA file and to the ISO image.

- 3. Mount the ISO image by logging in to vCenter.
 - a. In vCenter, navigate to the Workload Optimization Manager VM.
 - Right-click the VM and choose Edit Settings.
 - In the CD/DVD Drive drop-down menu, select **Datastore ISO**, then browse to the Workload Optimization Manager update ISO image and choose it.
 - d. Ensure that Connect at power on is selected.



4. Log in to the Workload Optimization Manager VM.

Use SSH to log in to the Workload Optimization Manager VM using the turbo account and password.

- 5. If you are prompted to override the CD-ROM lock, select **Yes** and click **OK** to disconnect anyway and override the lock.
- 6. Mount the ISO image.

```
sudo mount /dev/cdrom /mnt/iso
```

7. Verify the correct version of the ISO image is mounted.

```
ls /mnt/iso
```

Verify that the ISO image contains the correct version for your update.

8. Load the latest Docker images.

```
sudo /mnt/iso/turboload.sh
```

This script loads all the images to the Workload Optimization Manager instance.

The output is similar to the following example:

If the load does not succeed, the script lists any images that did not load, along with instructions to load them manually.

9. Run the following command as a single line command to update Workload Optimization Manager.

```
/mnt/iso/turboupgrade.sh | tee \
/opt/turbonomic/t8c_upgrade_$(date +%Y-%m-%d_%H_%M_%S).log
```

Wait until the script is finished.

10. Verify that you are running the correct version of MariaDB.

For this version of the product, Workload Optimization Manager supports MariaDB, version 10.5.20. Even after updating to this Workload Optimization Manager version, it is possible that your installation is running an earlier version of MariaDB.

While still in the SSH session, check the MariaDB version.

```
mysql -u root --password=my_pwd -e "SHOW VARIABLES LIKE 'version';"
```

The output is similar to the following example:

```
+-----+
| Variable_name | Value |
+-----+
| version | 10.5.20-MariaDB |
```

If the MariaDB version is earlier than 10.5.20, you must update your MariaDB. For complete instructions and information, see <u>Verifying your MariaDB Version</u> (on page 48).

11. Unmount the ISO image.

```
sudo umount /dev/cdrom
```

12. Clear your browser data and refresh your browser.



After clearing the browser data and refreshing your browser, you have full access to Workload Optimization Manager features. However, features that rely on current analysis data will not be available until after a full market cycle – usually 10 minutes. For example, the Pending Actions charts will not show any actions until after a full market cycle.

13. Optionally, enable new probes in your environment.

NOTE:

As Workload Optimization Manager evolves, the set of delivered probes change. Also, from one version to the next, the set of probes that are enabled by default can change. When you update to a new version, the update does not change your probe configuration. An update to a newer version does not automatically enable any new probes in your deployment. If you want to take advantage of new probes in an update, then you must enable them manually.

For steps to enable new probes in your updated version, see <u>Enabling and Disabling Probe Components (on page 68)</u>. Use these steps to edit the platform's cr.yaml file.

NOTE:

During the online or offline upgrade process, you should not apply these changes at this time.

14. Verify that the Workload Optimization Manager application installed correctly.

```
kubectl get pods -n turbonomic
```

After all of the pods start, the READY column should read 1/1, 2/2, and so on and the STATUS column should read Running for each pod.

15. Notify other users to clear their browser data and refresh their Workload Optimization Manager browser sessions.

Reference: Working with YAML Files

YAML is the primary file format to create and configure resources on kubernetes, including everything to do with the Workload Optimization Manager platform. The Custom Resource YAML provides a convenient, single place to define the majority of configuration details for Workload Optimization Manager. When editing YAML files, you must be careful to respect the file syntax, including indents in the file. General rules for edits include:

- Always uses spaces, not tabs, for all indentation. Since spacing and indentations matter, and can yield an invalid result or a parameter completely skipped over, you should work with YAML files with an editor that supports using vertical lines associated with indentations to visually spot a misalignment. If your editor of choice makes this difficult, you can use the linux expand utility when you're done, to convert tabs to equivalent spaces.
- Indention uses two spaces per level.
- Be careful to keep the same indentation for all properties in a given section.
- Never use the same property name twice in the same section. Doing this will render the YAML file invalid, though you will likely not see any notification of a problem. Rather, all but one of the property definitions will be silently ignored.

Spacing matters

For the Workload Optimization Manager Custom Resource, indentation defines where parameters are applied (globally or to specific components), so ensure you line up the text appropriately. The following example shows examples of specifications that are applied at a global level ($\{"spec": \{"global": [\{"tag":"8.6.4"\}]\}\}$) which sets the container image tag for all instances. Then indented we see properties that are global for the remote database ($\{"spec": \{"properties": \{"global": [\{"dbPort":"6033"\}]\}\}\}$) describes a property of dbPort that would be set for remote DB connections.

Each line is indented two spaces from the higher level.

```
spec:
   global:
    repository: turbonomic
   tag: 8.6.4
   properties:
    global:
        dbPort: 6033
```



```
kubeturbo:
   enabled: true
aws:
   enabled: true
```

Combine properties correctly

A YAML file is read top down, and if there are different parameters that apply to the same component, they need to be combined. The following example shows a YAML where properties for the ui component of image tag *and* memory limit resources.

```
spec:
 global:
    repository: turbonomic
    tag: 8.6.4
  ui:
    image:
      tag: 8.0.5
 properties:
    global:
      dbPort: 6033
 kubeturbo:
    enabled: true
 aws:
    enabled: true
  ui:
    resources:
      limits:
        memory: 4Gi
```

This YAML will not set both image tag and memory limit resources for the ui component because they are set in two different sections. The memory limits would be applied since that is the last section to be read, and it would overwrite the first set of properties with the image tag. The following YAML will set both image tag and memory limit resources for the ui component:

```
spec:
 global:
   repository: turbonomic
    tag: 8.6.4
  ui:
    image:
      tag: 8.0.5
   resources:
      limits:
        memory: 4Gi
 properties:
    global:
      dbPort: 6033
 kubeturbo:
    enabled: true
  aws:
    enabled: true
```

To avoid having the same property name twice in the same section, search for an existing instance of the key you want to add. With the complex embedded structure in many k8s resources, this can be quite challenging; however, you can use an online validator that does not accept duplicate keys to check your entire CR file (such as YAMLint - The YAML Validator).



Finding a property

In this documentation we refer to specific properties in the CR file using a "path" expression. For example, assume the path /spec/global/repository to designate a repository property in the file. You can find the property in the file as follows:

- 1. Find a line that says spec: with no indentation at all.
- 2. Between that line and the next unindented line (not counting comments, which start with #), find a line that says global: and is at the next level of indentation.
- 3. Between that line and the next line with the same indentation, find a line that starts with repository:. That line is where the addressed property is defined.

In this example, find the repository property specified by /spec/global/repository:

```
apiVersion: charts.helm.k8s.io/vlalphal
kind: Xl
metadata:
   name: xl-release
spec:
   properties:
      global:
      repository:  # This is NOT the correct property
      ...
# Global settings
global:
   repository:  # This is the one we're after
```

The first repository property is not at /spec/global/repository, but at /spec/properties/global/repository.



Product Overview

Thank you for choosing Workload Optimization Manager, the premier solution for Application Resource Management (ARM) of cloud and virtual environments.

Application Resource Management is a top-down, application-driven approach that continuously analyzes applications' resource needs and generates fully automatable actions to ensure applications always get what they need to perform. It runs 24/7/365 and scales with the largest, most complex environments.

To perform Application Resource Management, Workload Optimization Manager represents your environment holistically as a *supply chain* of resource *buyers* and *sellers*, all working together to meet application demand. By empowering buyers (VMs, instances, containers, and services) with a budget to seek the resources that applications need to perform, and sellers to price their available resources (CPU, memory, storage, network) based on utilization in real-time, Workload Optimization Manager keeps your environment within the *desired state* – operating conditions that achieve the following conflicting goals at the same time:

- Assured application performance
 - Prevent bottlenecks, upsize containers/VMs, prioritize workload, and reduce storage latency.
- Efficient use of resources
 - Consolidate workloads to reduce infrastructure usage to the minimum, downsize containers, prevent sprawl, and use the most economical cloud offerings.

Workload Optimization Manager is a containerized, microservices architected application running in a Kubernetes environment (or within a VM) on your network or a public cloud VPC. You then assign services running on your network to be Workload Optimization Manager targets. Workload Optimization Manager discovers the entities (physical devices, virtual components and software components) that each target manages, and then performs analysis, anticipates risks to performance or efficiency, and recommends actions you can take to avoid problems before they occur.

How Workload Optimization Manager Works

To keep your infrastructure in the desired state, Workload Optimization Manager performs Application Resource Management. This is an ongoing process that solves the problem of assuring application performance while simultaneously achieving the most efficient use of resources and respecting environment constraints to comply to business rules.

This is not a simple problem to solve. Application Resource Management has to consider many different resources and how they are used in relation to each other, and numerous control points for each resource. As you grow your infrastructure, the factors for each decision increase exponentially. On top of that, the environment is constantly changing – to stay in the desired state, you are constantly trying to hit a moving target.

To perform Application Resource Management, Workload Optimization Manager models the environment as a *market* made up of *buyers* and *sellers*. These buyers and sellers make up a *supply chain* that represents tiers of entities in your inventory. This supply chain represents the flow of resources from the datacenter, through the physical tiers of your environment, into the virtual



tier and out to the cloud. By managing relationships between these buyers and sellers, Workload Optimization Manager provides closed-loop management of resources, from the datacenter, through to the application.


See Supply Chain of Entities (on page 123) for a visual layout of the buyer and seller relationships.

Workload Optimization Manager uses *Virtual Currency* to give a budget to buyers and assign cost to resources. This virtual currency assigns value across all tiers of your environment, making it possible to compare the cost of application transactions with the cost of space on a disk or physical space in a data center.

The price that a seller charges for a resource changes according to the seller's supply. As demand increases, prices increase. As prices change, buyers and sellers react. Buyers are free to look for other sellers that offer a better price, and sellers can duplicate themselves (open new storefronts) to meet increasing demand. Workload Optimization Manager uses its *Economic Scheduling Engine* to analyze the market and make these decisions. The effect is an invisible hand that dynamically guides your IT infrastructure to the optimal use of resources.

To get the most out of Workload Optimization Manager, you should understand how it models your environment, the kind of analysis it performs, and the desired state it works to achieve.

The Desired State



The goal of Application Resource Management is to assure performance while maintaining efficient use of resources. When performance and efficiency are both maintained, the environment is in the desired state. You can measure performance as a function of delay, where zero delay gives the ideal QoS for a given service. Efficient use of resources is a function of utilization where 100% utilization of a resource is the ideal for the most efficient utilization.

If you plot delay and utilization, the result is a curve that shows a correlation between utilization and delay. Up to a point, as you increase utilization, the increase in delay is slight. There comes a point on the curve where a slight increase in utilization results in an unacceptable increase in delay. On the other hand, there is a point in the curve where a reduction in utilization doesn't yield a meaningful increase in QoS. The desired state lies within these points on the curve.

You could set a threshold to post an alert whenever the upper limit is crossed. In that case, you would never react to a problem until delay has already become unacceptable. To avoid that late reaction you could set the threshold to post an alert before the upper limit is crossed. In that case, you guarantee QoS at the cost of over-provisioning – you increase operating costs and never achieve efficient utilization.

Instead of responding *after* a threshold is crossed, Workload Optimization Manager analyzes the operating conditions and constantly recommends actions to keep the entire environment within the desired state. If you execute these actions (or let Workload Optimization Manager execute them for you), the environment will maintain operating conditions that assure performance for your customers, while ensuring the lowest possible cost thanks to efficient utilization of your resources.

The Market and Virtual Currency

To perform Application Resource Management, Workload Optimization Manager models the environment as a market, and uses market analysis to manage resource supply and demand. For example, bottlenecks form when local workload demand exceeds the local capacity – in other words, when demand exceeds supply. By modeling the environment as a market, Workload Optimization Manager can use economic solutions to efficiently redistribute the demand or increase the supply.



Workload Optimization Manager uses two sets of abstraction to model the environment:


Modeling the physical and virtual IT stack as a service supply chain

The supply chain models your environment as a set of managed entities. These include applications, VMs, hosts, storage, containers, availability zones (cloud), and data centers. Every entity is a buyer, a seller, or both. A host machine buys physical space, power, and cooling from a data center. The host sells resources such as CPU cycles and memory to VMs. In turn, VMs buy host services, and then sell their resources (VMem and VCPU) to containers, which then sell resources to applications.

See Supply Chain of Entities (on page 123) for a visual layout of the buyer and seller relationships.

 Using virtual currency to represent delay or QoS degradation, and to manage the supply and demand of services along the modeled supply chain

The system uses virtual currency to value these buy/sell transactions. Each managed entity has a running budget — the entity adds to its budget by providing resources to consumers, and the entity draws from its budget to pay for the resources it consumes. The price of a resource is driven by its utilization — the more demand for a resource, the higher its price.



These abstractions open the whole spectrum of the environment to a single mode of analysis – market analysis. Resources and services can be priced to reflect changes in supply and demand, and pricing can drive resource allocation decisions. For example, a bottleneck (excess demand over supply) results in rising prices for the given resource. Applications competing for the same resource can lower their costs by shifting their workloads to other resource suppliers. As a result, utilization for that resource evens out across the environment and the bottleneck is resolved.

Risk Index

Workload Optimization Manager tracks prices for resources in terms of the *Risk Index*. The higher this index for a resource, the more heavily the resource is utilized, the greater the delay for consumers of that resource, and the greater the risk to your QoS. Workload Optimization Manager constantly works to keep the Risk Index within acceptable bounds.

You can think of Risk Index as the cost for a resource – Workload Optimization Manager works to keep the cost at a competitive level. This is not simply a matter of responding to threshold conditions. Workload Optimization Manager analyzes the full range of buyer/seller relationships, and each buyer constantly seeks out the most economical transaction that is available.



This last point is crucial to understanding Workload Optimization Manager. The virtual environment is dynamic, with constant changes to workload that correspond with the varying requests your customers make of your applications and services. By examining each buyer/seller relationship, Workload Optimization Manager arrives at the optimal workload distribution for the current state of the environment. In this way, it constantly drives your environment toward the desired state.

NOTE:

The default Workload Optimization Manager configuration is ready to use in many environments. However, you can fine-tune the configuration to address special services and resources in your environment. Workload Optimization Manager provides a full range of policies that you can set to control how the software manages specific groups of entities. Before you make such policy changes, you should understand default Workload Optimization Manager operation. For more information about policies, see Working With Policies (on page 672).

The Workload Optimization Manager Supply Chain

Workload Optimization Manager models your environment as a market of buyers and sellers. It discovers different types of entities in your environment via the targets you have added, and then maps these entities to the supply chain to manage the workloads they support. For example, for a hypervisor target, Workload Optimization Manager discovers VMs, the hosts and datastores that provide resources to the VMs, and the applications that use VM resources. For a Kubernetes target, it discovers services, namespaces, containers, container pods, and nodes. The entities in your environment form a chain of supply and demand where some entities provide resources while others consume the supplied resources. Workload Optimization Manager stitches these entities together, for example, by connecting the discovered Kubernetes nodes with the discovered VMs in vCenter.

For information about specific members of the supply chain, see Supply Chain of Entities (on page 123).

Supply Chain Terminology

Cisco introduces specific terms to express IT resources and utilization in terms of supply and demand. These terms are largely intuitive, but you should understand how they relate to the issues and activities that are common for IT management.

Term	Definition
Commodity	The basic building block of Workload Optimization Manager supply and demand. All the resources that Workload Optimization Manager monitors are commodities. For example, the CPU capacity or memory that a host can provide are commodities. Workload Optimization Manager can also represent clusters and segments as commodities.
	When the user interface shows <i>commodities</i> , it's showing the resources a service provides. When the interface shows <i>commodities bought</i> , it's showing what that service consumes.
Composed Of	The resources or commodities that make up the given service. For example, in the user interface you might see that a certain VM is <i>composed of</i> commodities such as one or more physical CPUs, an Ethernet interface, and physical memory.
	Contrast <i>Composed Of</i> with <i>Consumes</i> , where consumption refers to the commodities the VM has bought. Also contrast <i>Composed Of</i> with the commodities a service offers for sale. A host might include four CPUs in its composition, but it offers CPU Cycles as a single commodity.
Consumes	The services and commodities a service has bought. A service <i>consumes</i> other commodities. For example, a VM consumes the commodities offered by a host, and an application consumes commodities from one or more VMs. In the user interface you can explore the services that provide the commodities the current service consumes.
Entity	A buyer or seller in the market. For example, a VM or a datastore is an entity.
Environment	The totality of data center, network, host, storage, VM, and application resources that you are monitoring.
Inventory	The list of all entities in your environment.
Risk Index	A measure of the risk to Quality of Service (QoS) that a consumer will experience. The higher the Risk Index on a provider, the more risk to QoS for any consumer of that provider's services.



Term	Definition
	For example, a host provides resources to one or more VMs. The higher the Risk Index on the provider, the more likely that the VMs will experience QoS degradation.
	In most cases, for optimal operation the Risk Index on a provider should not go into double digits.

Workload Optimization Manager Targets

End-of-life (EOL) notice: When a specific release or version of an integration partner technology reaches end-of-life (EOL) or its end of support date, Workload Optimization Manager no longer provides support for that version. Workload Optimization Manager follows integration partners' official EOL timeline for version support. Targeting a non-supported version, or one that is no longer supported by the vendor, is at your own risk.

You can assign instances of the following technologies as Workload Optimization Manager targets.

- Applications and Databases
 - Apache Tomcat 7.x, 8.x, and 8.5.x
 - AppDynamics 4.1+
 - Applnsights
 - Datadog
 - Dynatrace 1.1+
 - IBM WebSphere Application Server 8.5+
 - Instana release-242 or later
 - JBoss Application Server 6.3+
 - JVM 6.0+
 - SQL Server 2012, 2014, 2016, 2017, 2019, and 2022
 - MySQL 5.7.x
 - NewRelic
 - Oracle 11g R2, 12c, 18c, and 19c
 - Oracle WebLogic 12c
- Cloud Native
 - Kubernetes, including any compliant k8s distribution (Rancher, Tanzu, open source, etc.)
 - Cloud-hosted k8s services (AKS, EKS, GKE, IBM, Cisco IKS, ROKS, ROSA, etc.)
 - Red Hat OpenShift 3.11 and higher (OCP 4.x)
- Fabric and Network
 - Cisco UCS Manager 3.1+
 - HPE OneView 3.00.04
- Guest OS Processes
 - SNMP
 - WMI: Windows versions 8 / 8.1, 10, 2008 R2, 2012 / 2012 R2, 2016, 2019 and 7
- Hyperconverged
 - Cisco HyperFlex 3.5
 - Nutanix Community Edition
 - VMware vSAN
- Hypervisors
 - IBM PowerVM 8, 9, 10
 - Microsoft Hyper-V 2008 R2, Hyper-V 2012/2012 R2, Hyper-V 2016, Hyper-V 2019
 - VMware vCenter 7.0 and 8.0



- Orchestrator
 - ActionScript
 - Flexera One
 - ServiceNow
- Private Cloud
 - Microsoft System Center 2012/2012 R2 Virtual Machine Manager, System Center 2016 Virtual Machine Manager, and System Center Virtual Machine Manager 2019
- Public Cloud
 - Amazon AWS
 - Amazon AWS Billing
 - Google Cloud Platform (GCP)
 - GCP Billing
 - Microsoft Azure Service Principal
 - Azure Billing
 - Microsoft Enterprise Agreement
- Storage
 - EMC ScaleIO 2.x and 3.x
 - EMC VMAX using SMI-S 8.1+
 - EMC VPLEX Local Architecture with 1:1 mapping of virtual volumes and LUNs
 - EMC XtremIO XMS 4.0+
 - HPE 3PAR InForm OS 3.2.2+, 3PAR SMI-S, 3PAR WSAPI
 - IBM FlashSystem running on Spectrum Virtualize 8.3.1.2 or later (8.4.2.0 or later recommended)
 - NetApp Cluster Mode using ONTAP 8.0+ (excluding AFF and SolidFire)
 - Pure Storage F-series and M-series arrays running Purity 5.3.6 (Pure API 1.6)
- Virtual Desktop Infrastructure
 - VMware Horizon

Sustainability Features

Workload Optimization Manager helps companies reduce their energy consumption and carbon footprint by optimizing IT infrastructure while ensuring that applications get the resources that they need to perform optimally. This core functionality, along with visibility into sustainability data, is crucial to setting and achieving sustainability goals. To visualize this data, Workload Optimization Manager provides the following features.

Sustainability Charts


Workload Optimization Manager monitors the energy consumption and carbon footprint of your IT infrastructure, and then displays relevant data in charts. Currently, these capabilities are supported for hosts and VMs discovered via vCenter targets. When you set the scope to any of these entities and then click the **Details** tab, you can view sustainability data in the **Energy** and **Carbon Footprint** charts.



For details, see Energy Chart (on page 630) and Carbon Footprint Chart (on page 626).

Data Center Policies

Workload Optimization Manager <u>calculates</u> (on page 627) carbon footprint using industry standards that take into account energy consumption, datacenter efficiency, and carbon intensity data. You can create Data Center policies to adjust the calculations according to the requirements of your data centers. For example, a data center in a particular location might have different requirements than data centers in other locations. After you adjust the calculations via policies, Workload Optimization Manager can accurately report your organization's carbon footprint.



For details, see Data Center Policies (on page 490).


Sustainability Dashboards in Embedded Reporting

If you have enabled the Embedded Reporting add-on, add the sustainability dashboards to gain insight into how you can reduce your carbon footprint and energy consumption.

Sustainable IT Dashboard - Private Cloud

This dashboard focuses on the energy consumption and carbon footprint of hosts. It also shows opportunities to reduce consumption and footprint by executing Workload Optimization Manager actions.






You can change the scope of the dashboard by selecting data centers or clusters at the top left section.

Application Carbon Footprint - Private Cloud

This dashboard focuses on the energy consumption and carbon footprint of VMs. The Top Applications by Carbon Footprint view provides insight into the carbon dioxide equivalent (CO2e) emissions of the VMs that power your applications. The dashboard also shows opportunities to reclaim resources by executing VM resize actions, as well as optimization opportunities that can help reduce consumption and footprint further.



You can change the scope of the dashboard by selecting data centers, applications, or VMs at the top left section. The expandable Help section explains the data and data collection methodology for some of the graphs.

For both dashboards, the expandable Help section explains the data and data collection methodology for some of the graphs.

To add these dashboards:

- 1. Enable Embedded Reporting. For details, see Enabling Embedded Reporting (on page 1268).
- 2. Download the JSON files for the dashboards from GitHub.
- 3. Log in to Workload Optimization Manager and then click **Reports** on the main menu.

The Embedded Reporting main page opens.

4. Click **Import** and then import the JSON files you downloaded. Be sure to select **Turbo Timescale** as your database.

The dashboards are now ready to use.



Getting Started

To get started with the platform, open a web browser to your Workload Optimization Manager installation. The Workload Optimization Manager platform serves the user interface to your browser, where you can log in and get started managing your environment. In this way, you can access the unique capabilities of Workload Optimization Manager from any internet connection.

Logging In to Workload Optimization Manager

To get started with the platform, open a web browser to your Workload Optimization Manager installation. The Workload Optimization Manager platform serves the user interface to your browser, where you can log in and get started managing your environment. In this way, you can access the unique capabilities of Workload Optimization Manager from any internet connection.

Before you can log in, your enterprise must have a valid Workload Optimization Manager account, or an instance of Workload Optimization Manager must be installed in your environment. To get the IP address of your Workload Optimization Manager installation, contact your system administrator.

To log in to Workload Optimization Manager:

- Navigate your Web browser to the Workload Optimization Manager installation.
 For the URL, provide the IP address or machine name for the installation. This URL opens the Workload Optimization Manager Login page. You should bookmark this URL for future use.
- Provide the user name and password for your account.
 Your system administrator creates user accounts. Contact your system administrator for login information.

After you log in, the browser opens to the <u>Home Page (on page 109)</u>. This page is your starting point for sessions with the Workload Optimization Manager platform. From the Home Page you can see the overviews of your environment.

To display this information, Workload Optimization Manager communicates with *target services* such as hypervisors, storage controllers, and public cloud accounts. Note that your Workload Optimization Manager administrator sets up the target configuration. For information about supported targets and how to configure them, see <u>Target Configuration</u> (on page 135).



The Home Page

When you launch Workload Optimization Manager, the Home Page is the first view you see. From there you can:

- Choose a View to see overviews of your environment:
 - APPLICATION See your environment in the context of your <u>Business Applications (on page 325)</u>.
 - ON-PREM See details for the on-prem environment. Notice that the Supply Chain excludes cloud entities and only shows the entities that are on-prem.
 - CLOUD See details for the cloud environment, including pending actions, a listing of your cloud accounts by cost, the locations of cloud datacenters that you are using, estimated costs, and other cost-related information.
- Use the Supply Chain Navigator to inspect lists of entities

Click an entity tier in the Supply Chain to see a list of those entities. For example, click Virtual Machine to see a list of all the VMs in your environment.

- Navigate to other Workload Optimization Manager pages, including:
 - Search Set the session scope to drill down to details about your environment
 - Plan Run what-if scenarios
 - Place Use Workload Optimization Manager to calculate the best placement for workloads, and execute the placement at the time you specify
 - Dashboards Set up custom views with charts that focus on specifics in your environment
 - Settings Configure Workload Optimization Manager to set up business rules and policies, configure targets, define groups, and perform other administrative tasks

Getting Home




Wherever you are in your Workload Optimization Manager session, you can always click the Home icon to return to the **Home Page**.

APPLICATION View

The **APPLICATION** view presents your environment in the context of your <u>Business Applications</u> (on page 325). See the overall health of your applications, examine any performance and compliance risks, and execute the actions that Workload Optimization Manager recommends to address these risks.





This view also shows the <u>Business Transactions (on page 327)</u> and <u>Services (on page 330)</u> that make up your Business Applications. You can see finer details and set SLOs at these levels of the application model.

NOTE:

If certain application entities do not stitch into the supply chain infrastructure for some reason, Workload Optimization Manager displays them in both the ON-PREM and the CLOUD views. Once Workload Optimization Manager can stitch them into the infrastructure, it classifies them according to the class of the infrastructure and displays them in the correct views.

ON-PREM View

When you set your session to the Global Scope, you can then select the **ON-PREM** view. This shows an overview of your on-prem environment. If you don't have any workload on the public cloud, then you should use this as your starting point for a Workload Optimization Manager session. If you have a hybrid environment (on-prem and on the public cloud), then you can refer to this view to see a detailed on-prem overview.





The Supply Chain shows all the on-prem entities in your environment. The charts show details about your environment, including:

- Overviews of pending actions
 - When appropriate, the overview includes estimated one-time savings or costs associated with the actions.
- Top Cluster utilization

See a list of the most utilized clusters. The chart shows these clusters, along with a count of actions for each. To drill down into the cluster details, click the cluster name. To see and execute the specific actions, click the **ACTIONS** button for that cluster. To see all the clusters in your environment, click **SHOW ALL**.

- Optimized Improvements
 - Compare current resource utilization with the utilization you would see if you choose to execute all the pending actions.
- Action history

You can see a history of all actions that have been recommended and executed, or of just the actions that have been accepted and executed.

CLOUD View

When you set your session to the Global Scope, you can then select the **CLOUD** view. This shows an overview of your cloud environment. If all your workload is on the public cloud, then you should use this as your starting point for a Workload Optimization Manager session. If you have a hybrid environment (on-prem and on the public cloud), then you can refer to this view to see a detailed cloud overview.

To view cloud cost information, you must have one or more public cloud targets set up in your Workload Optimization Manager installation. For information about setting up public cloud targets, see <u>Cloud Targets (on page 238)</u>.

In addition, to view full cost information in AWS, you must have created a Cost and Usage report in your AWS account and you must store it in an S3 bucket.



In this view, the Supply Chain shows all the cloud entities in your environment. The charts show details about your cloud environment, including:

Overviews of pending actions

The overview includes the estimated monthly savings or cost associated with those actions.

Top Accounts utilization

See a list of the most utilized public cloud accounts. The chart shows these accounts, along with an estimate of the monthly cost for each. To see all the cloud accounts in your environment, click **SHOW ALL**.

Necessary Investments and Potential Savings

For the current set of pending actions, these charts show the impact in dollar value. Necessary Investments are from actions to provision more workloads or to resize workloads up. Potential Savings are from actions to resize down, or to purchase discounts and put them into active use.

- Charts that show your current discounts. For details, see <u>Discounts (on page 113)</u>.
- Billed Cost by Service

This chart shows costs over time for each cloud service that you use in your cloud accounts. For example, you can see the cost for AWS CloudWatch, compared to the cost for AWS S3 storage.

Tracking Cloud Cost

Workload Optimization Manager tracks your cloud costs based on the cost information it discovers from targets (for example, accounts, billing reports, and on-demand or discount costs) and price adjustments (on page 717).

NOTE

It is possible for Workload Optimization Manager to report negative amounts. For example, when discounts are larger than costs, the result is a negative amount. Currently, these amounts are not shown directly in cost-focused charts (such as the Expenses charts). To check for any negative amounts, hover on a data point in a chart and then review the data in the tooltip.

Cost for Services

Workload Optimization Manager uses the billing reports from your cloud service providers, as they are associated with your cloud targets. Workload Optimization Manager parses these reports to get cost breakdowns by service, service provider, Azure Resource Group, and cloud account. You can see cost data in the Expenses charts and Cost Breakdown by Tag charts.

Workload Expenses

Workloads are the VMs running in your environment, or other hosted processes such as database servers and containers. Workload Optimization Manager tracks the following expenses for your workloads:

Compute

For compute expenses Workload Optimization Manager uses hourly expense per template as specified in the associated public cloud account.

■ Storage

Workload Optimization Manager discovers the storage tier that supports a given workload, and uses the tier pricing to calculate storage cost.

License

For AWS environments, Workload Optimization Manager can calculate OS costs. To calculate the OS cost for a VM, Workload Optimization Manager subtracts the template cost from the published workload cost. It assumes the difference is the license cost for that workload. If the OS is open source, then there will be no difference, and license cost is zero. Analysis does not consider AWS Marketplace costs.

For Azure environments, Workload Optimization Manager can track OS costs for existing VMs. For actions to purchase reservations, Workload Optimization Manager does not include the OS cost. Analysis considers the base OS cost, but does not consider additional costs for support or other add-on features that are bundled with the OS. The affected OS types are Ubuntu PRO, SUSE 24/7, and RHEL with HA.

Workload Optimization Manager uses this cost information when making scaling decisions, both in real time and in plans. You can see this information in Expenses charts and in the results of Migrate to Cloud plans.



Costs for Dedicated Tenancy on AWS

When you create VMs on AWS, you can specify their tenancy. When you specify Dedicated Tenancy (DT), the VMs you create are Amazon EC2 instances running on hardware that is dedicated to a single customer. To understand DT in the context of Workload Optimization Manager, you should consider:

- For AWS, the Workload Optimization Manager supply chain shows an Availability Zone as a Host. The supply chain does not indicate whether certain VMs have tenancy dedicated to specific resources in the given availability zone. Also, Workload Optimization Manager does not discover or show the costs for dedicated hosting of your workloads.
- Pricing for DT workloads is different than pricing for Shared Tenancy. Workload Optimization Manager does not discover that difference, and uses Shared Tenancy cost for the DT workloads. In action descriptions, the listed savings or investments will be based on Shared Tenancy costs.
- Workload Optimization Manager discovers the true costs of RIs for DT workloads. However, because the on-demand VM costs are based on Shared Tenancy, Workload Optimization Manager can overstate the savings you would get for purchasing and using RI capacity. In most cases, recommendations to purchase RIs will be correct. However, the time to achieve ROI could take longer than action descriptions and charts indicate.
- Some instance types that are valid for Shared Tenancy are not valid for DT. To see which instance types are valid for your DT VMs, consult the AWS documentation or your AWS representative.
- Under some circumstances Workload Optimization Manager can recommend changing a workload to a valid instance type for the tenant, even though the current type is already valid. This can happen when the instance type is not included in the Offer File for the tenancy. For example, assume the t3a template family does not support dedicated tenancy. However, assume that the user created a t3a instance with dedicated tenancy in the EC2 console. In that case, Workload Optimization Manager will see this as a misconfiguration and recommend changing to a different instance type.

To address these issues, you can create groups that set a scope to your DT workloads. For example, you can use naming conventions, tagging, or other means to identify your DT workloads. Then you can create dynamic groups based on those indicators. With those groups, you can create policies and dashboards that correspond to the differences you see in your DT environment. Use this approach to address issues for:

Available Instance Types

To resize a workload, Workload Optimization Manager generates an action to change that workload to a different instance type. Because Workload Optimization Manager does not discover the difference between instance types that are valid for DT and for Shared Tenancy, it can recommend scaling a DT workload to an unavailable instance type. To avoid this, create a policy for the DT group, and exclude the unavailable instance types.

Displaying Costs

Workload Optimization Manager charts show the costs for your environment. If the scope includes Dedicated Tenancy workloads, then the calculated cost will be incomplete. For example, since AWS does not return pricing data for converted RIs (that is, RIs that have been exchanged at least once) that are on *All Upfront* payment plans, Workload Optimization Manager does not include such RIs in its calculations of RI utilization or cost.

Use scope to minimize this effect. You can create separate dashboards for your DT and Shared Tenancy workloads.

Discounts

Workload Optimization Manager analysis takes advantage of cloud provider discounts to calculate optimal workload placement and to arrive at the best possible costs for your deployments on the cloud. Workload Optimization Manager discovers the following discounts:

- AWS Reserved Instances (RIs) and Savings Plans
- Azure reservations
- GCP committed use discounts

The Cloud View in the Homepage includes the following charts that show discount data:

Potential Savings or Necessary Investments Charts (on page 621)

If Workload Optimization Manager has found actions you can take to improve performance or to reduce cost, then you can see an overview of them in the Potential Savings or Necessary Investments charts. To see a listing of the specific actions, click **Show All** at the bottom of the chart. For more about actions, see <u>Workload Optimization Manager Actions (on page 508)</u>.



■ Discount Utilization (on page 665)

This chart shows how well you have utilized your current discount <u>inventory</u> (on page 663). The desired goal is to maximize the utilization of your inventory and thus take full advantage of the discounted pricing offered by your cloud provider.

■ Discount Coverage (on page 661)

This chart shows the estimated percentage of VMs covered by discounts. If you have a high percentage of on-demand VMs, you should be able to reduce your monthly costs by increasing coverage. To increase coverage, you scale VMs to instance types that have existing capacity.

Discount Inventory (on page 663)

This chart lists the cloud provider discounts discovered in your environment.

Recommended RI Purchases (on page 659)

Workload Optimization Manager can recommend purchasing instance types at a discounted rate to help you increase the percentage of VMs covered by discounted pricing and reduce on-demand costs. This chart shows your pending purchases. Download the list of purchases and then send it your cloud provider or representative to initiate the purchase process.

NOTE:

Purchase actions should be taken along with the related VM scaling actions. To purchase discounts for VMs at their current sizes, run a <u>Buy VM Reservation Plan (on page 577)</u>.

Currently, Workload Optimization Manager can recommend purchase actions for AWS and Azure. Purchase actions for GCP will be introduced in a future release.

Configuring Targets

A target is a service that performs management in your virtual environment. Workload Optimization Manager uses targets to monitor workload and to execute actions in your environment. When you configure a target, you specify the address of the service, and the credentials to connect as a client to it.

For each target, Workload Optimization Manager communicates with the service via the management protocol that it exposes – The REST API, SMI-S, XML, or some other management transport. Workload Optimization Manager uses this communication to discover the managed entities, monitor resource utilization, and execute actions.

To configure a target, you will choose the target type, specify the target's address or key, and then provide credentials to access the target. Workload Optimization Manager then discovers and validates the target, and then updates the supply chain with the entities that the target manages.

NOTE:

Workload Optimization Manager regularly checks the status of your targets. If target discovery or validation fails, the Target Configuration page updates the status. Under some circumstances, the target can become discoverable or valid again, but the status does not update. In this case, select the target and then click **Rediscover** or **Validate**.

You have the option of using the enhanced target settings experience using the new target view. See <u>Configuring Targets</u> – <u>Enhanced View (on page 118)</u>.

For a list of supported targets and configuration requirements, see Target Configuration (on page 135).

Configuring a Target

1. Navigate to the Settings Page.



Click to navigate to the Settings Page. From there, you can perform a variety of Workload Optimization Manager configuration tasks.

2. Choose Target Configuration.






Target Configuration

Click to navigate to the Target Configuration Page.

3. Review the list of targets.



This page lists all the targets that you currently have configured for Workload Optimization Manager. Click New View to enable the enhanced target settings experience using the new target view. You can inspect or edit these targets, or add a new target.

4. Filter the list of targets.



For a long list of targets, you can:

- Filter targets by target type.
- Use Search to filter targets by text string (partial matching is supported).



- Use Filter to filter targets by status (for example, only show validated targets). You can also use Filter to sort targets by name or status.
- 5. Select one or more targets to work with.



When you select a target you can:

Rediscover

Direct Workload Optimization Manager to fully discover the entities that this target manages. This will rebuild the topology that is associated with this target.

Validate

Direct Workload Optimization Manager to validate its connection with the target. For example, if you create a new user account on the target, you can edit the target connection to use that account, and then revalidate.

Delete (delete icon)


When you delete a target, Workload Optimization Manager removes all the associated entities from the supply chain.

Expand an entry to see target details.




You can also click anywhere in the entry to edit the target's configuration. For example, if you entered the wrong username or password, you can change those credentials and validate the target again.





7. Create a new target and add it to Workload Optimization Manager.





Click New Target, select the target category and type, and then provide the address and credentials for that target.

After you add the target, the Target Configuration page refreshes to show the current validation status.

- Validating
 - Validation is in progress.
- Validated
 - Validation was successful. Workload Optimization Manager can now monitor the target and will start discovering the entities that the target manages.
- Validation Failed
 - Validation was unsuccessful. Expand the target to see additional information.

Configuring Targets - Enhanced View

In the enhanced target settings experience, you can easily view targets in a tabular form with improved search, sort, and filtering capabilities. Targets with health issues are easily identified alongside information on who changed the target configuration and when it was changed. The Target Details page for some target integrations communicate the stages of validation and discovery, as well as any encountered error conditions to aid in troubleshooting your target configurations. Related targets are also shown where applicable. Follow the instructions below to configure your target using the new view.



NOTE:

To switch to the old target experience, navigate to **Settings > Target Configuration** and turn off **New View** at the top-right section of the page. For information on the standard view, see <u>Configuring Targets</u> (on page 114).

To configure a target, you will choose the target type, specify the target's address or key, and then provide credentials to access the target. Workload Optimization Manager then discovers and validates the target, and then updates the supply chain with the entities that the target manages.

NOTE:

Workload Optimization Manager regularly checks the status of your targets. If target discovery or validation fails, the Target Configuration page updates the status. Under some circumstances, the target can become discoverable or valid again, but the status does not update. In this case, select the target and then click **Rediscover** or **Validate**.

For a list of supported targets and configuration requirements, see Target Configuration (on page 135).

Configuring a target using the enhanced view

1. Navigate to the Settings page.



Click to navigate to the Settings page. From there, you can perform a variety of Workload Optimization Manager configuration tasks.


2. Choose Target Configuration.



Target Configuration

Click to navigate to the Target Configuration Page.


3. Review the list of targets.



This page lists all the targets that you currently have configured for Workload Optimization Manager in a sortable table. The table is sorted by target health by default. You can inspect or edit these targets, or add a new target.


4. Filter the list of targets.





For a long list of targets, you can:

- a. Filter targets by target type.
- b. Use Search to filter targets by Target Name using a text string (partial matching is supported).
- c. Use Filter to filter targets by status (for example, only show validated targets). You can also use Filter to filter targets by target type or health.
- 5. Select one or more targets to work with.



When you select a target you can:

Rediscover


Direct Workload Optimization Manager to fully discover the entities that this target manages. This will rebuild the topology that is associated with this target.

Delete

When you delete a target, Workload Optimization Manager removes all the associated entities from the supply chain.

6. View or edit the target details by clicking the icon under the **Details** column.






Use the target details page to view or edit target details. In addition to target details, this page shows the last discovered and last modified dates, target health, state, and any related targets.


NOTE:

A value of "N/A" in the Last Modified column indicates that the target is a derived target, and therefore the details cannot be edited.



7. Create a new target and add it to Workload Optimization Manager.






Click **New Target**, select the target category and type, and then provide the address and credentials for that target.

After you add the target, the Target Configuration page refreshes to show the current validation status.

- Validating
 - Validation is in progress.
- Validated
 - Validation was successful. Workload Optimization Manager can now monitor the target and will start discovering the entities that the target manages.
- Validation Failed
 - Validation was unsuccessful. Expand the target to see additional information.



Supply Chain of Entities



To perform Application Resource Management, Workload Optimization Manager models your environment as a market of buyers and sellers linked together in a supply chain. This supply chain represents the flow of resources from the datacenter, through the physical tiers of your environment, into the virtual tier and out to the cloud. By managing relationships between these buyers and sellers, Workload Optimization Manager provides closed-loop management of resources, from the datacenter, through to the application.

Reading the Supply Chain

By looking at the Supply Chain, you can see:

- How many entities you have on each tier
 Each entry in the supply chain gives a count of entities for the given type.
- The overall health of entities in each tier

The ring for each entry indicates the percentage of pending actions for that tier in the datacenter. Ring colors indicate how critical the actions are - Green shows the percentage of entities that have no actions pending. To get actual counts of pending actions, hover on a ring to more details.



The flow of resources between tiers


The arrow from one entry to another indicates the flow of resources. For example, the Virtual Machine entry has arrows to Hosts and to Storage. If the VMs are running in a Virtual Data Center, it will have another arrow to that as well. This means that your VMs consume resources from hosts, storage, and possibly from VDCs.

Listing Entities From the Home Page

The Supply Chain shows the relationships of entities in your environment. When you're on the **Home Page** with a global scope, the supply chain filters its display according to the view you have chosen:

- APPLICATIONS All your Business Applications (on page 325)
- ON-PREM All your on-prem entities
- CLOUD All your entities on the public cloud

To see a list of entities, click an entity tier in the Supply Chain.



Working With a Scoped View

By default, the **Home Page** shows a Global view of your environment. To drill down into specifics of your environment, you can set a scope to your Workload Optimization Manager session. A scoped view shows details about the specific entities in that scope.

Once you have set a scope, you can use the Supply Chain to zoom in on a related tier to see details about the entities on that tier.

If you find the current scope to be useful, you can save it as a named group. Using named groups is an easy way to return to different scopes that you have saved.

Things You Can Do

- Scoping the Workload Optimization Manager Session (on page 124)
- Navigating With the Supply Chain (on page 133)
- Viewing Cluster Headroom (on page 134)

Scoping the Workload Optimization Manager Session

The default scope for the **Home Page** shows an overview of the global environment. What if you want to focus on less than the global environment? Assume you are responsible for a subset of workloads in your environment. This could be:

Workloads managed on a single host cluster



- The workloads in a single datacenter
- A custom group of workloads you have created in Workload Optimization Manager


It's easy to set the session scope so that Workload Optimization Manager zooms in on the part of the environment that you want to inspect. Once you set the scope, you can get a quick picture of system health for that scope. If you find a certain scope to be useful, you can save it as a named group that you can return to later.

1. Navigate to the Search Page.



Click to navigate to the Search Page. This is where you can choose the scope you want.

2. Choose the type of entities to search.



In the Search Page, choose a type of entities that you want to search through. Find the list of entity types on the left. Select **All** to search the complete environment. Or you can focus on entities by type, by groups, or by clusters. When you select an entity type, the page updates to show all entities of that type.

3. Use **Search** to filter the listing.

For example, if you're showing **All** and you search for "Development", then you will see all clusters, groups, and entities with "Development" in their names.



4. Expand an entry to see details.

For example, expand a group or an entity to see utilization details and pending actions.

NOTE:


For hosts in the public cloud, utilization and capacity for host and datacenter resources don't affect Workload Optimization Manager calculations. When you expand an entry for a public cloud host, the details do not include information for these resources.





- 5. Select one or more entries to set the focus of the Home Page.
 - Choose an entity type on the left, and set the scope to one or more of those entities.
 - For different types of groups, click to set a single group as your scope.


If you choose a category of entities to limit the list, then you can select one or more of the entities for your session scope. After you select the entities you want to include in your scope, click **SCOPE TO SELECTION** to set the session scope to those entities.



If you choose Groups or Clusters, then you can select a single entry to set the scope for your session. When you select an entry in the list, that sets the focus of the **Home Page**. For example, if you select a cluster in the **Search** listing, you set the **Home Page** focus to that cluster. Use the **Home Page** bread crumbs to set a different scope, or you can return to **Search** and set a different scope from there.



Overview Charts



The Overview Charts show your environment's overall operating health for the current session scope. A glance at the Overview gives you insights into service performance health, overall efficiency of your workload distribution, projections into the future, and trends over time.

The charts in this view show data for the current scope that you have set for the Workload Optimization Manager session. For the global scope, the charts roll up average, minimum, and peak values for the whole environment. When you reduce the scope (for example, set the scope to a cluster), the charts show values for the entities in that scope.

Some charts included in this view are:

- Pending Actions
 - See all the actions that are pending for the current scope.
- Health
 - Quickly see the health of the entities in this scope- How many entities have risks, and how critical the risks are.
- Optimized Improvements
 - A comparison of utilization in your environment before executing the pending actions, and then after.
- Capacity and Usage
 - This chart lists resources that are used by the current scope of entities, showing utilization as a percentage of the capacity that is currently in use.
- Multiple Resources
 - See the utilization over time of various resources that are used by the current scope of entities.
- Top Entities
 - For example, Top Virtual Machines. These charts list the top consumer entities in the current scope.
- Risks Avoided
 - Each action addresses one or more identified risks or opportunities in your environment. This chart shows how many risks have been addressed by the executed actions.
- Accepted Actions
 - This chart shows how many actions have been executed or ignored, and whether they have been executed manually or automatically.



What You Can Do:


- Set scope: See <u>Scoping the Workload Optimization Manager Session</u> (on page 124)
- Create new charts: See <u>Creating and Editing Chart Widgets</u> (on page 614)

Setting Chart Focus

The charts update to reflect the focus that you have set for your viewing session. While viewing the Overview Charts, you can set the focus in different ways:

- Set Supply Chain Focus
 Choose a tier in the supply chain to set the view focus see <u>Navigating With the Supply Chain (on page 133)</u>
- Use **Search** to set the scope of the viewing session see <u>Scoping the Workload Optimization Manager Session</u> (on page 124)

Chart Time Frame



You can set a time frame from recent hours to the past year (1), and set that to the charts in the view. Use the Time Slider to set specific start and end times within that range (2). The green section in the slider shows that you can set the time range to include a projection into the future. For this part of the time range, charts show the results you would see after you execute the current set of pending actions.

For most charts, you can also configure the chart to hard-code the time range. In that case, the chart always shows the same time scale, no matter what scale and range you set for the given view.

Note that Workload Optimization Manager stores historical data in its database. As you run Workload Optimization Manager in your environment for more time, then you can set a time range to show more history.

Details View

The Details View shows more details about the entities in your session scope. These charts focus on the utilization of resources by these entities, so you can get a sense of activity in that scope over time.





What You Can Do:

- Set scope: See <u>Scoping the Workload Optimization Manager Session</u> (on page 124)
- Create new charts: See <u>Creating and Editing Chart Widgets (on page 614)</u>


Setting Chart Focus

The charts update to reflect the focus that you have set for your viewing session. While viewing the Overview Charts, you can set the focus in different ways:

- Set Supply Chain Focus
 Choose a tier in the supply chain to set the view focus see Navigating With the Supply Chain (on page 133)
- Set Scope

Use **Search** to set the scope of the viewing session - see <u>Scoping the Workload Optimization Manager Session</u> (on page 124)

Chart Time Frame




You can set a time frame from recent hours to the past year (1), and set that to the charts in the view. Use the Time Slider to set specific start and end times within that range (2). The green section in the slider shows that you can set the time range to include a projection into the future. For this part of the time range, charts show the results you would see after you execute the current set of pending actions.

For most charts, you can also configure the chart to hard-code the time range. In that case, the chart always shows the same time scale, no matter what scale and range you set for the given view.

Note that Workload Optimization Manager stores historical data in its database. As you run Workload Optimization Manager in your environment for more time, then you can set a time range to show more history.



Scope Policies



The Policy View gives you a look at the Automation Policies that are set for the entities in the current scope. For each policy, you can see whether it is enabled. In addition,

1. To create a policy, click **New Policy**. When you create a new policy, it automatically includes the current scope. You can add other groups to the policy scope.

NOTE:

You can enable more than one policy for the same scope. If two policies apply different values for the same setting, then the most conservative value takes effect.

- 2. To edit a policy, click the policy name. You can then change the policy settings and whether the policy is enabled.
- 3. To see the current policy settings, expand a settings category. For each setting, you can see which policy determines the value either the default policy or a custom policy that is applied to this scope.

For more information, see Automation Policies (on page 677).

Entity Placement Constraints



When you drill down to a single entity, you can see details about the entity's relationships in the supply chain. This shows you which entities provide resources to this entity. When considering providers for this entity, you can see the name of each current provider, and how many alternative providers Workload Optimization Manager can choose from if the current one becomes overutilized.




Reviewing the constraints on an entity helps you understand the actions that Workload Optimization Manager recommends. If an action seems questionable to you, then you should look at the constraints on the affected entities. It's possible that some policy or constraint is in effect, and it keeps Workload Optimization Manager from recommending a more obvious action.

Experimenting With Placement Constraints

For each provider or consumer in the list, you can open a **Constraints** fly-out that gives more details about limits on the current element's supply chain relationships.

For example, assume the **PROVIDERS** list shows your VM's **CURRENT PLACEMENT** is on Host A, and for **OTHER POTENTIAL PLACEMENT** you see that Workload Optimization Manager can choose from 4 hosts. When you click **Constraints**, the flyout displays a list of host constraints that currently result in the four potential hosts (1) for this VM.



The list information includes:

■ CONSTRAINT TYPE

Most constraints are boundaries that are inherent in your environment such as a cluster boundaries or a networks, or the can be constraint rules such as discovered HA or DRS rules authored Workload Optimization Manager placement policies (sometimes called *segments*)

■ SCOPE NAME

For a given rule or constraint, the scope to which it was applied.

SOURCE


If this is a discovered constraint, the source shows the type of target that imposes this constraint. For example, for a DRS rule the source will be vCenter.

■ POTENTIAL HOSTS

For the given constraint, how many hosts that constraint allows. To see a list of the potential hosts, click the POTENTIAL HOSTS value.


To dig deeper into how these constraints affect your entity, click **FIND MORE PLACEMENT OPTIONS** (2). This puts you into a simulation mode that you can use to experiment with changing the effective constraints. For example, you might see that a cluster boundary is limiting your placement possibilities, and you would like the option to place the current VM on other clusters. Armed with this information, you could navigate to Policies and create a Merge Cluster policy.





In this mode you can enable and disable different combinations of constraints (1). As you do, the **POTENTIAL HOSTS** (2) label updates to show how many hosts are available to your entity. For example, by turning off the 4-Host constraints, you have 12 potential hosts for this VM. To see the resulting list of hosts, click the **POTENTIAL HOSTS** label (3).

List of Entities



The list of entities is a quick way to drill down to details about your environment.


1. You can sort the list of entities by various categories.



2. You can see specifics about resource consumption or state. For example, you can see the amount of capacity that has been assigned to a VM that is currently idle.

This list always updates to reflect the focus you have selected in the Supply Chain Navigator. When you select an entity type in the supply chain, the entities list updates to show the entities of that type for your current scope. For example, select Host to see a list of hosts in the current scope. For more information, see Navigating with the Supply Chain (on page 133).

Navigating With the Supply Chain



After you have set the scope of your Workload Optimization Manager session, you can use the Supply Chain to change the focus of the main view, and see details about different types of entities within the current scope.

Drilling Down in a Scoped Session

When you set a scope to your Workload Optimization Manager session, the **Home Page** shows information about your environment, including:


- Overview
 - Charts and lists to give you an overview of your environment for the current scope. This overview corresponds to all the entities in scope.
- Details Charts that give you a more detailed look at your environment for the given scope
- Policies Any policies that are defined for the entities in the current scope
- Entity Lists Details about the entities in the current scope
- Pending Actions Actions that are pending for any entities in the current scope

The Supply Chain shows the currently selected tier of entities. The change the focus of the scoped view, select different tiers in the Supply Chain. The Policies, Entities List, and Pending Actions tabs update to focus on the tier you selected. These tabs show information for all the entities of that type that are in the current scope. For example, if you click the Host tier, these tabs update to show information about the hosts in your current scope.



To zoom in on a specific entity, you can click its name in the Entities List. This sets the scope to that specific entity. To return to the previous scope, use the browser's **Back** button.

Viewing Cluster Headroom



Cluster headroom shows you how much extra capacity your clusters have to host workloads. When you set the scope to a cluster, the **Home Page** then includes charts that show headroom for that cluster, as well as time to exhaustion of the cluster resources.

To view cluster headroom:

- 1. Navigate to the Search page.
- 2. Choose the Clusters category.
- 3. Select the cluster you want to view.
- When the Home Page displays, scroll down to show the headroom charts.

Make sure you have selected the Host tier in the supply chain navigator.

To calculate cluster capacity and headroom, Workload Optimization Manager runs nightly plans that take into account the conditions in your current environment. The plans use the Economic Scheduling Engine to identify the optimal workload distribution for your clusters. This can include moving your current VMs to other hosts within the given cluster, if such moves would result in a more desirable workload distribution. The result of the plan is a calculation of how many more VMs the cluster can support.

To calculate VM headroom, the plan simulates adding VMs to your cluster. The plan assumes a certain capacity for these VMs, based on a specific VM template. For this reason, the count of VMs given for the headroom is an approximation based on that VM template.

To specify the templates these plans use, you can configure the nightly plans for each cluster. For more information, see Configuring Nightly Plans (on page 596)



Target Configuration

A target is a service that performs management in your virtual environment. Workload Optimization Manager uses targets to monitor workload and to execute actions in your environment. Target Configuration specifies the ports Workload Optimization Manager uses to connect with these services. You must install Workload Optimization Manager on a network that has access to the specific services you want to set up as targets.

For each target, Workload Optimization Manager communicates with the service via the management protocol that it exposes – The REST API, SMI-S, XML, or some other management transport. Workload Optimization Manager uses this communication to discover the managed entities, monitor resource utilization, and execute actions.

NOTE:

Workload Optimization Manager does not support duplicate instances of the same target. When configuring targets, you must not configure two or more targets to the same address in your environment. For example, you must not configure two different targets to the same AWS account, nor two targets to the same vCenter Server instance.

If you do configure duplicate targets, then actions can fail to execute with an error that begins: Analysis Exception occurred...

To resolve this issue, identify the duplicate targets, and delete them until you have only one target for each address.

End-of-life (EOL) notice: When a specific release or version of an integration partner technology reaches end-of-life (EOL) or its end of support date, Workload Optimization Manager no longer provides support for that version. Workload Optimization Manager follows integration partners' official EOL timeline for version support. Targeting a non-supported version, or one that is no longer supported by the vendor, is at your own risk.

You can assign instances of the following technologies as Workload Optimization Manager targets.

- Applications and Databases
 - Apache Tomcat 7.x, 8.x, and 8.5.x
 - AppDynamics 4.1+
 - Applnsights
 - Datadog
 - Dynatrace 1.1+
 - IBM WebSphere Application Server 8.5+
 - Instana release-242 or later
 - JBoss Application Server 6.3+
 - JVM 6.0+
 - SQL Server 2012, 2014, 2016, 2017, 2019, and 2022
 - MySQL 5.7.x
 - NewRelic
 - Oracle 11g R2, 12c, 18c, and 19c



- Oracle WebLogic 12c
- Cloud Native
 - Kubernetes, including any compliant k8s distribution (Rancher, Tanzu, open source, etc.)
 - Cloud-hosted k8s services (AKS, EKS, GKE, IBM, Cisco IKS, ROKS, ROSA, etc.)
 - Red Hat OpenShift 3.11 and higher (OCP 4.x)
- Fabric and Network
 - Cisco UCS Manager 3.1+
 - HPE OneView 3.00.04
- Guest OS Processes
 - SNMP
 - WMI: Windows versions 8 / 8.1, 10, 2008 R2, 2012 / 2012 R2, 2016, 2019 and 7
- Hyperconverged
 - Cisco HyperFlex 3.5
 - Nutanix Community Edition
 - VMware vSAN
- Hypervisors
 - IBM PowerVM 8, 9, 10
 - Microsoft Hyper-V 2008 R2, Hyper-V 2012/2012 R2, Hyper-V 2016, Hyper-V 2019
 - VMware vCenter 7.0 and 8.0
- Orchestrator
 - ActionScript
 - Flexera One
 - ServiceNow
- Private Cloud
 - Microsoft System Center 2012/2012 R2 Virtual Machine Manager, System Center 2016 Virtual Machine Manager, and System Center Virtual Machine Manager 2019
- Public Cloud
 - Amazon AWS
 - Amazon AWS Billing
 - Google Cloud Platform (GCP)
 - GCP Billing
 - Microsoft Azure Service Principal
 - Azure Billing
 - Microsoft Enterprise Agreement
- Storage
 - EMC ScaleIO 2.x and 3.x
 - EMC VMAX using SMI-S 8.1+
 - EMC VPLEX Local Architecture with 1:1 mapping of virtual volumes and LUNs
 - EMC XtremIO XMS 4.0+
 - HPE 3PAR InForm OS 3.2.2+, 3PAR SMI-S, 3PAR WSAPI
 - IBM FlashSystem running on Spectrum Virtualize 8.3.1.2 or later (8.4.2.0 or later recommended)
 - NetApp Cluster Mode using ONTAP 8.0+ (excluding AFF and SolidFire)
 - Pure Storage F-series and M-series arrays running Purity 5.3.6 (Pure API 1.6)
- Virtual Desktop Infrastructure
 - VMware Horizon



Transport Layer Security Requirements

Workload Optimization Manager requires Transport Layer Security (TLS) version 1.2 to establish secure communications with targets. Most targets should have TLS 1.2 enabled. However, some targets might not have TLS enabled, or they might have enabled an earlier version. In that case, you will see handshake errors when Workload Optimization Manager tries to connect with the target service. When you go to the Target Configuration view, you will see a Validation Failed status for such targets.

If target validation fails because of TLS support, you might see validation errors with the following strings:

- No appropriate protocol
 - To correct this error, ensure that you have enabled the latest version of TLS that your target technology supports. If this does not resolve the issue, please contact Cisco Technical Support.
- Certificates do not conform to algorithm constraints

To correct this error, refer to the documentation for your target technology for instructions to generate a certification key with a length of 2048 or greater on your target server. If this does not resolve the issue, please contact Cisco Technical Support.

Adding and Removing Targets

The target services your Workload Optimization Manager installation will manage appear in the Target Configuration list. You can add, remove, and edit entries in this list. Note that the target service's account must be configured with privileges that support the Workload Optimization Manager activities you want to perform. For example, the following list shows how vCenter privileges correspond to activities Workload Optimization Manager can perform:

- Read Only Enables Workload Optimization Manager monitoring and simulation (what-if scenarios) only
- vCenter Administrator Enables Workload Optimization Manager monitoring, simulation (what-if scenarios), and automation functions
- Enable Datastore Browse Enabling this property for the account gives Workload Optimization Manager the privileges it needs to enable its storage management functionality

Adding Targets

To add a target service, click the **Target Configuration** button, provide the requested information, and click **Apply** to validate those targets and start a new discovery.

NOTE:

As you add targets, be sure not to add duplicate entries for the same target.

Typical information you provide includes:

- Target Type Choose among the supported technologies
 - After you choose the technology, then choose the specific target type for that technology. For example, for Cloud Management, you can choose AWS.
- Hostname or IP address The address of the target service you want to add
- User Name A valid account username for the target service
- Password A password for the target service account

Removing Targets

To remove a target, select the entry in the list and then click **Delete**.

Applications and Databases Targets

Applications and Databases targets support domains of particular application servers that are controlled by management servers. For such managed domains you will add the management server as a target, and Workload Optimization Manager will discover the managed application servers.



NOTE:

As it manages your applications environment, Workload Optimization Manager discovers connected application components to stitch them into a supply chain of entities. For connections that are made by name and not IP address, Workload Optimization Manager makes DNS calls to resolve these names to IP addresses. This can happen during repeated discovery cycles.

Supply Chain

Applications and Databases targets add Business Application, Business Transaction, Service, Application Component, Application Server, and Database Server entities to the supply chain. You can navigate to the associated target page to see how these entities map to the target nomenclature.

Apache Tomcat

Workload Optimization Manager supports connecting to individual Tomcat targets. Workload Optimization Manager connects to the Tomcat process as a remote client via remote JMX access. Target configuration includes the port used by the JMX/RMI registry.

Prerequisites

- A valid JMX user account for the Tomcat server.
 - If Tomcat security is enabled, this must be a Tomcat JMX user with a readonly role.
- Tomcat should run on JVM version 7 or 8
- For VMware environments, VMware Tools must be installed on the VM that hosts the Tomcat server. For Hyper-V
 environments, Hyper-V Integration Services must be installed.
 - This ensures that the VM hosting the Tomcat server can get its IP address.
- Remote JMX access is enabled through a port that is opened to the firewall.
- Discovered infrastructure.

Workload Optimization Manager discovers Tomcat servers that are running on VMs or containers. The hosting VM or container must already be in your Workload Optimization Manager inventory.

To set the target for a server running on a VM, you must have first discovered the hosting VM through a Hypervisor target. To set the target for a server running in a container, you must have configured container discovery for Tomcat applications.

- For information about container targets, see <u>Kubernetes Platform Targets (on page 180)</u>
- For information about hypervisor targets, see <u>Hypervisor Targets (on page 205)</u>

Configuring JMX Remote Access

Workload Optimization Manager monitors and controls the Tomcat server via JMX Remote access. You must configure a JMX Remote port.

Note that to work with a firewall you should also set the RMI Server port – If you don't set an RMI port, then JMX sets an arbitrary *ephemeral port*, and you can't guarantee that the port will be open to your firewall.

There are two ways to set JMX Remote port on Linux platforms:

Ports specified as system properties

You can set the port via the system property, com.sun.management.jmxremote.port. For example:

```
com.sun.management.jmxremote.port=8050
```

A common way to set this property is to declare it in the CATALINA_OPTS system variable — You can set this in the setenv.sh script. For example:

```
CATALINA_OPTS="$CATALINA_OPTS
```

-Dcom.sun.management.jmxremote



-Dcom.sun.management.jmxremote.port=8050"

export CATALINA_OPTS

Note that this sets the JMX Remote port, but it does not set the RMI Server port – Tomcat startup will specify an ephemeral port for the RMI server.

Ports specified in a JMX Remote Lifecycle Listener

This listener component fixes the ports used by the JMX/RMI Server. When you configure the listener, you specify both the JMX Remote port and the RMI Server port. This is the preferred method when working with a firewall. For more information, see the Apache Tomcat documentation.

On Windows, the typical installation is with Tomcat as a service. There are two ways to set the JMX Remote port:

Via setenv.bat

Add the property to the CATALINA_OPTS environment variable:

```
set "CATALINA_OPTS=%CATALINA_OPTS% -Dcom.sun.management.jmxremote.port=8050"
```

Use the Tomcat configuration utility (tomcat7w or tomcat8w)

Set the port with the following command:

```
-Dcom.sun.management.jmxremote.port=8050"
```

To discover the JMX port that is set to an already running Tomcat, you can look in the following locations:

- For Linux platforms, look in the configuration files Either:
 - setenv.sh Assuming you configured the port by adding it to the CATALINA_OPTS environment variable
 - \$CATALINA_HOME/conf/server.xml Assuming you configured a JMX Remote Lifecycle Listener in this file
- For Windows platforms, look in:
 - setenv.bat Assuming you configured the port by adding it to the CATALINA_OPTS environment variable
 - The Windows registry Assuming you installed Tomcat as a Windows service using the Tomcat Configuration utility

Adding a Tomcat Target

You can add an individual Tomcat server as a target, or you can add all matching servers within a given scope.

To add a server as a target, specify:

Target Name

Name displayed in the Workload Optimization Manager UI

■ Username

Username of an account with the Admin role

Password

Password of an account with the Admin role

Scope

A group of applications, stitched to the underlying VMs when the VMs are discovered as part of a separate Workload Optimization Manager target.

If you set the target scope, Workload Optimization Manager scans each VM within that group or cluster and tries to connect to the target over the specified port. Workload Optimization Manager adds any instances of the target it finds as entities from which metrics are retrieved.

The maximum supported size of the group is 500 VMs, and the recommended size is 250 VMs. Adding more VMs to the group can result in poor performance for discovery and monitoring. To target a larger number of VMs by scope, you should split them across smaller groups and set each group as the scope for a separate target.

■ JMX Remote Port

A JMX port that is set to an already running Tomcat process.



Full Validation

When selected, Workload Optimization Manager will require all database servers hosted on the VMs in the selected scope to be a valid target. If Workload Optimization Manager is unable to authenticate a database server in the scope, the target will not validate and data will not be collected.

Proxy Host

The address of the proxy used for this target. Only fill out proxy information if you connect to the AppDynamics instance via a proxy.

Proxy Port

The port to use with the proxy specified above. By default, this is 8080.

Proxy Username

The username to use with the proxy specified above.

Proxy Password

The password to use with the proxy specified above.

Secure Proxy Connection

When checked, Workload Optimization Manager will connect to the proxy via HTTPS.

Monitored Resources

Workload Optimization Manager monitors the following resources:

Application Component

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Heap

Heap is the portion of a VM or container's memory allocated to individual applications.

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Threads

Threads is the measurement of thread capacity utilized by applications.

Connection

Connection is the measurement of database connections utilized by applications.

Remaining GC Capacity

Remaining GC capacity is the measurement of Application Component uptime that is *not* spent on garbage collection (GC).

Virtual Machine

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Actions

Workload Optimization Manager can recommend the following actions:

- Application Component (Tomcat Application)
 - Resize Heap



This action can only be executed outside Workload Optimization Manager.

Resize Thread Pool

This action can only be executed outside Workload Optimization Manager.

Resize Connection Capacity

This action can only be executed outside Workload Optimization Manager.

Virtual Machine

- Provision additional resources (VMem, VCPU)
- Move Virtual Machine
- Move Virtual Machine Storage
- Reconfigure Storage
- Reconfigure Virtual Machine
- Suspend VM
- Provision VM

Application Insights

Workload Optimization Manager supports workload management of the application infrastructure monitored by Application Insights via the Workload Optimization Manager integration, which provides a full-stack view of your environment, from application to hosting server. With information obtained from Application Insights, Workload Optimization Manager is able to make recommendations and take actions to both assure performance and drive efficiency with the full knowledge of the demands of each individual application.

Prerequisites

A valid Application Insights user account with the same permissions detailed for Microsoft Azure (on page 268) targets.

Adding an Application Insights Target

NOTE:

If an application is monitored by Application Insights or Azure, do not add it as a separate Workload Optimization Manager application target.

To add Application Insights as a target, specify:

Unique Target Description

A user-created name that will appear in the Workload Optimization Manager UI.

Tenant Name

The tenant associated to the Azure subscription associated to Application Insights.

Azure Subscription ID

The ID of the Azure subscription with access to the Azure target associated to Application Insights.

■ Client ID

The Client ID of the App registration that gives Workload Optimization Manager access to resources in your Azure subscription.

Client Secret Key

The secret key for the App registration.

Offer ID

If applicable, the Azure Offer ID related to the Azure subscription.

■ Enrollment Number

If an Azure EA account, the enrollment number associated to the Azure subscription.

Proxy Host



The address of the proxy used for this target. Only fill out proxy information if you connect to the AppDynamics instance via a proxy.

Proxy Port

The port to use with the proxy specified above. By default, this is 8080.

Proxy Username

The username to use with the proxy specified above.

Proxy Password

The password to use with the proxy specified above.

Secure Proxy Connection

When checked, Workload Optimization Manager will connect to the proxy via HTTPS.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

Application Insights	Workload Optimization Manager
Application	Application Component

Stitching Application Insights Applications to the Workload Optimization Manager Environment

Each application monitored by Application Insights can have several associated applications, and each of these applications can be deployed on a different hosting server. Likewise, a hosting server may host multiple groups or partial groups of multiple applications.

In order to accurately stitch metrics from Application Insights, the host name or IP address of the hosting server must be discoverable through the Application Insights instance. For most monitored application instances, this is automatic. If the hosting server is not discoverable, Azure tags on the application can be provided to indicate the IP address or hostname.

You can provide an Azure tag in the following name: value format:

CWOM-Host-Name: RoleInstance=hostname; RoleInstance=hostname; RoleInstance=hostname;

In the preceding example, RoleInstance is the name of the application instance, and hostname is the hosting server. For example: CWOM-Host-Name : cluster-app-a=120.120.120.10; cluster-app-b=120.120.120.121; cluster-app-c=120.120.120.12;.

NOTE: If these tags are provided, they will replace any values discovered through the Application Insights API.

Monitored Resources

Workload Optimization Manager monitors the following resources:

NOTE:

The exact resources monitored will differ based on application type. This list includes all resources you may see.

Application Component

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).



Actions

NOTE:

The specific actions that Workload Optimization Manager recommends can differ, depending on the processes that Workload Optimization Manager discovers.

For other application components, Workload Optimization Manager can recommend actions based on the resources it can discover for the application. For example, Node.js® applications report CPU usage, so Workload Optimization Manager can generate vCPU resize actions and display them in the user interface.

Workload Optimization Manager can recommend the following actions:

Application Component

- Suspend VM
 - This action can only be executed outside Workload Optimization Manager.
- Provision VM

This action can only be executed outside Workload Optimization Manager.

Cisco AppDynamics

Workload Optimization Manager supports workload management of the application infrastructure monitored by AppDynamics, via adding the AppDynamics instance to Workload Optimization Manager as a target.

The Workload Optimization Manager integration with AppDynamics provides a full-stack view of your environment, from application to physical hardware. With information obtained from AppDynamics, Workload Optimization Manager is able to make recommendations and take actions to both assure performance and drive efficiency with the full knowledge of the demands of each individual application.

In its default configuration, the AppDynamics target will collect up to 1100 AppDynamics nodes within the default collection period when a proxy is used, and up to 5000 nodes when no proxy is required. Larger AppDynamics environments are expected to take longer than one cycle to collect complete data.

NOTE:

For Kubernetes environments, Workload Optimization Manager stitches New Relic, AppDynamics, Instana, and Dynatrace containerized application components into the supply chain to provide a unified view of your applications. For more information, see <u>Cloud Native Targets (on page 180)</u>.

Prerequisites

A valid AppDynamics user account.

For all types of application instances, the service account must have the Read Only User role. For monitoring database instances, this user must also have the DB Monitoring User role.

NOTE

In newer versions of AppDynamics where these roles are available, they should be used instead:

- Applications and Dashboards Viewer
- DB Monitoring User
- Server Monitoring

To use a custom role, ensure that the role has the View Server Visibility permission for both applications and databases.

AppDynamics Database Servers

AppDynamics also monitors database servers. In order for your database servers to be correctly stitched to the rest of your environment, you must:

Enable enhanced metric collection.

For Hyper-V hosts, you must install Hyper-V Integration Services on the target VM hosting the database. For more information, please refer to the following integration services TechNet article:



https://technet.microsoft.com/en-us/library/dn798297%28v=ws.11%29.aspx

For VMware hosts, you must install VMware Tools on the target VMs.

 Ensure that the database name in AppDynamics is resolvable to an IP address by the Workload Optimization Manager instance.

You may need to make changes to your DNS or the file /etc/resolv.conf on the Workload Optimization Manager instance.

Adding an AppDynamics Target

NOTE:

It is possible to monitor certain applications or database servers with both AppDynamics and Workload Optimization Manager, but this must be avoided as it will cause the entities to appear duplicated in the market.

If an application is monitored by AppDynamics, do not add it as a separate Workload Optimization Manager application target.

To add an AppDynamics instance as a target, specify:

Hostname or IP Address

The host name or IP Address of the AppDynamics controller instance.

Port

the port used to connect to the AppDynamics controller. By default, this is set to ports 80 (HTTP) and 443 (HTTPS).

NOTE: For SaaS-based AppDynamics instances, you must use port 443.

■ Username or API Client Name@Account

Username and account ID with the necessary role(s). The format must be *Username@Tenant*, and the user must have the "Read Only User" and "DB Monitoring User" permissions. This username can be found on the "License > Account" page in AppDynamics. For oAuth authentication, the username must be a user defined as an API Client.

NOTE:

The username and password cannot contain any of the following special characters:

Password or Client Secret

Password for the account used to connect to the AppDynamics instance. For oAuth, this will be the client secret key.

NOTE

The username and password cannot contain any of the following special characters:

Collect Virtual Machine Metrics

Whether to collect VM metrics from this target. When **Collect Virtual Machine Metrics** is turned on, Workload Optimization Manager uses the VM metrics it collects from this target, instead of the VM data that can optionally be collected from related infrastructure targets.

■ Secure Connection

When checked, Workload Optimization Manager will connect via HTTPS. Make sure the required certificate is configured for use on the host.

Use API Client (OAuth)

When checked, enables Open Authorization (OAuth) token-based authentication for the target connection.

Proxy Host

The address of the proxy used for this target. Only fill out proxy information if you connect to the AppDynamics instance via a proxy.

Proxy Port

The port to use with the proxy specified above. By default, this is 8080.

Proxy Username



The username to use with the proxy specified above.

Proxy Password

The password to use with the proxy specified above.

Secure Proxy Connection

When checked, Workload Optimization Manager will connect to the proxy via HTTPS.

For more information about creating API client users, see the AppDynamics Documentation.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

AppDynamics	Workload Optimization Manager
Business Application	Business Application
Business Transaction	Business Transaction
Tier	Service
Node	Application Component
Database	Database Server
Machine (when the machine type is Container)	Container
Server	Virtual Machine

Monitored Resources

Workload Optimization Manager monitors the following resources:

NOTE

The exact resources monitored will differ based on application type. This list includes all resources you may see.

Business Application

- Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Business Transaction

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Service

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

For Kubernetes, this is the desired *weighted average* response time of all Application Component replicas associated with a Service.

- Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.



For Kubernetes, this is the maximum number of transactions per second that each Application Component replica can handle.

■ Application Component

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

This commodity applies to Java, .NET, and Node.js only.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

This commodity applies to Java, .NET, and Node.js only.

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Heap

Heap is the portion of a VM or container's memory allocated to individual applications.

This commodity applies to Java, .NET, and Node.js only.

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Connection

Connection is the measurement of database connections utilized by applications.

Remaining GC Capacity

Remaining GC capacity is the measurement of Application Component uptime that is *not* spent on garbage collection (GC).

Threads

Threads is the measurement of thread capacity utilized by applications.

Database Server

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

This commodity applies to SQL, MySQL, and Oracle only.

- Connection

Connection is the measurement of database connections utilized by applications.

This commodity applies to MongoDB only.

- Transaction Log

Transaction log is the measurement of storage capacity utilized by a Database Server for transaction logging.

This commodity applies to SQL only.

DB Cache Hit Rate

DB cache hit rate is the measurement of Database Server accesses that result in cache hits, measured as a percentage of hits versus total attempts. A high cache hit rate indicates efficiency.

This commodity applies to SQL and Oracle only.

Virtual Machine

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

NOTE:

To collect data, a machine agent must be present and database hardware monitoring must be enabled.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.



NOTE:

To collect data, a machine agent must be present and database hardware monitoring must be enabled.

For a given VM, the resources you see depend on how the VM is discovered, and whether the VM provides resources for an application discovered by this target:

- If the VM hosts an application that is discovered through this target, then you will see VM metrics discovered through this target.
- If the VM is discovered through a different target, and it does not host any application discovered through this target, then you will see VM metrics discovered through that different target.
- If the VM is discovered through this target, but it does not host any application discovered through this target, then Workload Optimization Manager does not display metrics for the VM.

Actions

NOTE:

The specific actions that Workload Optimization Manager recommends can differ, depending on the processes that Workload Optimization Manager discovers.

For other application components, Workload Optimization Manager can recommend actions based on the resources it can discover for the application. For example, Node.js® applications report CPU usage, so Workload Optimization Manager can generate vCPU resize actions and display them in the user interface.

Workload Optimization Manager can recommend the following actions:

Database Server

- Resize Database Memory (DBMem)
 - This action can only be executed outside Workload Optimization Manager.
- Resize Connections

This action can only be executed outside Workload Optimization Manager.

NOTE:

For different types of Database Servers, the AppDynamics target returns different metrics. This affects Workload Optimization Manager actions as follows:

MySQL:

For MySQL database servers, analysis does not generate resize actions for DB Memory, Connections, or Transaction Log. The target does not discover DB Cache Hit Rate, DB Memory, Connections, or Transaction Log.

■ SQL Server:

For SQL database servers, analysis does not generate resize actions for DB Memory, Connections, or Transaction Log. The target does not discover DB Memory or Connections.

■ MongoDB:

For MongoDB database servers, analysis does not generate resize actions for DB Memory, Connections, or Transaction Log. The target does not discover DB Cache Hit Rate, DB Memory, Transactions, or Transaction Log.

Oracle

For Oracle database servers, analysis does not generate resize actions for DB Memory, Connections, or Transaction Log. The target does not discover DB Memory, Connections, or Transaction Log.

Datadog

The Workload Optimization Manager-Datadog integration combines application performance data with infrastructure data that Workload Optimization Manager collects from Datadog to generate full-stack aware, automatable actions that optimize application performance and reduce cost. By using IBM Workload Optimization Manager analytics and automation capabilities, you can dynamically allocate resources to ensure optimal application performance, while you minimize infrastructure costs and comply with licensing and other operational policies.



Prerequisites

A valid Datadog user account with read-only API and Application Key access

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

Datadog	Workload Optimization Manager
Tags, which are configured in Datadog to define your business application	Business Application
Resources	Business Transaction
Service	Service
Apps	Application Component
Container	Container
Host	Virtual Machine

Supported Applications

Workload Optimization Manager discovers the following application types and associated commodities from the Datadog target:

Application Type	Commodities
Stand-Alone Java Application	Virtual CPU, Virtual Memory, Heap, Remaining GC Capacity
Tomcat	Virtual CPU, Virtual Memory, Response Time, Transactions, Heap, Remaining GC Capacity

Adding a Datadog Target

NOTE:

If an application is monitored by Datadog, do not add it as a separate Workload Optimization Manager application target.

To add a Datadog instance as a target, specify the following values:

- Datadog URL
 - The address of the Datadog server.
- API Key
 - The API Key that is provided by the Datadog platform. For more information, see <u>Datadog API Keys</u>.
- Application Key
 - The Application Key that is provided by the Datadog platform. For more information, see <u>Datadog API Keys</u>.
- Collect Virtual Machine Metrics
 - Whether to collect VM metrics from this target. When **Collect Virtual Machine Metrics** is turned on, Workload Optimization Manager uses the VM metrics it collects from this target, instead of the VM data that can optionally be collected from related infrastructure targets.
- Collect Tag Information
 - Whether to collect tags from this target. Tags are key-value pairs that you define in the target and then assign to different entities. When **Collect Tag Information** is turned on, Workload Optimization Manager collects tags assigned to Virtual Machines.
 - You can use these tags in Workload Optimization Manager when you search for, filter, or group entities discovered from the target. To view the collected tags, set the scope to a particular entity and then check the **Related Tag Information** chart.
- Business Application Datadog Tag



The Datadog tag that is defined in the configuration file to identify Business Applications. The tag name must begin and end with alphabetical characters and can contain hyphens, dots, and underscores. Custom tag values that have a matching tag name with the target configuration value are identified as a valid Business Application.

Proxy Host (Optional)

The IP address of the Proxy Host.

Proxy Port

The port that is required by the proxy.

Proxy Username

The username that is required by the specified proxy.

Proxy Password

The password that is required by the specified proxy.

Secure Proxy Connection

When this option is checked, Workload Optimization Manager connects to the proxy over HTTPS.

Monitored Resources

Workload Optimization Manager monitors the following resources:

NOTE:

The exact resources monitored will differ based on application type. This list includes all resources you may see.

Business Application

NOTE:

For the Datadog target to discover and link Business Applications with the underlying entities in the supply chain, you must configure application tags at the host level in the main Datadog yaml file. The Application Tag name should match the Business Application Datadog Tag name defined in the Target Configuration page.

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Business Transaction

- Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Service

NOTE:

For the Datadog target to link services with the underlying entities in the supply chain, you must configure the service and env tags at the host level in the main Datadog yaml file.

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

- Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Application Component

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.



This commodity applies only to JVM applications.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

This commodity applies only to Tomcat applications.

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Hear

Heap is the portion of a VM or container's memory allocated to individual applications.

- Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Remaining GC Capacity

Remaining GC capacity is the measurement of Application Component uptime that is *not* spent on garbage collection (GC).

Container

Virtual Memory (VMem)

VMem is the virtual memory utilized by a container against the memory limit. If no limit is set, node capacity is used.

VCPL

VCPU is the virtual CPU (in mCores) utilized by a container against the CPU limit. If no limit is set, node capacity is used).

Virtual Machine

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Actions

Workload Optimization Manager can recommend the following actions:

NOTE:

The actions that Workload Optimization Manager recommends might differ, depending on the application type that Workload Optimization Manager discovers and supports for the Datadog target.

Application Component

Resize Heap

This action can only be executed outside Workload Optimization Manager.

Actions to resize heap are driven by the application type. For Tomcat applications, analysis only generates resize actions for the Remaining GC Capacity commodity. For JVM applications, analysis only generates resize actions for the Heap commodity.

Dynatrace

Workload Optimization Manager supports discovery of applications that are managed by the Dynatrace platform. Workload Optimization Manager includes the discovered information about these applications in its calculations for VM actions.

NOTE:

For Kubernetes environments, Workload Optimization Manager stitches New Relic, AppDynamics, Instana, and Dynatrace containerized application components into the supply chain to provide a unified view of your applications. For more information, see <u>Cloud Native Targets</u> (on page 180).



Prerequisites

A Dynatrace Server instance

This instance must be configured to monitor applications running in your environment.

Workload Optimization Manager supports both SaaS and on-prem Dynatrace server installations.

Managed VMs that host applications managed by Dynatrace

For Workload Optimization Manager to discover applications through Dynatrace, the applications must be running on VMs in your environment. Also, these VMs must be managed by Workload Optimization Manager targets such as hypervisors or public cloud targets.

An API access token with the proper scopes

Workload Optimization Manager uses the API token to authenticate its calls to the Dynatrace API. This token must have permission to execute GET methods via the Dynatrace API, both Version 1 and Version 2. Generate a new generic access token with these scopes:

Workload Optimization Manager Functionality	Required Permissions
Monitoring	- API V1 scopes:
	 Access problem and event feed, metrics, and topology API V2 scopes:
	Read entitiesRead metrics

NOTE:

If you are updating to Workload Optimization Manager version 3.4.2 or later, from a version that is earlier than 3.4.2, you must generate a new API token for each existing Dynatrace target. Then you must enter that token in the target configuration, and validate the target.

If the target still fails to validate after you update the access token, take note of your configuration settings, delete the target, and configure the target again. Be sure to use the new API token that you have generated.

Adding a Dynatrace Target

NOTE:

You can manage certain applications or database servers with both Dynatrace and Workload Optimization Manager. You should avoid such a configuration because it can cause Workload Optimization Manager to generate duplicate entities in the market.

If you manage an application via a Dynatrace server, and you configure that Dynatrace server as a Workload Optimization Manager target, then be sure you have *not* added that application as a separate application target in Workload Optimization Manager.

To add a Dynatrace server instance as a target, specify:

■ Hostname or IP Address

For an on-prem installation of Dynatrace, give the host name or IP and endpoint, separated by a slash. For example, 10.10.10.10/e/b70e3eb2-e82b-4c13-a5a4-560d9865841r.

For a SaaS installation, provide the URL without the $\{IP_ADDRESS\}/e/$ statement in the path. For example, ayz12745.live.dynatrace.com

API Token

The token that Workload Optimization Manager can use to authenticate its calls to the Dynatrace API. This token must have permission to execute GET methods via the Dynatrace API V1 and V2. Refer to the Prerequisites section for more information.

Collect Virtual Machine Metrics

Whether to collect VM metrics from this target. When **Collect Virtual Machine Metrics** is turned on, Workload Optimization Manager uses the VM metrics it collects from this target, instead of the VM data that can optionally be collected from related infrastructure targets.



Collect Tag Information

Whether to collect tags from this target. Tags are key-value pairs that you define in the target and then assign to different entities. When **Collect Tag Information** is turned on, Workload Optimization Manager collects tags assigned to the following entities:

- Business Applications
- Services
- Application Components
- Containers
- Virtual Machines

You can use these tags in Workload Optimization Manager when you search for entities discovered from the target. You can also use tags to filter or group Services, Containers, and Virtual Machines. To view the collected tags, set the scope to a particular entity and then check the **Related Tag Information** chart.

Proxy Host

The address of the proxy used for this target. Only fill out proxy information if you connect to the Dynatrace server via a proxy.

Proxy Port

The port to use with the proxy specified above. By default, this is 8080.

Proxy Username

The username for the account to log into the proxy specified above.

Proxy Password

The password to use with the proxy specified above.

■ Secure Proxy Connection

Whether to use a secure connection with the proxy. When this is turned on, Workload Optimization Manager connects to the proxy through HTTPS.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

Dynatrace	Workload Optimization Manager
Application	Business Application
	NOTE: For Dynatrace Applications, Workload Optimization Manager displays Business Application entities in the supply chain when they have been active for at least three days.
Service	Service
Process	Application Component, Database Server
NA	Container
Host	Virtual Machine

Monitored Resources

Workload Optimization Manager monitors the following resources:

NOTE:

The exact resources monitored will differ based on application type. This list includes all resources you may see.

Business Application

Response Time



Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Service

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Application Component

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

- Remaining GC Capacity

Remaining GC capacity is the measurement of Application Component uptime that is *not* spent on garbage collection (GC).

This commodity applies only to Java applications.

Heap

Heap is the portion of a VM or container's memory allocated to individual applications.

This commodity applies only to Java applications.

Database Server

For Database Server applications, Workload Optimization Manager only discovers metrics for MySQL and SQL Server databases.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Database Memory (DBMem)

Database memory (or DBMem) is the measurement of memory utilized by a Database Server.

This commodity applies only to SQL and MySQL databases.

Actions to resize database memory are driven by data on the Database Server, which is more accurate than data on the hosting VM.

- DB Cache Hit Rate

DB cache hit rate is the measurement of Database Server accesses that result in cache hits, measured as a percentage of hits versus total attempts. A high cache hit rate indicates efficiency.

This commodity applies only to SQL databases.

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

This commodity applies only to SQL databases.

■ Container

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.



Virtual Machine

- Virtual CPU (VCPU)
 - Virtual CPU is the measurement of CPU that is in use.
- Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

For a given VM, the resources you see depend on how the VM is discovered, and whether the VM provides resources for an application discovered by this target:

- If the VM hosts an application that is discovered through this target, then you will see VM metrics discovered through this target.
- If the VM is discovered through a different target, and it does not host any application discovered through this target, then you will see VM metrics discovered through that different target.
- If the VM is discovered through this target, but it does not host any application discovered through this target, then Workload Optimization Manager does not display metrics for the VM.

Actions

Workload Optimization Manager can recommend the following actions:

Application Component

Resize Heap

This action can only be executed outside Workload Optimization Manager.

IBM WebSphere

The typical WebSphere deployment is a cell of WebSphere servers, controlled by a Deployment Manager. A cell makes up a managed domain that incorporates multiple VMS that host managed application servers. The Deployment Manager is a WebSphere instance that provides a single point of entry for the managed domain.

NOTE:

When adding a WebSphere Deployment Manager as a target, you must ensure that the name of each WebSphere node is resolvable to an IP address by the Workload Optimization Manager instance.

You may need to make changes to your DNS or the file /etc/resolv.conf on the Workload Optimization Manager instance to make it aware of the domain names in use in your environment.

To configure the WebSphere installation, you can use the WebSphere Integrated Solutions Console. This is a client that exposes configuration settings including the SOAP port and the PMI settings.

To manage the servers in an installation, WebSphere uses the Performance Monitoring Infrastructure (PMI). Each WebSphere server runs a PMI service that collects performance data from the various application server components. Workload Optimization Manager uses PMI for monitoring and control of the WebSphere installation.

Prerequisites

- The PMI service set to monitor at the Basic level or greater
- A service user account

To execute actions the service account must have an Administrator role. For read-only monitoring and analysis, you can set the target with a more restricted role (Monitor), but then you will have to execute all recommended actions manually, through the WebSphere interface.

NOTE

You cannot use Active Directory (AD) accounts to target WebSphere.

■ Discovered infrastructure

Workload Optimization Manager discovers WebSphere servers that are running on VMs or containers. The hosting VM or container must already be in your Workload Optimization Manager inventory.



To set the target for a server running on a VM, you must have first discovered the hosting VM through a Hypervisor target. To set the target for a server running in a container, you must have configured container discovery for WebSphere applications.

- For information about hypervisor targets, see <u>Kubernetes Platform Targets (on page 180)</u>
- For information about container targets, see Hypervisor Targets (on page 205)

Finding the SOAP Connector Address

To configure a WebSphere target, you need to know the port that the server listens on for administrative communications. Launch the WebSphere Administration Console:

- Navigate to System Administration > Deployment Manager
- Under Additional Properties, click Ports

The entry for SOAP_CONNECTOR_ADDRESS gives the currently set port number.

Adding a WebSphere Target

You can add an individual WebLogic server as a target, or you can add all matching targets within a given scope.

To add a server as a target, specify:

Target Name

Name displayed in the Workload Optimization Manager UI

Username

Username of an account with the Admin role

Password

Password of an account with the Admin role

Scope

A group of applications, stitched to the underlying VMs when the VMs are discovered as part of a separate Workload Optimization Manager target.

If you set the target scope, Workload Optimization Manager scans each VM within that group or cluster and tries to connect to the target over the specified port. Workload Optimization Manager adds any instances of the target it finds as entities from which metrics are retrieved.

The maximum supported size of the group is 500 VMs, and the recommended size is 250 VMs. Adding more VMs to the group can result in poor performance for discovery and monitoring. To target a larger number of VMs by scope, you should split them across smaller groups and set each group as the scope for a separate target.

Port Number

The WebSphere remote port

Full Validation

When selected, Workload Optimization Manager will require all database servers hosted on the VMs in the selected scope to be a valid target. If Workload Optimization Manager is unable to authenticate a database server in the scope, the target will not validate and data will not be collected.

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Service
 - Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

- Application Component
 - Virtual Memory (VMem)
 - Virtual Memory is the measurement of memory that is in use.
 - Virtual CPU (VCPU)



Virtual CPU is the measurement of CPU that is in use.

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Heap

Heap is the portion of a VM or container's memory allocated to individual applications.

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Threads

Threads is the measurement of thread capacity utilized by applications.

- Connection

Connection is the measurement of database connections utilized by applications.

Remaining GC Capacity

Remaining GC capacity is the measurement of Application Component uptime that is *not* spent on garbage collection (GC).

Actions

Workload Optimization Manager can recommend the following actions:

Service

Workload Optimization Manager does not recommend actions to perform on the Service itself, but it does recommend actions to perform on the Application Components and hosting VMs. For example, assume a Service that manages three SQL databases. If a surge in requests degrades performance across all three databases, then Workload Optimization Manager can start a new application component to run another instance of the database application, and bind it to the service. On the other hand, if SQL requests drop off so that the load balancer only forwards requests to two of the databases, Workload Optimization Manager can suspend the dormant database and unbind it.

■ Application Component

Resize Heap

This action can only be executed by Workload Optimization Manager if the entity is running in a domain controller. Actions for standalone entities can only be executed outside Workload Optimization Manager.

Resize Connection Capacity

This action can only be executed outside Workload Optimization Manager.

■ Virtual Machine

- Provision additional resources (VMem, VCPU)
- Move Virtual Machine
- Reconfigure Storage
- Suspend VM

Instana

Workload Optimization Manager supports discovery of applications that are managed by the Instana platform. Workload Optimization Manager includes the discovered information about these applications in its calculations for environment health.

NOTE:

For Kubernetes environments, Workload Optimization Manager stitches New Relic, AppDynamics, Instana, and Dynatrace containerized application components into the supply chain to provide a unified view of your applications. For more information, see Cloud Native Targets (on page 180).

Prerequisites

Instana release-242 or later



Workload Optimization Manager version 3.6.3 (or later) requires release-242 or later to manage an on-prem or SaaS instance of Instana.

■ An on-prem or SaaS instance of Instana

This instance must be configured to monitor applications running in your environment.

For an on-prem instance, you must also install <u>Beelnstana</u>. If Beelnstana is not installed, Workload Optimization Manager will return a NullPointerException and will not be able to collect metrics for Application Components and the underlying entities in the supply chain.

Virtual machines and/or containers that are running applications managed by Instana

For Workload Optimization Manager to discover applications through Instana, the applications must be running on virtual machines or in Kubernetes containers located in your environment. Also, these entities must be managed by Workload Optimization Manager hypervisor, public cloud, or Kubernetes targets.

A valid Instana API token

This must be an API token created with the default permissions.

Adding an Instana Target

NOTE:

It is possible to monitor certain applications or database servers with both Instana and another Workload Optimization Manager target. You should avoid such a configuration because it can cause Workload Optimization Manager to generate duplicate entities in the supply chain.

If you monitor an application via an Instana server, and you configure that Instana server as a Workload Optimization Manager target, then be sure you have not configured a separate application target in Workload Optimization Manager for that same application.

To add an Instana server instance as a target, specify:

Hostname or IP Address

The host name or IP of the Instana server.

API Token

The Instana API Token.

Collect Virtual Machine Metrics

Whether to collect VM metrics from this target. When **Collect Virtual Machine Metrics** is turned on, Workload Optimization Manager uses the VM metrics it collects from this target, instead of the VM data that can optionally be collected from related infrastructure targets.

Proxy Host

The address of the proxy used for this target. Only fill out proxy information if you connect to the Instana server via a proxy.

Proxy Port

The port to use with the proxy specified above. By default, this is 8080.

Proxy Username

The username for the account to log into the proxy specified above.

Proxy Password

The password to use with the proxy specified above.

Secure Proxy Connection

When checked, Workload Optimization Manager will connect to the proxy over HTTPS.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

Instana	Workload Optimization Manager
Application	Business Application



Instana	Workload Optimization Manager
Database	Database Server
Endpoint	Business Transaction
Service	Service
Process	Application Component
Docker / Crio Container	Container
Host	Virtual Machine

Instana Permissions

Workload Optimization Manager Functionality	Required Permissions
Monitoring	 Default Workload Optimization Manager uses the default API Token for monitoring access.

Monitored Resources

Workload Optimization Manager monitors the following resources:

NOTE:

The exact resources monitored will differ based on application type. This list includes all resources you may see.

Business Application

- Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Service Level Indicator (SLI)

A service level indicator (SLI) is the defined quantitative measure of one characteristic of the level of service that is provided to a customer. Common examples of such indicators are error rate or response latency of a service.

NOTE:

Currently, SLI data is available in the Entity Information chart.

■ Business Transaction

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Service Level Indicator (SLI)

A service level indicator (SLI) is the defined quantitative measure of one characteristic of the level of service that is provided to a customer. Common examples of such indicators are error rate or response latency of a service.

NOTE:

Currently, SLI data is available in the Entity Information chart.

Service

Response Time



Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Service Level Indicator (SLI)

A service level indicator (SLI) is the defined quantitative measure of one characteristic of the level of service that is provided to a customer. Common examples of such indicators are error rate or response latency of a service.

NOTE:

Currently, SLI data is available in the Entity Information chart.

Application Component

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Remaining GC Capacity

Remaining GC capacity is the measurement of Application Component uptime that is *not* spent on garbage collection (GC).

This commodity applies only to Java applications.

Heap

Heap is the portion of a VM or container's memory allocated to individual applications.

This commodity applies only to Java applications.

Database Server

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

This commodity applies only to Oracle, MySQL, and SQL databases.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

This commodity applies only to Oracle, MySQL, and SQL databases.

Database Memory (DBMem)

Database memory (or DBMem) is the measurement of memory utilized by a Database Server.

This commodity applies only to MySQL and SQL databases.

DB Cache Hit Rate

DB cache hit rate is the measurement of Database Server accesses that result in cache hits, measured as a percentage of hits versus total attempts. A high cache hit rate indicates efficiency.

This commodity applies only to Oracle, MySQL, and SQL databases.

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

This commodity applies only to Oracle databases.

Connection

Connection is the measurement of database connections utilized by applications.

This commodity applies only to Oracle databases.

Container

Virtual Memory (VMem)



Virtual Memory is the measurement of memory that is in use.

This commodity applies only to Docker containers.

Virtual Machine

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Actions

Workload Optimization Manager can recommend the following actions:

Application Component

Resize Heap

This action can only be executed outside Workload Optimization Manager.

■ Database Server

Resize Database Memory (DBMem) - MySQL and SQL Server only

This action can only be executed outside Workload Optimization Manager.

Actions to resize database memory are driven by data on the Database Server, which is more accurate than data on the hosting VM.

Resize Connection Capacity - Oracle only

This action can only be executed outside Workload Optimization Manager.

Workload Optimization Manager does not recommend actions for Instana Business Applications, Business Transactions, or Services. However, it considers resource utilization by these applications when recommending actions for the underlying virtual machines or containers. Workload Optimization Manager propagates this underlying information upward in the supply chain to show the impact of infrastructure risks on the Business Applications, Transactions, and Services.

JBoss

Workload Optimization Manager supports connecting to JBoss targets running in these operation modes:

Managed Domain

A collection of JBoss servers in a domain, with a single Domain Controller process acting as the central management control point. In this case, the VM that hosts the Domain Controller will be the target. You configure a Domain Controller via the domain-controller entry in the host.xml file on the JBoss machine.

Standalone

A single JBoss server. The VM that hosts the server is the target.

Prerequisites

- The target VM is properly configured as Domain Controller or standalone, depending on the operation mode.
- Workload Optimization Manager discovers JBoss servers that are running on VMs, or on containers that are deployed on VMs. To set the target for a JBoss server, you must have first discovered the hosting VM through a hypervisor target.

For information about hypervisor targets, see Hypervisor Targets (on page 205).

- Workload Optimization Manager monitors the Threads resource in application servers to track utilization of thread pool capacity. To monitor threads in JBoss, each JBoss server must define a thread pool in its configuration files. For instructions on specifying thread pools, see the JBoss documentation.
- JBoss supports Role-Based Access Control (RBAC) as a way to specify a set of permissions for user accounts.

JBoss disables RBAC by default. If you enable RBAC, Workload Optimization Manager requires the Monitor role for the target JBoss account in order to discover JBoss servers.



Adding a JBoss Target

You can add an individual JBoss server as a target, or you can add all matching targets within a given scope.

To add a server as a target, specify:

Target Name

Name displayed in the Workload Optimization Manager user interface

Username

The username for a JBoss account that has a role with the necessary permissions.

Password

The password for the JBoss account that you will use.

Scope

A group of JBoss servers, stitched to the underlying VMs when the VMs are discovered as part of a separate Workload Optimization Manager target.

After you set the target scope, Workload Optimization Manager scans each VM within that group or cluster and tries to connect to the target over the specified port. Workload Optimization Manager adds any instances of the target it finds as entities from which metrics are retrieved.

The maximum supported size of the group is 500 VMs, and the recommended size is 250 VMs. Adding more VMs to the group may result in delays in discovery and monitoring. If larger numbers of VMs are to be targeted, the recommendation is to split them across smaller groups in multiple targets.

■ JBoss Webservice port

The port for connections to the JBoss server. The default port for HTTP access is 9990.

Full Validation

When enabled, Workload Optimization Manager will require all JBoss servers hosted on the VMs in the selected scope to be valid targets. If Workload Optimization Manager is unable to authenticate a JBoss server in the scope, the target will not validate and data will not be collected.

■ Secure Connection

When enabled, Workload Optimization Manager will connect to JBoss servers via HTTPS. Be sure that the required certificate has been configured for use on the host.

Proxy Information

Specify proxy information only if you connect to a JBoss instance via proxy.

- Proxy Host

The address of the proxy used for this target. Only fill out proxy information if you connect to the AppDynamics instance via a proxy.

Proxy Port

The port to use with the proxy specified above. By default, this is 8080.

Proxy Username

The username to use with the proxy specified above.

Proxy Password

The password to use with the proxy specified above.

Secure Proxy Connection

When checked, Workload Optimization Manager will connect to the proxy via HTTPS.

Application Component Names

Workload Optimization Manager displays discovered JBoss servers in the user interface. These names indicate whether they're standalone or in a managed domain.

The name is divided into three sections:

- Domain Controller name or "STANDALONE"
- The server name
- The name or IP address of the VM hosting the JBoss server



For example:

STANDALONE:acm-jboss73 [ACM-JBoss7.3-171.47]

Monitored Resources

Workload Optimization Manager monitors the following resources:

Application Component

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Heap

Heap is the portion of a VM or container's memory allocated to individual applications.

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Threads

Threads is the measurement of thread capacity utilized by applications.

Connection

Connection is the measurement of database connections utilized by applications.

Remaining GC Capacity

Remaining GC capacity is the measurement of Application Component uptime that is *not* spent on garbage collection (GC).

Actions

Workload Optimization Manager can recommend the following actions:

■ Application Component

Resize Heap

This action can only be executed outside Workload Optimization Manager.

Resize Thread Pool

This action can only be executed outside Workload Optimization Manager.

Resize Connection Capacity

This action can only be executed outside Workload Optimization Manager.

JVM Application

Workload Optimization Manager supports connecting to individual JVM Applications as targets. Workload Optimization Manager connects to the JVM process as a remote client via remote JMX access. Target configuration includes the port used by the JMX/RMI registry.

Prerequisites

A valid JMX user account for the JVM application

If JMX security is enabled this must be a JMX user with a readonly role

- The application should run on JVM version 6.0 or higher
- For VMware environments, VMware Tools must be installed on the VM that hosts the application

This ensures that the VM hosting the application can get the application's IP address

- Remote JMX access is enabled through a port that is opened to the firewall
- Discovered infrastructure

Workload Optimization Manager discovers JVM applications that are running on VMs or containers. The hosting VM or container must already be in your Workload Optimization Manager inventory.



To set the target for a server running on a VM, you must have first discovered the hosting VM through a Hypervisor target. To set the target for a server running in a container, you must have configured container discovery for JVM applications.

- For information about container targets, see <u>Kubernetes Platform Targets (on page 180)</u>
- For information about hypervisor targets, see <u>Hypervisor Targets (on page 205)</u>

Adding JVM Application Targets

When you configure JVM targets, you declare a given scope and add all matching applications within that given scope. To do this, specify:

Scope:

A group of applications, stitched to the underlying VMs when the VMs are discovered as part of a separate Workload Optimization Manager target.

If you set the target scope, Workload Optimization Manager scans each VM within that group or cluster and tries to connect to the target over the specified port. Workload Optimization Manager adds any instances of the target it finds as entities from which metrics are retrieved.

The maximum supported size of the group is 500 VMs, and the recommended size is 250 VMs. Adding more VMs to the group can result in poor performance for discovery and monitoring. To target a larger number of VMs by scope, you should split them across smaller groups and set each group as the scope for a separate target.

- Port Number: The JMX Remote port
- Username/Password: Credentials for a user account with an Admin role

The credentials you provide must match the credentials you specify for JMX login configuration when you start up the application.

If you disable authentication on the application, then you must still provide arbitrary values for **Username** and **Password**. To disable JMX authentication, use the following flags in the command line as you start the application:

```
\verb|-Dcom.sun.management.jmxremote.authenticate=false|\\
```

-Dcom.sun.management.jmxremote.ssl=false

Configuring JMX Remote Access

Workload Optimization Manager monitors and controls JVM applications via JMX Remote access. You must configure a JMX Remote port.

Note that to work with a firewall you should also set the RMI Server port – If you don't set an RMI port, then JMX sets an arbitrary *ephemeral port*, and you can't guarantee that the port will be open to your firewall.

To set the JMX Remote port, pass in the port at the command line when you start your application. For example, to set the port to 8090, start your application with the following options:

-Dcom.sun.management.jmxremote -Dcom.sun.management.jmxremote.port=8090

Multiple JVM Targets On Single VM

Note that you can specify targets with different ports, but that run on the same VM (use the same IP address). You can also specify targets via the same scope, but with different ports – This is another way to assign applications running on the same VM to different ports. To do this:

To do this, add the targets in two separate steps. For example, assume you want to add two JVM application targets, and they both run on the VM at 10.10.123.45. One application is on port 123, and the other application is on port 456. To specify these two targets:

Specify the first target with the following parameters:

Scope: VMs_myCluster.mycorp.com

Port number: 123Username: AppUser



– Password: *********

Then click ADD.

Specify the second target with the following parameters:

Scope: VMs_myCluster.mycorp.com

Port number: 456

Then click ADD.

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Application Component (JVM Application)
 - Heap

Heap is the portion of a VM or container's memory allocated to individual applications.

- Remaining GC Capacity

Remaining GC capacity is the measurement of Application Component uptime that is *not* spent on garbage collection (GC).

Data is collected if JVM profiler is enabled.

Virtual Machine

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Actions

Workload Optimization Manager can recommend the following actions:

- Application Component (JVM Application)
 - Resize Heap

This action can only be executed outside Workload Optimization Manager.

Resize Thread Pool

This action can only be executed outside Workload Optimization Manager.

Resize Connection Capacity

This action can only be executed outside Workload Optimization Manager.

Suspend VM

This action can only be executed by Workload Optimization Manager if a VM is hosted in a vCenter environment. Actions for applications running on other hypervisors can only be executed outside Workload Optimization Manager.

Provision VM

This action can only be executed outside Workload Optimization Manager.

Virtual Machine

- Provision additional resources (VMem, VCPU)
- Move Virtual Machine
- Move Virtual Machine Storage
- Reconfigure Storage
- Reconfigure Virtual Machine
- Suspend VM
- Provision VM



MySQL

To manage MySQL databases, Workload Optimization Manager can connect to one or more database servers within a defined scope.

Prerequisites

User Permissions are enabled on the MySQL Server. See <u>Enabling User Permissions on MySQL (on page 166)</u>

Adding a MySQL Database Target

You can add all matching targets within a given scope.

To add a database server as a target, you specify:

■ Target ID

Name displayed in the Workload Optimization Manager UI

Username

Username of the account Workload Optimization Manager uses to connect to the target.

Password

Password of the account Workload Optimization Manager uses to connect to the target.

Scope

A group of applications, stitched to the underlying VMs when the VMs are discovered as part of a separate Workload Optimization Manager target.

If you set the target scope, Workload Optimization Manager scans each VM within that group or cluster and tries to connect to the target over the specified port. Workload Optimization Manager adds any instances of the target it finds as entities from which metrics are retrieved.

The maximum supported size of the group is 500 VMs, and the recommended size is 250 VMs. Adding more VMs to the group can result in poor performance for discovery and monitoring. To target a larger number of VMs by scope, you should split them across smaller groups and set each group as the scope for a separate target.

Port Number

The MySQL remote port. If blank, Workload Optimization Manager will use the MySQL default port of 3306.

■ Full Validation

When selected, Workload Optimization Manager will require all database servers hosted on the VMs in the selected scope to be a valid target. If Workload Optimization Manager is unable to authenticate a database server in the scope, the target will not validate and data will not be collected.

Monitored Resources

Workload Optimization Manager monitors the following resources:

Database Server

Database Memory (DBMem)

Database memory (or DBMem) is the measurement of memory utilized by a Database Server.

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

- Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Connection

Connection is the measurement of database connections utilized by applications.

DB Cache Hit Rate

DB cache hit rate is the measurement of Database Server accesses that result in cache hits, measured as a percentage of hits versus total attempts. A high cache hit rate indicates efficiency.



Virtual Machine

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Storage

Virtual storage is the measurement of virtual storage capacity that is in use.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

Actions

Workload Optimization Manager can recommend the following actions:

Database Server

Resize

Database memory (DBMem)

Actions to resize database memory are driven by data on the Database Server, which is more accurate than data on the hosting VM. Workload Optimization Manager uses database memory and cache hit rate data to decide whether resize actions are necessary.

A high cache hit rate value indicates efficiency. The optimal value is 100% for on-prem (self-hosted) Database Servers, and 90% for cloud Database Servers. When the cache hit rate reaches the optimal value, no action generates even if database memory utilization is high. If utilization is low, a resize down action generates.

When the cache hit rate is below the optimal value but database memory utilization remains low, no action generates. If utilization is high, a resize up action generates.

■ Virtual Machine

Resize

Resize resource capacity, reservation, or limit to improve performance.

Enabling User Permissions on MySQL Server

Follow the following steps in order to enable appropriate user permissions on a MySQL Server.

Edit the MySQL server's configuration file.

You must edit the <code>.conf</code> file on the MySQL server to grant user permissions. Open a secure shell session on the server and edit the file. Depending on the platform your MySQL is running on, you'll fin the file at different locations:

Debian Linux:

/etc/mysql/my.cnf

■ Red Hat Linux (Fedora or Centos):

/etc/my.cnf

■ FreeBSD Linux:

You must create the file at /var/db/mysql/my.cnf

Open the file in an editor and find the section, [mysqld]. Then make the following changes:

Comment out the line:

skip-networking

Commenting out this line enables remote connections over TCP/Is.



[mysqld]

■ Bind your MySql server address

In the config file, add the line:

bind-address=<MySQL_IP_Address>

■ Enable the collection of Transaction metrics

In the config file, add the line:

```
innodb_monitor_enable = trx_rw_commits, trx_nl_ro_commits, trx_ro_commits,
trx_rollbacks
```

For example, if your MySQL server has the address, 123.45.66.77, then after you have bound the IP address and enabled Transaction metrics, the section of the .conf file should appear as follows:

user = mysql pid-file = /var/run/mysqld/mysqld.pid socket = /var/run/mysqld/mysqld.sock port = 3306 basedir = /usr datadir = /var/lib/mysql tmpdir =/tmplanguage = /usr/share/mysql/English bind-address = 123.45.66.77 # skip-networking

innodb_monitor_enable = trx_rw_commits, trx_nl_ro_commits, trx_ro_commits, trx_rollbacks

When you are done, save the .conf file.

NOTE: Some MySQL installations use multiple configuration files. If a setting you made does not have the desired effect, make sure that a different configuration file is not overwriting the value.

2. Enable collection of Response Time metrics.

Execute the following command to log into to the MySQL server:

Uncomment the following line for MySQL versions 5.6+

```
$mysql -u root -p mysql
```

. . . .

Then execute the following SQL commands:

UPDATE performance_schema.setup_instruments SET ENABLED = 'YES' WHERE NAME LIKE 'statement/sql%';



```
UPDATE performance_schema.setup_instruments SET TIMED = 'YES' WHERE NAME LIKE 'statement/sql%';
```

NOTE:

If you want these changes to take effect each time you restart the MySql server, add these statements to a file, and start the server with the --init-file option. For example, if you name the file MyInit.txt, then start the MySql server with the following option:

```
--init-file=MyInit.txt
```

3. Give your Workload Optimization Manager server remote access to the database.

If you are not already logged into the MySql server, execute the following command:

```
$mysql -u root -p mysql
```

Then execute the following commands:

Assume a user named USER_NAME with a password PWD_STRING. Then assume that your Workload Optimization Manager has an IP address of 10.10.123.45. The following command grants privileges to that Workload Optimization Manager, if it connects with the specified user account:

```
GRANT SELECT ON performance_schema.* TO 'USER_NAME'@'10.10.123.45' IDENTIFIED BY 'PWD_STRING';

GRANT PROCESS ON *.* TO 'USER_NAME'@'10.10.123.45' IDENTIFIED BY 'PWD_STRING';

FLUSH PRIVILEGES;
```

Note that the FLUSH PRIVILEGES command causes MySql to retain these settings upon restart.

When you're finished running these SQL commands, log out of MySQL.

New Relic

Workload Optimization Manager supports workload management of the application infrastructure monitored by New Relic, from application instance to host. With information obtained from New Relic, Workload Optimization Manager can make recommendations and take actions to both assure performance and drive efficiency to address the demands of each individual application. For Kubernetes environments, Workload Optimization Manager stitches containerized application components into the supply chain to provide a unified view of your applications.

NOTE:

For Kubernetes environments, Workload Optimization Manager stitches New Relic, AppDynamics, Instana, and Dynatrace containerized application components into the supply chain to provide a unified view of your applications. For more information, see Cloud Native Targets (on page 180).

Prerequisites

A valid New Relic user account that includes both APM and infrastructure monitoring.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

New Relic	Workload Optimization Manager
APM: Key Transactions	Business Transaction
APM: Application / Service (New Relic One)	Service
APM: Application Instance	Application Component
Infra: Database	Database Server



New Relic	Workload Optimization Manager
Infra: Host	Virtual Machine

Supported Applications

Workload Optimization Manager discovers the following application types (and associated commodities) via the New Relic target:

Application Type	Commodities
.NET	Virtual CPU, Virtual Memory, Response Time, Transactions
GO	Virtual CPU, Virtual Memory, Response Time, Transactions
Java	Virtual CPU, Virtual Memory, Response Time, Transactions, Heap, Collection Time, Threads
Node.js	Virtual CPU, Virtual Memory, Response Time, Transactions, Heap, Collection Time
PHP	Virtual CPU, Virtual Memory, Response Time, Transactions
Python	Virtual CPU, Virtual Memory, Response Time, Transactions

Supported Databases

Workload Optimization Manager supports the following Database types and commodities:

NOTE: Database commodities are exposed only if the New Relic account used to connect to Workload Optimization Manager has a New Relic Infrastructure Pro subscription.

Database	Commodities
SQL	Cache Hit Rate, Virtual Memory, Transactions
MySQL	Cache Hit Rate, Transactions NOTE: Workload Optimization Manager does not show Cache Hit Rate values for New Relic MySQL version 8.0 and higher. For more information, see the New Relic documentation.
OracleDB	Cache Hit Rate, Transactions, Response Time
MongoDB	Virtual Memory, Connections

Adding a New Relic Target

NOTE:

If an application is monitored by New Relic, do not add it as a separate Workload Optimization Manager application target.

To add New Relic as a target, specify:

- Account ID
 - The New Relic Account ID.
- REST API Key

The REST API Key *provided by the New Relic platform*. In the New Relic environment, this API key is called the *User key*. For more information, see New Relic API Keys.

GraphQL API Key



The GraphQL API Key is identical to the New Relic *User key*, which in Workload Optimization Manager is called the REST API Key. You can use the New Relic *User key* value for both the GraphQL API Key and REST API Key fields. For more information, see New Relic API Keys.

■ EU Region

If checked, Workload Optimization Manager will use the EU API endpoints.

Collect Virtual Machine Metrics

Whether to collect VM metrics from this target. When **Collect Virtual Machine Metrics** is turned on, Workload Optimization Manager uses the VM metrics it collects from this target, instead of the VM data that can optionally be collected from related infrastructure targets.

■ Collect Tag Information

Whether to collect tags from this target. Tags are key-value pairs that you define in the target and then assign to different entities. When **Collect Tag Information** is turned on, Workload Optimization Manager collects tags assigned to the following entities:

- Containers
- Virtual Machines

You can use these tags in Workload Optimization Manager when you search for entities discovered from the target. You can also use tags to filter or group Containers and Virtual Machines. To view the collected tags, set the scope to a particular entity and then check the **Related Tag Information** chart.

Proxy Host (Optional)

The IP of the Proxy Host.

Proxy Port (Optional)

The port required by the proxy.

■ Proxy Username (Optional)

The username required by the proxy.

Proxy Password (Optional)

The password required by the proxy.

Secure Proxy Connection

When checked, Workload Optimization Manager will connect to the proxy via HTTPS.

Monitored Resources

Workload Optimization Manager monitors the following resources:

NOTE:

The exact resources monitored will differ based on application type. This list includes all resources you may see.

Application Component

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

- Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Heap

Heap is the portion of a VM or container's memory allocated to individual applications.

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

- Connection

Connection is the measurement of database connections utilized by applications.



Remaining GC Capacity

Remaining GC capacity is the measurement of Application Component uptime that is *not* spent on garbage collection (GC).

Threads

Threads is the measurement of thread capacity utilized by applications.

Database

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Database Memory (DBMem)

Database memory (or DBMem) is the measurement of memory utilized by a Database Server.

Connection

Connection is the measurement of database connections utilized by applications.

DB Cache Hit Rate

DB cache hit rate is the measurement of Database Server accesses that result in cache hits, measured as a percentage of hits versus total attempts. A high cache hit rate indicates efficiency.

Business Transaction

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

■ Service

- Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Container

Virtual Memory (VMem)

VMem is the virtual memory utilized by a container against the memory limit. If no limit is set, node capacity is used.

VCPU

VCPU is the virtual CPU (in mCores) utilized by a container against the CPU limit. If no limit is set, node capacity is used).

■ Virtual Machine

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

For a given VM, the resources you see depend on how the VM is discovered, and whether the VM provides resources for an application discovered by this target:

- If the VM hosts an application that is discovered through this target, then you will see VM metrics discovered through this target.
- If the VM is discovered through a different target, and it does not host any application discovered through this target, then you will see VM metrics discovered through that different target.
- If the VM is discovered through this target, but it does not host any application discovered through this target, then Workload Optimization Manager does not display metrics for the VM.



Actions

NOTE:

The specific actions that Workload Optimization Manager recommends can differ, depending on the processes that Workload Optimization Manager discovers.

For other application components, Workload Optimization Manager can recommend actions based on the resources it can discover for the application. For example, Node.js® applications report CPU usage, so Workload Optimization Manager can generate vCPU resize actions and display them in the user interface.

Workload Optimization Manager can recommend the following actions:

■ Application Component

- Suspend VM
 - This action can only be executed outside Workload Optimization Manager.
- Provision VM

This action can only be executed outside Workload Optimization Manager.

Oracle

To connect to an Oracle database, you will:

- Add a Dynamic Performance view to the Oracle database
- Configure a service account on the database that Workload Optimization Manager can use to log on
- Find the Service Name and port for the database

Prerequisites

- User permissions that grant access to Workload Optimization Manager through a specific user account. See <u>Creating a Service User Account in Oracle (on page 175)</u>.
- Dynamic Performance View (V\$) must be enabled. See "Adding a Dynamic Performance View", below.
- Access through the firewall to the Oracle database port that you specify for the Workload Optimization Manager target connection

Adding a Dynamic Performance View

In order to collect data from the Oracle database, Workload Optimization Manager uses the Dynamic Performance View (referred to as V\$). V\$ is not enabled by default. You must run a script to build the tables and views that are necessary to enable V\$. In some environments only the DBA has privileges to run this script.

To enable ∨\$:

- Open a secure shell session (ssh) on the database host as a system user or a user with the sysdba role
- In the shell session enter the following commands:

```
sqlplus /nolog
connect /as sysdba
CREATE USER My_Username IDENTIFIED BY My_Password container=all;
GRANT CONNECT TO My_Username container=all;
GRANT sysdba TO My_Username container=all;
```

NOTE:

If security or other practices prohibit assigning SYSDBA to this user, you can use the following command to provide access to all V\$ views:

```
GRANT select any dictionary TO My_Username;
```

This creates a user account named My_Username with full privileges to access the V\$ Dynamic Performance view.



Adding an Oracle Database to Workload Optimization Manager

You can add an individual database server as a target, or you can add all matching targets within a given scope.

To add a database server as a target, specify:

Target Name

The target name that will display in the Workload Optimization Manager user interface.

Username/Password

Valid client credentials for the database server. For Workload Optimization Manager to execute actions, the account must have administrator privileges. Also, you must have enabled user permissions to this user account, including remote access from the Workload Optimization Manager server.

Scope

A group of applications, stitched to the underlying VMs when the VMs are discovered as part of a separate Workload Optimization Manager target.

If you set the target scope, Workload Optimization Manager scans each VM within that group or cluster and tries to connect to the target over the specified port. Workload Optimization Manager adds any instances of the target it finds as entities from which metrics are retrieved.

The maximum supported size of the group is 500 VMs, and the recommended size is 250 VMs. Adding more VMs to the group can result in poor performance for discovery and monitoring. To target a larger number of VMs by scope, you should split them across smaller groups and set each group as the scope for a separate target.

NOTE:

All database servers in the scope must share the same service name, credentials, and port. For databases that have a different value for any of these, you must create a separate target using those values.

Oracle Port

The port that connects to the database. You must open the firewall on the database server to allow access through this port. For further information, see "Finding the Service Name and Port", below.

Oracle Service Name

The service name for the database that you are connecting to.

Full Validation

When selected, Workload Optimization Manager will require all database servers hosted on the VMs in the selected scope to be a valid target. If Workload Optimization Manager is unable to authenticate a database server in the scope, the target will not validate and data will not be collected.

Finding the Service Name and Port

To specify an Oracle target, you must provide the service name and port that you want to connect to. To find the service name for your database:

- Open a secure shell session (ssh) on the database host as a system user or a user with the sysdba role
- In the shell session, enter the command, lsnrctl status

Find the line that has the string PROTOCOL=tcp and note the port number.

■ In the shell session enter the following commands:

```
sqlplus /nolog
connect /as sysdba
SELECT SYS_CONTEXT('userenv', 'db_name') FROM dual;
```

Note the service name that displays as a result of these commands.

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Database Server
 - Database Memory (DBMem)



Database memory (or DBMem) is the measurement of memory utilized by a Database Server.

Actions to resize database memory are driven by data on the Database Server, which is more accurate than data on the hosting VM.

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Connection

Connection is the measurement of database connections utilized by applications.

Transaction Log

Transaction log is the measurement of storage capacity utilized by a Database Server for transaction logging.

DB Cache Hit Rate

DB cache hit rate is the measurement of Database Server accesses that result in cache hits, measured as a percentage of hits versus total attempts. A high cache hit rate indicates efficiency.

Virtual Machine

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Storage

Virtual storage is the measurement of virtual storage capacity that is in use.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

Actions

Workload Optimization Manager can recommend the following actions:

Database Server

Resize

Actions to resize database memory are driven by data on the Database Server, which is more accurate than data on the hosting VM. Workload Optimization Manager uses database memory and cache hit rate data to decide whether resize actions are necessary.

A high cache hit rate value indicates efficiency. The optimal value is 100% for on-prem (self-hosted) Database Servers, and 90% for cloud Database Servers. When the cache hit rate reaches the optimal value, no action generates even if database memory utilization is high. If utilization is low, a resize down action generates.

When the cache hit rate is below the optimal value but database memory utilization remains low, no action generates. If utilization is high, a resize up action generates.

■ Virtual Machine

Resize

Resize resource capacity, reservation, or limit to improve performance.



Creating a Service User Account in Oracle

To collect data from the Oracle database, Workload Optimization Manager requires a service account that has privileges to access the V\$ Dynamic Performance view. To create this account:

- Open a secure shell session (ssh) on the database host as a system user or a user with the sysdba role
- In the shell session enter the following commands:

```
sqlplus /nolog
connect /as sysdba
CREATE USER My_Username IDENTIFIED BY My_Password container=all;
GRANT CONNECT TO My_Username container=all;
GRANT sysdba TO My_Username container=all;
```

This creates a user account named My_Username with full privileges to access the ∨\$ Dynamic Performance view.

NOTE:

The above example uses a fictitious username. To comply with Oracle 12C norms, the username should include a prefix of c##.

Some enterprises don't allow accounts with sysdba access. Cisco recommends using sysdba, according to the Oracle documentation. However, you can work with your Oracle DBA staff to provide read access to the following views, which are the ones that Workload Optimization Manager needs:

- V\$INSTANCE
- V\$LOG
- V\$LOGFILE
- V\$PARAMETER
- V\$PGASTAT
- V\$RESOURCE_LIMIT
- V\$SGASTAT
- V\$SYS_TIME_MODEL
- V\$SYSMETRIC
- V\$SYSSTAT

Oracle WebLogic

The typical WebLogic deployment is a managed domain with one Administration Server that provides a single point of entry for administration and management of the domain. The domain can include other WebLogic Servers which are the Managed Servers. You set the WebLogic Administration Server as a Workload Optimization Manager target.

For a standalone WebLogic deployment, the single server acts as its own Administration Server – You can set the standalone server as a Workload Optimization Manager target.

WebLogic deployments can include clusters to distribute workload across multiple WebLogic servers. Workload Optimization Manager recommended actions respect the cluster architecture. For example, if you have enabled horizontal scaling for your WebLogic servers, then Workload Optimization Manager can recommend provisioning new servers for a given cluster.

Prerequisites

A service user account.

To execute actions the service account must have an Admin role. For read-only monitoring and analysis, you can set the target with a more restricted role, but then you will have to execute all recommended actions manually, through the WebLogic interface.

- WebLogic requires both the local and remote ends of the connection be resolvable by DNS. The Workload Optimization Manager IP address and all WebLogic server IP addresses must be resolvable by your local DNS server.
- Discovered infrastructure



Workload Optimization Manager discovers WebLogic servers that are running on VMs or containers. The hosting VM or container must already be in your Workload Optimization Manager inventory.

To set the target for a server running on a VM, you must have first discovered the hosting VM through a Hypervisor target. To set the target for a server running in a container, you must have configured container discovery for WebLogic applications.

- For information about container targets, see Kubernetes Platform Targets (on page 180)
- For information about hypervisor targets, see <u>Hypervisor Targets</u> (on page 205)

Finding the T3 Listen Port

To configure a WebLogic target, you need to know the port that the server listens on for administrative communications. Launch the WebLogic Administration Console:

- Navigate to Domain Structure and display the domain you're interested in
- Navigate to Environment > Servers and select the Domain Administration Server you're setting as a target The console displays configuration information for the server, including the T3 listen port.

Adding a WebLogic Target

You can add one or more WebLogic targets in a given scope, including both standalone servers and domain managers.

To add a this target, specify:

Target Name

Name displayed in the Workload Optimization Manager UI

Username

Username of an account with the Admin role

Password

Password of an account with the Admin role

■ Scope

A group of applications, stitched to the underlying VMs when the VMs are discovered as part of a separate Workload Optimization Manager target.

If you set the target scope, Workload Optimization Manager scans each VM within that group or cluster and tries to connect to the target over the specified port. Workload Optimization Manager adds any instances of the target it finds as entities from which metrics are retrieved.

The maximum supported size of the group is 500 VMs, and the recommended size is 250 VMs. Adding more VMs to the group can result in poor performance for discovery and monitoring. To target a larger number of VMs by scope, you should split them across smaller groups and set each group as the scope for a separate target.

Port Number

The WebLogic remote port

Full Validation

When selected, Workload Optimization Manager will require all database servers hosted on the VMs in the selected scope to be a valid target. If Workload Optimization Manager is unable to authenticate a database server in the scope, the target will not validate and data will not be collected.

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Service
 - Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

- Application Component
 - Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.



Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Heap

Heap is the portion of a VM or container's memory allocated to individual applications.

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Threads

Threads is the measurement of thread capacity utilized by applications.

Connection

Connection is the measurement of database connections utilized by applications.

Remaining GC Capacity

Remaining GC capacity is the measurement of Application Component uptime that is *not* spent on garbage collection (GC).

Actions

Workload Optimization Manager can recommend the following actions:

Service

Workload Optimization Manager does not recommend actions to perform on the Service itself, but it does recommend actions to perform on the Application Components and hosting VMs. For example, assume a Service that manages three SQL databases. If a surge in requests degrades performance across all three databases, then Workload Optimization Manager can start a new application component to run another instance of the database application, and bind it to the service. On the other hand, if SQL requests drop off so that the load balancer only forwards requests to two of the databases, Workload Optimization Manager can suspend the dormant database and unbind it.

Application Component

- Resize Heap

This action can only be executed by Workload Optimization Manager if the entity is running in a domain controller. Actions for standalone entities can only be executed outside Workload Optimization Manager.

Resize Connection Capacity

This action can only be executed outside Workload Optimization Manager.

Virtual Machine

- Provision additional resources (VMem, VCPU)
- Move Virtual Machine
- Reconfigure Storage
- Suspend VM

SQL Server

Workload Optimization Manager supports the following versions of this target:

SQL Server 2012, 2014, 2016, 2017, 2019, and 2022

Workload Optimization Manager discovers both standalone and clustered SQL Servers, and represents them as Database Server entities in the supply chain.

Prerequisites

A user account with SQL permissions including Connect SQL and View Server State on the database



- The following services must be running, and set to enabled:
 - Net.Tcp Listener Adapter
 - Net.Tcp Port Sharing Service
- TCP/IP is enabled on the port used for Workload Optimization Manager discovery.

Creating a Service User Account

The user account that Workload Optimization Manager uses for its service login must include the following:

- The account must exist in the Security folder within the SQL Server Object Explorer, with the following properties:
 - Enable SQL Server Authentication
 - Disable Enforce password policy
- The account's security properties must include:
 - Permission to connect to the database through SQL
 - Permission to view the server state

Adding a SQL Server Target

Specify the following:

Target Name

Name displayed in the Workload Optimization Manager UI

Username

Username for the account. This username must not include the AD domain

AD Domain

The Active Directory domain used by Workload Optimization Manager in conjunction with the Username for authentication. Leave blank for local accounts.

Password

Password for the account. This username must not include the AD domain

Scope

A group of applications, stitched to the underlying VMs when the VMs are discovered as part of a separate Workload Optimization Manager target.

If you set the target scope, Workload Optimization Manager scans each VM within that group or cluster and tries to connect to the target over the specified port. Workload Optimization Manager adds any instances of the target it finds as entities from which metrics are retrieved.

The maximum supported size of the group is 500 VMs, and the recommended size is 250 VMs. Adding more VMs to the group can result in poor performance for discovery and monitoring. To target a larger number of VMs by scope, you should split them across smaller groups and set each group as the scope for a separate target.

Browsing Service Port

The UDP port for the browsing service that listens for incoming connections to the SQL instances running on the SQL Server. If the browsing service is reachable via the specified port, Workload Optimization Manager discovers the SQL instances used by the VM group that you defined as your scope, as well as the listening ports on those SQL instances. The default UDP port is 1434.

If the service is unreachable, or if you did not specify a UDP port, Workload Optimization Manager will use the TCP port that you specified in the SQLServer Port field to discover SQL instances. See the next item.

SOLServer Port

The TCP port for the SQL Server. Workload Optimization Manager will use this port if the browsing service is unreachable, or if you did not specify a browsing service port. The default TCP port is 1433.

Full Validation

When selected, Workload Optimization Manager will require all database servers hosted on the VMs in the selected scope to be a valid target. If Workload Optimization Manager is unable to authenticate a database server in the scope, the target will not validate and data will not be collected.



Standalone and Clustered SQL Servers

Workload Optimization Manager discovers both standalone and clustered SQL Servers, and represents them as Database Server entities in the supply chain.

- When you set the scope to a SQL Server entity and view the Entity Information chart, the Server Configuration field indicates whether that entity is a standalone server or is part of a cluster.
- When you search for Database Servers or create groups of Database Servers, use the Server Configuration filter to get a list of standalone or clustered servers.

For clustered environments:

- Workload Optimization Manager represents each SQL Server instance in the cluster as a Database Server entity, and automatically creates a group for these instances.
- To see all the auto-created groups, go to **Settings > Groups** and then search for group names starting with MSSQL:Cluster:. Click a group name to set the scope to that group. In the resulting supply chain, the Database Server entity shows the number of SQL Server instances in the cluster. This entity is stitched to the Virtual Machine entity, which represents the corresponding SQL Server nodes. Click **Database Server** to see a list of instances, and identify which instance is currently active and which ones are idle (redundant). Workload Optimization Manager only monitors resources for the active instance, and shows resource metrics when you set the scope to that instance.
- If you have several clusters, you can use filters to identify all the active/idle instances in those clusters. In Search, select **Database Servers**, and then set the filter as follows:
 - Active instances
 - Server Configuration=Clustered and State=ACTIVE
 - Idle (redundant) instances
 - Server Configuration=Clustered and State=IDLE

Monitored Resources

Workload Optimization Manager monitors the following resources:

■ Database Server

NOTE

For clustered environments, Workload Optimization Manager only monitors resources for the currently active SQL Server instance, and shows resource metrics when you set the scope to that instance.

- Connection
 - Connection is the measurement of database connections utilized by applications.
- Database Memory (DBMem)
 - Database memory (or DBMem) is the measurement of memory utilized by a Database Server.
 - Actions to resize database memory are driven by data on the Database Server, which is more accurate than data on the hosting VM.
- DB Cache Hit Rate
 - DB cache hit rate is the measurement of Database Server accesses that result in cache hits, measured as a percentage of hits versus total attempts. A high cache hit rate indicates efficiency.
- Response Time
 - Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).
- Storage Access (IOPS)
 - Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.
- Storage Amount
 - Storage Amount is the measurement of storage capacity that is in use.
- Transaction Log
 - Transaction log is the measurement of storage capacity utilized by a Database Server for transaction logging.
- Transaction



Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Virtual Storage

Virtual storage is the measurement of virtual storage capacity that is in use.

Virtual Machine

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Storage

Virtual storage is the measurement of virtual storage capacity that is in use.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Actions

Workload Optimization Manager can recommend the following actions:

Virtual Machine

- Provision additional resources (VMem, VCPU)
- Move Virtual Machine
- Move Virtual Machine Storage
- Reconfigure Storage
- Reconfigure Virtual Machine
- Suspend VM
- Provision VM

NOTE:

Without separate targets to discover Guest OS Processes or Application Servers, Workload Optimization Manager does not generate actions on applications. Instead, it generates resize actions on the host VMs. For on-prem environments, if host utilization is high enough on the host running the application VM, Workload Optimization Manager can also recommend provisioning a new host.

Cloud Native Targets

Containers support separation of concerns in a way similar to virtual machines, but allow greater flexibility and use far less overhead. Containers can be deployed singly (uncommon) or within a cluster containing multiple nodes. A single container can implement a complete application, or one container can implement a single process that contributes to a larger, distributed application.

To support cloud native environments, Workload Optimization Manager targets Kubernetes clusters. Workload Optimization Manager supports target clusters managed on Kubernetes v1.8 or higher, whether the clusters are managed directly via kubeadm, or via other platforms including:

- Red Hat OpenShift
- Pivotal Kubernetes Service
- Amazon Elastic Kubernetes Service (EKS)
- Azure Kubernetes Service (AKS)
- Cisco Container Platform (CCP)
- Google Kubernetes Engine (GKE)

With Cloud Native targets, Workload Optimization Manager discovers entities related to container platforms in your environment. Discovery can also stitch the container cluster entities together with managed applications. For example, discovery can show



the full application stack if your container environment includes applications managed by the following technologies, and you have added them as targets to Workload Optimization Manager:

- Cisco AppDynamics (on page 143)
- Instana (on page 156)
- Dynatrace (on page 150)
- New Relic (on page 168)

Prerequisites

Running Kubernetes 1.8+ Cluster

Adding a Kubernetes Target

Detailed steps for adding a Kubernetes target can be found on the KubeTurbo Wiki.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

Cloud Native	Workload Optimization Manager
Service	Service (on page 330)
Container	Container (on page 345)
A Container's Spec	Container Spec (on page 347)
Pod	Container Pod (on page 359)
Controller	Workload Controller (on page 351)
Namespace	Namespace (on page 364)
Cluster	Container Cluster (on page 367)
Node	Virtual Machine (on page 371)

NOTE:

If a container pod is attached to a <u>volume (on page 424)</u>, Workload Optimization Manager discovers it as a Persistent Volume (PV), and shows which pods are connected to the PV.

Monitored Resources

Workload Optimization Manager monitors the following resources:

■ Service

- Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

■ Container

Virtual Memory (VMem)

VMem is the virtual memory utilized by a container against the memory limit. If no limit is set, node capacity is used.

VMem Request

If applicable, VMem Request is the virtual memory utilized by a container against the memory request.

VCPU



VCPU is the virtual CPU (in mCores) utilized by a container against the CPU limit. If no limit is set, node capacity is used).

VCPU Request

If applicable, VCPU Request is the virtual CPU (in mCores) utilized by a container against the CPU request.

VCPU Throttling

VCPU Throttling is the throttling of container virtual CPU that could impact response time, expressed as the percentage of throttling for all containers associated with a Container Spec. In the Capacity and Usage chart for containers, *used* and *utilization* values reflect the actual throttling percentage, while *capacity* value is always 100%.

■ Container Spec

Workload Optimization Manager monitors the historical usage of any instance of a container running for the workload (assuming the workload name stays the same). Charts show the trend of usage even with restarts or redeployments.

Container Pod

VMem

VMem is the virtual memory utilized by a pod against the node physical capacity.

VMem Request

VMem Request is the virtual memory request allocated by a pod against the node allocatable capacity.

VCPI

VCPU is the virtual CPU (in mCores) utilized by a pod against the node physical capacity.

VCPU Request

VCPU Request is the virtual CPU request (in mCores) allocated by a pod against the node allocatable capacity.

VMem Request Quota

If applicable, VMem Request Quota is the amount of virtual memory request a pod has allocated against the namespace quota.

VCPU Request Quota

If applicable, VCPU Request Quota is the amount of virtual CPU request (in mCores) a pod has allocated against the namespace quota.

- VMem Limit Quota

If applicable, VMem Limit Quota is the amount of virtual memory limit a pod has allocated against the namespace quota.

VCPU Limit Quota

If applicable, VCPU Limit Quota is the amount of virtual CPU limit (in mCores) a pod has allocated against the namespace quota.

■ Workload Controller

Workload Optimization Manager monitors quotas (limits and requests) for VCPU and VMem, and associates how much each Workload Controller is contributing to a quota based on all replicas. This allows Workload Optimization Manager to generate rightsizing decisions, and manage the quota as a constraint to rightsizing. Metrics on resource consumption are shown in the Container Spec, Container, and Container Pod views.

Namespace

VMem Request Quota

VMem Request Quota is the total amount of virtual memory request for all pods allocated to the namespace against the namespace quota.

VCPU Request Quota

VCPU Request Quota is the total amount of virtual CPU request (in mCores) for all pods allocated to the namespace against the namespace quota.

VMem Limit Quota

VMem Limit Quota is the total amount of virtual memory limit for all pods allocated to the namespace against the namespace quota.

VCPU Limit Quota



VCPU Limit Quota is the total amount of virtual CPU limit (in mCores) for all pods allocated to the namespace against the namespace quota.

■ Container Cluster

Workload Optimization Manager monitors resources for the containers, pods, nodes (VMs), and volumes in a cluster.

Node (VM)

Workload Optimization Manager monitors the following resources for nodes that host Kubernetes pods. These resources are monitored along with the resources from the infrastructure probes, such as vCenter or a public cloud mediation probe.

VMem

VMem is the virtual memory currently used by all containers on the node. The capacity for this resource is the Node Physical capacity.

VCPU

VCPU is the virtual CPU currently used by all containers on the node. The capacity for this resource is the Node Physical capacity.

Memory Request Allocation

Memory Request Allocation is the memory available to the node to support the ResourceQuota request parameter for a given namespace (Kubernetes namespace or Red Hat OpenShift project).

CPU Request Allocation

CPU Request Allocation is the CPU available to the node to support the ResourceQuota request parameter for a given namespace (Kubernetes namespace or Red Hat OpenShift project).

Virtual Memory Request

Virtual Memory Request is the memory currently guaranteed by all containers on the node with a memory request. The capacity for this resource is the Node Allocatable capacity, which is the amount of resources available for pods and can be less than the physical capacity.

Virtual CPU Request

Virtual CPU Request is the CPU currently guaranteed by all containers on the node with a CPU request. The capacity for this resource is the Node Allocatable capacity, which is the amount of resources available for pods and can be less than the physical capacity.

Memory Allocation

Memory Allocation is the memory ResourceQuota limit parameter for a given namespace (Kubernetes namespace or Red Hat OpenShift project).

CPU Allocation

CPU Allocation is the CPU ResourceQuota limit parameter for a given namespace (Kubernetes namespace or Red Hat OpenShift project).

Actions

Workload Optimization Manager recommends actions for the Kubernetes container platform supply chain as follows.

Service

None

Workload Optimization Manager does not recommend actions for Kubernetes Services, but it does recommend actions for the replicas that back those Services.

For details, see Workload Controller Scale Actions (on page 356).

■ Container

None

Workload Optimization Manager does not recommend actions on containers.

■ Container Spec

Resize (via Workload Controllers)

A Container Spec retains the historical utilization data of ephemeral containers. Workload Optimization Manager uses this data to make resize decisions that assure optimal utilization of resources. By default, all replicas of the same container for the same workload type resize consistently.



For details, see Workload Controller Resize Actions (on page 352).

Container Pod

Move

Move a pod between nodes (VMs) to address performance issues or improve infrastructure efficiency. For example, if a particular node is congested for CPU, you can move pods to a node with sufficient capacity. If a node is underutilized and is a candidate for suspension, you must first move the pods before you can safely suspend the node.

Provision/Suspend

When recommending node provision or suspend actions, Workload Optimization Manager will also recommend provisioning pods (based on demand from DaemonSets) or suspending the related pods.

For details, see Container Pod Actions (on page 361).

■ Workload Controller

Resize or Scale

Actions associated with a Workload Controller resize Container Specs vertically or scale replicas horizontally. This is a natural representation of these actions because the parent controller's Container Specs and number of replicas are modified. The Workload Controller then rolls out the changes in the running environment.

For details, see <u>Workload Controller Resize Actions</u> (on page 352) and <u>Workload Controller Scale Actions</u> (on page 356).

■ Namespace

Resize Quota

Workload Optimization Manager treats quotas defined in a namespace as constraints when making resize decisions. If existing actions would exceed the namespace quotas, Workload Optimization Manager recommends actions to resize up the affected namespace quota.

Note that Workload Optimization Manager does not recommend actions to resize *down* a namespace quota. Such an action reduces the capacity that is already allocated to an application. The decision to resize down a namespace quota should include the application owner.

For details, see Namespace Actions (on page 366).

Container Cluster

None

Workload Optimization Manager does not recommend actions for a Container Cluster. Instead, it recommends actions for the containers, pods, nodes (VMs), and volumes in the cluster. Workload Optimization Manager shows all of these actions when you scope to a Container Cluster and view the Pending Actions chart.

Node (VM)

A Kubernetes node (cloud or on-prem) is represented as a Virtual Machine entity in the supply chain.

Provision

Provision nodes to address workload congestion or meet application demand.

Suspend

Suspend nodes after you have consolidated pods or defragmented node resources to improve infrastructure efficiency.

Reconfigure

Reconfigure nodes that are currently in the NotReady state.

NOTE:

For nodes in the public cloud, Workload Optimization Manager reports the cost savings or investments attached to these actions.

For details, see Node Actions (on page 373).



Fabric Targets

A fabric target is a service that unites compute, network and storage access into a cohesive system. When you connect Workload Optimization Manager to fabric targets, it monitors the performance and resource consumption of your fabric interconnects, IO modules, chassis, and physical machines to assure application performance and utilize resources as efficiently as possible.

Once connected, Workload Optimization Manager discovers the blade servers that host the VMs, the chassis and datastores that provide resources to the blade servers, the IO modules and fabric interconnects that provide network resources, and the virtual datastores that provide storage resources to the VMs.

As part of this process, Workload Optimization Manager will stitch information from the fabric target and connected hypervisor targets to provide more granular data and information related to the applications and VMs running on the hypervisor-stitched blade servers. Combined with other targets, this information will support a top-down, application-driven approach to managing your environment.

For example:

When Workload Optimization Manager discovers that blade servers housed in a particular chassis have been designated as vCenter hosts, the supply chain stitches the blade servers and chassis to the corresponding vCenter data center to establish their relationship. When you set the scope to that data center and view the Health chart, you will see the blade servers in the list of hosts. In addition, when the data center is included in a merge policy (a policy that merges data centers for the purpose of VM placement), the VMs in the blade servers apply the policy, allowing them to move between data centers as necessary.

When you add application server targets, your applications and their individual components and services are discovered, enabling a view of your infrastructure from an individual application service to the physical hardware. Adding public cloud targets also allow for workloads to potentially migrate from your UCS infrastructure to the cloud, based on cost or available resources.

Supply Chain

Fabric targets add IO Module, Fabric Interconnect, Domain, and Chassis entities to the supply chain. The Chassis entities host physical machines (blade servers) — The physical machines also consume network connection commodities from IO Modules. The Fabric Interconnect supplies connectivity to the overall network, and also hosts the UCS Manager for UCS Targets. The Domain serves as the bottom-level pool of network resource, supplying the Fabric Interconnect.

Cisco UCS Manager

The Cisco Unified Computing System (UCS) Manager is a management solution that participates in server, fabric, and storage provisioning, device discovery, inventory, configuration, diagnostics, monitoring, fault detection, auditing, and statistics collection.

Workload Optimization Manager supports Cisco UCS Manager 2.2+.

UCS integrates all of these resources in a scalable multi-chassis platform to converge administration onto a single point. Managing these various entities on a network fabric with Workload Optimization Manager enables automation at the hardware level, including automated provisioning of hosts.

Prerequisites

A service account Workload Optimization Manager can use to connect to Cisco UCS Manager

Adding UCS Targets

To add a UCS target, select the **Fabric and Network** category and choose one of the UCS Fabric options to match the version of UCS you want to manage. Then provide the following information:

Address: The IP address of the Cisco UCS Manager

This gives access to the Fabric Manager that resides on the interconnect.

Workload Optimization Manager connects to the Cisco UCS Manager via the HTTP protocol by default.



 Username/Password: The credentials of the account Workload Optimization Manager will use to connect to Cisco UCS Manager.

specify the IP address and credentials for Cisco UCS Manager. Workload Optimization Manager discovers the fabric interfaces associated with that manager.

NOTE:

When providing a username, if the account is managed in Active Directory you must include the domain in case-sensitive spelling. For example, MyDomain\john is not the same as mydomain\john. For local user accounts, just provide the username.

- Port Number: The port Workload Optimization Manager will use to connect to the target.
- Secure Connection: When checked, Workload Optimization Manager will connect using SSL.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

UCS	Workload Optimization Manager
Server / Blade / Rack Unit	Host
Chassis	Chassis
Datacenter	Datacenter
IO Module	IO Module
Fabric Interconnect	Switch
Network	Network

Fabric targets add IO Module, Fabric Interconnect (Switch), and Chassis entities to the supply chain. Hosts consume resources from Chassis entities, and network connection commodities from IO Modules. The Fabric Interconnect supplies connectivity to the overall network, and also hosts the UCS Manager. The Domain serves as the bottom-level pool of network resource, supplying the Fabric Interconnect. Be sure that all the FC, Ether and Physical Ports are properly configured with suitable roles in UCS so that the supply chain is populated accurately without disjoints.

Monitored Resources

Workload Optimization Manager monitors the following resources:

■ Host

Power

Power is the measurement of electricity consumed by a given entity, expressed in watts.

Memory (Mem)

Memory is the measurement of memory that is reserved or in use.

CPU

CPU is the measurement of CPU that is reserved or in use.

– IC

IO is the utilization of a host's IO adapters.

Net

Net is the utilization of data through the host's network adapters.

Swap

Swap is the measurement of a host's swap space that is in use.

Balloon

Balloon is the measurement of memory that is shared by VMs running on a host.

This commodity applies to ESX only.



CPU Ready

CPU Ready is the measurement of a host's ready queue capacity that is in use.

This commodity applies to ESX only.

Chassis

Power

Power is the measurement of electricity consumed by a given entity, expressed in watts.

Cooling

Cooling is the percentage of the acceptable temperature range that is utilized by the entity. As the temperature nears the high or low running temperature limits, this percentage increases.

■ I/O Module

Net Throughput

Net Throughput is the rate of message delivery over a port.

Switch

Net Throughput

Net Throughput is the rate of message delivery over a port.

PortChannel

PortChannel is the amalgamation of ports with a shared net throughput and utilization.

Actions

Workload Optimization Manager can recommend the following actions:

■ Host

- Start
- Provision
- Suspend

■ Chassis

Provision

Switch

- Add Port to Port Channel
- Remove Port from Port Channel
- Add Port

UCS Blade Provisioning

When managing a UCS fabric target, Workload Optimization Manager can provision any blade servers that are installed in a chassis but not currently in operation. If the workload demands more physical compute resources, Workload Optimization Manager can automatically direct UCS to provision a blade, or it can recommend that you provision a blade and you can execute the action from the To Do list. To enable this capability, you must perform two basic steps:

Configure the way UCS and vCenter Server manage information as blades are provisioned

To enable Workload Optimization Manager to perform automatic provisioning of UCS blades, you must configure UCS to work with vCenter Server as they both manage resources such as server pools, policies, and Service Profile Templates. This ensures that as Workload Optimization Manager directs the UCS Manager to provision a new blade, vCenter Server will recognize that the new physical host is available. Once vCenter Server can recognize the new blade, Workload Optimization Manager can direct vCenter Server to move workloads onto the server.

Workload Optimization Manager provisions new blades based on the service profiles of operating blades. To enable this, the configuration must include Service Profile Templates, and the operating blades must be bound to these templates.

For information about configuration that enables automated provisioning of blades, see the Cisco Communities post, "UCS PowerTool and VMware PowerCLI automated management of Auto-deploy" at the following location:



https://communities.cisco.com/community/technology/datacenter/ucs_management/cisco_ucs_developed_integrations/blog/2013/09/16/ucs-powertool-and-vmware-powercli-automated-management-of-auto-deploy

This post includes a video that shows "a joint PowerShell integration utilizing both Cisco UCS PowerTool and VMware PowerCLI." You can also download the scripts from this post and modify them as necessary for your deployment.

■ Set the Host Provision action to Automate or Manual for the blade servers. By default, Workload Optimization Manager sets the Host Provision action to Recommend.

For any hosts other than blade servers managed by UCS, Workload Optimization Manager cannot provision hosts automatically or manually. Instead, it recommends that you provision a host, and you then install the physical machine and wire it to the network.

In a UCS deployment you can have blade servers installed in the chassis and ready to provision. In that case, Workload Optimization Manager can direct UCS to provision a new blade to meet workload demands. For these servers, you can set the Host Provision action to Automatic or Manual.

NOTE:

It's important that you only set Automatic or Manual host provisioning to UCS blades. If you set Host Provision to Automatic for other types of hosts, Workload Optimization Manager will attempt to perform the action and fail. As a result, you might never see the recommendation to provision a new host of that type.

Workload Optimization Manager groups blade servers by chassis. To restrict Automatic or Manual settings to blade servers, use this group. You can set the action acceptance mode for all blade servers in your environment, or you can set the mode differently for individual chassis.

HPF OneView

HPE OneView is a management solution that streamlines provisioning and lifecycle management across compute, storage, and fabric. Through a unified API, infrastructure can be configured, monitored, updated, and re-purposed.

HPE OneView integrates all of these resources in a scalable multi-enclosure platform to converge administration onto a single point. Managing these various entities on a network fabric with Workload Optimization Manager enables automation at the hardware level, including automated provisioning of hosts.

Prerequisites

- A service account Workload Optimization Manager can use to connect to HPE OneView.
- HPE OneView 2.0 and compatible hardware.
- The Banner Page option for the user account should be disabled in the HPE OneView user interface.
- You should disable Require Acknowledgement for the user account in the HPE OneView user interface.

Adding HPE OneView Targets

To add a HPE OneView as a target, select the **Fabric** category and choose the HPE OneView radio button. Then provide the following information:

Address:

The IP address of the HPE OneView target

This gives access to the Fabric Manager that resides on the VM.

Workload Optimization Manager uses the HTTPS protocol by default. In order to force the HTTP protocol, the Address must be entered in one of two ways. For example, an IP of 8.8.8.8 must be entered as http://8.8.8.8 or by using a specific HTTP port, such as 8.8.8.8:80.

Username/Password:

The credentials of the account Workload Optimization Manager will use to connect to the HPE OneView target.

Specify the IP address and credentials for HPE OneView. Workload Optimization Manager discovers the fabric interfaces associated with that instance.



When providing a username, if the account is managed in Active Directory you must include the domain in case-sensitive spelling. For example, MyDomain@john is not the same as mydomain@john. For local user accounts, just provide the username.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

HPE OneView	Workload Optimization Manager
IO Module	IO Module
Fabric Interconnect	Switch
Domain	Domain
Chassis	Physical Machines

Fabric targets add IO Module, Fabric Interconnect (Switch), Domain, and Chassis entities to the supply chain. The Chassis entities host physical machines – The physical machines also consume network connection commodities from IO Modules. The Fabric Interconnect supplies connectivity to the overall network. The Domain serves as the bottom-level pool of network resource, supplying the Fabric Interconnect.

NOTE:

For HPE OneView targets, the "Fabric Interconnect" entity exists as a false "Switch", and only as a pass-through for network resources. Unlike other fabric targets, such as UCS, there is no physical hardware that serves this function.

Monitored Resources

Workload Optimization Manager monitors the following resources:

■ Virtual Machine

NOTE:

Workload Optimization Manager only monitors VM resources if HPE OneView is stitched to a hypervisor in the supply chain.

- Virtual Memory (VMem)
 - Virtual Memory is the measurement of memory that is in use.
- Virtual CPU (VCPU)
 - Virtual CPU is the measurement of CPU that is in use.
- Virtual Storage
 - Virtual storage is the measurement of virtual storage capacity that is in use.
- Storage Access (IOPS)
 - Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.
- Latency
 - Latency is the measurement of storage latency.

■ Host

- Power
 - Power is the measurement of electricity consumed by a given entity, expressed in watts.
- Memory (Mem)
 - Memory is the measurement of memory that is reserved or in use.
- CPU
 - CPU is the measurement of CPU that is reserved or in use.
- IO



IO is the utilization of a host's IO adapters.

Net

Net is the utilization of data through the host's network adapters.

Swap

Swap is the measurement of a host's swap space that is in use.

Balloon

Balloon is the measurement of memory that is shared by VMs running on a host.

CPU Ready

CPU Ready is the measurement of a host's ready queue capacity that is in use.

■ Chassis

- Power

Power is the measurement of electricity consumed by a given entity, expressed in watts.

Cooling

Cooling is the percentage of the acceptable temperature range that is utilized by the entity. As the temperature nears the high or low running temperature limits, this percentage increases.

Storage

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

NOTE:

When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.

I/O Module

Net Throughput

Net Throughput is the rate of message delivery over a port.

Switch

Net Throughput

Net Throughput is the rate of message delivery over a port.

PortChannel

PortChannel is the amalgamation of ports with a shared net throughput and utilization.

DPod (if Network Flow target is present)

Memory (Mem)

Memory is the measurement of memory that is reserved or in use.

CPU

CPU is the measurement of CPU that is reserved or in use.

Storage

Storage is the utilization of the storage attached to the entity.

– Flow

Flow is the utilization of the network flow capacity utilized by the entity. This is divided into Flow1 (Low Cost) and Flow2 (Medium Cost) utilization.



Actions

Workload Optimization Manager can recommend the following actions:

Virtual Machine

- Provision additional resources (VMem, VCPU)
- Move Virtual Machine
- Move Virtual Machine Storage
- Reconfigure Storage
- Reconfigure Virtual Machine
- Suspend VM
- Provision VM

Host

- Start
- Provision
- Suspend

Switch

- Add Port to Port Channel
- Remove Port from Port Channel
- Add Port
- DPod (if Network Flow target is present)
 - Provision new DPod

Guest OS Processes Targets

Using WMI (Windows Management Instrumentation) or SNMP, Workload Optimization Manager can discover OS processes that are running on your VMs. Analysis creates an Application Component entity for each process.

Workload Optimization Manager does not generate actions for these discovered Application Components. For many types of applications, you can a target dedicated to that application. You should use Guest OS Process targets for cases where there is no other target you can use for the application. For more information, see Applications and Databases Targets (on page 137).

WMI

Workload Optimization Manager will discover application and operating system resources using WMI (Windows Management Instrumentation) in your entire environment, or a portion of your environment, based on scope.

Prerequisites

- Underlying VM host targets added to Workload Optimization Manager (for discovery)
- A WMI user account Workload Optimization Manager can use to connect to the WMI targets. This account can either be
 an administrator user, or a non-administrator belonging to certain local user groups. For a full list of requirements, see
 Creating a WMI User Account (on page 194)
- WMI enabled on target VMs. For assistance in enabling WMI, see Enabling WMI (on page 194).

NOTE:

For Hyper-V hosts, you must install Hyper-V Integration Services on the target VMs. For more information, please refer to the following integration services TechNet article: https://technet.microsoft.com/en-us/library/dn798297(v=ws.11).aspx.

For VMware hosts, you must install VMware Tools on the target VMs.



Adding WMI Targets

To add WMI targets, select the **Guest OS Processes > WMI** option on the Target Configuration page and provide the following information:

Target Name

The display name that will be used to identify the target in the Target List. This is for display in the UI only; it does not need to match any internal name.

Username

The username Workload Optimization Manager will use to connect to the WinRM service on the Virtual Machine hosting the application. This should not include the Active Directory domain.

Password

The password Workload Optimization Manager will use to connect to the WinRM service on the Virtual Machine hosting the application.

Scope

Workload Optimization Manager will search for Windows applications on the VMs found within the set scope. This scope can be set to the entire environment, single or multiple clusters, or particular virtual machines. Select this option and choose the scope for application discovery.

NOTE:

A single scope (target) must not contain more than 500 virtual machines. Workload Optimization Manager recommends utilization of multiple WMI targets for environments exceeding this limit. Contact Workload Optimization Manager Support for assistance in using multiple WMI targets.

Domain Name

The Active Directory domain used by Workload Optimization Manager in conjunction with the Username for authentication. Leave blank for local accounts.

Secure connection

When selected, Workload Optimization Manager will use a secure (SSL) connection.

NTLM for Domain Accounts

This option is selected by default. When selected, Workload Optimization Manager will use the NTLM protocol instead of the Kerberos protocol for domain accounts. NTLM is always used for local accounts.

Full Validation

When selected, Workload Optimization Manager will require all database servers hosted on the VMs in the selected scope to be a valid target. If Workload Optimization Manager is unable to authenticate a database server in the scope, the target will not validate and data will not be collected.

Enabling Guest Load Metrics

NOTE:

For environments that use WMI or SNMP probes, you must configure the Workload Optimization Manager installation to enable guest load metrics. Without this configuration, the WMI and SNMP probes will not display discovered guest load data.

To enable guest load metrics, you must edit the CR file and restart the platform:

Open the cr.yaml file for editing.

```
/opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```

2. Enable guest metrics in the properties section of the file:

```
properties:
   repository:
    showGuestLoad: true
```

Save your changes to the file.



4. Apply your changes.

Run the command:

kubectl apply -f /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml

5. To restart the component, delete the repository pod.

Run the command (where {POD_ID} is the ID that is appended to the pod in the get pods listing):

kubectl delete pod -n cwom repository-{POD_ID}

Monitored Resources

Workload Optimization Manager monitors the following resources:

■ WMI/SNMP Application

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual Machine

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual Storage

Virtual storage is the measurement of virtual storage capacity that is in use.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

Actions

NOTE:

The specific actions that Workload Optimization Manager recommends can differ, depending on the processes that Workload Optimization Manager discovers.

For other application components, Workload Optimization Manager can recommend actions based on the resources it can discover for the application. For example, Node.js® applications report CPU usage, so Workload Optimization Manager can generate vCPU resize actions and display them in the user interface.

Workload Optimization Manager can recommend the following actions:

Virtual Machine

- Provision additional resources (VMem, VCPU)
- Move Virtual Machine
- Move Virtual Machine Storage
- Reconfigure Storage
- Reconfigure Virtual Machine
- Suspend VM
- Provision VM



Without separate targets to discover Guest OS Processes or Application Servers, Workload Optimization Manager does not generate actions on applications. Instead, it generates resize actions on the host VMs. For on-prem environments, if host utilization is high enough on the host running the application VM, Workload Optimization Manager can also recommend provisioning a new host.

Creating a WMI User Account

The service account Workload Optimization Manager uses to connect to WMI should be an Active Directory domain account.

Some enterprises require that the service account does not grant full administrator rights. In that case, you can create a restricted service account for WMI:

- 1. Add the account to each of the following local groups:
 - WinRMRemoteWMIUsers___(or Remote Management Users)
 - Performance Monitor Users

NOTE

These groups are standard Windows Server 2012 security groups. If you are using an earlier version of Windows Server and do not see these groups, contact Cisco Support for assistance.

Grant permissions to the account.

In the WMI Management console, grant the Enable Account and Remote Enable advanced security permissions to the service account:

- Open the WMI Management console (wmimgmt).
- Right-click WMI Control (Local) and choose Properties.
- Go to the Security tab and then click Security to display the Security for Root dialog.
- Click Advanced, select the service account, and click Edit.
- Confirm that This namespace and subnamespace is selected.
- Select Enable Account and Remote Enable and click OK.

Enabling WMI

Enabling WMI

To enable Workload Optimization Manager discovery of Windows-based Guest Processes, you must configure and enable WMI with WinRM, usually by using a group policy for AD Domains.

When local credentials are provided to Workload Optimization Manager, NTLM is the authentication mechanism. When domain credentials are provided, either NTLM or Kerberos can be specified.

NOTE:

If Kerberos is specified, the IP address of the target must be resolvable to a host name using DNS.

While these steps will change slightly between Windows Server versions, the general instructions are:

- 1. Open an elevated PowerShell prompt on the virtual machines to be discovered as a WMI Target.
- 2. Enable the WS-Management protocol and set the default configuration for remote management.

Run the command:

```
winrm quickconfig
```

3. Enable the WinRM Negotiate authentication scheme.

This policy is enabled by default. To enable this policy if it is disabled, run the command:

```
winrm set winrm/config/service/auth '@{Negotiate="true"}'
```

Set the WinRM AllowUnencrypted property to true if non-SSL connections are preferred.



This property must be set on both the server and the client. Note that setting this value to true does not mean that WMI passes sensitive data in an unencrypted form. It will send only the content of the SOAP messages as plain text:

Server setting:

```
winrm set winrm/config/service '@{AllowUnencrypted="true"}'
```

Client setting:

```
winrm set winrm/config/client '@{AllowUnencrypted="true"}'
```

Restart the Remote Registry service.

After restarting the Remote Registry service, Workload Optimization Manager will discover the WMI targets.

SSL Connections

To connect using SSL, then a certificate must be assigned to WinRM, and an SSL listening socket enabled. Workload Optimization Manager will accept self-signed certificates. Complete details can be found in the official WinRM documentation.

Some example SSL-related commands:

List certificates on the system.

```
ls cert://localmachine/my
```

Find Thumbprint for the default certificate.

```
7B56C33F029E7605D5C58E5597D0A077FE1D7F1C CN=winsql-server1.corp.mycorp.com
```

Enable SSL listener.

```
winrm create winrm/config/listener?Address=*+Transport=HTTPS @{Hostname="winsql-server1.corp.mycorp.com";CertificateThumbprint="7B56C33F029E7605D5C58E5597D0A077FE1D7F1C";Port="5986"}
```

SNMP

Workload Optimization Manager will discover application and operating system resources using SNMP (Simple Network Management Protocol) on Linux hosts within the specified scope of your environment.

Prerequisites

- Underlying VM host targets added to Workload Optimization Manager (for discovery)
- SNMP service enabled/configured on target VMs to allow access to the OIDs required. The credentials used must allow
 access to the following OIDs:

```
- 1.3.6.1.2.1.1.1 - sysDescr

- 1.3.6.1.2.1.25.4.2.1.2 - hrSWRunName

- 1.3.6.1.2.1.25.5.1.1 - hrSWRunPerfEntry

- 1.3.6.1.2.1.25.3.3.1.2 - hrProcessorLoad

- 1.3.6.1.4.1.2021.4.5 - memTotalReal

- 1.3.6.1.4.1.2021.4.6 - memAvailReal

- 1.3.6.1.4.1.2021.4.11 - memTotalFree

- 1.3.6.1.4.1.2021.4.14 - memBuffer

- 1.3.6.1.4.1.2021.4.15 - memCached
```



For environments that include SNMP targets, Workload Optimization Manager can discover incorrect memory values for Linux systems. This can occur for the systems that use the net-snmp package, version 5.7.2-43.el7. You should use versions less than 5.7.2-43.el7, or greater than or equal to 5.7.2-47.el7.

For Hyper-V hosts, you must install Hyper-V Integration Services on the target VMs. For more information, please refer to the following integration services TechNet article:

https://technet.microsoft.com/en-us/library/dn798297%28v=ws.11%29.aspx

For VMware hosts, you must install VMware Tools on the target VMs.

Adding SNMP Targets

To add SNMP targets, select the **Guest OS Processes > SNMP** option on the Target Configuration page and provide the following information:

Target Name

The display name that will be used to identify the target in the Target List. This is for display in the UI only; it does not need to match any internal name.

Scope

Workload Optimization Manager will search for SNMP applications on the VMs found within the set scope. This scope can be set to the entire environment, single or multiple clusters, or particular virtual machines. Select this option and choose the scope for application discovery.

NOTE:

A single scope (target) must not contain more than 500 virtual machines. Workload Optimization Manager recommends utilization of multiple SNMP targets for environments exceeding this limit.

Community

The SNMP v2c community string Workload Optimization Manager will use to connect to the SNMP agent on the VM

Port number

The Port number Workload Optimization Manager will use to connect to the SNMP agent on the VM

Full Validation

When selected, Workload Optimization Manager will require all database servers hosted on the VMs in the selected scope to be a valid target. If Workload Optimization Manager is unable to authenticate a database server in the scope, the target will not validate and data will not be collected.

■ Enable SNMPv3

When checked, Workload Optimization Manager will use SNMPv3 to connect to the virtual machines in the selected scope

SNMPv3 Username/SecurityName

The Username/SecurityName that Workload Optimization Manager will use to connect to the virtual machines hosting the application

■ SNMPv3 Enable Privacy

When checked, Workload Optimization Manager will encrypt using the privacy password to keep the connection private.

SNMPv3 Authentication Password

The Authentication Password Workload Optimization Manager will use to connect to the virtual machines in the selected scope. This allows requests to be authenticated, confirming the sender's identity.

SNMPv3 Privacy Password

The Privacy Password Workload Optimization Manager will use to connect to the virtual machines in the selected scope. For requests to be encrypted, the SNMP manager and the SNMP agent must share knowledge of the privacy password associated with the username.

■ SHA-1 For Authentication

When checked, Workload Optimization Manager uses SHA-1 Authentication to connect to the virtual machines in the selected scope. When unchecked, Workload Optimization Manager uses MD5

AES For Privacy



When checked, Workload Optimization Manager will use AES 128 to connect to the virtual machines in the selected scope. When unchecked, Workload Optimization Manager uses DES

NOTE:

Workload Optimization Manager does not support AES 192 or 256 for SNMP targets.

Enabling Guest Load Metrics

NOTE:

For environments that use WMI or SNMP probes, you must configure the Workload Optimization Manager installation to enable guest load metrics. Without this configuration, the WMI and SNMP probes will not display discovered guest load data.

To enable guest load metrics, you must edit the CR file and restart the platform:

1. Open the cr.yaml file for editing.

```
/opt/turbonomic/kubernetes/operator/deploy/crds/charts_v1alpha1_x1_cr.yaml
```

2. Enable guest metrics in the properties section of the file:

```
properties:
   repository:
    showGuestLoad: true
```

- Save your changes to the file.
- Apply your changes.

Run the command:

```
kubectl apply -f /opt/turbonomic/kubernetes/operator/deploy/crds/charts_v1alpha1_x1_cr.yaml
```

5. To restart the component, delete the repository pod.

Run the command (where {POD_ID} is the ID that is appended to the pod in the get pods listing):

```
kubectl delete pod -n cwom repository-{POD_ID}
```

Monitored Resources

Workload Optimization Manager monitors the following resources:

- WMI/SNMP Application
 - Virtual CPU (VCPU)
 - Virtual CPU is the measurement of CPU that is in use.
 - Virtual Memory (VMem)
 - Virtual Memory is the measurement of memory that is in use.
- Virtual Machine
 - Virtual CPU (VCPU)
 - Virtual CPU is the measurement of CPU that is in use.
 - Virtual Memory (VMem)
 - Virtual Memory is the measurement of memory that is in use.
 - Virtual Storage
 - Virtual storage is the measurement of virtual storage capacity that is in use.
 - Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.



Latency

Latency is the measurement of storage latency.

Actions

NOTE:

The specific actions that Workload Optimization Manager recommends can differ, depending on the processes that Workload Optimization Manager discovers.

For other application components, Workload Optimization Manager can recommend actions based on the resources it can discover for the application. For example, Node.js® applications report CPU usage, so Workload Optimization Manager can generate vCPU resize actions and display them in the user interface.

Workload Optimization Manager can recommend the following actions:

Virtual Machine

- Provision additional resources (VMem, VCPU)
- Move Virtual Machine
- Move Virtual Machine Storage
- Reconfigure Storage
- Reconfigure Virtual Machine
- Suspend VM
- Provision VM

NOTE:

Without separate targets to discover Guest OS Processes or Application Servers, Workload Optimization Manager does not generate actions on applications. Instead, it generates resize actions on the host VMs. For on-prem environments, if host utilization is high enough on the host running the application VM, Workload Optimization Manager can also recommend provisioning a new host.

Enabling SNMP

Workload Optimization Manager requires that SNMP is enabled and configured in order to discover Guest Processes. While these steps will change slightly between OS versions, this topic gives you the general instructions:

Enabling SNMP v2

- 1. Obtain and install the SNMP server package for your Linux distribution and version. This is commonly called net-snmp in most package managers. Also install the net-snmp-utils package if it is available.
- 2. Configure the SNMP daemon by editing /etc/snmp/snmpd.conf or running snmpconf -i at the command line in order to verify that:
 - SNMP v2c is enabled.
 - A read-only community name has been set. This community name will be used by Workload Optimization Manager to communicate with the SNMP agent on the VM.

NOTE:

The community name you select must have at least read-only access to all OIDs in the system.

- 3. Configure the daemon to listen on a public interface. Most default installations only listen on 127.0.0.1.
- Start the SNMP daemon process.

These long form and short form sample snmp.conf files illustrate the necessary changes.

Long form, VACM:

```
# First, map the community name "mycommunity1" into a "security name"
# sec.name source community
com2sec notConfigUser default mycommunity1
```



Short form, older syntax:

rocommunity mycommunity1 default system

Verify Your SNMP Setup

Verify that your SNMP setup is successful by using the following command from a remote machine, replacing the community string and IP address:

```
snmpwalk -Os -v 2c -c COMMUNITY_STRING IP_ADDRESS iso.3.6.1.2.1.1.1
```

If successful, the command will return the kernel version of the machine (similar to the output of uname -a).

Enabling SNMP v3

Obtain and install the SNMP server package for your Linux distribution and version.

Most package managers call this package net-snmp. To verify your configuration in step 5 below, you should also install the net-snmp-utils package on the Workload Optimization Manager VM.

- 2. Stop the SNMP service.
- 3. Create the SNMPv3 user.

Run the following command:

```
net-snmp-config --create-snmpv3-user [-ro] [-A authpass] [-X privpass] [-a MD5|SHA] [-x DES|AES] [use rname]
```

For example, the command:

```
i. net-snmp-create-v3-user -ro -A snmpv3authPass -a SHA -X snmpv3encPass -x AES snmpv3user
```

results in output similar to:

```
adding the following line to /var/lib/net-snmp/snmpd.conf: createUser snmpv3user SHA "snmpv3authPass" AES snmpv3encPass adding the following line to /etc/snmp/s nmpd.conf: rouser snmpv3user
```

4. Verify your SNMP setup.

To verify the configuration, run the following command on the Workload Optimization Manager VM:

```
snmpwalk -Os -v 2c -c COMMUNITY_STRING IP_ADDRESS iso.3.6.1.2.1.1.1
```

Hyperconverged Targets

A hyperconverged target is a service that unites compute, network and storage access into a cohesive system. When you connect Workload Optimization Manager to hyperconverged targets, it will monitor the performance and resource consumption of your hyperconverged infrastructure to maintain application performance while utilizing resources as efficiently as possible.



As part of this process, Workload Optimization Manager will stitch information from the hyperconverged target to the associated hypervisor and fabric targets, supporting Application Resource Management (ARM) and providing deeper insight into the state of the hardware and information related to the entities in the supply chain. Combined with application server targets, this information will support a top-down, application-driven approach to managing your environment.

Cisco HyperFlex

Cisco HyperFlex provides a hyperconverged platform that combines the networking and compute power of UCS with the storage capabilities of the HyperFlex HX Data Platform.

With the additional and refined storage information provided by HyperFlex, Workload Optimization Manager narrows the Desired State and recommends actions using the joint compute and storage information, gaining valuable insight into the interconnected nature of your environment.

For Workload Optimization Manager to make the most informed decisions, you must also add the compute nodes and any associated hypervisors. HyperFlex environments typically include:

- Converged (HX) Nodes
 - A combination of the cluster's storage devices into a single multi-tiered, object-based datastore.
- Compute Nodes
 - Cisco B or C series servers that make up the compute resources of the cluster, and are typically managed by a hypervisor.
- Controller VMs
 - Each HyperFlex node includes a Controller VM that intercepts and handles all the I/O from associated virtual machines. Workload Optimization Manager will not recommend actions for these VMs.

Prerequisites

 A service account on the controller VM that Workload Optimization Manager can use to connect to the HyperFlex environment

Adding HyperFlex Targets

To add a HyperFlex target, select the **Hyperconverged > HyperFlex** option on the Target Configuration page and provide the following information:

- Address
 - The name or IP address of the HyperFlex controller VM. If a port is appended to the IP address, it must be a secure (HTTPS) port.
- Username/Password
 - Credentials for a user account Workload Optimization Manager will use to connect to the controller VM.

To specify a root user for the target, give the name as local/root. Note that earlier versions of Workload Optimization Manager accepted a username of root. If an existing HyperFlex target fails to validate after you have upgraded Workload Optimization Manager, then check to make sure the username for a root account is properly set to local/root.

If you use vSphere SSO for authentication to the HyperFlex target, you must prepend your username with vc-. For example, if your username is Administrator@vsphere.local, you would enter it as vc-Administrator@vsphere.local.

Port Number

Port Number Workload Optimization Manager will use to connect to the controller VM.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

Нуре	erFlex	Workload Optimization Manager
Volur	me	Storage



HyperFlex	Workload Optimization Manager
HX Cluster	Disk Array

HyperFlex targets add Disk Array entities to the supply chain, and receive more granular information from the compute resources in your environment.

Monitored Resources

Workload Optimization Manager monitors the following resources:

■ Storage

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

NOTE:

When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.

■ Disk Array

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

Actions

Workload Optimization Manager can recommend the following actions:

Storage

Move

This action can only be executed outside Workload Optimization Manager.

Provision

This action can only be executed outside Workload Optimization Manager.

Resize Up

This action can only be executed outside Workload Optimization Manager.

Disk Array

Provision

This action can only be executed outside Workload Optimization Manager.

Suspend

This action can only be executed outside Workload Optimization Manager.



Resize Up

This action can only be executed outside Workload Optimization Manager.

NOTE:

For this target, Workload Optimization Manager discovers the HX Cluster as a Disk Array. When you see a provision action on this entity, you should determine which of the following is most relevant, based on your environment:

- Add disks to converged nodes
- Add a new converged node
- Add a new HX Cluster

Nutanix

Nutanix products provide hyperconverged platforms that include VM hosting and a distributed storage fabric. The platform presents storage in two tiers – Local HDD storage and server-attached flash (hot storage).

Nutanix environments may include:

- One or more Nutanix appliances
 - An appliance contains up to four server nodes.
- Nutanix nodes
 - Servers that expose compute and storage resources. Each node provides local HDD and hot storage. Nodes combine to form a unified cluster that pools resources.
- Controller VMs
 - Each node includes a Controller VM that manages the node's resources within the cluster pool. To minimize storage latency, the Controller VM keeps the most frequently accessed data in the hot storage.

Workload Optimization Manager supports management of Nutanix fabrics, where the supply chain treats a Nutanix Storage Pool as a disk array. Workload Optimization Manager recognizes Nutanix storage tiers when calculating placement of VMs and VStorage. In addition, Workload Optimization Manager can recommend actions to scale flash capacity up or down by adding more hosts to the cluster, or more flash drives to the hosts.

To specify a Nutanix target, provide the Cluster External IP address. This is a logical IP address that always connects to one of the active Controller VMs in the cluster. In this way, you can specify a Nutanix target without having to specify an explicit Controller VM.

NOTE:

The Controller VM must remain *pinned* to its host machine – You must not move the Controller VM to a different host. If the Nutanix cluster uses the Nutanix Acropolis OS to manage VMs, Workload Optimization Manager automatically pins the Controller VMs. However, if you use vCenter Server or Hyper-V to manage VMs on the hosts, you must configure a group to pin the Controller VMs. For more information, see Pinning Nutanix Controller VMs (on page 205).

Prerequisites

 A service account with cluster administrator rights on the Nutanix cluster(s) for action execution. For entity discovery, a minimum of READ access is required.

Finding the Cluster External IP Address

To configure a Nutanix target, provide the Cluster External IP address for the given Nutanix cluster.

The Cluster External IP address is a logical IP that resolves to the cluster's Prism Element Leader. If the Prism Element Leader fails, then the Cluster External IP address will resolve to the newly elected Prism Element Leader.

To find this IP address, open the Web Console (the Prism Element) on the cluster and navigate to the **Cluster Details** view. In this view you can see the **Cluster External IP** address. If there is no IP address specified, you can specify the address at this time. For more information, see the Nutanix documentation.



Operating Modes

A Nutanix node is a server that hosts VMs – In this sense the node functions as a hypervisor. A cluster of nodes can host VMs using the following Hypervisor technologies:

- Nutanix Acropolis
 - The native Nutanix host platform, which combines software-defined storage with built-in virtualization.
- VMware ESXi
- Microsoft Hyper-V

Controller VM Pinning

Each Nutanix node hosts a Controller VM that runs the Nutanix software and manages I/O for the hypervisor and all VMs running on the host. Each Controller VM must remain on its host node –The Controller VM must be *pinned* to that host, and must not be moved to any other host.

For more information about how to pin the Controller VM, see Pinning Nutanix Controller VMs (on page 205).

Adding Nutanix Targets

NOTE:

This describes how to add a Nutanix cluster to Workload Optimization Manager as a target. If Nutanix is not managing hosts running Acropolis as the hypervisor, you will have to add the vCenter or Hyper-V hypervisors as targets after you have added the Nutanix cluster as a target. For more information, see Hypervisor Targets (on page 205).

To add Nutanix targets, select the **Hyperconverged > Nutanix** option on the Target Configuration page and provide the following information:

- Address
 - The Cluster External IP address for the Nutanix cluster.
- Port Number
 - The listening port of the cluster.
- Secure Connection
 - When Workload Optimization Manager will use a secure connection.
- Username/Password
 - Credentials for an account on the Nutanix cluster with sufficient privileges.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

Nutanix	Workload Optimization Manager
Container	Storage
Storage Pool	Disk Array
Nutanix Cluster	Storage Controller

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Storage
 - Storage Amount
 - Storage Amount is the measurement of storage capacity that is in use.
 - Storage Provisioned
 - Storage provisioned is the utilization of the entity's capacity, including overprovisioning.



Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

NOTE:

When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.

Disk Array

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

Storage Controller

NOTE:

Not all targets of the same type provide all possible commodities. For example, some storage controllers do not expose CPU activity. When a metric is not collected, its chart in the user interface will not display data.

CPU

CPU is the measurement of CPU that is reserved or in use.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

The storage allocated to a storage controller is the total of all the physical space available to aggregates managed by that storage controller.

Actions

Workload Optimization Manager can recommend the following actions:

Virtual Machine (Nutanix VM)

Move

VMotion to hosts can be automated, but storage moves on Nutanix can only be executed outside Workload Optimization Manager.

Resize

Resize actions require the VM to power down, and power back on again.

Datastore (Storage)

- Provision
- Resize Up/Down
- Suspend
- Move

This action can only be executed outside Workload Optimization Manager.

Storage Controller

Provision

This action can only be executed outside Workload Optimization Manager.



Pinning Nutanix Controller VMs

Each Nutanix node hosts a Controller VM that runs the Nutanix software and manages I/O for the hypervisor and all VMs running on the host. Each Controller VM must remain on its host node –The Controller VM must be *pinned* to that host, and must not be moved to any other host.

For a cluster using vCenter or Hyper-V hypervisors, you must use Workload Optimization Manager policies to pin the Controller VMs to their respective nodes. To do this, you will create a dynamic group of Nutanix Controller VMs, and then disable move actions for all members of this group.

To pin the Controller VMs:

1. Create a group of Controller VMs.

In Workload Optimization Manager you can create dynamic groups based on VM name – All VMs with matching names automatically belong to the group. Nutanix uses the following naming convention for Control VMs:

NTNX-<SerialNumber>-A-CVM, where <SerialNumber> is the serial number of the Controller VM.

You can create a dynamic group that automatically includes these Nutanix controller VMs. (For complete instructions on creating groups, see <u>Creating Groups (on page 669)</u>.)

Create a new group.

In Workload Optimization Manager navigate to Settings > Groups and create a new group.

- Set the group type to **Dynamic**.
- Add a filter to match VMs by their names.

Add a filter that uses the regular expression, NTNX.*CVM. This regular expression will match the Nutanix Controller VMs.

Be sure to save the group. All the Nutanix Controller VMs will automatically become members of this group.

2. Disable moves for all VMs in this group.

To do this, create an automation policy for the group and disable actions. (For complete instructions to create these policies, see Creating Automation Policies (on page 680)).

- In Workload Optimization Manager go to the **Policy > Action > VM** view.
- Set the scope to the group you made.
 - In the Scope column, expand My Groups and select the group you just made.
- Disable moves for this group.
 - In the **Parameter** column under **Action Acceptance**, set the value to **Disabled**. This will override the global action mode.
- Save the action acceptance mode.

Be sure to click Apply Settings Change.

Hypervisor Targets

A hypervisor is a service that creates and runs virtual machines (VMs) and/or containers, providing these entities compute and storage resources. When you connect Workload Optimization Manager to hypervisor targets in your environment, Workload Optimization Manager assures application performance by utilizing these resources as efficiently as possible.

Once connected to a hypervisor target, Workload Optimization Manager discovers the VMs, containers, physical machines that host the VMs or containers, datastores that provide storage resources to the physical machines, and virtual datastores that provide storage resources.

As additional targets are added, Workload Optimization Manager will discover the resources belonging to your physical and virtual infrastructure. For example, adding the underlying hardware as part of a UCS and/or storage target will provide additional visibility into the physical infrastructure of your environment. To extend the virtual infrastructure, application server or guest operating process targets can be added.

Workload Optimization Manager represents your environment holistically as a supply chain of resource buyers and sellers, all working together to meet application demand. By empowering buyers (VMs, instances, containers, and services) with a budget



to seek the resources that applications need to perform, and sellers to price their available resources (CPU, memory, storage, network) based on utilization in real-time, Workload Optimization Manager maintains your environment within the desired state.

For more information, see Application Resource Management (on page 100).

Supply Chain

Each hypervisor requires a physical machine (host) and one or more datastores to provide compute and storage resources. Virtual machines (VMs) or containers run on those physical resources, and the VMs in turn provide resources to applications.

At the bottom of the supply chain, physical machines consume resources from data centers.

If your environment includes SAN technologies such as disk arrays, then the storage consumes resources from that underlying technology. If you add these storage targets, then Workload Optimization Manager extends the supply chain analysis into the components that make up the disk array. For more information, see Storage Manager Targets (on page 297).

IBM PowerVM

For IBM® Power8, Power9, and Power10 environments that use Hardware Management Console (HMC) versions 9 or 10, Workload Optimization Manager will discover and continuously decide on the optimal logical partition (LPAR) Processing Unit (PU) allocation and Virtual Processor (VP) capacity based on historical demand that is collected from the HMC.

IBM Power Systems and LPARs are represented as Hosts and Virtual Machines and are visible across all HMC targets in the Workload Optimization Manager UI. Recommended LPAR resize PU and VP actions indicate optimal LPAR size, and can use existing Workload Optimization Manager workflow capabilities for external approval and execution.

Workload Optimization Manager automatically creates dynamic groups and Automation policies for the IBM Power Systems and LPARs.

- Workload Optimization Manager creates two dynamic groups, one for LPARs and one for systems. These groups are scoped to all LPARs and all Systems across all PowerVM targets that are added to the system.
 - These groups are dynamic If you allocate or remove entities (VMs, hosts, and so on), Workload Optimization Manager automatically adds or removes those entities in the group.
 - The name of each group begins with IBM PowerVM. For example, IBM PowerVM: All LPARs and IBM PowerVM: All Systems.
- Workload Optimization Manager creates Automation policies to specify utilization and scaling constraints that are known to be appropriate for PowerVM environments. The name for each policy begins with the name IBM PowerVM. For more information, see Automation Policies (on page 677).

Workload Optimization Manager then applies these policies to the groups that correspond to the entity type.

Prerequisites

- Supported Hardware Management Console (HMC) versions:
 - HMC 10 Power8, Power9, Power10
 - HMC 9 Power8 or Power9 only; Power7 LPARs and Systems are ignored.
- Compute-Long Term Monitoring Metrics (LTM) must be enabled on each Power System in HMC.
 - Manually enable Compute-LTM using HMC for each Power System that you would like Workload Optimization Manager to discover.
 - In Workload Optimization Manager, select Automatically enable HMC Long Term Metric collection on Power Systems in the target addition and edit pages to enable Compute-LTM on all hosts during discovery. This option is cleared by default.
- An HMC user account that Workload Optimization Manager can use to connect to the PowerVM target.

The HMC user account should have the following roles:

- The hmcviewer role is required.
- The Manage Partition Utilization Data task role is required to automatically enable Compute-LTM on each HMC Power System without having to do this manually.
- The HTTPS top port 443 from Workload Optimization Manager to Power HMC instance must allow connections from Workload Optimization Manager to the HMC.



Considerations

Before you configure an IBM PowerVM target, review the following considerations:

- Workload Optimization Manager recommends Resize LPAR actions only.
- Stitching to entities above the LPAR/VM or below the System/Host is not currently enabled.
- Where multiple HMCs are managing the same Power Systems (Clustered/HA configuration) add only one of the HMC nodes as a target to Workload Optimization Manager.
- Plans are not currently supported. Planning features are being considered in a future release.
- Processor pools are not currently supported.
- Reporting that uses ThoughtSpot is not currently supported.
- The Details tab requires manual configuration for static group scopes.
- VIOS LPARs are not discovered currently.
- In a few cases, actions to resize LPAR PU and VP resources may result in recommendations for PU allocations above VP capacity and vice versa.

Adding IBM PowerVM Targets

To add IBM PowerVM targets, select the **Hypervisors > IBM PowerVM** option on the Target Configuration page and provide the following information:

NOTE:

If you do not see the IBM PowerVM target, you must enable the PowerVM probe before adding the target. To enable the probe, set the following in the charts_vlalphal_xl_cr.yaml resource:

```
spec:
  powervm:
  enabled: true
```

Display name

The display name that is used to identify the target in the Target List. This is for display in the UI only; it does not need to match any internal name.

The name provided here is also used for the Data Center and Cluster name to which Systems managed by this HMC belong.

Address

The FQDN or IP address of the PowerVM HMC.

Port number

The port number for the remote management connection. The default HTTPS port is 443.

Username

The username for a dedicated Workload Optimization Manager user account on the PowerVM HMC instance.

Password

Password for given user account.

Automatically enable HMC Long Term Metric collection on Power Systems

When selected, Workload Optimization Manager automatically enables Compute-Long Term Monitor metrics (LTM) on each power system that is managed by the HMC. By default, Workload Optimization Manager will not make any changes on HMC; however, Compute-LTM must be enabled on each Power System either automatically (enable this option) or manually.

To do this, the user account that is used by Workload Optimization Manager must have Manage Partition Utilization Data as a Task Role in HMC.

Automatically enable energy monitoring on energy monitoring capable Power Systems

When selected, Workload Optimization Manager automatically enables energy monitoring for hosts that are energy monitoring capable and enabled on each power system that is managed by the HMC.



Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

HMC	Workload Optimization Manager
Logical Partition (LPAR)	Virtual Machine (VM)
System	Host
-	Data Center; skeleton entity used to complete the topology This entity uses the target Display Name. There is one Data Center for each PowerVM target.

The following table describes the mapping between HMC systems states and Workload Optimization Manager.

HMC System State	Workload Optimization Manager Power State
INITIALIZING	UNKNOWN
OPERATING	ACTIVE
STANDBY	UNKNOWN
POWER_OFF	IDLE

Monitored Resources

Workload Optimization Manager monitors the following resources:

■ Virtual Machine

Processing Unit (PU)

For PowerVM, processing unit is a unit of measurement for shared processing power across one or more virtual processors. One shared processing unit on one virtual processor accomplishes approximately the same work as one dedicated processor.

PUs can be a decimal value in a VM setting. A VM that has a capacity of 0.5 PU means that 0.5 PU is always readily available for that VM to use, and that amount can only be used for that VM.

Virtual Processor (VP)

For PowerVM, virtual processor (VP) is the guest OS representation of the capacity of the VM. VPs have a one to one correlation with PUs, meaning 1 VP being utilized in a VM equates to 1 PU being used; however, VPs do not have to equal to PUs on a system. VPs are a virtual representation, therefore they can be overprovisioned.

For example, a VM can have 0.5 PUs but 3 VPs. In this scenario a VM's capacity is 0.5 PU but it can use more than its assigned capacity; the max it can use is the number of VPs. The number of VPs must never exceed 20x the value of PU, therefore the highest utilization a VM can be at is 2000% of its PU capacity.

NOTE:

Only shared-uncapped VM utilization can go up to 2000% of its PU capacity; the utilization for all other VM types cannot go above 100% of its PU capacity.

■ Host

Energy

Energy is the measurement of electricity consumed by a given entity over a period of time, expressed in watt-hours (Wh).

Carbon Footprint

Carbon footprint is the measurement of carbon dioxide equivalent (CO2e) emissions for a given entity. Workload Optimization Manager measures carbon footprint in grams.

Power

Power is the measurement of electricity consumed by a given entity, expressed in watts.



Memory (Mem)

Memory is the measurement of memory that is reserved or in use.

Datacenter

The Datacenter entity is not monitored but is used in the supply chain to represent each PowerVM HMC and the Hosts and VMs associated with it.

Power

Power is the measurement of electricity consumed by a given entity, expressed in watts.

Actions

Workload Optimization Manager can recommend the following actions:

■ Virtual Machine

Resize PU / Resize VP (IBM PowerVM)

Resize PU (processing units) or VP (virtual processor) to optimize LPAR processing unit allocation and virtual processor capacity based on historical demand collected from the HMC.

When Workload Optimization Manager generates an action, the action details include a list of policies that constrain the action recommendation. In this list, policy names that begin with IBM PowerVM: indicate policies that implement the constraints suitable for PowerVM. You can click to navigate to the policy definition. You can see the policy definition, but you cannot edit it.

The policies that Workload Optimization Manager generates affect Workload Optimization Manager actions in the following ways:

Entity	Policy Impact on Actions
Virtual Machine	Workload Optimization Manager does not support native execution of Resize PU (processing units) and Resize VP (virtual processor) actions. However, actions can be executed using external automation platforms through Action Orchestration workflows such as Action Scripts or Webhooks.
	The following policy settings affect the resize actions that Workload Optimization Manager generates:
	 Min/Max Observation Period
	Observation period settings only apply to Resize VP actions.
	For details, see Aggressiveness and Observation Periods (on page 454).
	 Increment Constant for Processing Unit
	Change the increment constant value to use for VM PU resize actions. PUs can be a decimal value in a VM setting.
	For details, see Increment Constant for Processing Unit (on page 454).
	 Increment Constant for Virtual Processors
	Change the increment constant value to use for VM VP resize actions. VPs must be ar integer value in a VM setting.
	For details, see Increment Constant for Virtual Processors (on page 454).
Host	- Memory
	The memory that is given to a VM from the host system; what is provided by the host is all that the VM can use.
	Memory Overprovisioned Percentage
	Change the percentage of the existing capacity that Workload Optimization Manager considers to be 100% of capacity.
	For details, see <u>Utilization Constraints</u> (on page 486).



Microsoft Hyper-V

If you have a small number of Hyper-V hosts in your environment, you can add them individually as Workload Optimization Manager targets. Also, if you have deployed the Hyper-V hosts in a clustered domain (for example as a failover cluster), you can specify one Hyper-V host as a target and Workload Optimization Manager automatically add the other members of that cluster.

Note that for large Hyper-V environments, it's typical to manage the hosts via System Center Virtual Machine Manager (VMM). You can specify the VMM server as a target and Workload Optimization Manager will use it to discover and manage its child Hyper-V hosts. If you use VMM, you should not add individual Hyper-V hosts as targets. For information about adding VMM targets, see Adding Virtual Machine ManagerTargets (on page 234).

NOTE:

Even if you manage Hyper-V using a VMM target, you must still configure remote management on each Hyper-V server. This Hyper-V topic includes instructions to configure remote management – see <u>Enabling Windows Remote Management</u> (on page 213).

For accurate SMB storage calculations, Workload Optimization Manager requires a VMM target.

Prerequisites

- Create a user account that Workload Optimization Manager can use to connect to your Hyper-V servers. See <u>Creating a Service User Account in Hyper-V (on page 212)</u>
- Configure remote management on each Hyper-V server. Refer to <u>Enabling Windows Remote Management (on page 213)</u>
- The time on each Hyper-V host must be in synch with the rest of the managed Hyper-V environment.
- Your Hyper-V environment must not use Server Message Block (SMB) storage.

To manage SMB storage, Workload Optimization Manager requires a VMM target, and that VMM instance must manage the Hyper-V hypervisors and the SMB storage that they use.

Managing a Hyper-V plus SMB environment via Hyper-V targets will result in incorrect data collection for SMB storage.

Adding Hyper-V Targets

Once you've enabled remote management, you can add your Hyper-V hosts as targets. To add Hyper-V targets, select the **Hypervisors > Hyper-V** option on the Target Configuration page and provide the following information:

Address

The FQDN of the Hyper-V host. If you're using the "Discover Host Cluster" below to add an entire cluster, enter the name of any one of the Hyper-V hosts in the cluster.

Note that you can enter an IP address for the host, but you must first configure an SPN on the host. Cisco recommends that you use the FQDN in this field.

Port number

The port number for the remote management connection. The default HTTP port is 5985; the default HTTPS port is 5986.

Secure connection

Select this option to use a secure connection (HTTPS). Make sure the required certificate is configured for use on the host.

■ Full domain name

The full domain name of the cluster to which the host belongs.

■ Discover Host Cluster

Workload Optimization Manager discovers and adds all Hyper-V hosts in the named cluster if this option is checked. Note that each server must be configured to allow remote management. You may find it helpful to configure WinRM using a GPO so new servers are configured automatically (see Enabling WinRM Via a GPO (on page 214)).

Username

The username of a user account Workload Optimization Manager can use to connect to the Hyper-V host. If you checked "Discover Host Cluster" in the field above, use an account that is valid for all Hyper-V hosts in that cluster.

Password

Password for account used.



If your Hyper-V hosts are running in a Nutanix environment, you must understand pinning a Nutanix Controller VM. For more information, see Pinning Controller VMs in Generic Hypervisor Mode (on page 203).

Exporting Hyper-V Virtual Machines

In Hyper-V environments, you must be sure that all VMs have unique IDs.

Hyper-V supports the export of a VM, so that you can create exact copies of it by importing those exported files. The Copy import type creates a new unique ID for the imported VM. When importing VMs in your environment, you should always use the Copy import type.

Workload Optimization Manager uses the unique ID to discover and track a VM. If your environment includes multiple VMs with the same ID, then discovery will assume they are the same VM. As a result, the counts for VMs will be incorrect.

Monitored Resources

Workload Optimization Manager monitors the following resources:

■ Virtual Machine

- Virtual Memory (VMem)
 - Virtual Memory is the measurement of memory that is in use.
- Virtual CPU (VCPU)
 - Virtual CPU is the measurement of CPU that is in use.
- Virtual Storage
 - Virtual storage is the measurement of virtual storage capacity that is in use.
- Storage Access (IOPS)
 - Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.
- Latency
 - Latency is the measurement of storage latency.

■ Host

- Memory (Mem)
 - Memory is the measurement of memory that is reserved or in use.
- CPU
 - CPU is the measurement of CPU that is reserved or in use.
- IC
 - IO is the utilization of a host's IO adapters.
- Net
 - Net is the utilization of data through the host's network adapters.
- Swap
 - Swap is the measurement of a host's swap space that is in use.

Storage

- Storage Amount
 - Storage Amount is the measurement of storage capacity that is in use.
- Storage Provisioned
 - Storage provisioned is the utilization of the entity's capacity, including overprovisioning.
- Storage Access (IOPS)
 - Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.



When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.

Datacenter

NOTE:

For datacenter entities, Workload Optimization Manager does not monitor resources directly from the datacenter, but from the hosts in the datacenter. See host monitored resources for details.

Actions

Workload Optimization Manager can recommend the following actions:

Virtual Machine

- Start
- Move
- Suspend
- Resize Up/Down
- Terminate

This action can only be executed outside Workload Optimization Manager.

Provision

This action can only be executed outside Workload Optimization Manager.

Reconfigure

This action can only be executed outside Workload Optimization Manager.

■ Host

- Start
- Suspend
- Terminate

This action can only be executed outside Workload Optimization Manager.

Provision

This action can only be executed outside Workload Optimization Manager.

■ Storage

Provision

This action can only be executed outside Workload Optimization Manager.

Creating A Service User Account

The service account Workload Optimization Manager uses to connect to a Hyper-V host must be an Active Directory domain account. The account must have full access to the cluster. To create such an account, execute the following command at a PowerShell prompt:

Grant-ClusterAccess <domain>\<service_account> -Full

Additionally, the service account must have specific local access rights on each host. The easiest way to grant Workload Optimization Manager the access it requires is to add the domain account to the Local Administrators group on each Hyper-V server.

Some enterprises require that the service account does not grant full administrator rights. In that case, you can create a restricted service account on every Hyper-V host.



Workload Optimization Manager does not support Restricted User Accounts on Windows 2012 Hyper-V nodes.

To create a restricted service account on your Hyper-V hosts:

- 1. Add the service account to each of the following local groups:
 - WinRMRemoteWMIUsers or Remote Management Users
 - Hyper-V Administrators
 - Performance Monitor Users

NOTF:

These groups are examples only. If your version of Windows Server does not include these groups, contact Technical Support for assistance.

2. Grant permissions to the service account.

In the WMI Management console, grant the following permissions to the service account:

- Enable Account
- Remote Enable
- Act as Operating System (for Windows 2016)
- 3. Configure the WinRM security descriptor to allow access by the service account:
 - At a PowerShell prompt, run the command:

```
winrm configSDDL default
```

In the "Permissions for Default" dialog box, grant the service account Read and Execute access.

Enabling Windows Remote Management

Workload Optimization Manager communicates with your Hyper-V servers using Web Services Management (WS-Management), which is implemented on Microsoft platforms using Windows Remote Management (WinRM). The following steps show how to enable WinRM on a single host, using the command line.

1. Ensure Windows Firewall is running on the host.

For you to configure WinRM successfully, Windows Firewall must be running on the host. For more information, see the Microsoft Knowledge Base article #2004640 (http://support.microsoft.com/kb/2004640).

2. Set up a Service Principal Name (SPN) for the host machine.

The machine must have a SPN of the form, protocol/host_address. For example, WSMAN/10.99.9.2.

To get a list of SPNs for the machine, run the following in the command window:

```
setspn -l <vmm-server-name>
```

If there is no valid SPN in the list, create one by running the command:

```
setspn -A protocol/host-address:port
```

where port is optional. For example:

```
setspn -A WSMAN/10.99.9.2:VMM-02
```

Set up the Windows Remote Management (WinRM) service to run on startup.

Run the quickconfig utility to set up the WinRM service. The quickconfig utility:

- Configures the WinRM service to auto-start
- Configures basic authentication and disables unencrypted traffic
- Creates a firewall exception for the current user profile
- Configures a listener for HTTP and HTTPS on any IP address
- Enables remote shell access



To run quickconfig, log into a command window as Administrator on the host machine. Then execute the following commands:

winrm quickconfig

Enter y to accept the quickconfig changes

4. Set permissions on the host machine.

Execute the following commands in the command window to modify the settings made by quickconfig:

■ To set the memory capacity for remote shells:

```
winrm set winrm/config/winrs @{MaxMemoryPerShellMB="1024"}
```

To set up an unsecured HTTP connection:

```
winrm set winrm/config/service @{AllowUnencrypted="true"}
winrm set winrm/config/service/Auth @{Basic="true"}
```

These steps showed you how to enable WinRM for a single host. Some users find the following methods useful for enabling WinRM on multiple hosts:

- EnablingWinRmViaGlobal Policy Objects (on page 214)
- EnablingWinRMViaPowerShell (on page 215)

Enabling WinRM Via Global Policy Objects

You can configure WinRM for all of your Hyper-V targets by creating and linking a Global Policy Object (GPO) within the Hyper-V domain and applying the GPO to all servers.

Follow the steps below to enable Windows Remote Management (WinRM) for your Hyper-V targets.

- On the AD domain controller, open the Group Policy Management Console (GPMC). If the GPMC is not installed, see https://technet.microsoft.com/en-us/library/cc725932.aspx.
- 2. Create a new Global Policy Object:
 - a. In the GPMC tree, right-click Group Policy Objects within the domain containing your Hyper-V servers.
 - b. Choose Create a GPO in this domain, and link it here.
 - c. Enter a name for the new GPO and click **OK**.
- Specify the computers that need access:
 - a. Select the new GPO from the tree.
 - b. On the **Scope** tab, under **Security Filtering**, specify the computer or group of computers you want to grant access. Make sure you include all of your Hyper-V targets.
- 4. Right-click the new GPO and choose Edit to open the Group Policy Management Editor.
- 5. Configure the WinRM Service:
 - In the Group Policy Management Editor, select Computer Configuration > Policies > Administrative Templates >
 Windows Components > Windows Remote Management (WinRM) > WinRM Service.
 - b. Double-click each of following settings and configure as specified:

Allow automatic configuration of listeners ("Allow remote server management through WinRM" on older versions of Windows Server):	Enabled IPv4 filter: *
Allow Basic authentication:	Enabled
Allow unencrypted traffic:	Enabled

- 6. Configure the WinRM service to run automatically:
 - a. In the Group Policy Management Editor, expand Computer Configuration > Preferences > Control Panel Settings.
 - b. Under Control Panel Settings, right-click Services and choose New > Service.



c. In the New Service Properties window, configure the following settings:

Startup:	Automatic
Service name:	WinRM
Service option:	Service start

- Enable Windows Remote Shell:
 - a. In the Group Policy Management Editor, select Computer Configuration > Policies > Administrative Templates > Windows Components > Windows Remote Shell.
 - b. Double-click the following setting and configure as specified:

Allow Remote Shell Access:	Enabled

- Add a Windows Firewall exception:
 - a. In the Group Policy Management Editor, open Computer Configuration > Windows Settings > Security Settings > Windows Firewall > Windows Firewall.
 - b. Under Windows Firewall, right-click Inbound Rules and choose New > Rule.
 - c. In the New Inbound Rule Wizard, select Predefined: Windows Remote Management and Allow the connection.

The new group policy will be applied during the next policy process update. To apply the new policy immediately, run the following command at a Powershell prompt:

gpupdate /force

Enabling WinRM Via PowerShell

Using PsExec, you can run quickconfig on all your Hyper-V servers and change the default settings remotely. PsExec is a component of PsTools, which you can download from https://technet.microsoft.com/en-us/sysinternals/bb897553.aspx.

1. Create a text file containing the Hyper-V host names, for example:

hp-vx485 hp-vx486

2. Since Cisco requires changes to the default quickconfig settings, create a batch file containing the following command:

@echo off Powershell.exe Set-WSManQuickConfig -Force Powershell.exe Set-Item WSMan:\localhost\Shell\M axMemoryPerShellMB 1024

NOTE:

If you are connecting via HTTP, you must include the following command:

Powershell.exe Set-Item WSMan:\localhost\Service\AllowUnencrypted -Value \$True

Use PsExec to enable WinRM on the remote servers:

```
.\PsExec.exe @<hosts_file_path> -u <username> -p <password> -c <batch_file_path>
```

NOTE:

If you get an error message when executing this command, add the -h option (.\PsExec.exe -h).

vCenter Server

VMware vCenter Server provides a centralized management platform for VMware hypervisors. To manage your VMware environment with Workload Optimization Manager, you specify a vCenter Server instance as a target. Workload Optimization Manager discovers the infrastructure that target manages, and links it into a supply chain to deliver application performance management.



Prerequisites

Target User Account

A user account that Workload Optimization Manager uses to connect to your vCenter Server and execute actions. For information about setting permissions for this account, see <u>Creating a User Account In vCenter Server (on page 220)</u>.

General Considerations

Before you configure a vCenter Server target, you should consider the following:

Linked vCenters

For linked vCenters, you must add each vCenter Server separately so Workload Optimization Manager can communicate with each vCenter Server through a separate API endpoint.

Restricting Workload Optimization Manager Access to Specific Clusters

When you add a vCenter Server target, Workload Optimization Manager discovers all of the connected entities that are visible, based on the target account that it uses to connect to the vCenter Server target. If you have clusters or other entities you want to exclude from discovery, you can use the vSphere management client to the role of the Workload Optimization Manager account to No access for the given entities.

Shared Datastores

If you add more than one vCenter Server target that manages the same datastore, you can enable or disable datastore browsing to discover wasted files on the shared datastore:

- Enable datastore browsing:
 - To properly enable browsing, you must turn on the **Enable Datastore Browsing** option in the target configuration for each vCenter Server target that manages the shared datastore.
- Disable datastore browsing:
 - If you don't want datastore browsing over shared datastores, you must turn *off* the **Enable Datastore Browsing** option in the target configuration for each vCenter Server target that manages the shared datastore.

If set **Enable Datastore Browsing** differently for separate targets that manage the same datastore, datastore browsing can give inconsistent results for active and wasted files.

VSAN Permissions

In order to enable VSAN support and discover groups based on storage profiles, you must ensure that the user role Workload Optimization Manager is assigned has the Profile-driven storage view permission enabled. This permission is *disabled* in the built-in readonly role.

Guest Metrics

Enable Guest Metrics is enabled by default for all vCenter Server targets added to Workload Optimization Manager.

NOTE:

If your vCenter Server target was added prior to 8.7.3, this option is enabled as part of the update.

This target option instructs that Workload Optimization Manager request from the VC instance that it start collecting and reporting enhanced memory metrics from each virtual machine, using the VMware Tools installed on each VM. Without this option, Workload Optimization Manager only has access to the "Active" memory for each virtual machine, which is a less accurate representation of the memory that the VM is really using.

For accurate metrics use vCenter Server 6.5 U3 or higher with VMware Tools version 10.3.2 or higher on guest VMs. If you run vCenter Server version 7.0 or greater, then it can automatically update your VMware Tools through the user interface. For other versions of vCenter Server, you must manually update your VMware Tools deployments.

For the permissions required for Guest Metrics, see vCenter Permissions (on page 220).

VMware Cloud Deployments

VMware Cloud (VMC) is a managed cloud offering that provides dedicated VMware vSphere-based Software Defined Data Centers (SDDC). VMC on AWS hosts SDDC on AWS facilities. For on-premise VMC, SDDC runs on specific hardware that meets VMware specifications.

VMware Cloud on AWS, Azure VMware Services, Google Cloud VMware Engine, IBM Cloud for VMware and other cloud hosted VMware solutions are treated like any other VMware integration. The same familiar Workload Optimization Manager experience can be expected when using the VMware vCenter Server target integration against any vCenter Server target whether it is cloud hosted or not, provided you pay close attention to satisfying all of the vCenter target prerequisites,



especially permissions and roles. For example, VMware Cloud bare metal host instances may be modeled in Workload Optimization Manager as Hyperconverged templates, assigned a cost, and used to plan the migrating from existing onpremises host clusters to cloud hosted VMware solutions. Once in the cloud, you can use Workload Optimization Manager to plan migrations from one cloud hosted VMware solution to another. Provision and Suspend Host actions generated by Workload Optimization Manager may be more readily actionable on cloud hosted VMware solutions and automated using custom Action Scripts if required. If you have any requirements or improvements that relate specifically to cloud hosted VMware solutions, submit an enhancement request through IBM Ideas for future consideration.

For VMC environments, you can use the Workload Optimization Manager vCenter Server target to manage workloads, but you should be aware of the following concerns:

DRS Settings

VMC SDDC requires DRS to be set to migration level 3. You cannot change this setting.

Datacenter Names

VMC SDDC datacenter names are always SDDC Datacenter. This is true even for multiple VMC targets. You can use the Target Name filter to search and group VMs across the set of VMC SDDC datacenters and clusters that share this name.

- Discovery
 - · Workload Optimization Manager does not discover VMC service costs or subscription details.
 - The user interface does not show cost savings or investments.
- Migration Plans

Plans do not discover VMC bare metal hosts. You can use Workload Optimization Manager HCl Host Templates to represent the bare metal instances. Then the plan can determine the number of VMC instances you need to support your existing on-premise workloads.

Migrate to Cloud plans do not support VMC.

Adding vCenter Server Targets

To add vCenter Server targets, select the **Hypervisors > vCenter** option on the Target Configuration page and provide the following information:

Address

The name or IP address of the vCenter Server.

Username/Password

Credentials for the user account Workload Optimization Manager can use to connect to the vCenter Server. Include the domain if required (<domain>\<username>).

■ Enable Datastore Browsing

Enabling datastore browsing enables Workload Optimization Manager to discover wasted storage.

■ Enable Guest Metrics

Collecting advanced guest memory metrics can increase the accuracy of the VMEM data that Workload Optimization Manager uses for analysis of virtual machines. To enable guest metrics, ensure the following:

- VMware Tools is installed and running on the target VMs.
- The user account has the Performance.Modify Intervals performance privilege.

For more information, see <u>vCenter Performance Privileges</u>.

vCenter Server Imported Settings

In addition to discovering entities managed by the hypervisor, Workload Optimization Manager also imports a wide range of vSphere settings, such as Host DRS rules, annotations, Resource Pools, and DRS HA settings (See Other Information Imported From vCenter (on page 221)).

NOTE: Workload Optimization Manager does not import Storage DRS rules at this time.

VMware vSphere 6.0 introduced the ability to move VMs between vCenters. If you enabled this feature in your VMware environment, you can configure Workload Optimization Manager to include cross vCenter Server vMotions in its recommendations.



To configure Workload Optimization Manager to support cross vCenter Server vMotion recommendations, you must create a Workload Placement Policy that merges the datacenters on the different vCenters, and then another policy to merge the given clusters. Also note that the merged clusters must use the same network names in the different datacenters. To create a Merge Policy:

- 1. In the Policy Management Tab, select Placement Policy.
- 2. For policy type, select Merge.
- 3. For MERGE, choose the merge type, and click **Select**.

To merge datacenters choose Datacenter, to merge Host clusters choose Cluster, and for storage choose StorageCluster.

- 4. Choose the specific datacenters or clusters to merge in this policy, then click Select.
- 5. Click Save Policy.

NOTE:

Since Workload Optimization Manager can only execute vMotions between clusters that use the same switch type (VSS or VDS), make sure any clusters you merge use the same switch type. Although Workload Optimization Manager will not initiate VSS → VDS vMotions, vSphere may do so. If this happens, Workload Optimization Manager displays a compliance violation notification.

Monitored Resources

Workload Optimization Manager monitors the following resources:

Virtual Machine

Energy

Energy is the measurement of electricity consumed by a given entity over a period of time, expressed in watt-hours (Wh).

Carbon Footprint

Carbon footprint is the measurement of carbon dioxide equivalent (CO2e) emissions for a given entity. Workload Optimization Manager measures carbon footprint in grams.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual Storage

Virtual storage is the measurement of virtual storage capacity that is in use.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

■ Host

Energy

Energy is the measurement of electricity consumed by a given entity over a period of time, expressed in watt-hours (Wh).

Power

Power is the measurement of electricity consumed by a given entity, expressed in watts.

Carbon Footprint

Carbon footprint is the measurement of carbon dioxide equivalent (CO2e) emissions for a given entity. Workload Optimization Manager measures carbon footprint in grams.

Memory (Mem)

Memory is the measurement of memory that is reserved or in use.

CPU



CPU is the measurement of CPU that is reserved or in use.

IC

IO is the utilization of a host's IO adapters.

Net

Net is the utilization of data through the host's network adapters.

Swap

Swap is the measurement of a host's swap space that is in use.

Balloon

Balloon is the measurement of memory that is shared by VMs running on a host.

This commodity applies to ESX only.

CPU Ready

CPU Ready is the measurement of a host's ready queue capacity that is in use.

This commodity applies to ESX only.

Storage

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

NOTE:

When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.

Datacenter

NOTE:

For datacenter entities, Workload Optimization Manager does not monitor resources directly from the datacenter, but from the hosts in the datacenter. See host monitored resources for details.

■ Provider Virtual Datacenter

- Memory (Mem)

Memory is the measurement of memory that is reserved or in use.

CPU

CPU is the measurement of CPU that is reserved or in use.

Storage

Storage is the utilization of the storage attached to the entity.

Consumer Virtual Datacenter

Memory (Mem)

Memory is the measurement of memory that is reserved or in use.

CPU

CPU is the measurement of CPU that is reserved or in use.

Storage

Storage is the utilization of the storage attached to the entity.



Actions

In order to execute cross-vCenter migrations as a non-admin user, you must have the following permissions enabled for the user account in both the current and destination vCenter servers:

Entity	Permissions
Virtual Machine	Edit Inventory, Create From Existing (Move, Register, Remove, Unregister sub-options), Create New
Datacenter	Reconfigure Datacenter
Network	Assign Network

Workload Optimization Manager can recommend the following actions:

Virtual Machine

- Start
- Move
- Move VM Storage
- Suspend
- Resize Up/Down
- Terminate

This action can only be executed outside Workload Optimization Manager.

- Provision

This action can only be executed outside Workload Optimization Manager.

- Reconfigure

This action can only be executed outside Workload Optimization Manager.

■ Host

- Start
- Suspend
- Terminate

This action can only be executed outside Workload Optimization Manager.

Provision

This action can only be executed outside Workload Optimization Manager.

Storage

Provision

This action can only be executed outside Workload Optimization Manager.

Creating A Service User Account In vCenter

The service account you use must have specific permissions on the vCenter. The easiest way to grant Workload Optimization Manager the access it requires is to grant full administrator rights.

Some enterprises require that the service account does not grant full administrator rights. In that case, you can create a restricted service account that grants the following permissions to enable the required Workload Optimization Manager activities:

vCenter Permissions

Workload Optimization Manager Functionality	Required Permissions
Monitoring	■ Read-only role for all entity types



Workload Optimization Manager Functionality	Required Permissions	
	Assign either Global permissions or permissions for the given vCenter Server instance to the target user or user group. Requirement to monitor VSAN and storage profiles In order to enable VSAN support and discover groups based on storage profiles, you must enable the Profile-driven storage view permission. This permission is disabled in the built-in readonly role.	
Recommend Actions	 Read-only role for all entity types Assign either Global permissions or permissions for the given vCenter Server instance to the target user or user group. 	
Wasted Storage Reporting	■ Datastore > Browse Datastore	
Execute VM Move	 Resources > Assign VM to Resource Pool Resources > Migrate Powered Off VMs Resources > Migrate Powered On VMs Resources > Modify Resource Pool Resources > Query Vmotion 	
Execute VM Storage Move	 Datastore > Allocate Space Datastore > Browse Datastore Resources > Assign VM to Resource Pool Resources > Migrate Resources > Modify Resource Pool Resources > Move Resource Pool Resources > Query VMotion Virtual Machine > Change Configuration > Change resource Virtual Machine > Change Configuration > Change Swapfile placement 	
Execute VM Resize	 Virtual Machine > Change Configuration > Change CPU count Virtual Machine > Change Configuration > Change Memory Virtual Machine > Change Configuration > Change resource Virtual Machine > Interaction > Reset Virtual Machine > Interaction > Power Off Virtual Machine > Interaction > Power On 	
Discover Tags	■ Global > Global tag You must also open ports 10443 and 7443 on the target server	
Guest Metrics	■ Performance > Modify Intervals	

Other Information Imported from vCenter

In addition to discovering entities managed by the vSphere hypervisors and their resources, Workload Optimization Manager:

■ Imports any vSphere Host DRS rules when DRS is enabled, and displays them on the **Policy > Workload Placement** view under **Imported Placement Policies**. Imported rules are enabled by default, but you can disable them in Workload Optimization Manager.



NOTE:

In vCenter environments, Workload Optimization Manager does not import DRS rules if DRS is disabled on the hypervisor. Further, if Workload Optimization Manager did import an enabled DRS rule and somebody subsequently disables that DRS rule, then Workload Optimization Manager will discover that the rule was disabled and will remove the imported placement policy.

- Imports any custom annotations and displays related groupings in the Inventory > Groups tree view, under VC Annotations. The service account must enable the Global > Global tag privilege, and the target server must open ports 10443 and 7443.
- For vCenter Server versions 5.5 and later, discovers Virtual Machine Storage Profiles and displays them as groups
 anywhere that you can set scope. The groups appear under VC Storage Profiles. You can use these discovered storage
 profiles the same as any other groups For example, to scope dashboards, or to set the scope for specific action policies.
- Discovers resource pools and displays them as folders in the Inventory tree and as components in the Supply Chain Navigator. If you have the Cloud Control Module license, Workload Optimization Manager manages resource pools as Virtual Datacenters (VDCs) and can recommend resize actions. Root resource pools appear as Provider VDCs in the supply chain, whereas child resource pools appear as Consumer VDCs.
- Imports vSphere HA cluster settings and translates them into CPU and memory utilization constraints. These are displayed as cluster-level overrides under **Folders** on the **Policy > Analysis > Host** view.

Orchestrator Targets

Workload Optimization Manager supports Action Script, Flexera One, and ServiceNow orchestrator targets.

With orchestrator targets you can integrate Workload Optimization Manager actions with the orchestrator's application management process. For example, you can pass Workload Optimization Manager to a Change Request system for approval, and the system can pass the action back to Workload Optimization Manager for execution.

NOTE:

Workload Optimization Manager uses remote servers to execute ActionScript orchestration. Managing the processes remotely means that you do not install custom code on the Workload Optimization Manager server. This eliminates associated security risks at that point. However, you are responsible to maintain the security of your Action Script Server, and to ensure the integrity of your custom code.

ActionScript Server

Resource Requirements for the Server

The remote server can be a VM or a container. The capacity you configure for the server depends entirely on the processes you intend to run on it. Workload Optimization Manager does not impose any special resource requirements on the server.

Configuring Command Execution

To support execution of your scripts, you must install any software that is necessary to run the scripts, including libraries, language processors, or other processes that your scripts will call.

Workload Optimization Manager calls the scripts as commands on the server. The server must run an SSH service that you configured to support command execution and SFTP operations. Currently, Cisco tested action scripts with the OpenSSH sshd daemon.

The standard port for SSH is 22. You can configure a different port, and provide that for admins who configure the server as an Action Script target.

NOTE:

An action script can invoke any process you deployed on the remote server. You do not have to run scripts; however, you must be able to invoke the processes from the command line. The script manifest gives Workload Optimization Manager the details it needs to build the command line invocation of each script.



Configuring the ActionScript User Account

To run the scripts on your server, Workload Optimization Manager logs on using a user account that is authorized to run the scripts from the command line. You provide the user credentials when you configure the ActionScript target. To support this interaction, the user account must meet the following requirements:

Public Key

The user must have an RSA public key in the .ssh/authorized_keys file. When you configure the ActionScript target, you provide this as the Private Token for the target.

NOTE:

For the ActionScript target to validate, the permissions on the authorized_keys file must be set to 600.

Security for the .ssh Directory

The ActionScript User should be the only user with authorized access. Set file permissions to 700.

Supported Shells

The ActionScript User shell can be either the Bourne shell (usually at /bin/sh) or the Bourne-Again shell (usually at /bin/bash). Workload Optimization Manager passes parameters as it invokes your scripts. At this time it only supports script execution through these shells.

ActionScript Manifest

The ActionScript Manifest is a file that declares an array of Script Objects for each script you want to expose to Workload Optimization Manager. You can create the manifest as either a JSON or a YAML file. You can save the Manifest file to any location on your server, so long as the Scripts User has access to that location, and has read and execute privileges. The location of the manifest is provided as part of the ActionScript target configuration.

After Workload Optimization Manager validates the target, it then discovers these scripts and presents them in the Orchestration Policy user interface.

For details, see Deploying the ActionScript Manifest (on page 694).

Handling ActionScript Timeouts

Workload Optimization Manager limits script execution to 30 minutes. If a script exceeds this limit, Workload Optimization Manager sends a SIGTERM to stop the execution of the process.

Note that Workload Optimization Manager does not make any other attempt to end a process. For example, you might implement the script so it traps the SIGTERM and continues to run. The process should end at the soonest safe opportunity. However, if the process does not end, then you must implement some way to stop it outside of Workload Optimization Manager. A runaway process continues to use its execution thread, which can block other processes (action scripts or primary processes) if there are no more threads in the pool.

Adding ActionScript Targets

The ActionScript target can be added through the UI or the API. For details on adding the target using the API, see Adding ActionScript Targets using the API (on page 224).

To add an ActionScript target, select the **Orchestration > ActionScript** option on the Target Configuration page and provide the following information:

Name or Address

The IP address or FQDN of the script execution server.

Script Path

The path on the script execution server to the location of the ActionScript Manifest file.

Port

The port for the SSH connection. Commonly port 22.

User ID

The username for SSH access into the server.

Private Token

The private key for the user that has the public key set up in the .ssh/authorized_keys file on the remote server.



Public Host Key
 Optionally you can provide a public key on the host.

Adding ActionScript Targets using the API

The ActionScript target can be added through the UI or the API. This topic outlines the steps for adding the target using the API. Refer to the ActionScript Server (on page 222) topic for configuration information.

Obtaining Private Key String

In order to pass the private key as a string, newlines must be inserted appropriately with the \n character, as the JSON format will not preserve these required newlines. One method to insert these lines on *nix systems is the awk command. This command should follow the following format:

```
awk 'ORS="\\n"' path/to/keyfile > path/to/modified/keyfile
```

For example:

```
awk 'ORS="\\n"' ~/.ssh/id_rsa > /tmp/privkey.txt
```

You can then cat or vi/vim the file to copy the text and insert it into the API call. Example private key file, before modification:

----BEGIN RSA PRIVATE KEY----

MIIJKQIBAAKCAgEAxeKUk6WLFMf8seI2KztL4DoKKw0d6AG/39SH6or5SiNbAGkM Umv8ABA0aCQqMF01j9V3kzGn71DIWWTxLOMBH06I01dvd9XYPVRJotGjpxus+xmV GbeXxJsdHfXrbtMeLnpkwGC7qIu6W2o5Ez6YuLDKf+CeFZhGMOtVLiB2NWtzn33D KBh96tIom9EqKseovtQAj5VYDwPeuTaWX1RGMTl1tsNGyezEc4Z2sppT4VFVhsUV L+voDZzrtMfFiHUIqjPH4pK9c/iPj0um7YzmyMyARftyCsUq7iUZH4NlNLpikXVy xKiro6Quu7SZ4kcvr3ZF3970CON0hHzC3mFsvZvRFgYKzgc8/BcZ8ZzEUFfqBqY4 dejCU+jo86dYFL2Q8RfF2zsJenG0WbVRLtLGkc7RbMdBGjtt5roV5VAp+TyR9Hdd Dc5FYvt4fAAMJtcmTIzdEAPSbVzDhkSajxRhOXvezJn+2Ddr34/9ZvFE7nJNqP/8 KOGJ5H1dqG5mc7H+Ly3x5dXzPhcVNSUdNGqKnEvzFqMJaGByAq5AZc5HOmiIwFKs KSE/m8dSRoHrHmenGGmk1IMUnvCC1mKkbUEJ2V6R17x8zmM4DYNRSTwcSL SZ7U/yDuwpHwzeozNeoekGKeC23+jgyzr9/mzgmPF08q5F+wVg/7nlDRSXsCAwEA AQKCAgBPHMPbt25AM6gCEfcoF3/BOFMCXS8cpz5npRdlnIQHsNTb+CN1/Df2aoQZ MoQva8RTKbuxfEOweLJwktuc33B+bK51F+q31SXrdvwtfPSZhYYFqXejnXOupXjh loS2f07vE/2dr86mmLY7f98ro3X50KzsrQdmiMdfHWajl1TLDJdqJy5TpF8K91RG 3zuleMcs66MBxGo9LoXntDwwBog9e8Rk+fMeHWt46EQiKXLpfNPdmoNa8kyGzLqr PsbpRCjPrRX3rkTRzYjPeCZXiGJn2uJZmCpCxqbhTrGZmLVofC+WCceFeq2M0cHh R1XSUjVtR7KtyvvzZcQah6p8r6SCASQFeVbb13FJVkBd0J8Hzk5e4N5Qk3bv9V4W F7CC8dRV66kcAkf68ytLGXkQAsgo5RPBDYSp8E2JDLF4m+9w6aouPlg//QxG5+XA wqGJseTipiHbiALcIGsCpc5QCqab2SNddaDtIIpnp2Zmo5E10jutGeUAE3k+cnJ1 JIFCkRL0vsPk0xODSXbV2PMaUjMT65ue7uBkDqCtqHiSBXTk6DiWBjduDnoZlAmC I8M4o42mSPs2uoKcngJ2fboY5iSsXLQ8VT5Tix8fk7VzBFmOvchBUSFlyx6o3/01 OSV3Qrqz7tb1Xx+axQapIUEVbLV140kOjepvxF3HVELXRQd2eQKCAQEA8EzXro5j N/VgDQJ9pGphwUyQ9mNBC1c1jviAHHskh8gwa4BxhBLzZ+aUUoIx0/mAYK0rihN+ QJLI84c9tA62Au6Tq+CT60ad4SwxQ5m9mQZjq888T3dRssmY+f+5kYBzmaPHv18I Sohh2tHqNh68T1KmLbCABahc0ppqJTjP0Oi0kR7XUk5qEeDNNb65oDOtuNytiVd4 cNEq/cO8rqk2rTupLLjhVKzP9lgVXL/SBw/HBjpMyJ3DMrcPXH84JeMshJay/OnW eY3Y+hsqhw37zRxeuUtn5to0wVYayAmEhyXVinq7EVV5wsyUaJQE25ZZWLjjiBHP ZpLsSRc++uugnwKCAQEA0tBSQrDdOH+O6Ydu9Tno1IUeilTQ8+VGx3esFlKtiDTW cSEZSfZKbf/GQqHKbxLVXjCLhbfPbCvCcojbmGSmtWRWxlySYPSW4tBiYJSk6Fo8 J2hEYW3HQzyj23RjXIqhCUqY5wNWj1brU4CRxHtMyV1eYJWGmTaBfDm8VoBqhu9q



FAyPkJs4WZUkUI7Sbg2vcJyLLP4XETPlfACMptLrPs8RCyUjJAJYxpSdaSjLC7r9 9gBusQ0lIGpClrx+/86NYhdKDWmnd0lyjXNvMVwPIpoSVblXTZK7xRBgcNTsd2eh h1HLuhLXZ76SplvtNH6MQP46WoblounEx70NnsddpQKCAQEA11VD339DQktLo+7/ OCHPFZHMjueSwaHEtMQzyLORrsbBYXGMTqh0kM0aqMlV1mNpvVFYT2z5pHEIaibL w4mHkO/pqVnDtgwjkA9R1aEQeqg3SKysd5jOtzCXkQ0mIIC5G2X5KHUtOQWSepHX ${\tt XPRnND1c2c3fMqysNnDiklatDgIx5Grk1ZXwnKGth+2ZNipCHmw/IQxy8fWvae8n}$ oYZurW9Ugv5YhaUqT0jeDP9PP1s0QvrHN/13eQnM2szicPDC6XRdK7cKxRrfWJ3P $\verb|kobHfHh8iLuYblFc0sGRW7EZk04MvNhmnxxlYXoGOY0lFBNzl+45jEmOe0g7Fypz||$ 021NswKCAQAHx/6xTXvs4PByeDhFPuz0IzG8Y2MPDZBuPmGQtV6IX4LmzBT140xg YQd9WjmRnf1YK6yKs/0o/fiAZ8LLPjPVEC4Pxkz03TJQjuaCsBniJaqAvd2ARyAK wEtAB2y/dprZj/JS3JGuWsP24hD/UpnD+PlJ0VsVfqiK4EquWrC1alJ+ivQln0UW MWYUvyDPRRwLqQuODpblYKgAyrhmU/Sw7c2wPp+sbZW/Rq8Euae8+Br1oJB1YjAP ITzx+WUqpgIb88Yc9qBiy8g5pmAdT0uTuGIi3eN2Dot1u6QDpihQQ/f3WbKOXLGs t6EMGOqJfH5Ky9d1jfMd70j/IgaBLNStAoIBAQCKqJNuH7FSta/KQ5fJzFrD/Mil Q6yfB9D92UEabB1Et22Zr7Ry5WAv4DRcYWV1HrBJQBOw4Gc5WZcEnE1HvhkX519W hccplP+tyRf+h6ppYqdl/YaW2vEMTR1gvvtV8+2aMYTNRQJuTjJIsk1vWvX42IhQ $\verb|xqKM9xqmKGEsW+6e7U| heaxy8afkjf20/euGgzTuEPoy+IA8vKrSAnLLWm4xDYjMV| \\$ i9PFbuSyRV6tJqQZxZ58dS2ykL5YpTLM+ZFyZmhAqSJWULpsKAxxE2fnmniXOYVF E4VxEPsgNYH1k2eqtGRQwYR0ML/fihHbJIlQnMr6o7/tKljx+3PCZeRaVR4/ ----END RSA PRIVATE KEY----

The same private key, after running the above command:

----BEGIN RSA PRIVATE KEY----\n

MIIJKQIBAAKCAgEAxeKUk6WLFMf8seI2KztL4DoKKw0d6AG/39SH6or5SiNbAGkM\n Umv8ABA0aCQqMF01j9V3kzGn71DIWWTxLOMBH06I01dvd9XYPVRJotGjpxus+xmV\n GbeXxJsdHfXrbtMeLnpkwGC7gIu6W2o5Ez6YuLDKf+CeFZhGMOtVLiB2NWtzn33D\n ${\tt KBh96tIom9EqKseovtQAj5VYDwPeuTaWX1RGMT11tsNGyezEc4Z2sppT4VFVhsUV\n}$ L+voDZzrtMfFiHUIgjPH4pK9c/iPj0um7YzmyMyARftyCsUg7iUZH4NlNLpikXVy\n xKiro6Quu7SZ4kcvr3ZF3970C0N0hHzC3mFsvZvRFgYKzgc8/BcZ8ZzEUFfqBqY4\n dejCU+jo86dYFL2Q8RfF2zsJenG0WbVRLtLGkc7RbMdBGjtt5roV5VAp+TyR9Hdd\n Dc5FYvt4fAAMJtcmTIzdEAPSbVzDhkSajxRhOXvezJn+2Ddr34/9ZvFE7nJNgP/8\n ${\tt KOGJ5H1dgG5mc7H+Ly3x5dXzPhcVNSUdNGgKnEvzFgMJaGByAg5AZc5HOmiIwFKs\n}$ KSE/m8dSRoHrHmenGGmk1IMUnvCC1mKkbUEJ2V6R17x8zmM4DYNRSTwcSL\n SZ7U/yDuwpHwzeozNeoekGKeC23+jgyzr9/mzgmPF08q5F+wVg/7nlDRSXsCAwEA\n AQKCAgBPHMPbt25AM6gCEfcoF3/BOFMCXS8cpz5npRdlnIQHsNTb+CN1/Df2aoQZ\n ${\tt MoQva8RTKbuxfEOweLJwktuc33B+bK51F+q31SXrdvwtfPSZhYYFqXejnXOupXjh\n}$ loS2f07vE/2dr86mmLY7f98ro3X50KzsrQdmiMdfHWajl1TLDJdgJy5TpF8K91RG\n ${\tt 3zuleMcs66MBxGo9LoXntDwwBog9e8Rk+fMeHWt46EQiKXLpfNPdmoNa8kyGzLqr\\n}$ PsbpRCjPrRX3rkTRzYjPeCZXiGJn2uJZmCpCxgbhTrGZmLVofC+WCceFeg2M0cHh\n R1XSUjVtR7KtyvvzZcQah6p8r6SCASQFeVbb13FJVkBd0J8Hzk5e4N5Qk3bv9V4W\n F7CC8dRV66kcAkf68ytLGXkQAsgo5RPBDYSp8E2JDLF4m+9w6aouPlg//QxG5+XA\n wqGJseTipiHbiALcIGsCpc5QCqab2SNddaDtIIpnp2Zmo5E10jutGeUAE3k+cnJ1\n ${\tt JIFCkRL0vsPk0xODSXbV2PMaUjMT65ue7uBkDqCtgHiSBXTk6DiWBjduDnoZlAmC\n}$ I8M4o42mSPs2uoKcngJ2fboY5iSsXLQ8VT5Tix8fk7VzBFmOvchBUSFlyx6o3/01\n 0SV3Qrqz7tb1Xx+axQapIUEVbLV140k0jepvxF3HVELXRQd2eQKCAQEA8EzXro5j\n N/VgDQJ9pGphwUyQ9mNBC1c1jviAHHskh8gwa4BxhBLzZ+aUUoIx0/mAYK0rihN+\n $\tt QJL184c9tA62Au6Tq+CT60ad4SwxQ5m9mQZjq888T3dRssmY+f+5kYBzmaPHv181\\ n$ Sohh2tHqNh68T1KmLbCABahc0ppqJTjP0Oi0kR7XUk5gEeDNNb65oDOtuNytiVd4\n cNEq/cO8rqk2rTupLLjhVKzP9lgVXL/SBw/HBjpMyJ3DMrcPXH84JeMshJay/OnW\n eY3Y+hsghw37zRxeuUtn5to0wVYayAmEhyXVing7EVV5wsyUaJQE25ZZWLjjiBHP\n ZpLsSRc++uugnwKCAQEA0tBSQrDdOH+O6Ydu9Tno1IUeilTQ8+VGx3esFlKtiDTW\n cSEZSfZKbf/GQgHKbxLVXjCLhbfPbCvCcojbmGSmtWRWxlySYPSW4tBiYJSk6Fo8\n



J2hEYW3HQzyj23RjXIghCUqY5wNWj1brU4CRxHtMyV1eYJWGmTaBfDm8VoBghu9g\n ${\tt FAyPkJs4WZUkUI7Sbg2vcJyLLP4XETPlfACMptLrPs8RCyUjJAJYxpSdaSjLC7r9\n}$ 9gBusQOlIGpClrx+/86NYhdKDWmnd0lyjXNvMVwPIpoSVblXTZK7xRBgcNTsd2eh\n h1HLuhLXZ76SplvtNH6MQP46WoblounEx70NnsddpQKCAQEA11VD339DQktLo+7/\n OCHPFZHMjueSwaHEtMQzyLORrsbBYXGMTqh0kM0aqMlV1mNpvVFYT2z5pHEIaibL\n $\\ w4mHkO/pqVnDtgwjkA9R1aEQeqg3SKysd5j0tzCXkQ0mIIC5G2X5KHUt0QWSepHX\\n$ XPRnND1c2c3fMqysNnDiklatDgIx5Grk1ZXwnKGth+2ZNipCHmw/IQxy8fWvae8n\n oYZurW9Ugv5YhaUqT0jeDP9PP1s0QvrHN/13eQnM2szicPDC6XRdK7cKxRrfWJ3P\n kobHfHh8iLuYblFc0sGRW7EZk04MvNhmnxxlYXoGOY01FBNzl+45jEmOe0g7Fypz\n 021NswKCAQAHx/6xTXvs4PByeDhFPuz0IzG8Y2MPDZBuPmGQtV6IX4LmzBT14Oxg\n YOd9WjmRnf1YK6yKs/0o/fiAZ8LLPjPVEC4Pxkz03TJOjuaCsBniJagAvd2ARyAK\n wEtAB2y/dprZj/JS3JGuWsP24hD/UpnD+PlJ0VsVfqiK4EquWrClalJ+ivQln0UW\n $\verb|MWYUvyDPRRwLqQuODpblYKgAyrhmU/Sw7c2wPp+sbZW/Rq8Euae8+Br1oJB1YjAP\n|$ $\label{thm:control} ITzx+WUqpgIb88Yc9qBiy8g5pmAdT0uTuGIi3eN2Dot1u6QDpihQQ/f3WbKOXLGs\\n$ t6EMGOqJfH5Ky9d1jfMd70j/IgaBLNStAoIBAQCKqJNuH7FSta/KQ5fJzFrD/Mil\n Q6yfB9D92UEabB1Et22Zr7Ry5WAv4DRcYWV1HrBJQBOw4Gc5WZcEnE1HvhkX519w\n hccplP+tyRf+h6ppYqdl/YaW2vEMTR1gvvtV8+2aMYTNRQJuTjJIsk1vWvX42IhQ\n xqKM9xqmKGEsW+6e7UheaXY8afkjf20/euGgzTuEPoy+IA8vKrSAnLLWm4xDYjMV\n E4VxEPsgNYH1k2eqtGRQwYR0ML/fihHbJIlQnMr6o7/tKljx+3PCZeRaVR4/\n ----END RSA PRIVATE KEY----\n

Adding ActionScript Targets

The TargetApilnputDTO for this target has the following parameters:

- nameOrAddress
 - IP or FQDN of the script execution server.
- port
 - Port used to connect to the script execution server.
- userid
 - Username used to connect to the script execution server.
- privateKeyString
 - Path to the SSH private token corresponding to the user used to connect to the script execution server.
- manifestPath
 - Path to the ActionScript manifest file on the script execution server.

Use the POST https://l0.10.10.10/api/v3/targets request to add this target. Send the constructed TargetApilnputDTO as the body of the request.

Example Input:



```
"name": "userid",
         "value": "shepp"
      },
         "name": "privateKeyString",
         "value":"----BEGIN RSA PRIVATE KEY----\nMIIJKQIBAAKCAgEAxeKUk6WLFMf8seI2KztL4DoKKw0d6AG/39SH6or5S
iNbAGkM\nUmv8ABA0aCQqMF01j9V3kzGn71DIWWTxLOMBH06I01dvd9XYPVRJotGjpxus+xmV\nGbeXxJsdHfXrbtMeLnpkwG
C7gIu6W2o5Ez6YuLDKf+CeFZhGMOtVLiB2NWtzn33D\nKBh96tIom9EqKseovtQAj5VYDwPeuTaWX1RGMT11tsNGyezEc4Z2sppT4VFV
hsUV\nL+voDZzrtMfFiHUIgjPH4pK9c/iPj0um7YzmyMyARftyCsUg7iUZH4NlNLpikXVy\nxKiro6Quu7SZ4kcvr3ZF3970CON0hHz
C3mFsvZvRFgYKzgc8/BcZ8ZzEUFfqBqY4\ndejCU+jo86dYFL2Q8RfF2zsJenG0WbVRLtLGkc7RbMdBGjtt5roV5VAp+TyR9Hdd\nDc5F
Yvt4fAAMJtcmTIzdEAPSbVzDhkSajxRhOXvezJn+2Ddr34/9ZvFE7nJNgP/8\nKOGJ5H1dgG5mc7H+Ly3x5dXzPhcVNSUdNGgKnEvz
FgMJaGByAg5AZc5HOmiIwFKs\nKSE/m8dSRoHrHmenGGm5TtA4lu1IMUnvCC1mKkbUEJ2V6R17x8zmM4DYNRSTwcSL\nSZ7U/yDuwp
HwzeozNeoekGKeC23+jgyzr9/mzgmPF08q5F+wVg/7nlDRSXsCAwEA\nAQKCAgBPHMPbt25AM6gCEfcoF3/B0FMCXS8cpz5npRdlnI
QHsNTb+CN1/Df2aoQZ\nMoQva8RTKbuxfEOweLJwktuc33B+bK5lF+q3lSXrdvwtfPSZhYYFqXejnXOupXjh\nloS2fO7vE/2dr86m
mLY7f98ro3X50KzsrQdmiMdfHWajl1TLDJdgJy5TpF8K91RG\n3zuleMcs66MBxGo9LoXntDwwBog9e8Rk+fMeHWt46EQiKXLpfNPdmo
Na8kyGzLqr\nPsbpRCjPrRX3rkTRzYjPeCZXiGJn2uJZmCpCxgbhTrGZmLVofC+WCceFeg2M0cHh\nR1XSUjVtR7KtyvvzZcQah6p8r6S
CASQFeVbb13FJVkBd0J8Hzk5e4N5Qk3bv9V4W\nF7CC8dRV66kcAkf68ytLGXkQAsgo5RPBDYSp8E2JDLF4m+9w6aouPlg//QxG5+XA\n
wqGJseTipiHbiALcIGsCpc5QCqab2SNddaDtIIpnp2Zmo5E1OjutGeUAE3k+cnJ1\nJIFCkRL0vsPk0xODSXbV2PMaUjMT65ue7uBk
DqCtgHiSBXTk6DiWBjduDnoZlAmC\nI8M4o42mSPs2uoKcngJ2fboY5iSsXLQ8VT5Tix8fk7VzBFmOvchBUSFlyx6o3/01\n0SV3Qrq
z7tb1Xx+axQapIUEVbLV140k0jepvxF3HVELXRQd2eQKCAQEA8EzXro5j\nN/VgDQJ9pGphwUyQ9mNBC1c1jviAHHskh8gwa4BxhBL
zZ+aUUoIx0/mAYK0rihN+\nQJLI84c9tA62Au6Tq+CT60ad4SwxQ5m9mQZjq888T3dRssmY+f+5kYBzmaPHv18I\nSohh2tHqNh68T1K
mLbCABahcOppqJTjP0Oi0kR7XUk5gEeDNNb65oDOtuNytiVd4\ncNEq/cO8rqk2rTupLLjhVKzP91gVXL/SBw/HBjpMyJ3DMrcPXH84J
eMshJay/OnW\neY3Y+hsghw37zRxeuUtn5to0wVYayAmEhyXVing7EVV5wsyUaJQE25ZZWLjjiBHP\nZpLsSRc++uugnwKCAQEA0t
BSQrDdOH+O6Ydu9Tno1IUeilTQ8+VGx3esFlKtiDTW\ncSEZSfZKbf/GQgHKbxLVXjCLhbfPbCvCcojbmGSmtWRWxlySYPSW4tBiYJ
Sk6Fo8\nJ2hEYW3HQzyj23RjXIghCUqY5wNWj1brU4CRxHtMyV1eYJWGmTaBfDm8VoBghu9g\nFAyPkJs4WZUkUI7Sbg2vcJyLLP4XET
PlfACMptLrPs8RCyUjJAJYxpSdaSjLC7r9\n9gBusQOlIGpClrx+/86NYhdKDWmnd0lyjXNvMVwPIpoSVblXTZK7xRBgcNTsd2eh\nh1H
\verb|LuhLXZ76SplvtNH6MQP46WoblounEx70NnsddpQKCAQEA11VD339DQktLo+7/\n0CHPFZHMjueSwaHEtMQzyLORrsbBYXGMTqh0kM0a| and the control of the control o
qMlV1mNpvVFYT2z5pHEIaibL\nw4mHkO/pqVnDtgwjkA9R1aEQeqg3SKysd5jOtzCXkQ0mIIC5G2X5KHUtOQWSepHX\nXPRnND1c2c3f
MqysNnDiklatDgIx5Grk1ZXwnKGth+2ZNipCHmw/IQxy8fWvae8n\noYZurW9Ugv5YhaUqTOjeDP9PP1s0QvrHN/13eQnM2szicPDC6X
RdK7cKxRrfWJ3P\nkobHfHh8iLuYblFc0sGRW7EZk04MvNhmnxxlYXoGOY01FBNz1+45jEmOe0g7Fypz\n021NswKCAQAHx/6xTXvs4P
ByeDhFPuz0IzG8Y2MPDZBuPmGQtV6IX4LmzBT14Oxg\nYQd9WjmRnf1YK6yKs/Oo/fiAZ8LLPjPVEC4Pxkz03TJQjuaCsBniJaqAvd2A
RyAK\nwEtAB2y/dprZj/JS3JGuWsP24hD/UpnD+P1J0VsVfqiK4EquWrC1alJ+ivQln0UW\nMWYUvyDPRRwLqQuODpblYKgAyrhmU/
Sw7c2wPp+sbZW/Rq8Euae8+Br1oJB1YjAP\nITzx+WUqpgIb88Yc9qBiy8g5pmAdT0uTuGIi3eN2Dot1u6QDpihQQ/f3WbKOXLGs\nt6E
MGOqJfH5Ky9d1jfMd70j/IgaBLNStAoIBAQCKqJNuH7FSta/KQ5fJzFrD/Mil\nQ6yfB9D92UEabB1Et22Zr7Ry5WAv4DRcYWV1HrBJ
QBOw4Gc5WZcEnE1HvhkX519w\nhccp1P+tyRf+h6ppYqd1/YaW2vEMTR1gvvtV8+2aMYTNRQJuTjJIsk1vWvX42IhQ\nxqKM9xqmKGEsW
+6e7UheaXY8afkjf20/euGgzTuEPoy+IA8vKrSAnLLWm4xDYjMV\ni9PFbuSyRV6tJqQZxZ58dS2ykL5YpTLM+ZFyZmhAqSJWULpsKAxx
E2fnmniXOYVF\nE4VxEPsgNYH1k2eqtGRQwYR0ML/fihHbJI1QnMr6o7/tKljx+3PCZeRaVR4/\n----END RSA PRIVATE KEY----
\n"
      },
         "name": "manifestPath",
         "value": "/home/shepp/action-script/manifest.json"
   ],
   "type": "Action Script"
```

The API will return the TargetApiDTO for the ActionScript target upon success, or an error message upon failure.

Example Response:

{



```
"uuid": "73356329749216",
"displayName": "10.10.10.10-/home/shepp/action-script/manifest.json",
"category": "Orchestrator",
"inputFields": [
    "displayName": "Name or Address",
    "name": "nameOrAddress",
    "value": "10.10.10.10",
    "isMandatory": true,
    "isSecret": false,
    "isTargetDisplayName": false,
   "valueType": "STRING",
    "description": "IP or FQDNS for the Script Execution Server",
    "verificationRegex": ".*"
 },
    "displayName": "Port",
    "name": "port",
    "value": "22",
    "defaultValue": "22",
    "isMandatory": false,
    "isSecret": false,
   "isTargetDisplayName": false,
    "valueType": "STRING",
    "description": "Port to use for the Script Execution Server",
    "verificationRegex": ".*"
 },
    "displayName": "User ID",
   "name": "userid",
    "value": "shepp",
    "isMandatory": true,
    "isSecret": false,
   "isTargetDisplayName": false,
    "valueType": "STRING",
    "description": "Userid to use to execute command on the Script Execution Server",
    "verificationRegex": ".*"
  },
    "displayName": "Private Token",
   "name": "privateKeyString",
    "isMandatory": true,
    "isSecret": true,
    "isTargetDisplayName": false,
    "valueType": "STRING",
    "description": "SSH Private Token corresponding to the Userid",
    "verificationRegex": ".*"
 },
    "displayName": "Script Path",
    "name": "manifestPath",
    "value": "/home/shepp/action-script/manifest.json",
    "isMandatory": true,
    "isSecret": false,
```



```
"isTargetDisplayName": false,
      "valueType": "STRING",
      "description": "File Path to the ActionScript manifest file on the Execution Server",
      "verificationRegex": ".*"
    },
      "displayName": "Public Host Key",
      "name": "hostKey",
      "isMandatory": false,
      "isSecret": false,
      "isTargetDisplayName": false,
      "valueType": "STRING",
      "description": "Public key presented by the SSH server for host authenticaion; if not provided, the
presented key will be accepted and integrated into the target definition for future operations",
      "verificationRegex": ".*"
    }
  ],
  "lastValidated": "2020-07-28T20:46:22Z",
  "status": "Validated",
  "type": "Action Script",
  "readonly": false
Response headers
cache-control: no-cache, no-store, max-age=
```

Once the success response is received, the target is validated and ready for use.

Flexera One

Workload Optimization Manager integrates its management of workloads with Flexera One License Management. To do this, Workload Optimization Manager discovers the licenses and entitlements that you have configured in your Flexera environment. Workload Optimization Manager then creates groups and policies to represent these licenses and entitlements.

For each license, Workload Optimization Manager creates a dynamic group.

These groups contain the entities that are affected by a Flexera license. For example, Workload Optimization Manager might create one group of all the VMs affected by a license, and another group of all the host machines affected by that license.

These groups are dynamic – If you allocate or remove entities (workloads, hosts, etc.) under a given license, Workload Optimization Manager adds or removes those entities in the given group. Even if you have a license with no entities allocated to it, Workload Optimization Manager creates an empty group for that license.

The name of each group begins with Flexera. The group name then includes the name of the license, plus the entity type. For example, you might see the groups, Flexera: Microsoft SQL Server 2016 Standard VMs and Flexera: Microsoft SQL Server 2016 Standard Hosts.

For supported licenses, Workload Optimization Manager creates Placement and Automation policies.

A Flexera license can include placement constraints, or resource utilization constraints. Workload Optimization Manager can create policies to comply with those constraints:

Placement Policies

When calculating workload placement, Workload Optimization Manager uses placement policies to comply with constraints such as keeping workloads on licensed hosts, or clearing unlicensed workloads off of licensed hosts when necessary.



For more information, see Placement Policies (on page 673).

Automation Policies

Among other settings, these policies can specify operational, utilization, and scaling constraints to match the constraints in your Flexera license policies.

For more information, see Automation Policies (on page 677).

The name for each policy begins with the name Flexera. The policy name then includes the name of the license and constraint. For example, you might see a policy named Flexera: Microsoft SQL Server 2016 Standard restrict to hosts.

Workload Optimization Manager then applies these policies to the groups that correspond to the entity type and license name.

Workload Optimization Manager Policies for Flexera Licenses

Workload Optimization Manager generates policies to comply with the following types of Flexera licenses, where **Usage Rights** lists the configurations Workload Optimization Manager considers when creating policies:

License	Usage Rights	Notes
Microsoft Server Processor	Datacenter Edition "coverInstallsOnVirtualMachines": true, "limitNumberOfVirtualInstalls": false, "limitVirtualInstallsIncludesHost": true, "numberOfAllowedVirtualInstalls": 1	Create Placement Policies that limit on- prem VM moves to the licensed host.
	Standard Edition "coverInstallsOnVirtualMachines": true, "limitNumberOfVirtualInstalls": true, "limitVirtualInstallsIncludesHost": false, "numberOfAllowedVirtualInstalls": 1	Create Placement Policies that disable VM move actions.
Microsoft Server/ Management Core	Datacenter Edition "coverInstallsOnVirtualMachines": true, "limitNumberOfVirtualInstalls": false, "limitVirtualInstallsIncludesHost": false	Create Placement Policies that limit on-premise VM moves to the licensed host.
	Standard Edition "coverInstallsOnVirtualMachines": true, "limitNumberOfVirtualInstalls": true, "limitVirtualInstallsIncludesHost": false, "minimumNumberOfProcessors": 2	Create Placement Policies that disable VM move actions.
Microsoft Server Core	"coverInstallsOnVirtualMachines": false, "limitNumberOfVirtualInstalls": false, "limitVirtualInstallsIncludesHost": true, "minimumNumberOfThreadsPerVM": 4	Workload Optimization Manager analysis assumes licensing is based on the host. Create Placement Policies that limit onprem VM moves to the licensed host. Respect minimum vCPU thresholds. If there is a value for minimumNumberOfThreadsPerVM, create Automation Policies to enforce that minimum vCPU threshold for VMs.



Flexera Permissions

The account that Workload Optimization Manager uses to connect with a Flexera target must be a Read-Only account with the following roles:

- View IT assets
- call APIs

Adding Flexera Targets

You can configure a target to a Flexera SaaS account. To add a Flexera target, select the **Orchestration > Flexera** option on the Target Configuration page and provide the following information:

■ Flexera Region

The region for your Flexera account. Choose one of:

- NAM
- EU
- Organization ID

The unique identifier that defines your organization within Flexera One.

Refresh Token

The credential that Workload Optimization Manager can use to generate Access Tokens as needed.

Proxy Host

The address of the proxy used for this target. Only fill out proxy information if you connect to the Flexera instance via a proxy.

Proxy Port

The port to use with the proxy specified above. By default, this is 8080.

Proxy Username

The username to use with the proxy specified above.

Proxy Password

The password to use with the proxy specified above.

Secure Proxy Connection


When checked, Workload Optimization Manager will connect to the proxy via HTTPS.

Actions

Workload Optimization Manager does not generate unique actions for entities it discovers through a Flexera target. Instead, it uses the license specifications it discovers in Flexera to prevent actions that do not comply with license restrictions. It can also modify or generate actions to ensure license compliance.

When Workload Optimization Manager generates an action, the action details include a list of policies that constrain the action recommendation. In this list, policy names that begin with Flexera: indicate policies that implement the license constraints Workload Optimization Manager has discovered for Flexera. You can click to navigate to the policy definition. Note that you cannot see the policy definition, but you cannot edit it.





The policies that Workload Optimization Manager generates affect Workload Optimization Manager actions in the following ways:

Entity	Policy Impact on Actions
Virtual Machine	■ Resize vCPU
	Limit Resize actions to stay above a specified minimum.
	Workload Optimization Manager will not recommend a resize that falls below a specified minimum. However, if a VM is already below the specified minimum and shows no performance problems, it will not recommend a resize up. Move
	Workload Optimization Manager restricts licensed VMs to their matching licensed Hosts. If the host has capacity, it can move unlicensed VMs onto a licensed host. However, if the host sees bottlenecks, Workload Optimization Manager will move unlicensed VMs off of the host first.
	Move actions can also consolidate license consumption on hosts. Assume you have one host that supports two licenses (LA and LB), and another host that only supports one license (LA). Also assume a mix of workloads, some that require both LA and LB, and some that only require LA. Move actions can consolidate the LA workloads on the LA host, leaving more resources for workloads that also require LB.
Host	■ Provision Host
	Workload Optimization Manager can recommend to provision a new licensed host. For example, assume your environment includes hosts that support two different licenses (LA and LB). Now assume you add more workloads that require only LB licenses. Workload Optimization Manager can recommend that you provision a new host that supports the LB license. Reconfigure Host



Entity	Policy Impact on Actions
	Workload Optimization Manager can recommend Host Reconfigure actions to change the licensing on a host. Assume Workload Optimization Manager has executed actions to consolidate LB-only workloads on a host with LA and LB licenses. Workload Optimization Manager can recommend that you reconfigure that host to remove LA, and only support the LB license.

ServiceNow

You can configure Workload Optimization Manager policies that log Workload Optimization Manager actions in your ServiceNow instance, and that submit actions for approval in ServiceNow workflows.

For more information concerning orchestration, see Action Orchestration (on page 688).

NOTE

When creating the action orchestration policy as explained in the section above, the scope of the policy must match the scope of the ServiceNow target.

Prerequisites

■ A ServiceNow user with the web_service_admin role and the custom role x_turbo_turbonomic.user that is created during installation that can communicate with Workload Optimization Manager via the REST API.

Adding ServiceNow Targets

To add ServiceNow targets, select the **Orchestration > ServiceNow** option on the Target Configuration page and provide the following information:

Address

Hostname of the ServiceNow instance without the http or https protocols. For example, dev-env-266.service-now.com.

Username

Username for the account Workload Optimization Manager will use to connect to the ServiceNow instance

Password

Password for the account Workload Optimization Manager will use to connect to the ServiceNow instance

■ Client ID

The Client ID Workload Optimization Manager will use if Use oAuth is checked

Client Secret

The password Workload Optimization Manager will use if Use oAuth is checked

Port

Port used to access the ServiceNow Instance

■ Use oAuth

When checked, Workload Optimization Manager will use oAuth authentication to connect to the ServiceNow target

Proxy Host

IP address of the proxy server

Proxy Port

Port used to access the proxy

Proxy User

Username for the account Workload Optimization Manager will use to connect to the proxy

■ Port

Port used to access the ServiceNow Instance



ServiceNow Integration

In order to complete target addition, see the Workload Optimization Manager Actions for ServiceNow documentation.

Private Cloud

A private cloud manages resources in pools to support multi-tenancy and self-service provisioning of virtual workloads. Workload Optimization Manager manages these resource pools in real time as demand fluctuates. This includes demand across resource pools, virtual datacenters (VDCs), and tenants.

Adding a Private Cloud target to Workload Optimization Manager aids in the goal of Application Resource Management (ARM) by preventing bottlenecks within and between your managed entities, resizing virtual machines and containers, prioritizing managed workloads, and reducing storage latency throughout your private cloud, ensuring that applications running in your private cloud always have the resources they need to perform, when they need to perform.

On the private cloud, you can use Workload Optimization Manager to:

- Set up charge-back and show-back for private cloud or service-provider scenarios
- For service-providers, set up scoped views to limit exposure to the customer base
- Plan hardware requirements the planning scenarios takes cloud architectures into account

Supply Chain

For private clouds, Workload Optimization Manager discovers resource partitions that are managed by the cloud manager, the workloads running on these partitions (the VMs and applications), and the supply that hosts workload (the physical machines and storage). Workload Optimization Manager represents these partitions as the following types of Virtual Datacenters (VDCs):

Provider VDC

A collection of physical resources (PMs and datastores) within a private cloud. The cloud administrator has access to these resources, and defines the datacenter members. Administrators allocate Provider VDCs to manage resources that will be allocated to external customers through one or more Consumer VDCs.

■ Consumer VDC

A collection of resources that are available for customers to perform self-service management of workload through the cloud. It is an environment customers can use to store, deploy, and operate virtual systems. Consumer VDCs use the resources supplied by a Provider VDC.

NOTE:

Different targets use different names to refer to virtual data centers. In the Workload Optimization Manager supply chain, these entities are all represented by Consumer and Provider VDCs, as follows:

Workload Optimization Manager	vCenter Server	VMM
Consumer VDC	Resource Pool (Child)	Tenant or TenantQuota
Provider VDC	Resource Pool (Root)	Cloud

Virtual Machine Manager

In a Virtual Machine Manager(VMM) environment, the VMM management server processes commands and controls communications with the Hyper-V hosts. To manage VMM, you set the management server as a target. Workload Optimization Manager communicates with that target, and also with the Hyper-V hosts that the VMM server manages. For this reason, if you add a VMM target, you should not also add individual Hyper-V hosts as targets. You must grant Workload Optimization Manager access to the VMM management server, and also to all the associated Hyper-V machines.

Prerequisites

VMM Dynamic Optimization disabled (recommended) or set to Low aggressiveness, with a frequency of at least 60 minutes.



- Configure remote management on the VMM management Hyper-V server. Refer to <u>Enabling Windows Remote Management</u> (on page 213)
- Grant access on every host in the cluster that Workload Optimization Manager will manage to the following WMI namespaces and subspaces:
 - root/virtualization
 - root/virtualization/v2
 - root/microsoft/windows/storage
 - root/microsoft/windows/smb
 - root/wmi
 - root/cimv2
 - root/mscluster
- Apply necessary hot fixes on the VMM host

For example, if you are running VMM Server on a Windows Server version earlier than Windows Server 2012 R2, you must apply the hot-fix referenced in the Microsoft Knowledge Base article #2842230 (http://support.microsoft.com/kb/2842230).

Apply time synchronization

The VM that hosts Workload Optimization Manager must be synchronized with each target VMM management server. For instructions on synchronizing the clock on the Workload Optimization Manager server, see Synchronizing Time (on page 46).

- PowerShell execution must be enabled on the VMM management server.
- Configure port access

WinRM uses ports 5985 and 5986 for standard and secure communications, respectively. The firewall on your VMM server must open these ports.

Preexisting Hyper-V Targets

If any of the hosts that make up the VMM target were added separately as Hyper-V targets (and you do not plan to exclude these hosts), these targets must be deleted. Failure to do so will create duplicate entities in the market, which will negatively impact Workload Optimization Manager performance.

Adding VMM Targets

Workload Optimization Manager uses the address and credentials you provide to discover the VMM target. From the VMM target, Workload Optimization Manager gets the list of managed Hyper-V instances. It then uses that list to discover each Hyper-V instance. The Hyper-V credentials you provide must be valid for all of these machines.

Workload Optimization Manager will also import your Availability Sets, representing them as placement policies for the affected infrastructure.

To add VMM targets, select the **Private Cloud > VMM** option on the Target Configuration page, and provide the following information:

- The IP address or host name of the VMM management server
- Which port to use for the WSMan connection

For a standard connection (HTTP) use 5985. For a secure connection (HTTPS) use 5986.

■ Enable or disable a secure connection

If you enable a secure connection, then you must configure a certificate, and you must configure Workload Optimization Manager to communicate over HTTPS. For more information, see <u>Secure Setup for WSMan (on page 238)</u>.

Note that setting a secure connection for VMM does not also set secure connections for the underlying Hyper-V hosts. Any communications between Workload Optimization Manager and VMM will be secure. To configure secure connections to the underlying Hyper-V hosts, you must specify secure connections on each one.

Full domain name for the user account

This domain name identifies the user account for Active Directory authentication.

Login credentials for the Hyper-V servers that are managed by the VMM target (Optional)

Workload Optimization Manager must log into the Hyper-V servers that the VMM server manages. If you leave the Hyper-V credentials blank, then it will use the same credentials that VMM uses. If you provide Hyper-V credentials, then it will use that service account to log into every Hyper-V managed by the VMM.



Note that the service account Workload Optimization Manager uses to log into a Hyper-V host must satisfy certain requirements. For more information, see <u>Creating a Service User Account in Hyper-V (on page 212)</u>.

Hosts in the VMM target that you would like to exclude from Workload Optimization Manager.

Workload Optimization Manager will not discover or manage any hosts you enter in this field. These hosts do not participate in the market, and Workload Optimization Manager does not generate actions that involve these hosts. Enter multiple hosts in a comma-separated list. This field accepts both host names, and FQDNs (Fully Qualified Domain Names), and allows the use of the wild-card characters * and ?.

Microsoft VMM and Hyper-V VLANs

Windows Server Hyper-V provides support for VLANs on host and VM partitions. If your Hyper-V environment makes use of this VLAN support, then your VM moves must be sensitive to which hosts provide networking access to your defined VM networks. If a VM is a member of a given VM network, then any move of that VM must be to a host that has access to the same network.

For Hyper-V targets in a VMM environment, the Cloud Control Module is aware of the VM networks, and ensures that a move is to a host that provides connectivity over the given VM network. For example, if Host 1 and 2 provides connectivity to VM Network A, and Host 3 and 4 provide connectivity to VM Network B, Workload Optimization Manager will never recommend a VM with access to Network A, residing on Host 1, to move to Host 3. That would render the VM unable to communicate on Network A.

Configuring SMB 3.0 File Shares Discovery

With VMM, Workload Optimization Manager can discover SMB 3.0 shares as datastores, assuming these shares have been properly added to your VMM service center. When you add shares to your VMM environment, be sure to:

- Use the Fully Qualified Domain Name of the file server
 - As you the associated file server to your VMM environment (via the Add Storage Devices Wizard), be sure to specify the FQDN of the file server on the Specify Discovery Scope page of the wizard. Do not use the file server's IP address.
- Ensure that file server names are unique

Do not specify file servers with the same name, even if they belong to different domains. Workload Optimization Manager requires the file server names to be unique.

For information about setting up SMB 3.0 shares, please refer to your Microsoft documentation. For example, see "How to Assign SMB 3.0 File Shares to Hyper-V Hosts and Clusters in VMM".

Monitored Resources

Workload Optimization Manager monitors the following resources:

■ Virtual Machine

- Virtual Memory (VMem)
 - Virtual Memory is the measurement of memory that is in use.
- Virtual CPU (VCPU)
 - Virtual CPU is the measurement of CPU that is in use.
- Virtual Storage
 - Virtual storage is the measurement of virtual storage capacity that is in use.
- Storage Access (IOPS)
 - Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.
- Latency
 - Latency is the measurement of storage latency.

■ Host

- Memory (Mem)
 - Memory is the measurement of memory that is reserved or in use.
- CPU
 - CPU is the measurement of CPU that is reserved or in use.



– IO

IO is the utilization of a host's IO adapters.

Net

Net is the utilization of data through the host's network adapters.

– Swap

Swap is the measurement of a host's swap space that is in use.

Balloon

Balloon is the measurement of memory that is shared by VMs running on a host.

- CPU Ready

CPU Ready is the measurement of a host's ready queue capacity that is in use.

Datacenter

NOTE:

For datacenter entities, Workload Optimization Manager does not monitor resources directly from the datacenter, but from the hosts in the datacenter. See host monitored resources for details.

■ Provider Virtual Datacenter

Memory (Mem)

Memory is the measurement of memory that is reserved or in use.

- CPU

CPU is the measurement of CPU that is reserved or in use.

Storage

Storage is the utilization of the storage attached to the entity.

■ Consumer Virtual Datacenter

Memory (Mem)

Memory is the measurement of memory that is reserved or in use.

CPU

CPU is the measurement of CPU that is reserved or in use.

Storage

Storage is the utilization of the storage attached to the entity.

Actions

Workload Optimization Manager can recommend the following actions:

Virtual Machines

- Provision additional resources (VMem, VCPU)
- Move Virtual Machine
- Move Virtual Machine Storage
- Reconfigure Storage
- Reconfigure Virtual Machine
- Suspend VM
- Provision VM

■ Host

- Start
- Provision
- Suspend

■ Consumer Virtual Datacenters

- Resize Consumer vDC
- Provision Consumer vDC



Secure Setup of WSMan

Workload Optimization Manager provides a secure option for Hyper-V/VMM Targets which requires that WSMan be set up securely. Use PowerShell to generate a self-signed certificate, and create an HTTPS WinRM listener.

NOTE:

For clustered Hyper-V targets, you do not need to create a listener on each host. Only create a listener on the host that is being added to the "Address" field in the Target Configuration.

To enable secure WSMan on your Hyper-V host:

Generate a self-signed certificate using the following command:

```
New-SelfSignedCertificate -CertstoreLocation Cert:\LocalMachine\My -DnsName "myhost.example.org"
```

2. Find the thumbprint for the certificate for the host:

```
Get-childItem cert:\LocalMachine\My
```

3. Create an HTTPS WinRM listener for the host with the thumbprint you've found:

```
winrm create winrm/config/Listener?Address=*+Transport=HTTPS '@{Hostname="myhost.example.org"; Certi
ficateThumbprint="THUMBPRINT_YOU_FOUND"}'
```

4. Verify the presence of configured listeners:

```
Get-WSManInstance -ResourceURI winrm/config/listener -Enumerate
```

Public Cloud

The public cloud provides compute, storage, and other resources on demand. Workload Optimization Manager can analyze the performance of workloads running on the public cloud, and scale workloads as demand requires.

With public cloud targets, you can use Workload Optimization Manager to scale workloads at the lowest possible cost, or reduce costs by purchasing discounts, deleting unattached volumes, or stopping workloads temporarily.

Amazon Web Services

Amazon Web Services (AWS) provides a reliable and scalable infrastructure platform in the cloud. You gain access to this infrastructure through a subscription account with the appropriate organization API permissions. To specify an AWS target, you provide the credentials for that account and Workload Optimization Manager discovers the resources available to you through that account.

Before Adding Targets

Review the following items before adding AWS targets.

Permissions

The account for an AWS target must have permissions that enable Workload Optimization Manager to monitor entities in your environment, recommend actions, and execute actions.

For details, see AWS Permissions (on page 242).

Supported Regions

Workload Optimization Manager supports discovery and management of entities in certain AWS regions, including AWS GovCloud (US) regions.

For details, see Supported AWS Regions (on page 244) and Support for AWS GovCloud (on page 245).

AWS Billing Families



As you configure AWS targets, Workload Optimization Manager discovers AWS accounts that are consolidated into *billing families*. By recognizing billing families, Workload Optimization Manager more accurately calculates cloud investments and savings, and makes more accurate recommendations for RI coverage.

For details, see AWS Billing Families (on page 248).

Cost and Usage Report

In order for Workload Optimization Manager to display month-to-day spend, you must create a cost and usage report in AWS and store it in an S3 bucket.

For details, see:

- Creating Cost and Usage Reports in the AWS documentation
- Setting up an Amazon S3 bucket for Cost and Usage Reports in the AWS documentation

Reserved Instances (RIs)

In order to discover RI utilization, you must provide Workload Optimization Manager with access to the S3 bucket that contains the AWS Cost and Usage report. Without this access, Workload Optimization Manager's purchase and scale decisions will be made without consideration of this data.

In order to discover all RIs in an AWS Billing family, you must add a billing target via the master account. This master account needs cost explorer API access. Without the master account, Workload Optimization Manager will discover only those RIs that are purchased by accounts which have been added as targets.

■ Collection of Memory Metrics

We highly recommend enabling collection of memory metrics in your environment. Enabling memory metrics allows Workload Optimization Manager to generate Scale actions to optimize VM memory usage. For Workload Optimization Manager to collect memory metrics, you must enable the collection of these metrics on the VMs in your environment.

For details, see AWS Memory Metrics Collection (on page 249).

■ Firewall and Proxy Access

If you run Workload Optimization Manager behind a proxy or firewall, then you must configure Workload Optimization Manager to allow unrestricted access to certain URLs. This enables the full set of features for AWS targets.

For details, see Firewall and Proxy Access for AWS (on page 251).

Adding AWS Targets

For Workload Optimization Manager to manage an AWS account, you provide the credentials via the access key or IAM role that you use to access that account. For information about getting an Access Key for an AWS account, see the Amazon Web Services documentation.

The AWS Target has different target addition requirements based on connection via access key or IAM role.

To add an AWS target without an IAM role, specify the following:

Custom Target Name

The display name that will be used to identify the target in the Target List. This is for display in the UI only; it does not need to match any internal name.

■ GovCloud toggle

When enabled, this target will be added as an AWS GovCloud (US) target.

Access Key

Provide the Access Key for the account you want to manage.

Secret Access Key

Provide the Access Key Secret for the account you want to manage.

Proxy Host

The IP of your Proxy Host

Proxy Port

The port required for the proxy above

Proxy User

The username required for the proxy above



Proxy Password

The password required for the proxy above

To add an AWS target with an IAM role, specify the following:

NOTE:

Workload Optimization Manager does not support adding AWS targets via IAM roles for an instance that was deployed onprem as an OVA or VHD image. If your instance was deployed in this way, you must add the target *without* using IAM Roles (see above).

Workload Optimization Manager deployed in Kubernetes (Red Hat OpenShift, Amazon EKS, GKE) supports adding AWS targets via IAM roles if the cluster configurations support an OIDC provider and webhook method. See <u>AWS Target IAM Role</u> Requirements (on page 252).

We recommend that you set up IAM access via an IAM group that has the necessary permissions. After you create this group, create a user that is a member of it and specify that user for Workload Optimization Manager to access your AWS environment. For more information about IAM Groups, see http://docs.aws.amazon.com/IAM/latest/UserGuide/best-practices.html.

Custom Target Name

The name that identifies the target in Workload Optimization Manager. This name is for display purposes only and does not need to match any name in AWS.

IAM Role ARN

Provide the **ARN** for the IAM role used to access the AWS Billing information.

Proxy Host

The address of the proxy used for this target. Only fill out proxy information if you connect to the internet via a proxy.

Proxy Port

The port to use with the proxy specified above. By default, this is 8080.

Proxy Username

The username for the account to log into the proxy specified above.

Proxy Password

The password to use with the proxy specified above.

Adding an AWS Billing Target

The Workload Optimization Manager AWS Billing target allows users to grant access to a bill which is used to discover billing family relationships. It does not provide access to any operational concern of an AWS account. Note that you can have one AWS Billing target per Workload Optimization Manager instance.

For details, see AWS Billing (on page 254).

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

AWS	Workload Optimization Manager
Virtual Machine (VM)	Virtual Machine (VM)
Relational Database Service (RDS)	Database Server
Storage	Volume
Zone	Zone
Region	Region



Monitored Resources

Workload Optimization Manager monitors the following resources:

Virtual Machine

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

I/O Throughput

I/O Throughput is the measurement of an entity's throughput to the underlying storage.

Net Throughput

Net Throughput is the rate of message delivery over a port.

Database Server

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

- DB Cache Hit Rate

DB cache hit rate is the measurement of Database Server accesses that result in cache hits, measured as a percentage of hits versus total attempts. A high cache hit rate indicates efficiency.

Connection

Connection is the measurement of database connections utilized by applications.

Volume

Storage Amount

Storage Amount is the storage capacity (disk size) of a volume.

Workload Optimization Manager discovers Storage Amount, but does not monitor utilization.

For a Kubeturbo (container) deployment that includes volumes, Kubeturbo monitors Storage Amount utilization for the volumes. You can view utilization information in the Capacity and Usage chart.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the measurement of IOPS capacity that is in use.

I/O Throughput

I/O Throughput is the measurement of I/O throughput capacity that is in use.

Actions

Workload Optimization Manager can recommend the following actions:



NOTE:

Use the Potential Savings and Necessary Investments charts to view pending actions and evaluate their impact on your cloud expenditure.

Virtual Machine

- Stop and Start (also known as 'parking' actions)

Stop a VM for a given period of time to reduce your cloud expenses, and then start it at a later time.

Scale

Change the VM instance to use a different instance type or tier to optimize performance and costs.

Discount-related actions

If you have a high percentage of on-demand VMs, you can reduce your monthly costs by increasing RI coverage. To increase coverage, you scale VMs to instance types that have existing capacity.

If you need more capacity, then Workload Optimization Manager will recommend actions to purchase additional RIs. For details, see Actions for AWS VMs (on page 381).

Database Server

Stop and Start (also known as 'parking' actions)

Stop a Database Server for a given period of time to reduce your cloud expenses, and then start it at a later time.

Scale

Scale compute and storage resources to optimize performance and costs.

For details, see Cloud Database Server Actions (on page 413) and Parking: Stop or Start Cloud Resources (on page 597).

■ Volume

Scale

Scale attached volumes to optimize performance and costs.

Delete

Delete unattached volumes as a cost-saving measure. Workload Optimization Manager generates an action immediately after discovering an unattached volume.

For details, see Cloud Volume Actions (on page 425).

AWS Permissions

The account for an AWS target must have permissions that enable Workload Optimization Manager to monitor entities in your environment, recommend actions, and execute actions.

Generic AWS Permissions

You can use generic AWS permissions to set up access for the account Workload Optimization Manager uses to access your target. This is an easy way to configure a target account, but you do not have full control over the access you grant to that account. For finer control, you should set the minimum permissions.

Permission Level	Required Permissions
Read-Only (monitoring and recommendations)	 AmazonEC2ReadOnlyAccess AmazonS3ReadOnlyAccess AmazonRDSReadOnlyAccess AWSConfigRoleForOrganizations (only required for consolidated billing with the master account)
Execute Actions	 AmazonEC2FullAccess AmazonS3ReadOnlyAccess AmazonRDSFullAccess



Permission Level	Required Permissions
	 AWSConfigRoleForOrganizations (only required for consolidated billing with the master account)

Minimum Permissions

To explicitly control the access that you grant to Workload Optimization Manager, as a minimum the account for an AWS target must have the following permissions:

Workload Optimization Manager Functionality	Required Permissions
Monitoring	 autoscaling:DescribeAutoScalingGroups cloudwatch:GetMetricData cloudwatch:GetMetricStatistics cloudwatch:ListMetrics ec2:DescribeSpotInstanceRequests ec2:DescribeAvailabilityZones ec2:DescribeInstances ec2:DescribeImages ec2:DescribeVolumes
	 ec2:DescribeVolumeStatus ec2:DescribeVolumesModifications ec2:DescribeAddresses ec2:DescribeRegions ec2:DescribeReservedInstances ec2:DescribeReservedInstancesModifications ec2:DescribeSpotPriceHistory
	 ec2:DescribeAccountAttributes ec2:DescribeTags elasticloadbalancing:DescribeTargetGroups elasticloadbalancing:DescribeTargetHealth elasticloadbalancing:DescribeLoadBalancers
	 elasticloadbalancing:DescribeInstanceHealth iam:GetUser organizations:DescribeOrganization organizations:ListAccounts pi:GetResourceMetrics rds:DescribeDBInstances
	 rds:DescribeDBClusters rds:DescribeDBParameters rds:ListTagsForResource rds:DescribeOrderableDBInstanceOptions servicecatalog:SearchProducts
Action Execution	 autoscaling:SuspendProcesses autoscaling:ResumeProcesses autoscaling:DescribeLaunchConfigurations autoscaling:CreateLaunchConfiguration autoscaling:DeleteLaunchConfiguration autoscaling:UpdateAutoScalingGroup ec2:DescribeInstances



Workload Optimization Manager Functionality	Required Permissions
	■ ec2:DescribeVolumes
	 ec2:DescribeVolumesModifications
	■ ec2:ModifyInstanceAttribute
	■ ec2:StopInstances
	■ ec2:StartInstances
	■ ec2:ModifyVolume
	■ ec2:DescribeInstanceStatus
	 ec2:DescribeReservedInstancesOfferings
	■ ec2:DeleteVolume
	 iam:PassRole (required if IAM Instance Profile is specified for the ASG Launch Configuration for the ASG VM being resized)
	 KMS:CreateGrant (required if your EC2 instances use encrypted EBS volumes)
	■ rds:ModifyDBInstance
	■ rds:StartDBInstance
	■ rds:StopDBInstance
	 servicecatalog:DescribeProduct
	servicecatalog:ProvisionProduct
	servicecatalog:DescribeRecord
	servicecatalog:ListLaunchPaths
Savings Plans	■ savingsplans:DescribeSavingsPlans

AWS Billing Target Permissions

To enable access to an AWS Billing target, the account must also include these permissions.

Workload Optimization Manager Functionality	Required Permissions
Monitoring	 ce:GetReservationUtilization ce:GetSavingsPlansUtilizationDetails ce:GetSavingsPlansUtilization ce:GetSavingsPlansCoverage iam:GetUser organizations:DescribeOrganization organizations:ListAccounts pricing:DescribeServices pricing:GetAttributeValues s3:GetBucketAcl s3:GetObject

For details, see AWS Billing Targets (on page 254).

Supported AWS Regions

Workload Optimization Manager supports discovery and management of entities in the following AWS regions:

Region Code	Region Name	Notes
af-south-1	Africa (Cape Town)	Requires opt-in within AWS console



Region Code	Region Name	Notes
ap-south-1	Asia Pacific (Mumbai)	
ap-northeast-1	Asia Pacific (Tokyo)	
ap-northeast-2	Asia Pacific (Seoul)	
ap-northeast-3	Asia Pacific (Osaka)	
ap-southeast-1	Asia Pacific (Singapore)	
ap-southeast-2	Asia Pacific (Sydney)	
ap-southeast-3	Asia Pacific (Jakarta)	
ap-east-1	Asia Pacific (Hong Kong)	Requires opt-in within AWS console
ca-central-1	Canada (Central)	
eu-central-1	Europe (Frankfurt)	
eu-south-1	Europe (Milan)	Requires opt-in within AWS console
eu-west-1	Europe (Ireland)	
eu-west-2	Europe (London)	
eu-west-3	Europe (Paris)	
eu-north-1	Europe (Stockholm)	
me-south-1	Middle East (Bahrain)	Requires opt-in within AWS console
sa-east-1	South America (São Paulo)	
us-east-1	US East (N. Virginia)	
us-east-2	US East (Ohio)	
us-west-1	US West (N. California)	
us-west-2	US West (Oregon)	
us-gov-east-1	AWS GovCloud (US-East)	Restricted Access (GovCloud)
us-gov-west-1	AWS GovCloud (US-West)	Restricted Access (GovCloud)

Unreachable AWS Regions

When Workload Optimization Manager fails to reach one or more AWS regions as part of discovering your AWS environment, then AWS discovery will fail for that target.

There may be policy decisions that prevent Workload Optimization Manager from reaching all AWS regions. For example, if you operate Workload Optimization Manager behind a firewall, you might not be able to reach all the regions that are available to your AWS account. In that case, you need to specify which regions you want Workload Optimization Manager to discover.

For information about how to specify the regions that you want Workload Optimization Manager to discover, contact your support representative.

Support for AWS GovCloud

AWS GovCloud (US) provides dedicated regions for US government customers and their partners to architect secure cloud solutions and meet regulatory and compliance requirements.

Workload Optimization Manager discovers workloads in these regions when you add the required accounts as targets. Discovered workloads include VMs (including auto-scaling groups), volumes, database servers, and spot instances. Workload



Optimization Manager recommends actions on VMs, volumes, and database servers to address performance issues and optimize costs.

Prerequisites

When adding GovCloud targets, ensure the following prerequisites are met:

The GovCloud account must be either a master account with organization access, or a member account belonging to a master account already added to Workload Optimization Manager. In addition, each account within the organization must have a unique name.

When you add accounts, be sure to enable the **GovCloud** toggle to indicate that the account you are adding is for GovCloud.

For details about adding accounts as targets, see Amazon Web Services (on page 238).

- RI utilization information is identical to non-government targets.
- A billing target with organization access containing billing information for the GovCloud target must be added to Workload Optimization Manager in order to discover RIs.

For details about billing targets, see AWS Billing (on page 254).


Optionally, you can add the AWS standard account that manages invoicing for a GovCloud account. When you add this standard account, it appears in the Top Accounts chart and shows the total projected billed cost for the GovCloud account and the standard account itself.

Information in Charts

Use the following charts to view information about your government accounts and workloads.

■ Top Accounts chart

Use the Top Accounts chart as a starting point.




The chart shows the GovCloud master and member accounts that you have added as targets. Accounts with a star symbol are master accounts.


Be aware that the 30-day cost is shown as **N/A** since invoicing for that account is managed through an associated AWS *standard account*. Adding this standard account as a target is optional. When added, it appears in the Top Accounts chart and shows the total billed cost for the GovCloud account and the standard account itself.

■ Necessary Investments and Potential Savings charts

Set the scope to a government account or subscription, and then see the Necessary Investments and Potential Savings charts to evaluate the costs you would incur or save if you execute all the pending actions for your government workloads.








■ Discount Inventory chart

The government accounts that you added as targets enable Workload Optimization Manager to gain full insight into the discounts (on page 113) that you have purchased for your government workloads. Even as you selectively add secondary targets, Workload Optimization Manager remains aware of all discounts, and how they are utilized across the board. This increases the accuracy of the allocation and purchase recommendations that Workload Optimization Manager generates for your government workloads.



Workload Planning

You can run an Optimize Cloud plan to identify performance and efficiency opportunities for existing government workloads, or a Migrate to Cloud plan to migrate government VM groups to another cloud provider.

For on-prem clusters, you can run a Migrate to Cloud plan to see how you can safely migrate the VMs in these clusters to a government account/subscription and region.



AWS Billing Families



As you configure AWS targets, Workload Optimization Manager discovers AWS accounts that are consolidated into *billing families*. A billing family has one *master* account, and zero or more *member* accounts. By recognizing billing families, Workload Optimization Manager more accurately calculates cloud investments and savings, and makes more accurate recommendations for RI coverage.

In the Targets user interface:

- 1. Master accounts appear in bold, with a star next to them.
- 2. You can expand the account entry to see the related member accounts.
- 3. If you expand the entry for a member account, the related accounts includes the family master, indicated by a star.
- 4. Related accounts includes the member accounts

NOTE:

If you expand the entry for a member account, then the related accounts includes the family master, indicated by a star.

A gray name indicates a member account that is not configured as a target.

For RI purchases, different accounts in a billing family can share the same RI resources. At the same time, accounts in other billing families cannot use those RIs. This adds flexibility to your RI coverage, while maintaining order over the billing.

In Workload Optimization Manager, if you enable Billing Family Recognition, then you can see the billing family master and member accounts in the Targets user interface, and Workload Optimization Manager can recommend proper RI purchases within the correct billing families.

To enable Billing Family Recognition, ensure the following as you configure your AWS targets:

Use the proper role for each AWS target

To properly discover billing family information for a target, you must give Workload Optimization Manager credentials for an AWS role that includes the permission, organizations: DescribeOrganization. With that permission, Workload Optimization Manager can:

- Discover master accounts and member accounts in different billing families
- Display the account names in the user interface
- Discover billing information for each family and account



- Recommend RI actions that respect billing family boundaries
- Configure targets for the complete billing family

One billing family can consolidate a number of AWS accounts. For Workload Optimization Manager to include these accounts in its analysis, you must configure each one as a separate target. If you do not configure all the accounts in a billing family, then Workload Optimization Manager cannot discover complete billing information for that family, and its analysis will be based on incomplete information.

Workload Optimization Manager displays member accounts that have been configured as targets in regular text. For members that Workload Optimization Manager discovers but have not been configured as targets, Workload Optimization Manager displays their names in grayed text.

If you have enabled Billing Family Recognition, you should keep the following points in mind:

Billing families can grow

Workload Optimization Manager regularly checks the membership of your billing families. If it discovers a new member account, it adds that account to the list of members. If you have already configured the account as a target, then Workload Optimization Manager includes the new member in its analysis of billing families. If the new member is not already a target, then Workload Optimization Manager lists the new member in grayed text.

You can configure discounts per billing family

Workload Optimization Manager includes a feature to set a discount for a billing group, and to override that discount for specific template families within that scope. For more information, see <u>Cloud Discounts (on page 717)</u> and <u>Discount Override: AWS (on page 719)</u>.

You might see master accounts that have no member accounts

AWS treats every account you create as a part of a billing family. Assume you created an account, but you had no reason to consolidate its billing with any other accounts. In that case, the account appears in the Workload Optimization Manager user interface as a master account, but it has no member accounts.

AWS Memory Metrics Collection

We highly recommend enabling collection of memory metrics in your environment. Enabling memory metrics allows Workload Optimization Manager to generate Scale actions to optimize VM memory usage. For Workload Optimization Manager to collect memory metrics, you must enable the collection of these metrics on the VMs in your environment.

Some of the steps to do this are different depending on whether your VM is running a Linux or Windows OS. To enable memory statistics on your VMs, you must meet the following requirements:

- The VM image must have an SSM agent installed
 - Linux VMs:
 - By default, Linux AMIs dated 2017.09 and later include an installed SSM Agent.
 - Windows VMs:

You must install the SSM agent on the VMs. For more information, see Working with SSM Agent.

Access to the CloudWatch service

Your AWS Instance must have internet access or direct access to CloudWatch so it can push data to CloudWatch.

Access from Workload Optimization Manager

For Workload Optimization Manager to access the memory data, the account that it uses to connect to the AWS target must include the correct permissions. If you configured the AWS target via an AWS key (not an IAM role), then you must include the permissions as specified in the section for configuring an AWS target.

If you use an IAM role for the Workload Optimization Manager connection, then that role must include the following as a minimum:

- AmazonEC2ReadOnlyAccess
- AmazonS3ReadOnlyAccess
- AmazonRDSReadOnlyAccess



To set up the collection of memory statistics for your VMs:

1. Attach an IAM role to each VM instance.

Each EC2 instance must have an attached IAM role that grants CloudWatch access. To grant that access, we suggest you include the AmazonSSMFullAccess policy in the role.

Use the AWS System Manager to attach the necessary roles to your VMs.

NOTE:

If you want to grant the role lesser access, you can use the AmazonEC2RoleforSSM policy. This is a custom policy that allows the action ssm:GetParameter to access the resource, arn:aws:ssm:*:*parameter/*.

2. Install the CloudWatch agent on your Linux VMs.

Navigate to the AWS System Manager service for the account and region that you want to configure. In the service, navigate to the **Run Command** screen and set up the **AWS-ConfigureAWSPackage** command to install **AmazonCloudWatchAgent** on your VMs. For more information, please see the AWS documentation.

3. Create configuration data for the CloudWatch agent.

The configuration data is a JSON object that you will add to as a parameter to the Parameter Store. The object must include the following, depending on whether it's for a Linux or a Windows VM instance.

■ Linux Configuration:

```
{
  "agent":{
  "metrics_collection_interval":60,
  "logfile": "/opt/aws/amazon-cloudwatch-agent/logs/amazon-cloudwatch-agent.log"
  },
  "metrics":{
  "namespace": "custom",
   "metrics_collected":{
     "mem":{
      "measurement":[
         "name": "mem_available", "rename": "MemoryAvailable", "unit": "Bytes"
      1
     }
  },
   "append_dimensions":{
     "AutoScalingGroupName": "${aws:AutoScalingGroupName}",
     "ImageId": "${aws:ImageId}",
     "InstanceId": "${aws:InstanceId}",
     "InstanceType": "${aws:InstanceType}"
   }
  }
```

Windows Configuration:

```
{
  "metrics": {
    "namespace": "Windows System",
    "append_dimensions": {
        "InstanceId": "${aws:InstanceId}"
    },
    "aggregation_dimensions": [ ["InstanceId"] ],
    "metrics_collected": {
        "Memory": {
```



Note that you can configure optional parameters for the CW Namespace and region. However, if you configure more metrics for CloudWatch to collect, these metrics do not affect Workload Optimization Manager analysis and they do not show up in the user interface. Workload Optimization Manager only tracks Used Memory statistics.

- 4. Create a parameter store.
 - Create a parameter.

In the AWS System Manager, navigate to **Parameter Store** and create a parameter. Copy and paste the JSON agent configuration (created above) into the parameter **Value** field.

b. Name the parameter

For example, AmazonCloudWatch-MyMemoryParam. You can use a different name, but per the Amazon documentation, the name *must* begin with AmazonCloudWatch. For more information, see Store the CloudwatchConfig File in Parameter Store.

You must remember this parameter name.

- Click to create the parameter.
- 5. Deploy the CloudWatch parameter to your VMs.

In the AWS System Manager, navigate to the **Run Command** screen to configure and run the **AmazonCloudWatch-ManageAgent** command. The configuration should include:

- Action: configure
- Mode: ec2
- Optional Configuration Source: ssm
- Optional Configuration Location: Give the name of the parameter that you created above.
- Optional Restart: yes (this restarts the CloudWatch Agent, not the VM instance)
- Targets: The VMs that you will deploy the CloudWatch configuration to

When the command is configured, run it. This configures collection of memory metrics for your instances.

6. Verify that you are collecting Memory metrics for your instances.

Navigate to the CloudWatch page, and display **Metrics** in the **CWAgent** namespace. Then inspect the instances by ID to verify that you can see MemoryAvailable metrics.

Firewall and Proxy Access for AWS

If you run Workload Optimization Manager behind a proxy or firewall, then you must configure Workload Optimization Manager to allow unrestricted access to the following URLs. This enables the full set of features for AWS targets.



NOTE:

If your firewall performs IP based routing, be aware that Amazon reserves the right to change the DNS names on these endpoints over time. Also note, the AWS SDK is designed to use dynamic endpoints. It is possible that Amazon will change the endpoints the SDK depends on over time. As a result, the names of endpoints you must access might be different than the names listed here.

Autoscaling

```
autoscaling. {region-id}.amazonaws.com
```

AWS Bill

```
{bucket-name}.s3.{region-containing-report}.amazonaws.com
```

CloudWatch

```
monitoring. {region-id}.amazonaws.com
```

CloudWatch Events

```
events. {region-id}.amazonaws.com
```

CloudWatch Logs

```
logs.{region-id}.amazonaws.com
```

Cost Explorer

```
ce.us-east-1.amazonaws.com
```

■ EC2

```
ec2.{region-id}.amazonaws.com
```

■ Elastic Load Balancing

```
elasticloadbalancing.{region-id}.amazonaws.com
```

IAM

```
iam.amazonaws.com
```

Organizations

```
organizations. {region-id}.amazonaws.com
```

Performance Insights

```
pi.{region-id}.amazonaws.com
```

Price List

```
pricing.us-east-1.amazonaws.com
```

Relational Database Service (RDS)

```
rds.{region-id}.amazonaws.com
```

Resource Groups

```
resource-groups. {region-id}.amazonaws.com
```

Savings Plans (Optional: Required if you use Savings Plans in your environment)

```
savingsplans.amazonaws.com
```

Service Catalog

```
servicecatalog. {region-id}.amazonaws.com
```

■ S3

```
s3.{region-id}.amazonaws.com
```

Storage Gateway

```
storagegateway. {region-id}.amazonaws.com
```

AWS Target IAM Role Requirements

This appendix guides you through the steps to configure the Workload Optimization Manager AWS Mediation pods to leverage IAM roles. To do so, you must leverage the ability to provide fine grained IAM role support through a Service Account, and Kubernetes cluster configurations that support an OIDC provider and webhook method.



Prerequisites

Follow the steps below to configure the AWS Mediation pods to leverage IAM roles:

- 1. Follow the instructions provided by Amazon EKS, Red Hat OpenShift, or GKE to make sure you have the required configurations to support the Web Identity provider method, leveraging the AWS webhook and an OIDC provider.
 - Introducing EKS Granular IAM Roles for Pods via Service Accounts and OIDC Providers
 - Overview of setting up IAM Role for EKS WebIdentity Provider
 - Creating a Service Account with an IAM Role: EKS example
 - Red Hat OpenShift support for Granular IAM Roles
 - GKE and IAM roles described in this <u>blog</u> using <u>gtoken</u> to inject the token into the pod
 - AWS IAM Role Permissions and Trust Relationships

NOTE:

Follow the instructions from AWS in the links above to set up your cluster's OIDC provider as an IAM Identity Provider (Web Identity Provider - OIDC URL) in the AWS account that you will be targeting.

- 2. Configure a Kubernetes Service Account in the Workload Optimization Manager namespace that will assume an IAM role.
 - (Best Practice) Manually create a separate Service Account for the AWS Mediation pods to use. You must then modify the Custom Resource YAML to specify this Service Account to the AWS Mediation components. For example:

```
spec:
  mediation-aws:
    serviceAccountName: t8c-iam-role
mediation-awsbilling:
    serviceAccountName: t8c-iam-role
mediation-awscost:
    serviceAccountName: t8c-iam-role
```

After you update the Custom Resource YAML, apply the updated Custom Resource and ensure the three Mediation pods restarted.

Use the Workload Optimization Manager default Service Account with which the AWS Mediation pods are running.

NOTE:

Unless specified in the Workload Optimization Manager Custom Resource, the AWS Mediation pods will run with the default service account called "default" in the namespace. If you modify the default "default" account, there is nothing more to do except restart the AWS Mediation pods.

- Configure the IAM role in AWS.
 - Workload Optimization Manager AWS IAM role requirements, including cross account access if required, are described here. IAM policy definition must use the sts: AssumeRoleWithWebIdentity role.
 - Using the Web identity provider set up, and the Service Account you will use, update the Trust Relationships in the IAM role. See the instructions here.
 - The IAM role for Workload Optimization Manager to target your AWS account requires the following policies:

```
AmazonRDSReadOnlyAccess
AmazonEC2ReadOnlyAccess
AmazonS3ReadOnlyAccess
AWSOrganizationsReadOnlyAccess
```

4. Annotate the Service Account you will use with the IAM role. See this article for an example.

```
apiVersion: v1
kind: ServiceAccount
#use the name of the SA that will contain the annotation
name: default
metadata:
   annotations:
```



eks.amazonaws.com/role-arn: arn:aws:iam::<AWS_ACCOUNT_ID>:role/<IAM_ROLE_NAME>

5. Complete the Workload Optimization Manager AWS Account Target setup by going to the Workload Optimization Manager UI to configure the AWS Account targets using an IAM role. See Amazon Web Services (on page 238).

AWS Billing

The Workload Optimization Manager AWS Billing target allows users to grant access to a bill which is used to discover billing family relationships. It does not provide access to any operational concern of an AWS account. Note that you can have one AWS Billing target per Workload Optimization Manager instance.

Before Adding Targets

Review the following items before adding AWS Billing targets.

Permissions

To enable access to an AWS Billing target, the AWS account must include certain permissions.

For details, see AWS Billing Target Permissions (on page 244).

■ Cost and Usage Report

Billing targets use cost and usage reports.

Workload Optimization Manager supports cost and usage reports created at the management account, but not member accounts.

In order for Workload Optimization Manager to display month-to-day spend, you must create a cost and usage report in AWS and store it in an S3 bucket.

For details, see:

- Creating Cost and Usage Reports in the AWS documentation
- Setting up an Amazon S3 bucket for Cost and Usage Reports in the AWS documentation

Price Adjustments

Cloud service providers can offer their own price lists, including special costs for services or discounts for workloads. However, Workload Optimization Manager does not discover these adjustments. For example, to reflect any discounted prices in the Workload Optimization Manager display and in Workload Optimization Manager analysis, you must manually configure those discounts. In Workload Optimization Manager, you configure such discounts via **Price Adjustments** for specific billing groups in your cloud environment.

Price Adjustments are needed for AWS to show proper discounted rates that customers have, even after adding the AWS Master Billing Account target. If Price Adjustments are not set, Workload Optimization Manager will show on-demand pricing, which results in incorrect cost numbers in actions and the UI. See Price Adjustments (on page 717) for more information.

Adding an AWS Billing Target

The AWS Billing target has different target addition requirements based on connection via key or IAM role.

To add an AWS Billing without an IAM role, specify the following:

Custom Target Name

The display name that will be used to identify the target in the Target List. This is for display in the UI only; it does not need to match any internal name.

Access Key

Provide the **Access Key** for the account you want to manage.

Secret Access Key

Provide the Access Key Secret for the account you want to manage.

Cost and Usage Report Bucket

Name of the S3 bucket that contains the AWS Cost and Usage report.

Cost and Usage Report Path



Path in the S3 bucket to the AWS Cost and Usage report.

■ Cost and Usage Report Region

Region of the S3 bucket that contains the AWS Cost and Usage report.

Proxy Host

The address of the proxy used for this target. Only fill out proxy information if you connect to AWS via a proxy.

Proxy Port

The port to use with the proxy specified above. By default, this is 8080.

Proxy Username

The username for the account to log into the proxy specified above.

Proxy Password

The password to use with the proxy specified above.

To add an AWS Billing target with an IAM Role, specify the following:

Custom Target Name

The display name that will be used to identify the target in the Target List. This is for display in the UI only; it does not need to match any internal name.

■ IAM Role ARN

Provide the ARN for the IAM role used to access the AWS Billing information.

Cost and Usage Report Bucket

Name of the S3 bucket that contains the AWS Cost and Usage report.

Cost and Usage Report Path

Path in the S3 bucket to the AWS Cost and Usage report.

Cost and Usage Report Region

Region of the S3 bucket that contains the AWS Cost and Usage report.

Proxy Host

The address of the proxy used for this target. Only fill out proxy information if you connect to AWS via a proxy.

Proxv Port

The port to use with the proxy specified above. By default, this is 8080.

Proxy Username

The username for the account to log into the proxy specified above.

Proxy Password

The password to use with the proxy specified above.

Monitored Resources

Workload Optimization Manager does not monitor resources for AWS Billing targets.

Actions

Workload Optimization Manager does not recommend actions for AWS Billing targets. However, the billing information will be used in conjunction with the AWS target to generate actions.

Google Cloud Platform

Google Cloud Platform (GCP) provides a scalable infrastructure platform in the cloud. Workload Optimization Manager gains access to this infrastructure through a GCP <u>service account</u> with the appropriate permissions.



Before Adding Targets

Review the following items before adding GCP service accounts as targets.

Service Accounts

When you add a service account as a target, Workload Optimization Manager discovers the projects that define compute, storage, and networking resources for your workloads. It then creates a derived target for each discovered project. Derived targets are not directly modifiable within Workload Optimization Manager but can be validated like any other target.

Workload Optimization Manager discovers a broader resource hierarchy if you add a service account target with permissions to retrieve folders or your entire GCP organization.

Workload Optimization Manager uses cost data in its analysis to make accurate recommendations for your workloads. To enable cost discovery and monitoring, you must grant your GCP service account "Billing Account Viewer" access to the related billing account, and then add the billing account as a target.

For instructions on creating service accounts in a gcloud shell session, see GCP Target Service Account (on page 259) and GCP Billing Target Service Account (on page 262).

Permissions

To configure GCP targets, you create service accounts with roles that grant Workload Optimization Manager the permissions it needs to discover your GCP resources and costs, and to execute actions (optional).

For details, see GCP Permissions (on page 264).

Supported Regions and Zones

Workload Optimization Manager supports discovery and management of workloads in all currently available GCP <u>regions</u> and <u>zones</u>.

GCP APIs

For Workload Optimization Manager to discover your GCP environment and billing details, you must enable certain APIs. For details, see Enabling Required GCP APIs (on page 266).

■ Collection of Memory Metrics

We highly recommend enabling collection of memory metrics in your GCP environment. With memory metrics, Workload Optimization Manager can generate actions that not only boost performance but also maximize your savings.

GCP collects these metrics via Ops Agent. In order for Workload Optimization Manager to retrieve these metrics, you must install and configure Ops Agent on each VM that it monitors. See Ops Agent installation instructions here, and configuration details here.

NOTE:

GCP recommends using Ops Agent instead of its legacy monitoring agent.

■ Firewall and Proxy Access

If you run Workload Optimization Manager behind a firewall, you must configure Workload Optimization Manager to allow unrestricted access to the following GCP URLs:

- https://cloudresourcemanager.googleapis.com
- https://cloudbilling.googleapis.com
- https://compute.googleapis.com
- https://monitoring.googleapis.com
- https://bigquery.googleapis.com

Adding GCP Targets

Once a service account has been properly configured for use with Workload Optimization Manager, you must add it as a target from the Target Configuration page.

Specify the following when adding the target:

Display Name

The name that identifies the target in Workload Optimization Manager. This name is for display purposes only and does not need to match any name in GCP.

Service Account Key (JSON)



The service account key for the account you want to manage. Paste the JSON object for the account key into this field.

Proxy Information

Specify proxy information only if you connect to a GCP target via proxy.

Proxy Host

The address of the proxy used for this target. Only fill out proxy information if you connect to the AppDynamics instance via a proxy.

- Proxy Port

The port to use with the proxy specified above. By default, this is 8080.

Proxy Username

The username to use with the proxy specified above.

Proxy Password

The password to use with the proxy specified above.

Secure Proxy Connection

When checked, Workload Optimization Manager will connect to the proxy via HTTPS.

Adding GCP Billing Targets

Workload Optimization Manager uses cost data in its analysis to make accurate recommendations for your workloads. To enable cost discovery and monitoring, you must grant your GCP service account "Billing Account Viewer" access to the related billing account, and then add the billing account as a target.

For details, see GCP Billing (on page 266).

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

GCP	Workload Optimization Manager
Virtual Machine (VM) Instance	Virtual Machine (VM) NOTE: Workload Optimization Manager discovers GCP labels attached to VMs as tags. You can filter VMs by tags when you use Search or create groups. The Action Details page for a pending VM action also lists all the discovered tags.
Storage/Disk	Volume
Zone	Zone
Region	Region

NOTE:

GCP projects, folders, and billing accounts do not appear as entities in the supply chain. Use Search to scope to these resources. In Search, projects are grouped under Accounts, folders under Folders, and billing accounts under Billing Families.

For billing accounts, the latest billing data available from Google is always a few days old. As a result, billing-related charts in Workload Optimization Manager (such as the Billed Cost chart) do not have data for the current day. In addition, billing data shown in billing-related charts and GCP Billing reports might not match because Workload Optimization Manager uses UTC, while GCP uses local time. However, costs shown in both places are correct and reliable.

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Virtual Machine
 - Virtual Memory (VMem)



Virtual Memory is the measurement of memory that is in use.

In order for Workload Optimization Manager to retrieve vMem metrics, you must install and configure Ops Agent on each VM that it monitors.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Workload Optimization Manager calculates CPU based on the normalized CPU frequency and the number of vCPUs for a given VM. Normalized CPU frequency takes into account performance variations seen in different models of a given CPU platform. Because frequency is normalized, charts might show utilization values that are slightly higher than 100% (for example, 100.03%) when capacity is fully utilized.

Net Throughput

Net Throughput is the rate of message delivery over a port.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

- I/O Throughput

I/O Throughput is the measurement of an entity's throughput to the underlying storage.

For both Storage Access (IOPS) and I/O Throughput, Workload Optimization Manager calculates capacity or uses GCP-published capacity data, depending on the VM's machine type and disk.

Shared-core machine types share a physical core and are used for running small, non-resource intensive apps.

For shared-core machine types with *standard disks*, Workload Optimization Manager uses capacity data that GCP publishes <u>here</u>. Note that there are no published values for e2-micro and e2-small, so Workload Optimization Manager assumes the e2-medium capacity for these machine types.

For shared-core machine types with SSDs, Workload Optimization Manager calculates capacity based on the observed maximum limit that can be achieved for IOPS and I/O throughput, and uses the calculated capacity to analyze utilization more accurately.

- For machine types that are *not* shared-core:
 - Workload Optimization Manager uses <u>published</u> capacity data and assumes that I/O block size is 16KB per I/O
 - For machine types with <u>persistent disks</u>, Workload Optimization Manager assumes that the published capacity for the *SSD* disk type also applies to the *balanced* and *extreme* disk types. When a VM is attached to at least one of these disk types, capacity is assumed to be the per-VM limit for the SSD disk type. When a VM is attached only to the *standard* disk type, capacity is the per-VM limit for the standard disk type.

Volume

Currently, Workload Optimization Manager does not monitor resources for GCP volumes. It only monitors their attachment state and then generates delete actions for unattached volumes.

Actions

Workload Optimization Manager can recommend the following actions:

NOTE

Use the Potential Savings and Necessary Investments charts to view pending actions and evaluate their impact on your cloud expenditure.

Virtual Machine

Scale

Change the VM instance to use a different instance type or tier to optimize performance and costs.

Discount-related actions

If you have a high percentage of on-demand VMs, you can reduce your monthly costs by increasing Committed Use Discount (CUD) coverage. To increase coverage, you scale VMs to instance types that have existing capacity.



Actions to purchase CUDs will be introduced in a future release.

Stop and Start (also known as 'parking' actions)

Stop a VM for a given period of time to reduce your cloud expenses, and then start it at a later time.

Reconfigure

GCP provides a specific set of machine types for each zone in a region. If you create a policy that restricts a VM to certain machine types and the zone it is currently on does not support all of those machine types, Workload Optimization Manager will recommend a reconfigure action as a way to notify you of the non-compliant VM.

For details, see Actions for GCP VMs (on page 385).

Volume

Delete

Delete unattached volumes as a cost-saving measure. Workload Optimization Manager generates an action immediately after discovering an unattached volume.

Workload Optimization Manager currently supports delete actions for zonal (single zone) persistent disks.

Points to consider:

- Delete actions for <u>regional</u> persistent disks will be introduced in a future release. Currently, Workload Optimization Manager discovers these volumes, but does not show actions or costs in charts.
- Workload Optimization Manager will never generate delete actions for local SSDs since they are always attached to VMs. GCP automatically deletes local SSDs when you delete the corresponding VMs.

For details, see Cloud Volume Actions (on page 425).

GCP Target Service Account

This topic guides you through the steps to create a valid service account that Workload Optimization Manager can use to connect with a GCP operational target. The access you grant to this service account determine the access Workload Optimization Manager has to discover and manage entities in your GCP infrastructure. To create this account you will:

- Create a service account in GCP
- Generate key file for the service account
- Create custom roles for the project(s) you want Workload Optimization Manager to manage
- Add the custom roles to the GCP Service Account, plus the predefined Billing Account Viewer role

Creating a Service Account in GCP

Open a gcloud shell session in the project that you want to host the new Service Account. In gcloud shell, execute the following command, where:

- \$SERVICE_ACCOUNT_ID is the unique alphanumeric ID that you assign to this service account
- \$SERVICE ACCOUNT DISPLAY NAME is the display name that you want for the service account

When you execute the command, the shell should display the following output:

Note the following fields in the output for later use:

■ email



- name
- projectId

NOTE:

The projectId field identifies the project that hosts this Service Account. You should note that project for future reference, in case you want to review or edit the Service Account.

Generating the Key File

To generate the key file, execute the following command in the gcloud shell:

```
$ gcloud iam service-accounts keys create $SA_KEY_FILE_NAME \
    --iam-account=$SERVICE_ACCOUNT_EMAIL
```

Be sure to save the key file - you need it when you configure the GCP Target in Workload Optimization Manager.

Creating Custom Roles

You must create two different roles for access to your GCP projects and organization, and you can create a third role for permission to execute actions in projects.

NOTE:

To target specific folders, define a custom role at the organization level. It is not possible to define custom roles at the folder level.

1. Project Access Role:

In a location you can access from your gcloud shell session, create a file named CWOMSaAccessProject.yaml. Edit the file to have the following content:

```
title: "CWOM Role: Min Access - Project"
description: "Minimal Required Permissions for CWOM to manage the GCP Project"
stage: "ALPHA"
includedPermissions:
# discovery
- resourcemanager.projects.get
- compute.regions.list
- compute.zones.list
- compute.machineTypes.list
- compute.machineTypes.get
- compute.disks.list
- compute.disks.get
- compute.diskTypes.list
- compute.instances.list
- compute.instances.get
- compute.instanceGroupManagers.list
- compute.instanceGroupManagers.get
- compute.commitments.list
# Metrics Monitoring
- logging.views.list
- logging.views.get
- monitoring.services.get
- monitoring.services.list
- monitoring.timeSeries.list
```

- serviceusage.services.get



Then execute the following command to create the custom role in your organization, where you substitute CWOMSaAccessProject.yaml with the path to your yaml file:

```
$ gcloud iam roles create $CUSTOM_ROLE_NAME \
    --project=$PROJECT_ID \
    --file=CWOMSaAccessProject.yaml
```

In the resulting console output, note the role name. You need that name to add the role to your service account.

2. Organization Access Role:

In a location you can access from your gcloud shell session, create a file named CWOMSaAccessOrg.yaml. Edit the file to have the following content:

```
title: "CWOM Role: Access - Organization"
description: "Minimal Required Permissions for CWOM to access the GCP Organization"
stage: "ALPHA"
includedPermissions:
# Organization Structure View
- resourcemanager.organizations.get
- resourcemanager.projects.list
- resourcemanager.projects.get
- resourcemanager.folders.list
- resourcemanager.folders.list
- resourcemanager.folders.get
- billing.resourceAssociations.list
```

Then execute the following command to create the custom role in your organization, where you substitute CWOMSaAccessOrg.yaml with the path to your yaml file:

```
$ gcloud iam roles create $CUSTOM_ROLE_NAME \
    --organization=$ORGANIZATION_ID \
    --file=CWOMSaAccessOrg.yaml
```

In the resulting console output, note the role name. You need that name to add the role to your service account.

Project Action Role:

Create this role if you want Workload Optimization Manager to execute actions in your GCP environment.

In a location you can access from your gcloud shell session, create a file named CWOMSaProjectAction.yaml. Edit the file to have the following content:

```
title: "CWOM Role: Project Action Execution"
description: "Grant CWOM to execute actions in the GCP Project"
stage: "ALPHA"
includedPermissions:
# Action Execution
- compute.globalOperations.get
- compute.instances.setMachineType
- compute.instances.start
- compute.instances.stop
- compute.disks.delete
- compute.regionOperations.get
- compute.zoneOperations.get
```

Then execute the following command to create the custom role in your organization, where you substitute CWOMSaProjectAction.yaml with the path to your yaml file:



```
$ gcloud iam roles create $CUSTOM_ROLE_NAME \
    --project=$PROJECT_ID \
    --file=CWOMSaProjectAction.yaml
```

In the resulting console output, note the role name. You need that name to add the role to your service account.

Adding Custom Roles to the Service Account

You will now add the three roles you created to your Service Account, plus the predefined Billing Viewer role.

1. (Required) Add the predefined Billing Viewer role.

In the GCP Console, go to **Billing > Account Management**. This page should display the billing account and project you are going to use as the GCP Billing target in Workload Optimization Manager.

Add the Billing Account Viewer role to the Service Account

2. (Required) Add the Organization Access role that you created for the Service Account.

In the gcloud console session, execute this command, where \$ROLE_NAME is the role name you noted when you created the Organization Access role:

```
$ gcloud projects add-iam-policy-binding $PROJECT_ID \
    --member=serviceAccount:$SERVICE_ACCOUNT_EMAIL --role=$ROLE_NAME
```

(Required) Add the Project Access role that you created for the Service Account.

In the gcloud console session, execute this command, where \$ROLE_NAME is the role name you noted when you created the Project Access role:

```
$ gcloud projects add-iam-policy-binding $PROJECT_ID \
    --member=serviceAccount:$SERVICE_ACCOUNT_EMAIL --role=$ROLE_NAME
```

(Optional) Add the Project Action role that you created for the Service Account.

You only need to add this role if you want Workload Optimization Manager to execute actions in your GCP project.

In the $gcloud\ console\ session$, execute this command, where $ROLE_NAME\ is$ the role name you noted when you created the Project Action role:

```
$ gcloud projects add-iam-policy-binding $PROJECT_ID \
    --member=serviceAccount:$SERVICE_ACCOUNT_EMAIL --role=$ROLE_NAME
```

You now have created a Service Account that you can use to configure your GCP operational target.

GCP Billing Target Service Account

This topic guides you through the steps to create a valid service account that Workload Optimization Manager can use to connect with a GCP Billing target. To create this account you will:

- Create a service account in GCP
- Generate key file for the service account
- Create a custom role in the project(s) you want Workload Optimization Manager to manage
- Add the created custom role to the GCP Service Account, plus the predefined Billing Account Viewer role

Creating a Service Account in GCP

Open a gcloud shell session in the project that you want to host the new Service Account. In gcloud shell, execute the following command, where:

- \$SERVICE ACCOUNT ID is the unique alphanumeric ID that you assign to this service account
- \$SERVICE_ACCOUNT_DISPLAY_NAME is the display name that you want for the service account



```
$ gcloud iam service-accounts create $SERVICE_ACCOUNT_ID \
    --display-name="$SERVICE_ACCOUNT_DISPLAY_NAME" \
    --format=text --quiet
```

When you execute the command, the shell should display the following output:

displayName: <SERVICE_ACCOUNT_DISPLAY_NAME>

email: <SERVICE_ACCOUNT_EMAIL>

etag: MDEwMjE5MjA=

Note the following fields in the output for later use:

- email
- name
- projectId

NOTE:

The projectId field identifies the project that hosts this Service Account. You should note that project for future reference, in case you want to review or edit the Service Account.

Generating the Key File

To generate the key file, execute the following command in the gcloud shell:

```
$ gcloud iam service-accounts keys create $SA_KEY_FILE_NAME \
    --iam-account=$SERVICE_ACCOUNT_EMAIL
```

Be sure to save the key file - you need it when you configure the GCP Billing target in Workload Optimization Manager

Creating a Custom Billing Role

In a location you can access from your gcloud shell session, create a file named CWOMSaBilling.yaml. Edit the file to have the following content:

```
title: "CWOM Billing Data Viewer Role"
description: "Minimal Required Permissions for CWOM to view billed cost and pricing stored in the GCP Pro
ject"
stage: "ALPHA"
includedPermissions:
- bigquery.tables.get
- bigquery.tables.getData
- bigquery.tables.list
- bigquery.jobs.create
# derived cost probe will need
- compute.regions.list
- compute.zones.list
- compute.commitments.list
- compute.diskTypes.list
- compute.machineTypes.list
```

Then execute the following command to create the custom role in your organization, where you substitute CWOMSaBilling.yaml with the path to your yaml file:



```
$ gcloud iam roles create $CUSTOM_ROLE_NAME \
    --project=$PROJECT_ID \
    --file=CWOMSaBilling.yaml
```

In the resulting console output, note the role name. You need that name to add the role to your service account.

Adding the Custom Roles to the Service Account

You will now add the Custom Billing role you created to your Service Account, plus the predefined Billing Viewer role.

- 1. (Required) Add the predefined Billing Viewer role.
 - In the GCP Console, go to **Billing > Account Management**. This page should display the billing account and project you are going to use as the GCP Billing target in Workload Optimization Manager.
 - Add the Billing Account Viewer role to the Service Account
- 2. (Required) Add the Custom Billing role that you created for the Service Account.

In the gcloud console session, execute this command, where \$ROLE_NAME is the role name you noted when you created the Custom Billing role:

```
$ gcloud projects add-iam-policy-binding $PROJECT_ID \
    --member=serviceAccount:$SERVICE_ACCOUNT_EMAIL --role=$ROLE_NAME
```

You now have created a Service Account that you can use to configure your GCP Billing target.

GCP Permissions

To configure GCP targets, you create service accounts with roles that grant Workload Optimization Manager the permissions it needs to discover your GCP resources and costs, and to execute actions (optional).

Resource Discovery Permissions

The following permissions are required to discover GCP workloads and resources.

Scope	Minimum Authorization Scopes	Minimum IAM Roles/Permissions
Project	One of the following scope sets: Set 1: https://www.googleapis.com/auth/ cloudplatformprojects.readonly https://www.googleapis.com/auth/cloud-platform https://www.googleapis.com/auth/cloud-billing.readonly Set 2: https://www.googleapis.com/auth/ cloudplatformprojects.readonly https://www.googleapis.com/auth/compute https://www.googleapis.com/auth/monitoring.read https://www.googleapis.com/auth/cloud-billing.readonly	 resourcemanager.projects.get compute.regions.list compute.zones.list compute.machineTypes.list compute.disks.list compute.disks.get compute.diskTypes.list compute.instances.list compute.instances.get compute.instanceGroupManagers.list compute.instanceGroupManagers.get logging.views.list logging.views.get monitoring.services.get monitoring.services.list monitoring.timeSeries.list



Scope	Minimum Authorization Scopes	Minimum IAM Roles/Permissions
		serviceusage.services.get
Folder	To target specific folders, define a custom role at the organizatio to define custom roles at the folder level.	n level (see the next item). It is not possible
Organization	One of the following scope sets: Set 1: https://www.googleapis.com/auth/cloud-platform https://www.googleapis.com/auth/cloud-billing.readonly Set 2: https://www.googleapis.com/auth/cloud-platform.readonly https://www.googleapis.com/auth/iam.test https://www.googleapis.com/auth/cloud-billing.readonly Set 3: https://www.googleapis.com/auth/cloud-billing.readonly https://www.googleapis.com/auth/cloudplatformorganizations.readonly https://www.googleapis.com/auth/cloudplatformfolders.readonly https://www.googleapis.com/auth/cloudplatformprojects.readonly https://www.googleapis.com/auth/cloud-billing.readonly https://www.googleapis.com/auth/cloud-billing.readonly	 All project-level permissions resourcemanager.organizations.get resourcemanager.folders.get resourcemanager.folders.list resourcemanager.projects.list resourcemanager.projects.get billing.resourceAssociations.list

Cost Discovery Permissions

The following permissions are required to discover GCP billing families, billed costs, negotiated pricing, and committed use discounts.

Minimum Authorization Scopes	Minimum IAM Roles/Permissions
■ All project-level scopes (on page 264). ■ https:// www.googleapis.com/ auth/cloud-billing.readonly ■ One of the following scopes: - https:// www.googleapis.com/ auth/compute - https:// www.googleapis.com/ auth/cloud-platform	The service account should have the Billing Account Viewer role and the following permissions to the project that stores billing data: All project-level permissions (on page 264) billing.resourceAssociations.list billing.accounts.list compute.commitments.list For queries of billed costs and negotiated pricing via BigQuery, the service account should have the Billing Account Viewer role and the following permissions to the project that stores billing data: bigquery.tables.get bigquery.tables.get bigquery.tables.list bigquery.jobs.create

Action Execution Permissions

The following permissions are required to execute actions on GCP workloads.

Minimum Authorization Scopes	Minimum IAM Roles/Permissions
■ All project-level scopes (on page 264)	 All project-level permissions (on page 264) compute.instances.stop



Minimum Authorization Scopes	Minimum IAM Roles/Permissions
One of the following scopes:https://www.googleapis.com/auth/compute	 compute.instances.setMachineType compute.instances.start
 https://www.googleapis.com/auth/cloud-platform 	 compute.disks.delete compute.zoneOperations.get compute.regionOperations.get compute.globalOperations.get

Enabling Required GCP APIs

For Workload Optimization Manager to discover your GCP environment and billing details, you must enable the following APIs:

- Cloud Resource Manager API
 - Creates, reads, and updates metadata for GCP resource containers.
- Compute Engine API
 - Creates GCP VMs and volumes.
- Cloud Billing API
 - Enables developers to manage billing for their GCP projects programmatically.
- BigQuery API
 - A data platform for customers to create, manage, share, and query data.

To enable these APIs:

- Navigate the GCP Console to the library of APIs.
 - On the GCP Console home page, navigate to APIs & Services > Library.
- 2. Search for the API you want to enable.

In the API Library **Search** box, enter the name of the API you want to enable. Then press **Enter** to execute the search. Repeat these steps for each of:

- Cloud Resource Manager API
- Compute Engine API
- Cloud Billing API
- BigQuery API
- 3. Enable the given API.

In the list that appears, click the API name to navigate to that API page. If the API is not already enabled, click Enable.

After you enable the given API, the console displays a details page for that API.

4. Navigate to the console Home page.

For each API you want to enable, navigate back to the home page and repeat these steps.

GCP Billing

Workload Optimization Manager uses cost data in its analysis to make accurate recommendations for your workloads. To enable cost discovery and monitoring, you must grant your GCP service account "Billing Account Viewer" access to the related billing account, and then add the billing account as a target.

When you add a billing account, Workload Optimization Manager also discovers negotiated pricing and committed use discounts (CUD) for your workloads. The Discount Inventory chart in the user interface shows a list of discovered CUDs.

You can add multiple billing accounts. Data for these accounts will be aggregated and shown when you set the scope to your global environment.



Before Adding Targets

Review the following items before adding GCP Billing targets.

Service Accounts

For instructions on creating service accounts in a gcloud shell session, see GCP Target Service Account (on page 259) and GCP Billing Target Service Account (on page 262).

Permissions

To configure GCP targets, you create service accounts with roles that grant Workload Optimization Manager the permissions it needs to discover your GCP resources and costs, and to execute actions (optional).

For details, see GCP Permissions (on page 264).

Adding Billing Accounts as Targets

To add a billing account target, specify the following:

Display Name

The name that identifies the target in Workload Optimization Manager. This name is for display purposes only and does not need to match any name in GCP.

Service Account Key

The service account key for the account associated with the billing account.

■ GCP Project ID

The unique ID assigned to the project associated with the billing account. Costs accrued to this project are charged to the billing account you are adding.

BigQuery Settings

BigQuery is a data warehouse that helps you manage GCP data. Workload Optimization Manager uses BigQuery resources to discover cost data for your environment. If you do not configure any of these fields, this target will not discover any cost data for Workload Optimization Manager analysis.

For more information, see:

- BigQuery Resources
- BigQuery Tables
 - Example Queries for Cloud Billing Data Export
 - Schema Standard Usage Cost Data
 - · Schema Pricing Data

To configure your target to discover BigQuery data, specify values for the following fields.

BigQuery Cost Export Data Set Name

The data set for billed costs. After you specify a data set, you must also specify the corresponding BigQuery Cost Export Table Name.

You can find the data set name in the GCP Billing dashboard under Billing export / BIGQUERY EXPORT.

BigQuery Cost Export Table Name

This is the table of exported cost data. You can find the table name in the GCP BigQuery Explorer. Expand your project, and then expand the Cost Export Data Set Name.

Enable Resource Level Detail From Cost Export Table

When you configure Billing Export, you can enable **Detailed usage cost**. To expose this detailed data to Workload Optimization Manager, turn on this option and then give the name of the detailed data table in the **BigQuery Cost Export Table Name** field. You can find the table name in the GCP BigQuery Explorer.

NOTE:

Only turn on this option if you have enabled **Detailed usage cost**. If you want to provide a **Standard usage cost** table, do not turn on this option.

BigQuery Pricing Export Table Name



This field automatically populates with the table name used in BigQuery, cloud_pricing_export. You need to provide a different name if you do any of the following:

- · Use a different table for negotiated pricing
- Specify a value for the BigQuery Pricing Export Data Set Name field. In that case, you must also specify the corresponding pricing export table.
- BigQuery Pricing Export Data Set Name

The data set for pricing. You can find the data set name in the GCP Billing dashboard under **Billing export / BIGQUERY EXPORT**.

Billing Account ID

The identifier of the Billing Account you want to target. This field is required if you configure **BigQuery Pricing Export Data Set Name** and **BigQuery Pricing Export Table Name**.

Proxy Information

Specify proxy information only if you connect to a GCP target via proxy.

- Proxy Host

The address of the proxy used for this target. Only fill out proxy information if you connect to the AppDynamics instance via a proxy.

- Proxy Port

The port to use with the proxy specified above. By default, this is 8080.

Proxy Username

The username to use with the proxy specified above.

Proxy Password

The password to use with the proxy specified above.

Secure Proxy Connection

When checked, Workload Optimization Manager will connect to the proxy via HTTPS.

Monitored Resources

Workload Optimization Manager does not monitor resources for GCP Billing targets.

Actions

Workload Optimization Manager does not recommend actions for GCP Billing targets. However, the billing information will be used in conjunction with the GCP target to generate actions.

Microsoft Azure

Microsoft Azure is Microsoft's infrastructure platform for the public cloud. You gain access to this infrastructure through a service principal target. To specify an Azure target, you provide the credentials for the subscription and Workload Optimization Manager discovers the resources available to you through that service principal.

Through Azure service principal targets, Workload Optimization Manager automatically discovers the subscriptions to which the service principal has been granted access in the Azure portal. This in turn creates a derived target for each subscription that inherits the authorization provided by the service principal (e.g. contributor). You cannot directly modify a derived target, but Workload Optimization Manager validates the target and discovers its inventory as it does with any other target.

Before Adding Targets

Review the following items before adding Azure service principal targets.

Azure Subscription Setup

To configure an Azure service principal target, you must first set up your Azure subscription to grant Workload Optimization Manager the access it needs.

For details, see Azure Subscription Setup (on page 274).



Permissions

For the service principal account, you must provide permissions to support all the actions you want to perform on any subscription accounts.

For details, see Azure Permissions (on page 275).

Azure Resource Manager

Workload Optimization Manager requires Azure Resource Manager. This service provides the management layer that Workload Optimization Manager uses to discover and manage entities in your Azure environment.

NOTE:

Workload Optimization Manager does not discover Azure Classic VMs, as they do not utilize Azure Resource Manager.

Supported Regions

Workload Optimization Manager supports discovery and management of entities in certain Azure regions, including Azure Government regions.

For details, see Supported Azure Regions (on page 283) and Support for Azure Government (on page 284).

Azure Reservations

To manage the use of Azure reservations, the app registration for this target must have permissions to manage the reservations. In most cases, Reader permissions are sufficient.

For <u>scoped reservations</u>, Workload Optimization Manager supports the <u>subscription</u> and <u>shared</u> scopes. To discover these reservations, you must assign the Azure App registration Reader permissions to both the Reservation and the Reservation Order (order ID). For details about reservation orders, see the Microsoft article, Manage Reservations for Azure resources.

Workload Optimization Manager also discovers reservations scoped to a *resource group*, but treats them as shared (in the Discount Inventory chart, the scope for these reservations is shown as Shared*). This could result in unreliable actions, such as scaling VMs within the resource group to other reservations, which could potentially increase costs. If you have existing reservations scoped to a resource group, be sure to change their scope in Azure before executing VM scale actions. For best results, change their scope to *shared*.

Collection of Memory Metrics

We highly recommend enabling collection of memory metrics in your environment. Enabling memory metrics allows Workload Optimization Manager to generate Scale actions to optimize VM memory usage. For Workload Optimization Manager to collect memory metrics, you must enable the collection of these metrics on the VMs in your environment.

For details, see Azure Memory Metrics Collection (on page 286).

■ Support for Azure App Service

Workload Optimization Manager discovers Azure App Service plans and app instances through your Azure targets.

For details, see Support for Azure App Service (on page 287).

■ Firewall and Proxy Access

If you run Workload Optimization Manager behind a proxy or firewall, then you must configure Workload Optimization Manager to allow unrestricted access to certain URLs. This enables the full set of features for Azure Service Principal targets.

For details, see Firewall and Proxy Access for Azure (on page 287).

Adding Azure Service Principal Targets

Be sure you have the following information at hand:

Directory (tenant) ID and Application (client) ID

You should have noted the Directory (tenant) ID and Application (client) ID when you registered Workload Optimization Manager with Azure Active Directory.

For details, see Registering Workload Optimization Manager with Active Directory (on page 274).

Client Secret

You should have saved the client secret generated for Workload Optimization Manager.

For details, see Creating the Client Secret (on page 274).



To add targets, select Azure Service Principal in the Target Configuration page, and provide the following information:

Display Name

The name that identifies the target in Workload Optimization Manager. This name is for display purposes only and does not need to match any name in Azure.

US Government

Turn this on to configure the target as an Azure Government (on page 284) target.

Directory (Tenant) ID

The ID of the tenant that contains subscriptions to be managed with Workload Optimization Manager.

Application (Client) ID

The Client/App ID of the app registration that gives Workload Optimization Manager access to resources in your Azure subscription.

■ Client Secret Key

The client secret key for the app registration.

Proxy Host

The IP of your Proxy Host

Proxy Port

The port required for the proxy above

Proxy User

The username required for the proxy above

Proxy Password

The password required for the proxy above.

Secure Proxy Connection

When checked, Workload Optimization Manager will connect to the proxy via HTTPS.

NOTE:

After adding a target, allow at least 30 minutes for Workload Optimization Manager to fully discover resource groups in your environment.

Adding a Billing Target

In addition to service principal targets, you must also specify a billing target so Workload Optimization Manager can use custom pricing and discover reservations. When you configure a billing target, Workload Optimization Manager uses that richer pricing information to calculate workload size and reservation coverage for your Azure environment.

Currently, two billing targets are supported.

■ Azure Billing – use this target if Workload Optimization Manager will manage non-government subscriptions.

The Workload Optimization Manager Azure Billing target discovers your Azure billing account and *non-government* subscriptions. The target discovers the billing account and related subscriptions associated with your MCA Billing Account ID or EA Enrollment Number.

For details, see Azure Billing (on page 288).

Microsoft Enterprise Agreement – use this target if Workload Optimization Manager will manage government subscriptions.

You can configure Workload Optimization Manager to manage *Azure government* subscriptions within the context of a Microsoft Enterprise Agreement (EA).

For details, see Microsoft Enterprise Agreement (on page 293).

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

Azure	Workload Optimization Manager
Virtual Machine (VM)	Virtual Machine (VM)



Azure	Workload Optimization Manager
App Service - plan	Virtual Machine Spec
App Service - app instance	App Component Spec
SQL Database (vCore or DTU)	Database
Dedicated SQL Pool (for Azure Synapse Analytics)	Database
Disk	Volume
Zone	Zone
Region	Region

Discovery of Entities in Locked Storage and Resource Groups

An Azure subscription can use locked storage or locked resource groups. For such subscriptions, Workload Optimization Manager discovers incomplete data. Locked resources affect Workload Optimization Manager discovery in either of these scenarios:

Locked resource group

Workload Optimization Manager discovers all the entities in the resource group, but does not discover the resource group itself. For example, in the Top Accounts chart, the Resource Groups field will show no resource groups for a subscription that has a locked resource group.

Locked storage

Workload Optimization Manager discovers all the entities in the resource group except the locked storage. It also discovers the resource group.

Monitored Resources

NOTE:

When you first configure an Azure target, under some circumstances the target has No Quotas Available, and so Workload Optimization Manager cannot discover the available templates. This can happen when you initially set up the Azure account and you have not enabled any providers. If this occurs, you can install a single VM in your cloud subscription to make quotas available. You can also navigate to the Azure Subscriptions Blade and select the subscription you want. For the resource providers, register the Microsoft. Compute option. For more information, see the following Microsoft article: Resolve errors for resource provider registration.

Workload Optimization Manager monitors the following resources:

Virtual Machine

- Virtual Memory (VMem)
 - Virtual Memory is the measurement of memory that is in use.
- Virtual CPU (VCPU)
 - Virtual CPU is the measurement of CPU that is in use.
- Storage Amount
 - Storage Amount is the measurement of storage capacity that is in use.
- Storage Access (IOPS)
 - Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.
- I/O Throughput
 - I/O Throughput is the measurement of an entity's throughput to the underlying storage.

■ Virtual Machine Spec (App Service Plan)

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.



Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Number of Replicas

Number of Replicas is the total number of VM instances underlying an App Service plan.

■ App Component Spec (App Service Instance)

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Database

The resources that Workload Optimization Manager can monitor depend on the pricing model in place for the given database entity.

- SQL Database DTU Pricing Model
 - DTU

DTU is the measurement of compute capacity for the database. DTU represents CPU, memory, and IOPS/IO Throughput bundled as a single commodity.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

- SQL Database vCore Pricing Model
 - Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

I/O Throughput

I/O Throughput is the measurement of an entity's throughput to the underlying storage.

- Dedicated SQL Pool (for Azure Synapse Analytics)
 - DWU

DWU (Data Warehousing Unit) is the measurement of compute capacity for the dedicated SQL pool. DWU represents CPU, memory, and IO Throughput bundled as a single commodity.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Connection

Connection is the measurement of database connections utilized by applications.

Volume

Storage Amount

Storage Amount is the storage capacity (disk size) of a volume.

Workload Optimization Manager discovers Storage Amount, but does not monitor utilization.

For a Kubeturbo (container) deployment that includes volumes, Kubeturbo monitors Storage Amount utilization for the volumes. You can view utilization information in the Capacity and Usage chart.



Storage Access (IOPS)

Storage Access, also known as IOPS, is the measurement of IOPS capacity that is in use.

- I/O Throughput

I/O Throughput is the measurement of I/O throughput capacity that is in use.

Actions

Workload Optimization Manager can recommend the following actions:

NOTE

Use the Potential Savings and Necessary Investments charts to view pending actions and evaluate their impact on your cloud expenditure.

Virtual Machine

Scale

Change the VM instance to use a different instance type or tier to optimize performance and costs.

Discount-related actions

If you have a high percentage of on-demand VMs, you can reduce your monthly costs by increasing Azure reservations coverage. To increase coverage, you scale VMs to instance types that have existing capacity.

If you need more capacity, then Workload Optimization Manager will recommend actions to purchase additional reservations.

Stop and Start (also known as 'parking' actions)

Stop a VM for a given period of time to reduce your cloud expenses, and then start it at a later time.

For details, see Actions for Azure VMs (on page 383).

Virtual Machine Spec (App Service Plan)

Scale

Scale Azure App Service plans to optimize app performance or reduce costs, while complying with business policies.

Delete

Delete empty Azure App Service plans as a cost-saving measure. A plan is considered empty if it is not hosting any running apps.

For details, see Virtual Machine Spec Actions (on page 404).

App Component Spec (App Service Instance)

None

Workload Optimization Manager does not recommend actions for App Component Specs, but it does recommend actions for the underlying Virtual Machine Specs. For details, see <u>Virtual Machine Spec Actions (on page 404)</u>.

Database

Scale (SQL Database)

DTU Pricing Model

Scale DTU and storage resources to optimize performance and costs.

vCore Pricing Model

Scale vCPU, vMem, IOPS, throughput and storage resources to optimize performance and costs.

Suspend (Dedicated SQL Pool)

Suspend an idle dedicated SQL pool (used for Azure Synapse Analytics) to reduce compute costs.

NOTE:

Currently, Workload Optimization Manager does not generate actions to start a suspended pool. You can manually start a pool from Azure.

For details, see Cloud Database Actions (on page 434).

Volume

Scale



Scale attached volumes to optimize performance and costs.

Delete

Delete unattached volumes as a cost-saving measure. Workload Optimization Manager generates an action immediately after discovering an unattached volume.

For details, see Cloud Volume Actions (on page 425).

Azure Subscription Setup

To configure an Azure service principal target, you must first set up your Azure subscription to grant Workload Optimization Manager the access it needs.

Subscription must be registered with the Microsoft. Capacity resource provider. This can be done in the settings section of the Azure portal.

Azure Required Permissions and Roles

Workload Optimization Manager interacts with Azure targets through an Azure Active Directory application/Service Principal. As part of subscription setup, you must assign a permission level through one of the built-in Azure roles.

For details about permissions and roles, see Minimum Permissions and Roles for Azure (on page 275).

Registering Workload Optimization Manager with Azure Active Directory

The administrator of an Azure Active Directory (Tenant) can register an application with the tenant. This app registration gives an external application access to the tenant's resources. Workload Optimization Manager connects to an Azure target via an app registration.

For the latest information, refer to this Azure article.

To register the application:

- 1. Log into the Azure Management Portal.
- 2. Add an App registration to an available tenant. The tenant ID will correspond with the tenant ID that you set for the target.
- 3. From the newly-created App registration blade in the Management Portal, go to the Overview blade.
 - This blade displays the generated Directory (tenant) ID and Application (client) ID for this app.
- 4. From the newly created App registration blade in the Management Portal, go to the Certificates and Secrets blade.

This blade displays previously created certificates and client secrets, as well as provides the ability to create them.

Creating the Client Secret

To create the client secret:

- 1. Navigate to the **Certificates and Secrets** section of your registered app.
- Create a new client secret.
 - a. Click + New client secret.
 - b. In the **Add a client secret** area, provide the required information.
 - Description Provide a valid name.
 - Expires Choose Never.
 - c. Click Add.

The blade generates a client secret for you to use when configuring the target in Workload Optimization Manager.

3. Copy the client secret.

IMPORTANT:

The client secret only displays once, during creation. It will no longer display after you leave the page.



Enabling Workload Optimization Manager Access to Subscriptions

The final step in setting up your Azure subscription is to add the Active Directory Application (that you created above) to each and every subscription that you want Workload Optimization Manager to manage. Note that if you need to, you can assign different permissions to each subscription (for example, service principal).

Perform these steps for each subscription that Workload Optimization Manager will manage.

- 1. Navigate to your Azure subscriptions list.
- 2. Select the first subscription you want Workload Optimization Manager to manage.
- 3. Navigate to the Access control for that subscription.
- 4. Add a role. For details about roles, see Minimum Permissions and Roles for Azure (on page 275).
- 5. Add the application you registered with the tenant.

Azure Permissions

Minimum Permissions and Roles for Azure

You can use generic Azure roles to set up access for the account Workload Optimization Manager uses to access your target. This is an easy way to configure a target account, but you do not have full control over the access you grant to that account. For finer control, you should set the minimum permissions.

Read-Only Access

Use the combined Reader plus Storage Account Contributor for the minimum combination required for Workload Optimization Manager to discover and access metrics across your Azure environment. Storage Account Contributor is required to access the Storage Account keys and establish a connection that can retrieve VM memory statistics.

Action Execution Access

For action execution access, the user must have the Owner or Contributor role. Contributor is the least privileged role that enables Workload Optimization Manager to take actions on your Azure environment, including manually or automatically scaling VMs across instance types.

Azure Service Principal and Subscription Permissions

For the service principal account, you must provide permissions to support all the actions you want to perform on any subscription accounts.

Workload Optimization Manager Functionality	Required Permissions
Role validation	 Microsoft.Authorization/roleAssignments/read Validates the role assigned to the Service Principal by checking if it has the minimum required permissions Microsoft.Authorization/roleDefinitions/read Queries the permissions list from the assigned custom role
Discovery of subscriptions	 Microsoft.Resources/subscriptions/read Gets a list of accessible subscriptions for a tenant
Discovery of resource groups, locations, and SKUs	 Microsoft.Resources/subscriptions/locations/read List all locations available for the subscriptions Microsoft.Resources/subscriptions/resourceGroups/read Discovers all resource groups for the subscriptions Microsoft.Compute/skus/read Gets a list of Microsoft.Compute SKUs available for your subscription
Discovery of storage accounts	■ Microsoft.Storage/storageAccounts/read



Workload Optimization Manager Functionality	Required Permissions
	Gets a list of storage accounts or gets the properties of a specific storage account
Discovery of metrics for various entities	 Microsoft.Insights/Metrics/Read Reads metrics for various resources from Azure Monitor Microsoft.OperationalInsights/workspaces/read Queries a list of Log Analytics workspaces. Certain metrics (such as VM memory) are fetched from these workspaces. Microsoft.OperationalInsights/workspaces/query/read Allows queries to data (such as metrics) stored in Log Analytics workspaces Microsoft.OperationalInsights/workspaces/query/InsightsMetrics/read Queries the InsightsMetrics Log Analytics table for VM memory metrics. Azure Monitor Agent must be configured to send memory metrics to the table. Microsoft.OperationalInsights/workspaces/query/Perf/read (Only required if the Perf Log Analytics table is configured for VM memory metrics, instead of the InsightsMetrics Log Analytics table) Queries the Perf Log Analytics table for VM memory metrics
Discovery of VMs	 Microsoft.Compute/virtualMachines/instanceView/read Gets the detailed runtime status of a VM and its resources Microsoft.Compute/virtualMachines/read Gets the properties of a VM Microsoft.Compute/virtualMachines/extensions/read (Only required if using storage account for VM memory configuration) Gets the properties of a VM extension, to detect diagnostics extension before fetching memory metrics from storage account
Discovery of VM scale sets and availability sets Discovery of reservations	■ Microsoft.Compute/virtualMachineScaleSets/read Gets the properties of a VM scale set ■ Microsoft.Compute/virtualMachineScaleSets/ virtualMachines/instanceView/read Retrieves the instance view of a VM in a scale set ■ Microsoft.Compute/virtualMachineScaleSets/ virtualMachines/read Retrieves the properties of a VM in a scale set ■ Microsoft.Compute/virtualMachineScaleSets/ virtualMachines/extensions/read (Only required if VM memory is configured onto a storage account table via a diagnostics agent extension) Gets the properties of an extension for a VM in a scale set ■ Microsoft.Compute/availabilitySets/read Lists all availability sets and gets their properties ■ Microsoft.Compute/availabilitySets/vmSizes/read Lists available sizes for creating or updating a VM in an availability set
	■ Microsoft.Capacity/reservationorders/reservations/read



Workload Optimization Manager Functionality	Required Permissions
<u> </u>	Monitors reservations data and reads all reservations
	■ Microsoft.Capacity/catalogs/read
	Reads the catalog of reservations
Discovery of volumes	■ Microsoft.Compute/disks/read
	Gets the properties of volumes
	■ Microsoft.Storage/storageAccounts/listkeys/action
	(Only required if there are unmanaged disks in your environment)
	Discovers or queries unmanaged disks (volumes) in the storage account, and checks if unmanaged disks that became unattached are being deleted via a Workload Optimization Manager action
Discovery of SQL databases (vCore/	■ Microsoft.Sql/servers/read
DTU) and metrics	Lists all SQL servers in this subscription and gets their details
	■ Microsoft.Sql/servers/databases/read
	Lists and gets details about all SQL databases for all SQL servers in the subscription
	■ Microsoft.Sql/servers/databases/metrics/read
	Queries metrics for SQL databases
Discovery of resources used in Azure	■ Microsoft.Synapse/SKUs/read
Synapse Analytics	Reads SKU details for a Synapse Analytics Service resource, such as SQL pools
	■ Microsoft.Synapse/workspaces/read
	Reads details about Synapse workspaces
	■ Microsoft.Synapse/workspaces/keys/read
	Gets details of Synapse workspace key definitions
	■ Microsoft.Synapse/workspaces/sqlDatabases/read
	Reads a list of Synapse SQL Analytics databases
	■ Microsoft.Synapse/workspaces/sqlPools/read
	Reads a list of Synapse SQL Analytics pools
	Microsoft.Synapse/workspaces/sqlPools/ dataWarehouseUserActivities/read
	Reads user activities on Synapse SQL Analytics pools
	■ Microsoft.Synapse/workspaces/sqlPools/extensions/read
	Gets extensions for Synapse SQL Analytics pools
	Microsoft.Synapse/workspaces/sqlPools/ operationStatuses/read
	Reads the results of asynchronous operations on Synapse SQL Analytics pools
	■ Microsoft.Synapse/workspaces/sqlPools/usages/read
	Reads usage metrics for Synapse SQL Analytics pools
	■ Microsoft.Synapse/workspaces/sqlUsages/read
	Gets usage limits available for Synapse SQL Analytics pools
Discovery of App Services (plans/app instances) and metrics	■ Microsoft.Relay/namespaces/HybridConnections/read Lists all Service Bus Hybrid Connections used by web apps
	■ Microsoft.Web/geoRegions/Read



Workload Optimization Manager Functionality	Required Permissions
Functionality The state of the	Gets a list of available geographical regions for App Services Microsoft.Web/serverfarms/Read Lists and gets the properties of App Service plans Microsoft.Web/serverfarms/sites/read Gets a list of web apps that are part of App Service plans Microsoft.Web/serverfarms/skus/read Gets SKUs for App Service plans Microsoft.Web/sites/read Gets the properties of web apps that are part of App Service plans Microsoft.Web/sites/read Gets the properties of web apps that are part of App Service plans Microsoft.Web/sites/slots/Read Gets the properties of a web app deployment slot Microsoft.Web/serverfarms/metrics/read Queries metrics for App Services plans Microsoft.Web/serverfarms/usages/read Gets usage information for App Service plans Microsoft.Web/sites/metrics/read Gets metrics for web apps that are part of App Service plans Microsoft.Web/sites/usages/read
	Gets usage information for web apps that are part of App Service plans
Discovery of clusters managed by Azure Kubernetes Service (AKS)	 Microsoft.ContainerService/managedClusters/read Discovers and lists managed container clusters Microsoft.ContainerService/managedClusters/agentPools/read Discovers agent pools on managed container clusters
Discovery of desktop virtualization (VDI)	Microsoft.DesktopVirtualization/hostpools/read Discovers Azure Desktop Virtualization host pools
	 Microsoft.DesktopVirtualization/hostpools/ sessionhosts/read Discovers session hosts in Azure Desktop Virtualization host pools
Discovery of network resources	 Microsoft.Network/networkInterfaces/read Lists and gets details about network interfaces for resources Microsoft.Network/publicIPAddresses/read Lists and gets details about public IP addresses for resources
Discovery of cost data	 Microsoft.Commerce/RateCard/read Discovers pricing information from the pay-as-you-go rate card; also returns offer data, resource/meter metadata, and rates for the given subscription Microsoft.Consumption/pricesheets/read Discovers pricing information from an Enterprise Agreement price sheet, and lists the price sheets data for a subscription or a management group
Discovery of locks that could prevent action execution	 Microsoft.Authorization/locks/read Lists all locks for a subscription, and creates action prerequisites that may prevent action execution if locks prevent write operations
Execution of actions for VMs	■ Microsoft.Compute/virtualMachines/deallocate/action



Workload Optimization Manager Functionality	Required Permissions		
,	Stops a VM to execute a disruptive action; powers off the VM and releases the allocated compute resources		
	■ Microsoft.Compute/virtualMachines/powerOff/action		
	Suspends a VM by powering it off. The VM will continue to be billed while suspended.		
	■ Microsoft.Compute/virtualMachines/start/action		
	Restarts a VM that was stopped to execute a disruptive action		
	■ Microsoft.Compute/virtualMachines/vmSizes/read		
	Lists available sizes that a VM can update to		
	■ Microsoft.Compute/virtualMachines/write		
	Updates a VM (for example, its size) as part of executing scale actions		
	■ Microsoft.Network/networkInterfaces/join/action		
	Allows a VM or VM scale set to rejoin its network after a scale action executes, by attaching the network interface to the VM		
	■ Microsoft.KeyVault/vaults/deploy/action		
	(Only required if a VM to be scaled is using Azure Key Vault)		
	Enables access to secrets in a key vault when deploying Azure resources to the VM		
	 Azure Compute Gallery images 		
	(Only required during VM scaling execution if VM images are located in a separate Azure Compute Gallery image, such as in a different subscription)		
	 Microsoft.Compute/galleries/images/read 		
	Gets the properties of Azure Compute Gallery images		
	- Microsoft.Compute/galleries/images/versions/read		
	Gets the versions for Azure Compute Gallery images		
	Microsoft.Compute/galleries/read		
	Gets Azure Compute Gallery images		
Execution of actions for VM scale sets and availability sets	■ Microsoft.Compute/virtualMachineScaleSets/deallocate/action		
	Stops a VM scale set to execute a disruptive action; powers off and releases the compute resources of the instances used by the VM scale set		
	■ Microsoft.Compute/virtualMachineScaleSets/start/action		
	Restarts the VMs that were stopped to execute a disruptive action on VM scale set		
	■ Microsoft.Compute/virtualMachineScaleSets/vmSizes/read		
	Lists available sizes for creating or updating a VM in a scale set		
	■ Microsoft.Compute/virtualMachineScaleSets/write		
	Updates a VM scale set (for example, its size) as part of executing scale actions for VM scale sets		
	■ Microsoft.Insights/AutoscaleSettings/Write		
	Updates an autoscale setting as part of scale action execution		
Execution of actions for volumes	■ Microsoft.Compute/disks/write		
	Resizes or changes the storage tier of volumes		
	Executes scale actions for volumes and re-attaches volumes to VMs after scaling		



Workload Optimization Manager Functionality	Required Permissions		
•	■ Microsoft.Compute/disks/delete		
	Deletes unattached volumes for managed disks		
	 Microsoft.Storage/storageAccounts/blobServices/ containers/blobs/delete 		
	Deletes unmanaged disks that became unattached after the deletion of unattached volumes		
	 Microsoft.Storage/storageAccounts/blobServices/ containers/blobs/read 		
	Checks if a page blob exists before deleting unmanaged disks that became unattached, and returns the properties of an existing page blob		
	Microsoft.Storage/storageAccounts/blobServices/ containers/read		
	Lists blob containers		
	Finds containers hosting unmanaged disks that became unattached and are to be deleted		
	 Recovery Services Vault 		
	(Only required if volumes are used for disaster recovery)		
	Prevents the deletion of volumes used for disaster recovery, even if they become unattached		
	- Microsoft.RecoveryServices/Vaults/read		
	Gets a list of Recovery Services Vaults containing replicated disks		
	- Microsoft.RecoveryServices/vaults/		
	replicationProtectedItems/read		
	Reads the Disk IDs of any protected items in the vaults		
Execution of actions for SQL databases	■ Microsoft.Sql/servers/databases/write		
(vCore and DTU)	Executes scale actions for DTU and vCore databases, and updates database properties		
	■ Microsoft.Sql/servers/databases/pause/action		
	Pauses a database as part of executing a scale or suspend action		
	■ Microsoft.Sql/servers/databases/resume/action		
	Resumes a paused database as part of executing a scale or suspend action		
ecution of actions for dedicated SQL	■ Microsoft.Synapse/workspaces/sqlPools/pause/action		
pools for Azure Synapse Analytics	Pauses (suspends) Synapse SQL Analytics pools		
Execution of actions for App Services	■ Microsoft.Web/serverfarms/Delete		
(plans)	Deletes an empty App Service plan (one that is not hosting any running apps)		
	■ Microsoft.Web/serverfarms/Write		
	Updates an App Service plan as part of a scale action		
Uploads of plan results to Azure Migrate	These permissions are only required if you are <u>uploading the results</u> (on page 575) of a 'Migrate to Cloud' plan to Azure Migrate.		
9. 4.0	Microsoft.Migrate/migrateprojects/read		
	Gets the properties of a Migrate project		
	Microsoft.Migrate/migrateprojects/solutions/read		
	Gets the properties of a Migrate project solution		
	 Microsoft.Migrate/migrateprojects/solutions/getconfig/action 		



Workload Optimization Manager Functionality	Required Permissions
	Gets the configuration of a Migrate project solution

For example, create a JSON file for your custom policy similar to the following, where **Your_subscription_ID>** sets the role scope to the ID of the Azure subscription you want for this target:

```
"Name": "Minimal Access",
"Description": "Minimal access policy",
"IsCustom": "true",
"Actions": [
    "Microsoft.Authorization/locks/read",
    "Microsoft.Authorization/roleAssignments/read",
    "Microsoft.Authorization/roleDefinitions/read",
    "Microsoft.Capacity/catalogs/read",
    "Microsoft.Capacity/reservationorders/reservations/read",
    "Microsoft.Commerce/RateCard/read",
    "Microsoft.Compute/availabilitySets/read",
    "Microsoft.Compute/availabilitySets/vmSizes/read",
    "Microsoft.Compute/disks/delete",
    "Microsoft.Compute/disks/read",
    "Microsoft.Compute/disks/write",
    "Microsoft.Compute/galleries/images/read",
    "Microsoft.Compute/galleries/images/versions/read",
    "Microsoft.Compute/galleries/read",
    "Microsoft.Compute/skus/read",
    "Microsoft.Compute/virtualMachineScaleSets/deallocate/action",
    "Microsoft.Compute/virtualMachineScaleSets/read",
    "Microsoft.Compute/virtualMachineScaleSets/start/action",
    "Microsoft.Compute/virtualMachineScaleSets/virtualMachines/extensions/read",
    "Microsoft.Compute/virtualMachineScaleSets/virtualMachines/instanceView/read",
    "Microsoft.Compute/virtualMachineScaleSets/virtualMachines/read",
    "Microsoft.Compute/virtualMachineScaleSets/vmSizes/read",
    "Microsoft.Compute/virtualMachineScaleSets/write",
    "Microsoft.Compute/virtualMachines/deallocate/action",
    "Microsoft.Compute/virtualMachines/extensions/read",
    "Microsoft.Compute/virtualMachines/instanceView/read",
    "Microsoft.Compute/virtualMachines/powerOff/action",
    "Microsoft.Compute/virtualMachines/read",
    "Microsoft.Compute/virtualMachines/start/action",
    "Microsoft.Compute/virtualMachines/vmSizes/read",
    "Microsoft.Compute/virtualMachines/write",
    "Microsoft.Consumption/pricesheets/read",
    "Microsoft.ContainerService/managedClusters/agentPools/read",
    "Microsoft.ContainerService/managedClusters/read",
    "Microsoft.DesktopVirtualization/hostpools/read",
    "Microsoft.DesktopVirtualization/hostpools/sessionhosts/read",
    "Microsoft.Insights/AutoscaleSettings/Write",
    "Microsoft.Insights/Metrics/Read",
    "Microsoft.KeyVault/vaults/deploy/action",
    "Microsoft.Migrate/migrateprojects/read",
    "Microsoft.Migrate/migrateprojects/solutions/getconfig/action",
    "Microsoft.Migrate/migrateprojects/solutions/read",
```



```
"Microsoft.Network/networkInterfaces/join/action",
    "Microsoft.Migrate/migrateprojects/read",
    "Microsoft.Migrate/migrateprojects/solutions/getconfig/action",
    "Microsoft.Migrate/migrateprojects/solutions/read",
    "Microsoft.Network/networkInterfaces/join/action",
    "Microsoft.Network/networkInterfaces/read",
    "Microsoft.Network/publicIPAddresses/read",
    "Microsoft.OperationalInsights/workspaces/query/InsightsMetrics/read",
    "Microsoft.OperationalInsights/workspaces/query/Perf/read",
    "Microsoft.OperationalInsights/workspaces/query/read",
    "Microsoft.OperationalInsights/workspaces/read",
    "Microsoft.RecoveryServices/Vaults/read",
    "Microsoft.RecoveryServices/vaults/replicationProtectedItems/read",
    "Microsoft.Relay/namespaces/HybridConnections/read",
    "Microsoft.Resources/subscriptions/locations/read",
    "Microsoft.Resources/subscriptions/read",
    "Microsoft.Resources/subscriptions/resourceGroups/read",
    "Microsoft.Sql/servers/databases/metrics/read",
    "Microsoft.Sql/servers/databases/pause/action",
    "Microsoft.Sql/servers/databases/read",
    "Microsoft.Sql/servers/databases/resume/action",
    "Microsoft.Sgl/servers/databases/write",
    "Microsoft.Sql/servers/read",
    "Microsoft.Storage/storageAccounts/blobServices/containers/read",
    "Microsoft.Storage/storageAccounts/listkeys/action",
    "Microsoft.Storage/storageAccounts/read",
    "Microsoft.Synapse/SKUs/read",
    "Microsoft.Synapse/workspaces/keys/read",
    "Microsoft.Synapse/workspaces/read",
    "Microsoft.Synapse/workspaces/sqlDatabases/read",
    "Microsoft.Synapse/workspaces/sqlPools/dataWarehouseUserActivities/read",
    "Microsoft.Synapse/workspaces/sqlPools/extensions/read",
    "Microsoft.Synapse/workspaces/sqlPools/operationStatuses/read",
    "Microsoft.Synapse/workspaces/sqlPools/pause/action",
    "Microsoft.Synapse/workspaces/sqlPools/read",
    "Microsoft.Synapse/workspaces/sqlPools/usages/read",
    "Microsoft.Synapse/workspaces/sqlUsages/read",
    "Microsoft.Web/geoRegions/Read",
    "Microsoft.Web/serverfarms/Delete",
    "Microsoft.Web/serverfarms/Read",
    "Microsoft.Web/serverfarms/Write",
    "Microsoft.Web/serverfarms/metrics/read",
    "Microsoft.Web/serverfarms/sites/read",
    "Microsoft.Web/serverfarms/skus/read",
    "Microsoft.Web/serverfarms/usages/read",
    "Microsoft.Web/sites/metrics/read",
    "Microsoft.Web/sites/read",
    "Microsoft.Web/sites/slots/Read",
    "Microsoft.Web/sites/usages/read"
"dataActions": [
 "Microsoft.Storage/storageAccounts/blobServices/containers/blobs/delete",
 "Microsoft.Storage/storageAccounts/blobServices/containers/blobs/read"
```

],



Supported Azure Regions

Workload Optimization Manager supports discovery and management of entities in the following Azure regions:

Region Code	Region Name	Notes
eastus	East US	
eastus2	East US 2	
centralus	Central US	
northcentralus	North Central US	
southcentralus	South Central US	
westcentralus	West Central US	
westus	West US	
westus2	West US 2	
westus3	West US 3	
canadaeast	Canada East	
canadacentral	Canada Central	
brazilsouth	Brazil South	
northeurope	North Europe	
westeurope	West Europe	
francecentral	France Central	
ukwest	UK West	
uksouth	UK South	
germanywestcentral	Germany West Central	
norwayeast	Norway East	
switzerlandnorth	Switzerland North	
eastasia	East Asia	
southeastasia	Southeast Asia	
australiaeast	Australia East	
australiasoutheast	Australia Southeast	
australiacentral	Australia Central	
centralindia	Central India	



Region Code	Region Name	Notes
southindia	South India	
westindia	West India	
japaneast	Japan East	
japanwest	Japan West	
koreacentral	Korea Central	
koreasouth	Korea South	
uaenorth	UAE North	
southafricanorth	South Africa North	
usgovarizona	USGov Arizona	Restricted Access (Azure Government)
usgovtexas	USGov Texas	Restricted Access (Azure Government)
usgovvirginia	USGov Virginia	Restricted Access (Azure Government)

Support for Azure Government

<u>Azure Government</u> provides dedicated regions for US government customers and their partners to architect secure cloud solutions and meet regulatory and compliance requirements.

Workload Optimization Manager discovers workloads in these regions when you add the required accounts as targets. Discovered workloads include VMs (including availability/scale sets), volumes, and SQL databases. Workload Optimization Manager recommends actions on these entities to address performance issues and optimize costs.

NOTE:

Workload Optimization Manager currently does not support Azure Government integration with Application Insights. You can add accounts for Azure Government and Application Insights as targets, but Application Insights will only return performance data for non-government workloads.

Prerequisites

When adding GovCloud targets, ensure the following prerequisites are met:

- The Azure Government account must be a service principal account. When you add the account, be sure to enable the **US**Government toggle to indicate that the account you are adding is for Azure Government.
 - For details about adding service principal accounts as targets, see Microsoft Azure (on page 268).
- In order for Workload Optimization Manager to discover custom pricing and reservations for Azure Government, you must add the corresponding Enterprise Agreement (EA) accounts.
 - For details about adding EA accounts as targets, see Microsoft Enterprise Agreement (on page 293).

NOTE

- Currently, the Azure Billing target (on page 288) cannot be used to manage Azure Government accounts.
- To use Azure Government with a firewall or proxy, it must be configured to allow unrestricted access to certain URLs. For details, see <u>Firewall and Proxy Access for Azure (on page 287)</u>.


Information in Charts

Use the following charts to view information about your government accounts and workloads.

■ Top Accounts chart

Use the Top Accounts chart as a starting point.







The chart shows the Azure Government subscriptions discovered via the service principal accounts that you have added as targets.

Necessary Investments and Potential Savings charts

Set the scope to a government account or subscription, and then see the Necessary Investments and Potential Savings charts to evaluate the costs you would incur or save if you execute all the pending actions for your government workloads.






■ **Discount Inventory** chart

The government accounts that you added as targets enable Workload Optimization Manager to gain full insight into the discounts (on page 113) that you have purchased for your government workloads. Even as you selectively add secondary targets, Workload Optimization Manager remains aware of all discounts, and how they are utilized across the board. This increases the accuracy of the allocation and purchase recommendations that Workload Optimization Manager generates for your government workloads.





Workload Planning

You can run an Optimize Cloud plan to identify performance and efficiency opportunities for existing government workloads, or a Migrate to Cloud plan to migrate government VM groups to another cloud provider.

For on-prem clusters, you can run a Migrate to Cloud plan to see how you can safely migrate the VMs in these clusters to a government account/subscription and region.

Azure Memory Metrics Collection

We highly recommend enabling collection of memory metrics in your environment. Enabling memory metrics allows Workload Optimization Manager to generate Scale actions to optimize VM memory usage. For Workload Optimization Manager to collect memory metrics, you must enable the collection of these metrics on the VMs in your environment.

Workload Optimization Manager fetches memory metrics for Azure VMs using the following mechanisms, in order:

- 1. **Log Analytics Workspace InsightsMetrics table** (preferred method, supported by Azure) This mechanism is used when the VM is configured with the Azure Monitor Agent (AMA). This agent collects Guest OS Memory metrics and sends it to the Log Analytics Workspace InsightsMetrics table. Workload Optimization Manager then fetches these Available Memory metrics by querying this table.
 - For more information on the Azure Monitor Agent, see the Azure documentation.
- Log Analytics Workspace Perf table This mechanism is used when the VM is configured with the Log Analytics Agents
 (OMS/MMA) and the VM is connected to a Log Analytics Workspace. The Log Analytics Agents send the Guest OS Memory
 metrics to the Log Analytics Workspace Perf table. Workload Optimization Manager then fetches these Available Memory
 metrics by querying this table.
 - The Log Analytics Agents (OMS/MMA) will reach end of support by August 2024. For information on the recommended migration to the new Azure Monitor Agent (AMA), see the <u>Azure documentation</u>.
- 3. Storage Account SDK Based Diagnostics Monitoring This legacy VM memory collection mechanism installs an laaS Diagnostics Agent on the VM, which sends guest OS level memory metrics to a designated Storage Account table. During discovery process, Workload Optimization Manager collects VM memory from these tables. If this mechanism is being used, Workload Optimization Manager needs relevant StorageAccount read permissions so that the memory metrics can be read from these tables.
- 4. **Metrics REST API** If memory could not be collected for a VM using the previously-mentioned mechanisms, Workload Optimization Manager tries to fetch host OS based memory for the VM via REST API calls, which is the same mechanism used for collecting other VM metrics such as Percentage CPU usage. Workload Optimization Manager collects VM memory and tries to generate memory-based scaling actions where appropriate.

NOTE:

Azure provides Available Memory Bytes via REST API in Preview mode, or through the Azure Portal UI under the VM's **Monitoring > Metrics** section.


Azure Memory Source Group Discovery

Azure Memory Source groups reflect the source from where VM memory is being fetched.



In the Workload Optimization Manager user interface, to search for a specific Azure Memory Source group, choose **Groups** in the Search page and enter memory in the search field. Each group contains the list of VMs for which memory was fetched via the specified mechanism. These are dynamic groups that get continuously updated based on each discovery.

The Azure Memory Monitoring Unavailable group contains VMs for which memory could not be fetched using any of the collection mechanisms. This group may contain VMs that are not in a RUNNING power state, and metrics data is often not available for these VMs. Memory-related scaling actions are not generated for VMs in this group; however, other non-memory Scale actions may be generated.



Support for Azure App Service

Azure App Service is an HTTP-based service for hosting apps. With Azure App Service, app developers can easily create enterprise-ready apps and deploy them on a scalable and reliable cloud infrastructure.

Azure App Service offers several types of apps, including web apps, mobile apps, API apps, and logic apps. Each app runs as a set of *app instances* and is associated with a *plan* that defines compute resources (CPU, memory, and storage) available to the app.

When you add an Azure account as a target:

- Workload Optimization Manager discovers all the plans in that account, except App Service Environment v3 I4, I5, and I6. Plans appear as 'Virtual Machine Spec' entities in the supply chain.
- For plans associated with *web apps*, Workload Optimization Manager discovers the related app instances. In the supply chain, app instances appear as 'App Component Spec' entities. Workload Optimization Manager generates actions to scale these plans to optimize app performance.
- For plans associated with the other types of apps, Workload Optimization Manager does not generate scale actions or discover the related app instances.
- For plans that are not associated with any type of app, Workload Optimization Manager generates delete actions as a cost-saving measure.

For details about scale and delete actions, see Virtual Machine Spec (on page 402).

To discover plans and app instances, you must provide permissions to support all the actions you want to perform. For a list of permissions, see Azure Permissions (on page 275).

Firewall and Proxy Access for Azure

If you run Workload Optimization Manager behind a proxy or firewall, then you must configure Workload Optimization Manager to allow unrestricted access to the following URLs. This enables the full set of features for Azure targets.



Firewall and Proxy Access for Azure Service Principal

For Azure non-government:

- ratecard.azure-api.net
- management.core.windows.net
- management.azure.com
- login.microsoftonline.com
- ratecard.blob.core.windows.net
- api.loganalytics.io

For Azure Government:

- ratecard.azure-api.net
- management.core.usgovcloudapi.net
- management.usgovcloudapi.net
- login.microsoftonline.us
- ratecard.blob.core.usgovcloudapi.net
- api.loganalytics.us

Firewall and Proxy Access for Azure Billing

- api.loganalytics.io
- login.microsoftonline.com
- management.azure.com
- For <u>Billed Costs (on page 291)</u>:
 - Cost Details API
 - *.blob.core.windows.net
 - Cost export
 - · Less strict:
 - *.blob.core.windows.net
 - Strict:

```
[STORAGE_ACCOUNT].blob.core.windows.net
```

Replace [STORAGE_ACCOUNT] with the name of the storage account containing the cost export.

Azure Billing

The Workload Optimization Manager Azure Billing target discovers your Azure billing account and *non-government* subscriptions. The target discovers the billing account and related subscriptions associated with your MCA Billing Account ID or EA Enrollment Number.



IMPORTANT:

The Microsoft Enterprise Agreement target has been deprecated and will eventually be removed from the product.

If you have previously added a Microsoft Enterprise Agreement target to manage *non-government* subscriptions, be sure to move to the Azure Billing target immediately. To do this, remove the existing target from the user interface, and then add the Azure Billing target. For details about deprecation, see <u>Microsoft Enterprise Agreement (on page 293)</u>.

If you have Azure *government* subscriptions, use the Microsoft Enterprise Agreement target until further notice. Currently, the Azure Billing target cannot be used to manage government subscriptions. For details about adding a Microsoft Enterprise Agreement target, see <u>Microsoft Enterprise Agreement</u> (on page 293).

Level of Support for MCA and EA Accounts

The following table describes the current level of support for MCA and EA accounts.

NOTE:

Empty Azure EA subscriptions that are not incurring any charges will not stitch with the Azure Billing target, and a discrepancy will occur in the offer ID of the subscription. Once the subscription incurs a charge, the stitching occurs and the subscription should correctly associate with the Azure Billing target with the correct offer ID.

Item	MCA	EA
Required role to add the Azure Billing target	Billing Account Reader role	Enrollment Reader role
Discovery of pricing data	Pricing data is available for VMs, volumes, SQL databases (DTU and vCore), dedicated SQL pools (for Azure Synapse Analytics), and App Service plans (web apps, logic apps, and function apps).	Pricing data is available for VMs, volumes, SQL databases (DTU and vCore), dedicated SQL pools (for Azure Synapse Analytics), and App Service plans (web apps, logic apps, and function apps).
Discovery of Azure reservations	All reservations charged under the billing account are discovered. However, the percentage of workloads covered by reservations is currently not discovered.	All reservations charged under the billing account are discovered.
Usage of pricing data when recommending actions	All actions for Azure workloads are supported, including actions to optimize/buy reservations.	All actions for Azure workloads are supported, including actions to optimize/buy reservations.
Support for the Buy VM Reservations plan	The plan is fully supported.	The plan is fully supported.
Scope for cost exports (on page 292) (if used to collect billed costs (on page 291))	Cost exports must be created at the Billing Profile scope. If you previously set up a cost export at the Billing Account scope, you must delete the cost export and then create a new one at the Billing Profile scope. Create this cost export for each active Billing Profile that falls under your MCA Billing Account. All cost exports you create for your active Billing Profiles are required to have the same name.	Cost exports must be created at the Billing Account scope.
	These scopes are <i>not</i> supported – Subscription, Management Group, and Resource Group.	These scopes are <i>not</i> supported – Subscription, Management Group, and Resource Group.



Before Adding Targets

Review the following items before adding Azure Billing targets.

Roles and Permissions

To configure Azure Billing targets, you create service principal accounts with roles that grant Workload Optimization Manager the permissions it needs to discover your Azure billing resources and costs.

For EA accounts, the **Enrollment Reader** role is required.

- Only users with elevated access and the Enterprise Administrator role can apply the Enrollment Reader role to the service principal.
- The admin executing the put-assignment API must have elevated access in order to assign the Enrollment Reader at the tenant level.

For details, see the Microsoft documentation <u>here</u> and <u>here</u>.

For MCA accounts, the **Billing Account Reader** role is required. To assign the role, navigate to **Cost Management + Billing** > **Access > Add role**. Select the role and assign it to the service principal.

■ Billed Cost Data

Decide whether the target will collect billed cost data via the Azure Cost Details API or a cost export that you set up in your environment.

For details, see Azure Billed Costs (on page 291).

■ Firewall and Proxy Access

If you run Workload Optimization Manager behind a proxy or firewall, then you must configure Workload Optimization Manager to allow unrestricted access to certain URLs. This enables the full set of features for Azure targets.

For details, see Firewall and Proxy Access for Azure (on page 287).

Adding an Azure Billing Target

NOTE:

Remove any corresponding non-government EA targets before adding an Azure Billing target.

To add an Azure Billing target, select Azure Billing in the Target Configuration page, and provide the following information:

Display Name

The name that identifies the target in Workload Optimization Manager. This name is for display purposes only and does not need to match any name in Azure.

■ Billing Account ID

The ID of your billing account in Azure. You can find the billing ID in the **Cost Management + Billing** section of the Azure portal. The ID is different for MCA and EA accounts.

MCA Billing Account ID

In the Azure portal, navigate to **Cost management + Billing** and then click your MCA billing account. The screen that displays includes a field for the Billing Account ID. For example, an ID could be:

095c24bb-6d32-5f7s-98e3-40123a4b56cd:2f98765e-a5b5

EA Enrollment Number

In the Azure portal, navigate to **Cost management + Billing**, click to open the EA account, and navigate to **Properties**. The screen that displays includes a field for the Enrollment Number. For example, an Enrollment Number could be:

12345678

Use a cost export

NOTE:

Before turning this option on or off, read the guidelines in Azure Billed Costs (on page 291).

- Turned off: Workload Optimization Manager will collect data via the Cost Details API.
- Turned on: Workload Optimization Manager will collect data via a cost export.

If you turn on the setting, you must specify the name of the cost export.



To find the cost export name in the Azure portal, navigate to **Cost management + Billing** and then select **Exports**. A list of the cost exports you have created displays. For more information about setting up cost exports, see <u>Cost Export Setup (on page 292)</u>.

■ Directory (Tenant) ID

The ID of the tenant that contains subscriptions to be managed with Workload Optimization Manager. This should match the Directory ID that you give for the associated Service Principal target.

Application (Client) ID

The Client/App ID found in App registration. This ID gives Workload Optimization Manager access to resources in your Azure subscription, and should match the Client/App ID that you specify for the associated Service Principal target.

Client Secret Key

The secret key for the App Registration. This should match the secret key ID that you give for the associated Service Principal target.

Proxy Host

The IP of your Proxy Host

Proxy Port

The port required for the proxy above

Proxy User

The username required for the proxy above

Proxy Password

The password required for the proxy above.

Secure Proxy Connection

When checked, Workload Optimization Manager will connect to the proxy via HTTPS.

NOTE:

It takes 24 hours after successfully adding a target for any Azure reservation information to display in the user interface.

Monitored Resources

Workload Optimization Manager does not monitor resources for Azure Billing targets.

Actions

Workload Optimization Manager does not recommend actions for Azure Billing targets. However, the billing information will be used in conjunction with the Azure target to generate actions.

Azure Billed Costs

The Azure Billing (on page 288) target can collect billed cost data via the Azure Cost Details API or a cost export that you set up in your environment.

NOTE:

Support for the Cost Details API started in version 3.6.4. New deployments of the product will use this API by default.

For Azure Billing targets added in earlier releases of the product, any associated cost export will automatically carry over to version 3.6.4 or later. You can switch these targets to the Cost Details API any time.

Consideration	Cost Details API	Cost Export
Size of billed cost data	Microsoft recommends the Cost Details API for billed cost data that is less than 2 GB in size. Larger sizes will likely result in timeouts. Workload Optimization Manager generates ad hoc cost exports when you choose this option.	Microsoft recommends a cost export for billed cost data that is at least 2 GB in size. The data export is in CSV format, and contains all the cost and usage data that Azure Cost Management collects.



Consideration	Cost Details API	Cost Export	
Prerequisites	None	Set up a cost export. For details, see Cost Export Setup (on page 292).	
Firewall rule (if you run Workload Optimization Manager behind a firewall)	Allow unrestricted access to: *.blob.core.windows.net For a full list of firewall URLs, see Firewall and Proxy Access for Azure Billing (on page 288).	Allow unrestricted access to one of the following URLs: Less strict: *.blob.core.windows.net Strict: [STORAGE_ACCOUNT].blob.cor e.windows.net Replace [STORAGE_ACCOUNT] with the name of the storage account containing the cost export. For a full list of firewall URLs, see Firewall and Proxy Access for Azure Billing (on page 288).	
Target configuration in Workload Optimization Manager	Turn off the Use a cost export option.	Turn on the Use a cost export option, and then specify the cost export name.	

Cost Export Setup

Skip this section if your Azure Billing target will collect billed cost data via the Cost Details API.

For billed cost data collected via a cost export, the Azure Billing uses Cost and Usage reports. In order for Workload Optimization Manager to display month-to-day expenses, you must set up a daily cost export of actual cost on the Azure portal with an export type of month-to-date costs.

The cost export must be created as follows:

- EA accounts Create the cost export at the Billing Account scope.
- MCA accounts Create the cost export at the Billing Profile scope.

NOTE:

For MCA accounts, if you previously set up a cost export at the Billing Account scope, you must delete the cost export and then create a new one at the Billing Profile scope. Create this cost export for each active Billing Profile that falls under your MCA Billing Account. All cost exports you create for your active Billing Profiles are required to have the same name.

For both EA and MCA accounts, Subscription, Management Group, and Resource Group scopes are not supported.

In addition, you must provide the following permissions for the storage account and container associated with the cost export.

- Storage account Reader and Data Access
- Container Storage Blob Data Reader

We recommend creating a new cost export, even if you have an existing export that matches the setup noted here. Below is an example of a cost export setup.

- Export details
 - Metric

Actual cost (Usage and Purchases)

Export type

Daily export of month-to-date costs

- Storage
 - Use existing
 - Subscription



- EA-Development
- Storage account

turbocostexport

Container

cost-export-container

Directory

costExportDir

Microsoft Enterprise Agreement

IMPORTANT:

The Microsoft Enterprise Agreement target has been deprecated and will eventually be removed from the product.

Who is impacted?

Deprecation and removal impact customers who have previously added, or plan to add, a Microsoft Enterprise Agreement target to manage Azure *non-government* subscriptions.

- Customers who have previously added a Microsoft Enterprise Agreement target are advised to immediately remove the target from the user interface, and then add the Azure Billing target.
- Customers planning to add a Microsoft Enterprise Agreement target should use the Azure Billing target instead.

The Azure Billing target leverages the new cost management APIs and cost exports recommended by Microsoft. For instructions on adding the Azure Billing target, see Azure Billing (on page 288).

Now that the Microsoft Enterprise Agreement target has been deprecated:

- No new features will be introduced.
- The following charts may not show historical cost data initially. Customers who notice any data loss in their environment should note that the charts will rebuild the data over time.
 - Workload Cost Breakdown
 - Cost Breakdown by Tag
 - Top Billed Cost by Account
 - Top Billed Cost by Service
 - Billed Cost by Service Provider
- The target will continue to be available for customers to add or use, and will continue to discover pricing data.
- Customers can continue to report problems with the target. Workload Optimization Manager Support will answer questions, help with configuration issues, and provide any known workarounds.

Details about the removal will be available later.

Who is not impacted?

Deprecation and removal do *not* impact customers who have previously added, or plan to add, a Microsoft Enterprise Agreement target to manage Azure *government* subscriptions. Customers with these subscriptions should use the Microsoft Enterprise Agreement target until further notice. Currently, the Azure Billing target cannot be used to manage government subscriptions.

Overview of the Microsoft Enterprise Agreement Target

You can configure Workload Optimization Manager to manage *Azure government* subscriptions within the context of a Microsoft Enterprise Agreement (EA).

An EA defines specific pricing, including the pricing for reservations. When you configure an EA target, and set the EA key to your Azure targets, Workload Optimization Manager uses that richer pricing information to calculate workload placement and reservations coverage for your Azure environment.




To enable Workload Optimization Manager management of Azure EA environments, you must configure:

- One Microsoft Enterprise Agreement target
- At least one Service Principal target that can discover the underlying Azure subscriptions. For information about Azure service principal targets, see Microsoft Azure (on page 268).

In the Targets View, you can identify the targets related to Azure EA as follows:





1. EA Target

The target that discovers the EA to track pricing and reservations. You can have one EA target per Workload Optimization Manager deployment.

2. Azure Subscription Targets

The targets that manage the workloads in your Azure environment. These are discovered by Service Principal targets. Note that not all subscription targets *necessarily* participate in the EA. Expand these entries to see the related Service Principal target. For members of the EA, you can see the related EA target as well.

Subscriptions that do not participate in the EA appear as Standalone targets.

In this example, **EA-Prod** is one of the subscriptions in this EA.

NOTE:

In rare circumstances, you can have a subscription that is not in use. The subscription has no workloads associated with it. In this case, Workload Optimization Manager identifies the subscription as Standalone. This is because the target cannot discover any cost or usage information that would relate the subscription to its EA.

Empty Azure EA subscriptions that are not incurring any charges will not stitch with the Azure Billing target or the Azure EA target, and a discrepancy will occur in the offer ID of the subscription. Once the subscription incurs a charge, the stitching occurs and the subscription should correctly associate with the Azure Billing target with the correct offer ID.

3. Service Principal Targets



The Azure target that you configure to discover Azure subscription targets. Expand the entry to see the discovered targets. If you have configured an EA target, the entry lists that as well, along with the EA enrollment number.

In this example, the Service Principal target (**core.windows.net**) discovers the underlying subscriptions. Some subscriptions (such as **EA - Prod**) participate in the EA (3a) and other subscriptions (such as **EAtest**) are standalone or pay-as-you-go (3b).

Reservations and Azure EA

For Azure environments, Workload Optimization Manager can only discover and use reservations if you have configured a Microsoft Enterprise Account target, and if one or more subscriptions participate in that EA.

To discover and manage reservations in Azure environments, Workload Optimization Manager uses both the EA target and the associated subscription targets. On its own, a subscription target exposes costs for pay-as-you-go pricing. The EA target discovers pricing for the available reservations. Workload Optimization Manager combines this information to track:

- Utilization of reservations
- VMs covered by reservations
- VM costs (accounting for reservations)
- Purchase recommendations

NOTE

This release of Workload Optimization Manager does not support discovery and management of reservations for Classic VMs, Classic Cloud Services, and Suppressed Core VMs.

Cost Calculations for Azure Environments

To understand the reported costs in your Azure environment, consider these points:

- For targets that participate in the EA, Workload Optimization Manager uses the terms of the given EA, and bases costs on the Offer ID that is effective for the given subscription.
- For VMs in Azure, reservations pricing does not include the cost of the OS license. However pricing for on-demand VMs does include the license cost.

NOTE:

For Microsoft Azure EA environments, the projected cost for actions to purchase reservations might not match associated costs you find in the Microsoft Pricing Calculator.

Workload Optimization Manager actions can recommend purchases. For these recommendations, the action assumes a free Linux OS, so the cost estimate does not include the OS cost. However, The Microsoft Pricing Calculator does include costs for OS licenses. As a result, when you compare the Workload Optimization Manager cost estimates to the values in the Pricing Calculator, it's likely that the two estimates will not match. This difference also affects the Break Even Point that appears in the Recommended RI Purchases chart. Because the recommended purchases do not include Azure costs for OS licenses, the listed Break Even Point can be optimistic.

■ For on-prem workloads you migrated to Azure, Workload Optimization Manager recognizes Azure Hybrid Benefit (AHUB) savings for reservations and on-demand workloads. The costs you see in Workload Optimization Manager charts include this benefit. However, remember that recommended actions do not include any license cost, so the actions will not reflect any proposed AHUB savings (see above).

Before Adding Targets

Review the following items before adding Azure Billing targets.

Access Key and Enrollment Number

A Microsoft Azure EA access key and an EA enrollment number are required to add the target.

■ Firewall and Proxy Access

Your firewall must allow access to the consumption.azure.com: 443 address.

Access to Cost Data

Be sure to enable access to your cost data. You can enable access in the Azure portal or in the EA portal.



NOTE:

For additional information, see Assign access to Cost Management data.

Enabling Access to Cost Data via the Azure Portal

Log into to the Azure portal (https://portal.azure.com).

You should log in with an enterprise administrator account.

2. Open your Billing Account.

Navigate to Cost Management + Billing | Billing scopes. Select your billing account from the list of available accounts.

3. Configure cost access.

In the **Settings** group, select **Policies**. Then turn on **DEPARTMENT ADMINS CAN VIEW CHARGES** and **ACCOUNT OWNERS CAN VIEW CHARGES**.

Enabling Access to Cost Data via the EA Portal

1. Log into to the Azure portal (https://ea.azure.com).

You should log in with an enterprise administrator account.

- 2. Select Manage in the left-hand navigation pane
- 3. Configure cost access.

For the cost management scopes that you want to provide access to, enable the charge option to **DA view charges** and/or **AO view charges**.

NOTE:

After you configure cost access, most scopes also require Azure role-based access control (Azure RBAC) permission configuration in the Azure portal.

If you just enabled these settings, it can take up to 24 hours for the changes to take effect. For more information, see Troubleshoot enterprise cost views in the Microsoft Azure documentation.

If you perform self-service exchanges for your reservations, Workload Optimization Manager does not discover the new charges for the exchanged reservations through the Azure EA target. To track the charges after you have exchanged reservations, ensure you have an Azure subscription target for the affected scope of Azure workloads, and that subscription has read access to reservations information.

Adding Microsoft Enterprise Agreement Targets

To add targets, select Microsoft Enterprise Agreement in the Target Configuration page, and provide the following information:

Target Name

The name that identifies the target in Workload Optimization Manager. This name is for display purposes only and does not need to match any name in Azure.

Enrollment Number

The EA enrollment number (found in your EA admin account at ea.azure.com)

API Key

The API Access Key for the EA (found in your EA admin account at ea.azure.com)

Proxy Host

The IP address of the proxy server used, if any

Proxy Port

The port number of the proxy server

Proxy User

The username of the proxy user used to authenticate

Proxy Password

The password of the proxy user used to authenticate

When you add the target and it validates, Workload Optimization Manager:

Recognizes any existing Azure targets in your environment that are part of the EA



- Updates these targets with custom prices from the EA
- Discovers reservations in these targets

NOTE:

This can take up to 24 hours, as target stitching occurs after the next bill processing cycle.

Monitored Resources

Workload Optimization Manager does not monitor resources for Microsoft Enterprise Agreement targets.

Actions

Workload Optimization Manager does not recommend actions for Microsoft Enterprise Agreement targets. However, the billing information will be used in conjunction with the Azure target to generate actions.

Storage Targets

Adding a storage Target enables Workload Optimization Manager to connect to your storage subsystem through a native or SMI-S provider API. Workload Optimization Manager uses the target's API to access and collect information from each of the underlying disk arrays. The information is used to set disk performance characteristics according to the type and capacity of storage, leading to improved workload placement.

Similarly, Workload Optimization Manager determines the relationships between storage controllers and disk arrays, and the location of datastores within those arrays. This information also helps optimize workload placement at a more granular level.

For on-premises applications, this optimization will enable Workload Optimization Manager to make more informed decisions about which storage devices the workloads hosting your applications run on, and assist in assuring application SLO. In the cloud, storage data is handled as part of the public cloud target.

Both virtual machines and containers benefit from this level of optimization. In the case of short-lived containers, Workload Optimization Managerwill suggest the best datastore to hold persistent data, and paired with a container or hypervisor target, will select the optimal match of compute and storage resources. For longer-lived containers and virtual machines, each workload will be continually assessed for SLA/SLO, and recommendations to move or resize storages will ensure the continued efficiency of your environment.

The section below describes the storage supply chain. For information on how to add specific storage targets, the resources Workload Optimization Manager can monitor for the various supply chain entities, and the actions it can take to optimize the environment, refer to the target configuration instructions for your specific storage type.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

EMC VMAX	EMC XtremIO	HPE 3Par	NetApp	Nutanix	Pure	Workload Optimization Manager
Volume (Regular, Thin, Meta)	Volume	Virtual Volume	Volume	Container	Volume	Storage
Disk Group or Thin Pool	XTremIO Cluster	CPG	Aggregate	Storage Pool	Shelf Array	Disk Array
VMAX Array	XTremIO Cluster	Controller	Controller / Filer	Controller VM	Controller	Storage Controller

Storage targets (storage controllers) add Storage Controller and Disk Array entities to the supply chain. Disk Array entities in turn host Storage entities (datastores).



EMC VMAX

Workload Optimization Manager supports management of VMAX2 and 3 Series storage arrays. The VMAX series is a family of enterprise storage arrays designed for SAN environments. Workload Optimization Manager connects to VMAX storage systems via an EMC SMI-S provider that has the disk arrays added to it. A single SMI-S provider can communicate with one or more disk arrays. When you specify an SMI-S provider as a target, Workload Optimization Manager discovers all the added disk arrays.

NOTE:

Workload Optimization Manager does not utilize Unisphere. Data is collected exclusively from the SMI-S provider.

Workload Optimization Manager will create Storage Groups based on the SLO levels defined in VMAX3 Targets. By default, Storage vMotion actions will respect these SLO levels based on the configured response time.

Prerequisites

- EMC SMI-S Provider V8.x
- A service account that Workload Optimization Manager can use to connect to the EMC SMI-S Provider (typically the default admin account)

Adding VMAX Targets

To add VMAX targets, select the **Storage > VMAX** option on the Target Configuration page and provide the following information:

Address

The IP or host name of the SMI-S provider. If the provider address begins with https, you must follow the IP with the port used to connect.

Use Secure Connection

If checked, port 5989 will be used to connect. If unchecked, port 5988 will be used.

Username

The Username for the SMI-S provider.

Password

The Password for the SMI-S provider.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

EMC VMAX	Workload Optimization Manager
Volume (Regular, Thin, Meta)	Storage
Storage Resource Pool (VMAX3) / Thick Provisioned Pool (earlier)	Disk Array
Storage Group (VMAX3) / Thin Provisioned Pool (earlier)	Logical Pool
VMAX Array	Storage Controller

Monitored Resources

When calculating available storage, Workload Optimization Manager excludes disks devoted to the VMAX operating system by default. If these disks are assigned to new RAID groups or storage pools, the capacity of those disks will then be considered when calculating the capacity of the Storage Controller.

Workload Optimization Manager monitors the following resources:

Storage

Storage Amount



Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

NOTE:

When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.

Logical Pool

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

Disk Array

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

Storage Controller

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Actions

Workload Optimization Manager can recommend the following actions:

Storage

- Provision (Clone)
- Delete
- Move
- Resize (V-Volumes only)

This action can only be executed outside Workload Optimization Manager.

Logical Pool

Resize

This action can only be executed outside Workload Optimization Manager.



EMC XtremIO

EMC® XtremIO® is a flash-based (SSD) storage solution, designed to push data to applications at higher speeds. The system building blocks are SAN appliances called X-Bricks. A deployment is organized into clusters of X-Bricks, and the clusters are managed by the XtremIO Management Server (XMS).

Workload Optimization Manager connects to X-Bricks through the XMS. The XMS presents a unified view of each connected X-Brick cluster, rather than exposing the individual X-Bricks within each cluster. Within Workload Optimization Manager, each X-Brick cluster displays as a single storage controller with an associated disk array.

The relationship between Storage entities and individual X-Bricks within the cluster is not exposed through the XMS – Workload Optimization Manager cannot make recommendations to move datastores from one X-Brick to another. Additionally, the X-Brick has a fixed form factor – Workload Optimization Manager does not recommend resize actions for disk array or storage controller resources.

Workload Optimization Manager recognizes XtremIO arrays as flash storage and sets the IOPS capacity on discovered arrays accordingly.

Prerequisites

■ A service user account on XMS 4.0 or higher – typically the default xmsadmin account

Workload Optimization Manager uses this account to connect to the XMS and execute commands through the XtremIO API.

Adding XtremIO Targets

For EMC XtremIO targets, select the **Storage > EMC XtremIO** option on the Target Configuration page and provide the following information:

Address

The name or IP address of the XtremIO Management Server (XMS).

Username/Password

Credentials for a user account on the XMS.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

XTremIO	Workload Optimization Manager
Volume	Storage
XTremIO Cluster	Disk Array
XTremIO Cluster	Storage Controller

Storage targets (storage controllers) add Storage Controller and Disk Array entities to the supply chain. Disk Array entities then host Storage entities (datastores).

Monitored Resources

When calculating available storage, Workload Optimization Manager excludes disks devoted to the VNX operating system.

Workload Optimization Manager monitors the following resources:

Storage

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)



Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

NOTE:

When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.

Disk Array

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

Storage Controller

NOTE

Not all targets of the same type provide all possible commodities. For example, some storage controllers do not expose CPU activity. When a metric is not collected, its chart in the user interface will not display data.

- CPU

CPU is the measurement of CPU that is reserved or in use.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

The storage allocated to a storage controller is the total of all the physical space available to aggregates managed by that storage controller.

Actions

Workload Optimization Manager can recommend the following actions:

■ Storage

Provision

This action can only be executed outside Workload Optimization Manager.

Resize Up

This action can only be executed outside Workload Optimization Manager.

Storage Controller

Provision

This action can only be executed outside Workload Optimization Manager.

EMC ScaleIO

EMC ScaleIO is an example of Software-Defined Storage for the datacenter. It creates a Virtual SAN overlaying commodity infrastructure that consists of multiple LAN-connected Servers with locally attached commodity Storage. It presents a standard Block Storage interface to Applications accessing the Virtual SAN.

Workload Optimization Manager communicates with the EMC ScaleIO system via the REST API Gateway.



Prerequisites

- EMC ScaleIO 2.x or 3.x
- A service account that Workload Optimization Manager can use to connect to the ScaleIO Gateway.

Adding EMC ScaleIO Targets

To add EMC ScaleIO targets, select the **Storage > EMC ScaleIO** option on the Target Configuration page and provide the following information:

Address

The IP or host name of the Gateway.

Username

The Username for the Gateway service account.

Password

The Password for the Gateway service account.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

EMC ScaleIO	Workload Optimization Manager	
Volume	Storage	
Storage Pool	Disk Array	
Protection Domain	Storage Controller	

Monitored Resources

Workload Optimization Manager monitors the following resources:

Storage

NOTE:

Not all targets of the same type provide all possible commodities. For example, some storage controllers do not expose CPU activity. When a metric is not collected, its chart in the user interface will not display data.

- Storage Amount
 - Storage Amount is the measurement of storage capacity that is in use.
- Storage Provisioned
 - Storage provisioned is the utilization of the entity's capacity, including overprovisioning.
- Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

■ Disk Array

- Storage Amount
 - Storage Amount is the measurement of storage capacity that is in use.
- Storage Provisioned
 - Storage provisioned is the utilization of the entity's capacity, including overprovisioning.
- Storage Access (IOPS)
 - Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.



NOTE:

When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.

Storage Controller

- Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Actions

Workload Optimization Manager can recommend the following actions:

■ Storage

- Provision (Clone)
- Resize (disabled by default)

This action can only be executed outside Workload Optimization Manager.

Disk Array

Resize Disk Array

This action can only be executed outside Workload Optimization Manager.

Protection Domain

Provision (Clone)

This action can only be executed outside Workload Optimization Manager.

EMC VPLEX

Workload Optimization Manager supports management of EMC VPLEX virtual storage systems in a local configuration, via the VPLEX API. Currently, Workload Optimization Manager does not support Metro or Geo configurations.

VPLEX is used to aggregate and refine data collected between connected Storage and Hypervisor targets. VPLEX supports one-to-one, one-to-many, and many-to-one relationships between virtual volumes and LUNs. Only one-to-one mapping between virtual volume and LUNs is supported by Workload Optimization Manager.

Prerequisites

- VPLEX Management Server
- Hypervisor target supported by Workload Optimization Manager
- Storage target supported by Workload Optimization Manager

NOTE:

In order for Workload Optimization Manager to make use of the information provided by VPLEX, you must also add the hypervisor and storage layered under it as targets.

VPLEX Permissions

Workload Optimization Manager Functionality	Required Permissions
Monitoring	Service Account
Action Execution	Admin account



Adding EMC VPLEX Targets

To add EMC VPLEX targets, select the **Storage > EMC VPLEX** option on the Target Configuration page and provide the following information:

Address:

The IP or Hostname of the VPLEX Management Server

Username:

The Username for the VPLEX Management Server

Password:

The Password for the VPLEX Management Server

■ Port Number:

The port number for the remote management connection. The default port number for the VPLEX Management server is 443

Secure Connection:

Select this option to use a secure connection (HTTPS)

NOTE

The default port (443) uses a secure connection.

Actions

For this target, actions are generated and executed via the underlying storage targets. Workload Optimization Manager will use the enhanced visibility provided by VPLEX to make more accurate storage decisions, such as recommending storage vMotion between pools.

HPE 3PAR

HPE 3PAR StoreServ systems use controller nodes to manage pools of storage resources and present a single storage system to consumers. Workload Optimization Manager communicates with the HPE 3PAR system via both the WSAPI and SMI-S providers that are installed on the 3PAR controller node.

Prerequisites

- SMI-S Provider enabled and configured on the controller node.
- WSPAI Provider enabled and configured on the controller node.
- A service account on the controller node that Workload Optimization Manager can use to connect to the SMI-S and WSPAI providers.

NOTE:

For discovery and monitoring, the Workload Optimization Manager service account must have the Browse permission on all monitored domains. To exclude domains from monitoring, the Workload Optimization Manager service account must have no permissions on those domains. For action execution, Workload Optimization Manager requires the Edit permission.

Adding HPE 3PAR Targets

To add an HPE 3PAR target, select the **Storage > HPE 3Par** option on the Target Configuration page and provide the following information:

Address

The name or IP address of the 3PAR controller node.

By default, the controller provides SMI-S data over port 5988 (HTTP) or port 5989 (HTTPS). If your installation uses a different port for SMI-S, include the port number in the Address field.

Username/Password

Credentials for a user account on the controller node.



Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

HPE 3PAR	Workload Optimization Manager
Virtual Volume	Storage
CPG	Disk Array
AO Configuration	Logical Pool
Controller	Storage Controller

Storage targets (storage controllers) add Storage Controller, Logical Pool and Disk Array entities to the supply chain. Logical Pool and Disk Array entities then host Storage entities (datastores).

Setting Up the SMI-S Provider

The HPE 3PAR SMI-S Provider should be installed on the controller node. It is disabled by default – you must ensure that it is installed properly and running on the controller node.

To enable the SMI-S provider:

- 1. Log into the HPE 3PAR Command Line Interface (CLI).
 - Open a secure shell session (ssh) on the controller node. Default credentials are 3paradm/3pardata.
- Check the current status of the SMI-S provider.

In the shell session, run the command:

showcim

3. If the CIM service is not running, start it.

To enable the CIM service and the SMI-S provider, run the command:

startcim

To stop the SMI-S provider, execute the command stopcim -f -x.

Setting Up the WSAPI Provider

The HPE 3PAR WSAPI Provider should be installed on the controller node.

To enable the WSAPI provider:

- Log into the HPE 3PAR Command Line Interface (CLI).
 - Open a secure shell session (ssh) on the controller node. Default credentials are 3paradm/3pardata.
- 2. Check the current status of the WSAPI provider.

In the shell session, run the command:

showwsapi

3. If the WSAPI service is not running, start it by runing the command:

startwsapi

To allow only insecure connections run the command:

```
set wsapi -http enable
```

Or to allow only secure connections, run the command:



```
set wsapi -https enable
```

To stop the WSAPI provider, execute the command stopwsapi -f.

3Par Adaptive Optimization

Adaptive Optimization (AO) for HPE 3Par enables management of data storage across two or three tiers. AO places storage regions on the appropriate tier in response to periodic analysis that AO performs.

To work with the storage in an AO group, Workload Optimization Manager:

Discovers each Common Provisioning Group (CPG) as a disk array

In the Workload Optimization Manager user interface, these disk arrays do not host storage — They appear empty. Workload Optimization Manager will not recommend storage moves between these disk arrays, because such moves would conflict with AO block-level placement.

Creates a single logical pool that hosts all the datastores in an AO group

This logical pool represents the AO group, and it includes all the member CPGs. Workload Optimization Manager considers this single logical pool when it performs analysis – It can recommend moving storage into or out of the AO group. Also, Workload Optimization Manager aggregates resource capacity in this logical pool. For example, the IOPS capacity for the AO logical pool is a combination of IOPS capacity for the constituent CPGs.

You can see the AO logical pool in the Workload Optimization Manager user interface. The display name for this logical pool is the name of the AO Configuration.

Monitored Resources

Workload Optimization Manager monitors the following resources:

■ Storage

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

NOTE:

When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.

Disk Array

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

Logical Pool

Storage Amount



Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

Storage Controller

NOTE

Not all targets of the same type provide all possible commodities. For example, some storage controllers do not expose CPU activity. When a metric is not collected, its chart in the user interface will not display data.

- CPU

CPU is the measurement of CPU that is reserved or in use.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

The storage allocated to a storage controller is the total of all the physical space available to aggregates managed by that storage controller.

Actions

Workload Optimization Manager can recommend the following actions:

Storage

- Provision
- Resize Up/Down

Disk Array

- Provision
- Resize Up/Down

Logical Pool

Provision

This action can only be executed outside Workload Optimization Manager.

Resize Up/Down

This action can only be executed outside Workload Optimization Manager.

Storage Controller

Provision

This action can only be executed outside Workload Optimization Manager.

IBM FlashSystem

IBM® FlashSystem family comprises all-Flash storage-array platforms. The platform delivers an active-active dual controller system. Assuming a pair of controller nodes, the active-active controller pair can process I/O for a specific volume through either node.

A FlashSystem control enclosure contains multiple NVMe-attached IBM FlashCore® Modules or other self-encryption NVMe-attached SSD drives. Each control enclosure contains two identical node canisters. A node canister provides host interfaces, management interfaces, and interfaces to the control enclosure. The pair of nodes within a single enclosure is known as an input/output (I/O) group.



NOTE:

For deployments that include mirrored volumes, Workload Optimization Manager discovers the Primary copy, and uses data from that for analysis and to generate actions. It does not discover the Secondary copy.

Prerequisites

A service user account on the FlashSystem controller

You must configure a user account on the FlashSystem with a Monitor role. This user account must be dedicated to a single Workload Optimization Manager instance. To manage one FlashSystem with multiple Workload Optimization Manager instances, you must create a different user account for each Workload Optimization Manager instance.

Spectrum Virtualize REST version 8.3.1.2 or later (8.4.2.0 or later recommended)

To take advantage of significant improvements to the Spectrum Virtualize interface, we recommend that you use Spectrum Virtualize version 8.4.2.0 or later.

IBM FlashSystem Permissions

Workload Optimization Manager Functionality	Required Permissions
Monitoring	Service Account with a Monitor role

Considerations

When you configure a FlashSystem target, you should consider:

- FlashSystem devices under IBM SVC management are not currently supported.
- Workload Optimization Manager does not discover mirrored volumes or child pools.
- Clusters must consist of a single enclosure.

Adding IBM FlashSystem Targets

For FlashSystem targets, select the **Storage > IBM FlashSystem** option on the Target Configuration page. Then provide the following:

Address

The host name or Management IP address of the FlashSystem Cluster.

Username

The username for a dedicated Workload Optimization Manager user account on the FlashSystem instance.

Password

The password for the given user account.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

FlashSystem	Workload Optimization Manager	Description
Volume (VDisk)	Storage	A logical disk that the system presents to attached hosts. You create Volumes from the extents that are available in the pool.
Pool (MDiskGroup)	Logical Pool	An allocated amount of capacity that jointly contains all of the data for a specified set of volumes. All MDisks in a pool are split into extents of the same size.



FlashSystem	Workload Optimization Manager	Description
MDisk (Array)	Disk Array	A logical unit of physical storage. MDisks are not visible to host systems.
System (Enclosure or Controller)	Storage Controller	A FlashSystem control enclosure.

IBM FlashSystem Cluster targets add Storage Controller, Disk Array, and Logical Pool entities to the supply chain. Logical Pool entities provide Storage entities, which the supply chain stitches to Hypervisor storage (for example, vCenter datastores).

Monitored Resources

To discover and monitor resources, Workload Optimization Manager uses the Spectrum Virtualize REST interface, and it securely retrieves iostats files from the configuration node.

Workload Optimization Manager monitors the following resources:

■ Storage

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

NOTE:

When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.

Logical Pool

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

■ Disk Array

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

Storage Controller

CPU



CPU is the measurement of CPU that is reserved or in use.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

The storage allocated to a storage controller is the total of all the physical space available to aggregates managed by that storage controller.

Actions

Workload Optimization Manager can recommend the following actions:

■ Storage Controller

Provision

This action is disabled by default.

Disk Array

Resize

This action is disabled by default.

Move

This action is disabled by default.

Provision

This action is disabled by default.

Start

This action is disabled by default.

- Suspend

This action is disabled by default.

Logical Pool

Resize (add or remove MDisk)

This action is recommended by default.

Move

This action is disabled by default.

Provision

This action is disabled by default.

Start

This action is disabled by default.

Suspend

This action is disabled by default.

■ Storage

Delete

This action is manually executable by default.

Resize

This action is recommended by default.

Move

This action is recommended by default.

Provision

This action is recommended by default.

Start

This action is recommended by default.

Suspend



This action is disabled by default.

Virtual Machine

Storage vMotion

This action is recommended by default.

NetApp

The Storage Control Module adds support for NetApp filers running the Data ONTAP operating system. NetApp storage controllers are Storage Virtual Machines that manage storage arrays. Workload Optimization Manager connects to these storage controllers to support NetApp targets in Cluster-Mode (C-Mode).

Prerequisites

- Transport Layer Security (TLS) is enabled
- A service account Workload Optimization Manager can use to connect to the NetApp target

Enabling TLS

Starting with version 5.4, by default Workload Optimization Manager requires Transport Layer Security (TLS) version 1.2 to establish secure communications with targets. NetApp filers have TLS disabled by default, and the latest version they support is TLSv1. If your NetApp target fails to validate on Workload Optimization Manager 5.4 or later, this is probably the cause.

If target validation fails because of TLS support, you might see validation errors with the following strings:

- No appropriate protocol
 - To correct this error, ensure that you have enabled the latest version of TLS that your target technology supports. If this does not resolve the issue, please contact Cisco Technical Support.
- Certificates does not conform to algorithm constraints
 - To correct this error, refer to your NetApp documentation for instructions to generate a certification key with a length of 2048 or greater on your target server. If this does not resolve the issue, please contact Cisco Technical Support.

For information about enabling TLS, see the Data ONTAP System Administration Guide for sections on the SSL protocol.

Service User Account - Administrator Role

To discover and fully manage NetApp disk arrays, Workload Optimization Manager must have a service account that grants privileges to execute commands through the NetApp filer's OnTap API (ontapi). In most cases, you can create the administrator account via the NetApp OnCommand System Manager, or from the NetApp command line — For example:

```
security login create -role admin -username Cisco -application ontapi -authmethod password
```

If you prefer not to grant full administrator rights, see Creating Restricted Service Accounts In NetApp (on page 313)

Adding NetApp Targets

To add a NetApp target, select the **Storage > NetApp** option on the Target Configuration page and provide the following information:

- Address
 - The name or IP address of the NetApp cluster management server.
- Username/Password
 - Credentials for the NetApp service user account that you have configured for Workload Optimization Manager to use.

After validating the new target, Workload Optimization Manager discovers the connected storage entities. This table compares terms used in NetApp to those used in Workload Optimization Manager:



Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

NetApp	Workload Optimization Manager
Volume	Storage
Aggregate	Disk Array
Controller / Filer	Storage Controller

Storage targets (storage controllers) add Storage Controller and Disk Array entities to the supply chain. Disk Array entities then host Storage entities (datastores).

Monitored Resources

Workload Optimization Manager monitors the following resources:

NOTE:

In NetApp environments, the storage controller shows 100% utilization when there are no more disks in a SPARE state that the storage controller can utilize in an aggregate. This does not indicate that the storage controller has no capacity.

Storage

- Storage Amount
 - Storage Amount is the measurement of storage capacity that is in use.
- Storage Provisioned
 - Storage provisioned is the utilization of the entity's capacity, including overprovisioning.
- Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

NOTE:

When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.

■ Disk Array

- Storage Amount
 - Storage Amount is the measurement of storage capacity that is in use.
- Storage Provisioned
 - Storage provisioned is the utilization of the entity's capacity, including overprovisioning.
- Storage Access (IOPS)
 - Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.
- Latency
 - Latency is the measurement of storage latency.

Storage Controller

NOTE:

Not all targets of the same type provide all possible commodities. For example, some storage controllers do not expose CPU activity. When a metric is not collected, its chart in the user interface will not display data.

- CPU

CPU is the measurement of CPU that is reserved or in use.



Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

The storage allocated to a storage controller is the total of all the physical space available to aggregates managed by that storage controller.

Actions

Workload Optimization Manager can recommend the following actions:

Storage

- Move
- Provision

This action can only be executed outside Workload Optimization Manager.

Resize Up

This action can only be executed outside Workload Optimization Manager.

Disk Array

Resize Up

This action can only be executed outside Workload Optimization Manager.

Move

This action can only be executed outside Workload Optimization Manager.

Provision

This action can only be executed outside Workload Optimization Manager.

Storage Controller

Provision

This action can only be executed outside Workload Optimization Manager.

Note that Workload Optimization Manager can automate moving a datastore to a disk array on the same storage controller, as well as moves to a disk array on a different storage controller.

Restricted Service Accounts In NetApp

While Workload Optimization Manager prefers a NetApp service account with administrator rights, it is possible to create an account that has limited access, by following the steps outlined below, depending on NetApp mode.

NetApp 9.x Restricted Service Account Setup

If you prefer to use a service account that does not have full administrator rights:

- 1. Log into the NetApp filer from a command shell.
- 2. Create a role and assign it permission to execute each of the following commands:

For example:

security login role create -role RoleName -cmddirname "storage aggregate show" -vserver Cluster-Name

The required capabilities are listed below:

- cluster identity modify
- cluster identity show
- lun create
- lun igroup create



- lun igroup modify
- lun igroup show
- lun mapping create
- lun mapping delete
- lun mapping show
- lun modify
- lun show
- network interface create
- network interface delete
- network interface modify
- network interface show
- statistics show
- storage aggregate create
- storage aggregate modify
- storage aggregate show
- storage disk show
- system controller flash-cache show
- system node modify
- system node show
- version
- volume create
- volume modify
- volume move modify
- volume move show
- volume move start
- volume qtree create
- volume qtree show



- volume show
- volume snapshot create
- volume snapshot modify
- volume snapshot show
- vserver create
- vserver fcp nodename
- vserver iscsi nodename
- vserver modify
- vserver options
- vserver show
- 3. For execution privileges, execute the following commands for the given role, where Role-Name is the name of the role you are creating, and Cluster-Name identifies the cluster you want the role to affect. You must execute these commands individually to set privileges that affect each individual cluster:
 - security login role create -role Role-Name -access all -cmddirname "volume offline" -vserver C luster-Name
 - security login role create -role Role-Name -access all -cmddirname "volume unmount" -vserver C luster-Name
 - security login role create -role Role-Name -access all -cmddirname "volume move" -vserver Clu ster-Name
 - security login role create -role Role-Name -access all -cmddirname "volume delete" -vserver C luster-Name
- 4. Create a user that will use the newly-created role.

For example:

security login create -User-Name RoleUser -r Workload Optimization ManagerRole

- 5. Enter a password for the new user when prompted.
- 6. Give the user access to the ssh and ontapi applications by using the following commands, replacing Role-Name and RoleUser with the role and user you created:

 $\hbox{security login create -role Role-Name -username RoleUser -application ontapi -authmethod password} \\$

security login create -role Role-Name -username RoleUser -application ssh -authmetho d password

NetApp C-Mode Restricted Service Account Setup

If you prefer to use a service account that does not have full administrator rights:

Log into the NetApp filer from a command shell.

2. Create a role and assign it permission to execute each of the following commands:

- aggr-get-iter
- igroup-get-iter
- cluster-identity-get
- lun-map-get-iter
- net-interface-get-iter
- storage-disk-get-iter
- system-get-node-info-iter
- volume-get-iter
- vserver-get-iter
- fcp-node-get-name
- flash-device-get-iter
- iscsi-node-get-name
- options-list-info
- qtree-list-iter
- system-get-version
- lun-get-iter
- snapshot-get-iter
- perf-object-get-instances
- volume-get-iter
- volume-move-get-iter
- volume-move-start

For example, to enable volume offline, execute the following:

3. Create a user based on the role you create.

Give the user access to the ssh and ontapi applications. For example:

security login create -role Role-Name -username User-Name -application ontapi -authmethod password



Pure Storage

Workload Optimization Manager supports management of the following Pure Storage technologies:

- FlashArray//C
- FlashArray//X

The following technologies are not supported:

FlashBlade

Workload Optimization Manager supports Pure Storage F-series and M-series arrays running Purity 5.3.6 (Pure API 1.6).

Because of the improved performance of Pure Storage arrays, Workload Optimization Manager intelligently moves more demanding workloads to Flash-based datastores. Workload Optimization Manager analysis is also able to incorporate Pure Storage de-duplication and compression when recommending actions.

Prerequisites

A service account Workload Optimization Manager can use to connect to the FlashArray

This account needs privileges to execute commands through the Pure Storage API – Typically the default pureuser administrative account.

Adding Pure Storage Targets

To add a Pure Storage target, select the **Storage > Pure Storage** option on the Target Configuration page and provide the following information:

Address

The name or IP address of the Pure Storage FlashArray.

Username/Password

Credentials for the service account Workload Optimization Manager can use to connect to the FlashArray. The Username must not contain the domain. For example, Username=jjsmith is correct, while Username=myDomain\jjsmith will result in a failure to validate.

Secure connection

When checked, uses SSL to connect to the Pure target. Most Pure installations do not accept insecure connections. If you receive an error when adding the target with secure connections disabled, try re-adding with this option enabled.

Entity Mapping

After validating your targets, Workload Optimization Manager updates the supply chain with the entities that it discovered. The following table describes the entity mapping between the target and Workload Optimization Manager.

Pure	Workload Optimization Manager
Volume	Storage
Shelf Array	Disk Array
Controller	Storage Controller

Storage targets (storage controllers) add Storage Controller and Disk Array entities to the supply chain. Disk Array entities then host Storage entities (datastores).

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Storage
 - Storage Amount
 - Storage Amount is the measurement of storage capacity that is in use.
 - Storage Provisioned



Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

NOTE:

When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.

■ Disk Array

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Provisioned

Storage provisioned is the utilization of the entity's capacity, including overprovisioning.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

■ Storage Controller

NOTE:

Not all targets of the same type provide all possible commodities. For example, some storage controllers do not expose CPU activity. When a metric is not collected, its chart in the user interface will not display data.

CPU

CPU is the measurement of CPU that is reserved or in use.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

The storage allocated to a storage controller is the total of all the physical space available to aggregates managed by that storage controller.

Actions

Workload Optimization Manager can recommend the following actions:

■ Storage

Resize Up

This action can only be executed outside Workload Optimization Manager.

■ Storage Controller

Provision

This action can only be executed outside Workload Optimization Manager.

Disk Array

Provision

This action can only be executed outside Workload Optimization Manager.

Pure Storage assigns all the disks managed by a storage controller to a single array, with a fixed form-factor. There are no actions to perform for an array. For example, there is no action to move a disk array from one storage controller to another. Likewise, there are no actions to move or provision volumes because of the fixed form-factor.



Virtual Desktop Infrastructure Targets

A virtual desktop infrastructure target is a service that delivers digital workspaces to multiple application users through a single portal. When you connect Workload Optimization Manager to VDI targets, it monitors the performance and resource consumption of the business users utilizing the virtual desktops and the virtual desktop infrastructure itself. Workload Optimization Manager then performs Application Resource Management (ARM) using the enhanced data to assure application performance while also utilizing resources as efficiently as possible.

As part of this process, Workload Optimization Manager will use this information to provide deeper insight into the state of the hardware, and information related to the users and virtual desktops running in your environment.

Horizon

VMware Horizon provides end users access to all of their virtual desktops, applications, and online services through a single digital workspace.

With the information provided by Horizon, Workload Optimization Manager efficiently utilizes the VDI infrastructure to avoid inappropriately placed or sized desktops, ensure users are matched to desktop images that meet their demand, while gaining valuable insight into the interconnected nature of your environment.

Prerequisites

- Horizon 7.0 or higher
- The version of the vCenter target associated to the Horizon target must be 5.0+

Adding Horizon Targets

NOTE:

For each Horizon target, you must add only one connection server servicing that site. Workload Optimization Manager will use the default port of 443. Adding multiple connection servers for the same site will result in inconsistent and/or duplicate actions.

To add a Horizon target, select the **Virtual Desktop Infrastructure > Horizon** option on the Target Configuration page and provide the following information:

Address

The IP address of the Horizon connection server.

■ Username

Username for the user account Workload Optimization Manager will use to connect to the Horizon target. This account must be an Administrator (Read-Only) account.

Password

Password for the user account Workload Optimization Manager will use to connect to the Horizon target.

vCenter Username

Username for the user account Workload Optimization Manager will use to connect to the vCenter target related to Horizon. Leave this blank if the Horizon and vCenter credentials are identical.

vCenter Password

Password for the user account Workload Optimization Manager will use to connect to the vCenter target related to Horizon. Leave this blank if the Horizon and vCenter credentials are identical.

■ LDAP Server

The address of the specific LDAP server Workload Optimization Manager will use in conjunction with the Horizon target. By default, Workload Optimization Manager will do a lookup based on the domain entered in the Username and select a healthy DNS server from the response.

■ LDAP Server Port

The port Workload Optimization Manager will use to connect to the specified LDAP server. By default, Workload Optimization Manager will use port 389 for unsecure connections, and port 636 for secure connections.

Secure LDAP Connection



When checked, Workload Optimization Manager will use SSL to communicate to the LDAP Server

■ LDAP Username

The username Workload Optimization Manager will use to connect to the LDAP Server, in the user principal name format to authenticate in the directory service through Kerberos. For example, user.name@domain.com

LDAP Password

The password Workload Optimization Manager will use to connect to the LDAP Server

Monitored Resources

Workload Optimization Manager monitors the following commodities of the Horizon target:

- Business User
 - ImageCPU

ImageCPU is the measurement of CPU that is utilized by a user's desktop images, expressed as a percentage of CPU capacity.

- ImageMem

ImageMem is the measurement of memory that is utilized by a user's desktop images, expressed as a percentage of memory capacity.

ImageStorage

ImageStorage is the measurement of storage that is utilized by a user's desktop images, expressed as a percentage of storage capacity.

- Desktop Pool
 - Pool CPU

Pool CPU is the measurement of CPU that is utilized by active sessions in a desktop pool.

Pool Memory

Pool memory is the measurement of memory that is utilized by active sessions in a desktop pool.

Pool Storage

Pool storage is the measurement of storage that is utilized by active sessions in a desktop pool.

Active Sessions

Active sessions is the number of active sessions in a desktop pool, expressed as a percentage of the pool's capacity.

Total Sessions

Total sessions is the number of active and disconnected (non-terminated) sessions in a desktop pool, expressed as a percentage of the pool's capacity.

- View Pod
 - Active Sessions

Active sessions is the number of active sessions in a desktop pool, expressed as a percentage of the pool's capacity.

Total Sessions

Total sessions is the number of active and disconnected (non-terminated) sessions in a desktop pool, expressed as a percentage of the pool's capacity.

Actions

Workload Optimization Manager recommends actions for the various entities of the Horizon target as follows:

- Desktop Pool
 - Workload Optimization Manager does not recommend actions to perform on a desktop pool. Instead, it recommends
 actions to perform on the business users running active sessions in the pool.
- View Pod
 - Workload Optimization Manager does not recommend actions to perform on a view pod. Instead, it recommends
 actions to perform on the business users running active sessions in the view pod.



Business User

- Move Business User due to image congestion
- Move Business User due to desktop pool congestion

Under some circumstances, you can have Business Users who need larger desktop images. This appears as users with high utilization of the image resources. In this case, Workload Optimization Manager can recommend moving the Business Users to a different desktop pool that serves up larger images.

To support moving Business Users, you must create a placement policy that merges desktop pools. Be sure to merge only desktop pools that are *similarly configured* – they should run the same operating system and applications, and differ only in allocated memory and/or CPU.

To merge desktop pools:

- 1. Create a new placement policy.
- 2. Choose Merge as the policy type.
- 3. For the consumer type to merge, choose **Desktop Pool**.
- 4. Choose the pools that you want to merge.
- Save the policy.

For more information, see Creating Placement Policies (on page 673).

Port Configuration

To support communication between Workload Optimization Manager and your intended targets, Workload Optimization Manager must be able to reach the targets through the following ports.

NOTE

If you are using the Workload Optimization Manager SaaS client, the following ports need to be opened to the client instead of the SaaS server.

Applications and Databases

Target	Port
Apache Tomcat	1009
AppDynamics	443
Applnsights	443
DataDog	443
Dynatrace	443
Cisco WebSphere	8879, 8880
Instana	443
JBoss	9990
JVM/Java	9875
SQL Server	1434, 1433
MySQL	3306
New Relic	443
Oracle	1521
Oracle WebLogic	7001



Cloud Native

Target	Port
Kubernetes kubelet (with kubeturbo)	10250 or 10255
Workload Optimization Manager (through kubeturbo using WSS)	443

Fabric and Network

Target	Port
HPE OneView	80, 443
Cisco UCS	80, 443

Guest OS Process

Target	Port
SNMP (Linux/UNIX)	161
WMI (Windows)	135 + dynamic ports 49152 - 65535

Hyperconverged

Target	Port
Cisco HyperFlex	433
Nutanix	9440

Hypervisors

Target	Port
Cisco PowerVM	80, 443
Microsoft Hyper-V	5985, 5986
Microsoft Hyper-V (Kubernetes)	88
VMware vCenter (Monitoring)	443
VMware vCenter (Tags)	10443
VMware vCenter (Kubernetes)	88

Orchestrator

Target	Port
ActionScript	22
Flexera One	443
ServiceNow	443



Private Cloud

Target	Port
Microsoft VMM	5985, 5986

Public Cloud

Target	Port
All public cloud targets	443

SaaS Client

Target	Port
Workload Optimization Manager SaaS client to SaaS server	8081, 55671, 45671

Storage

Target	Port
EMC Storage	5988, 5989, 443
HPE 3PAR	5988, 5989, 8080
Cisco FlashSystem	7443, 443
NetApp	80, 443
Pure Storage	80, 443

Virtual Desktop Infrastructure

Target	Port
VMware Horizon	443



User Interface Reference

Cisco Workload Optimization Manager is a solution that assures application performance for any workload running in any virtualized or cloud environment.

After installing or setting up the product, you can see the results of Workload Optimization Manager analysis – actions to perform that directly improve your datacenter state – within 15 to 30 minutes.

While it's true that setup is straightforward, the Workload Optimization Manager platform is rich in its coverage. Analysis takes your full stack into account, and Workload Optimization Manager recommends actions before alarms go off and the situation becomes critical. The user interface for such a product is necessarily rich with high-level information as well as fine details. You can use this interface and drill down to specific details that clarify the actions Workload Optimization Manager recommends.

Cisco also understands the need to define business rules in your environment. For example, you might need to ensure that certain applications have exclusive access to "golden" storage, while others can use less expensive resources. Or, you might want to ensure that certain workloads resize at scheduled times. Workload Optimization Manager automation supports this kind of business rule, as well as HA, affinity, discount purchase profiles, and many other rules that you expect to set up in a modern datacenter. The user interface includes tools to configure Workload Optimization Manager so that action recommendations respect the needs within your environment.


This reference material describes Workload Optimization Manager and its user interface. If you have any questions about what you see in the user interface, or how to use the tools that Workload Optimization Manager offers, we hope you will find this material useful.

Entity Types - Applications

The supply chain strongly emphasizes our application-driven approach to managing your infrastructure. By showing the entity types that make up your applications at the top of the hierarchy, it is easier for you to see the health of your environment and evaluate actions from the perspective that matters – Application Performance.


For distributed applications the Workload Optimization Manager Supply Chain can include a Business Application entity, with underlying Business Transaction, Service, and Application Component entities. The application is ultimately hosted on one or more VMs or Containers.





Business Application

A Business Application is a logical grouping of <u>Business Transactions (on page 327)</u>, <u>Services (on page 330)</u>, <u>Application Components (on page 332)</u>, and other elements of the application model that work together to compose a complete application as end users would view it. For example, a mobile banking app is a Business Application with a *Business Transaction* that facilitates payments, a *Service* within the Business Transaction that records payment information, and underlying *Application Components* (such as JVMs) that enable the Service to perform its functions.



You can monitor overall performance, make resourcing decisions, and set policies in the context of your Business Applications.

Synopsis

Synopsis	
Provides:	The complete application to end users
Consumes from:	Business Transactions, Services, Application Components, Database Servers, and the underlying nodes



Synopsis	
Discovery:	Workload Optimization Manager discovers the following:
	 AppDynamics Business Applications
	 Dynatrace Applications
	If you do not have these targets, you can create your own Business Applications using the Application Topology feature. For details, see <u>Application Topology</u> (on page 335).

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Response Time
 - Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).
- Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

The **Response Time** and **Transaction** charts for a Business Application show average and peak/low values over time. You can gauge performance against the given SLOs. By default, Workload Optimization Manager estimates SLOs based on monitored values. You can set your own SLO values in policies.

Actions

None

Workload Optimization Manager does not recommend actions for a Business Application, but it does recommend actions for the underlying Application Components and infrastructure. The Pending Actions chart for a Business Application lists these actions, thus providing visibility into the risks that have a direct impact on the Business Application's performance.

Business Application Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

None

Workload Optimization Manager does not recommend actions for a Business Application, but it does recommend actions for the underlying Application Components and infrastructure. The Pending Actions chart for a Business Application lists these actions, thus providing visibility into the risks that have a direct impact on the Business Application's performance.

Transaction SLO

Enable this SLO if you are monitoring performance through your Business Applications.

Attribute	Default Setting/Value	
Enable Transaction SLO	Off	
	Workload Optimization Manager estimates SLO based on monitored values.	
Transaction SLO	None	
	If you enable SLO, Workload Optimization Manager uses the default value of 10. You can change this to a different value.	

Transaction SLO determines the upper limit for acceptable transactions per second. When the number of transactions reaches the given value, Workload Optimization Manager sets the risk index to 100%.



Response Time SLO

Enable this SLO if you are monitoring performance through your Business Applications.

Attribute	Default Setting/Value
Enable Response Time SLO	Off
	Workload Optimization Manager estimates SLO based on monitored values.
Response Time SLO [ms]	None
	If you enable SLO, Workload Optimization Manager uses the default value of 2000. You can change this to a different value.


Response time SLO determines the upper limit for acceptable response time (in milliseconds). If response time reaches the given value, Workload Optimization Manager sets the risk index to 100%.

Business Transaction

A Business Transaction represents a capability within your Business Application that fulfills a response to a user-initiated request. Its performance directly impacts user experience. You can monitor performance as experienced by your end users in the context of Business Transactions. For more information, see <u>Business Application (on page 325)</u>.



Synopsis



Synopsis	
Provides:	Response time and transactions to Business Applications
Consumes from:	Services (on page 330), Application Components (on page 332), Database Servers, and the underlying nodes
Discovery:	Workload Optimization Manager discovers the following: AppDynamics Business Transactions NewRelic Key Transactions If you do not have these targets, you can create your own Business Transactions using the Application Topology feature. For details, see Application Topology (on page 335).

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Response Time
 - Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).
- Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.



The **Response Time** and **Transaction** charts for a Business Transaction show average and peak/low values over time. You can gauge performance against the given SLOs. By default, Workload Optimization Manager estimates SLOs based on monitored values. You can set your own SLO values in policies.

Actions

None

Workload Optimization Manager does not recommend actions for a Business Transaction, but it does recommend actions for the underlying Application Components and infrastructure. The Pending Actions chart for a Business Transaction lists these actions, thus providing visibility into the risks that have a direct impact on the Business Transaction's performance.

Business Transaction Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

None

Workload Optimization Manager does not recommend actions for a Business Transaction, but it does recommend actions for the underlying Application Components and infrastructure. The Pending Actions chart for a Business Transaction lists these actions, thus providing visibility into the risks that have a direct impact on the Business Transaction's performance.

Transaction SLO

Enable this SLO if you are monitoring performance through your Business Transactions.

Attribute	Default Setting/Value	
Enable Transaction SLO	Off	
	Workload Optimization Manager estimates SLO based on monitored values.	
Transaction SLO	None If you enable SLO, Workload Optimization Manager uses the	
	default value of 10. You can change this to a different value.	

Transaction SLO determines the upper limit for acceptable transactions per second. When the number of transactions reaches the given value, Workload Optimization Manager sets the risk index to 100%.

Response Time SLO

Enable this SLO if you are monitoring performance through your Business Transactions.

Attribute	Default Setting/Value	
Enable Response Time SLO	Off	
	Workload Optimization Manager estimates SLO based on monitored values.	
Response Time SLO [ms]	None	
	If you enable SLO, Workload Optimization Manager uses the default value of 2000. You can change this to a different value.	

Response time SLO determines the upper limit for acceptable response time (in milliseconds). If response time reaches the given value, Workload Optimization Manager sets the risk index to 100%.




Service

A Service in the supply chain represents one or several Application Components that perform a defined, measurable function as part of an internal or user-initiated request. Its performance is key to understanding application performance, but only indirectly impacts user experience. You can measure performance as experienced internal to the Business Application in the context of Services.

This topic discusses Services discovered via APM targets. For details about Kubernetes Services, see <u>Kubernetes Service</u> (on page 338).

Synopsis



Synopsis	
Provides:	Response time and transactions to <u>Business Transactions (on page 327)</u> and Business Applications
Consumes from:	Application Components, Database Servers, and the underlying nodes
Discovery:	Workload Optimization Manager discovers the following: AppDynamics Tiers Dynatrace Services Instana Services NewRelic APM Applications / NewRelic Services (New Relic ONE) NOTE: If you do not have an APM target, you can create your own Services using the Application Topology feature. For details, see Application Topology (on page 335).

Monitored Resources

Workload Optimization Manager monitors the following resources:

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

■ Transaction



Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

The **Response Time** and **Transaction** charts for a Service show average and peak/low values over time. You can gauge performance against the given SLOs. By default, Workload Optimization Manager estimates SLOs based on monitored values. You can set your own SLO values in policies.

Actions

None

Workload Optimization Manager does not recommend actions for Services discovered via APM targets, but it does recommend actions for the underlying Application Components and nodes. The Pending Actions chart for Services list these actions, thus providing visibility into the risks that have a direct impact on their performance.

Service Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

This topic discusses policy settings for Services discovered via APM targets. For Services discovered via APM targets, a different set of policy settings apply. For details, see <u>Kubernetes Service Policies (on page 339)</u>.

Action Automation and Orchestration

Workload Optimization Manager does not recommend actions for Services discovered via APM targets, but it does recommend actions for the underlying Application Components and nodes. The Pending Actions chart for Services list these actions, thus providing visibility into the risks that have a direct impact on their performance.

Transaction SLO

Enable this SLO if you are monitoring performance through Services.

Attribute	Default Setting/Value
Enable Transaction SLO	Off
	Workload Optimization Manager estimates SLO based on monitored values.
Transaction SLO	None
	If you enable SLO, Workload Optimization Manager uses the default value of 10. You can change this to a different value.

Transaction SLO determines the upper limit for acceptable transactions per second. When the number of transactions reaches the given value, Workload Optimization Manager sets the risk index to 100%.

Response Time SLO

Enable this SLO if you are monitoring performance through Services.

Attribute	Default Setting/Value
Enable Response Time SLO	Off
	Workload Optimization Manager estimates SLO based on monitored values.
Response Time SLO [ms]	None If you enable SLO, Workload Optimization Manager uses the default value of 2000. You can change this to a different value.

Response time SLO determines the upper limit for acceptable response time (in milliseconds). If response time reaches the given value, Workload Optimization Manager sets the risk index to 100%.




Application Component

An Application Component is a software component, application code, or a unit of processing within a <u>Service (on page 330)</u> that consumes resources to enable it to perform its function for the <u>Business Application (on page 325)</u>. For example, Apache Tomcat is a Java Servlet container that hosts a range of Java applications on the web.

Workload Optimization Manager can recommend actions to adjust the amount of resources available to Application Components.

Synopsis



Synopsis	
Provides:	 Response Time and Transactions to Services, <u>Business Transactions (on page 327)</u>, and Business Applications Response Time, Transactions, Heap, Remaining GC Capacity, and Threads to end users
Consumes:	Compute resources from nodes
Discovery:	Workload Optimization Manager discovers the following: Apache Tomcat AppDynamics Nodes Dynatrace Processes NewRelic APM Application Instances Application Insights Components SNMP WMI Data Ingestion Framework metrics for Kubernetes environments

Monitored Resources

Workload Optimization Manager monitors the following resources:

NOTE:

The exact resources monitored will differ based on application type. This list includes all resources you may see.

Virtual CPU (VCPU)



Virtual CPU is the measurement of CPU that is in use.

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Heap

Heap is the portion of a VM or container's memory allocated to individual applications.

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Connection

Connection is the measurement of database connections utilized by applications.

Remaining GC Capacity

Remaining GC capacity is the measurement of Application Component uptime that is not spent on garbage collection (GC).

Threads

Threads is the measurement of thread capacity utilized by applications.

The charts for an Application Component show average and peak/low values over time. You can gauge performance against the given SLOs. By default, Workload Optimization Manager does not enable SLOs in the default policy for Application Components. It estimates SLOs based on monitored values, but does not use these values in its analysis.

NOTE:

In Kubernetes environments, SLOs defined in a Service policy override any SLOs set in the associated Application Components to prevent conflicts. In addition, the Response Time and Transaction charts for Application Components will show SLOs specified in the Service policy. For more information, see <u>Kubernetes Service Policies</u> (on page 339).

Actions

Workload Optimization Manager can recommend the following actions:

Resize

Resize the following resources to maintain performance:

Thread Pool

Workload Optimization Manager generates thread pool resize actions. These actions are recommend-only and can only be executed outside Workload Optimization Manager.

Connections

Workload Optimization Manager uses connection data to generate memory resize actions for on-prem Database Servers.

Heap

Workload Optimization Manager generates Heap resize actions if an Application Component provides Heap and Remaining GC Capacity, and the underlying VM or container provides VMem. These actions are recommend-only and can only be executed outside Workload Optimization Manager.

NOTE

Remaining GC capacity is the measurement of Application Component uptime that is *not* spent on garbage collection (GC). The resources that Workload Optimization Manager can resize depend on the processes that it discovers from your Applications and Databases targets. Refer to the topic for a specific target to see a list of resources that can be resized.

Application Component Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.



Action Automation and Orchestration

For details about Application Component actions, see Application Component Actions. (on page 333)

Action	Default Mode
Resize heap (up or down)	Recommend
Resize thread pool (up or down)	Recommend
Resize connections (up or down)	Recommend

You can use Action Scripts (on page 692) for action orchestration. Third-party orchestrators (such as ServiceNow) are not supported.

Transaction SLO

Enable this SLO to monitor the performance of your Application Components.

NOTE

In Kubernetes environments, SLOs defined in a Service policy override any SLOs set in the associated Application Components to prevent conflicts. In addition, the Response Time and Transaction charts for Application Components will show SLOs specified in the Service policy. For more information, see <u>Kubernetes Service Policies (on page 339)</u>.

Attribute	Default Setting/Value
Enable Transaction SLO	Off
	Workload Optimization Manager estimates SLO based on monitored values.
Transaction SLO	None
	If you enable SLO, Workload Optimization Manager uses the default value of 10. You can change this to a different value.

Transaction SLO determines the upper limit for acceptable transactions per second. When the number of transactions reaches the given value, Workload Optimization Manager sets the risk index to 100%.

Response Time SLO

Enable this SLO to monitor the performance of your Application Components.

NOTE:

In Kubernetes environments, SLOs defined in a Service policy override any SLOs set in the associated Application Components to prevent conflicts. In addition, the Response Time and Transaction charts for Application Components will show SLOs specified in the Service policy. For more information, see <u>Kubernetes Service Policies (on page 339)</u>.

Attribute	Default Setting/Value
Enable Response Time SLO	Off
	Workload Optimization Manager estimates SLO based on monitored values.
Response Time SLO [ms]	None
	If you enable SLO, Workload Optimization Manager uses the default value of 2000. You can change this to a different value.

Response time SLO determines the upper limit for acceptable response time (in milliseconds). If response time reaches the given value, Workload Optimization Manager sets the risk index to 100%.



Heap Utilization

The Heap utilization that you set here specifies the percentage of the existing capacity that Workload Optimization Manager will consider to be 100% of capacity. For example, a value of 80 means that Workload Optimization Manager considers 80% utilization to be 100% of capacity.

Attribute	Default Value	
Heap Utilization (%)	80	

Workload Optimization Manager uses Heap utilization and Remaining GC Capacity (the percentage of CPU time *not* spent on garbage collection) when making scaling decisions. Assume Heap utilization is at 80%, which is 100% of capacity. However, if Remaining GC Capacity is at least 90% (in other words, CPU time spent on garbage collection is only 10% or less), an 80% Heap utilization does not indicate a shortage after all. As a result, Workload Optimization Manager will not recommend Heap scaling.

If Heap utilization is low and Remaining GC Capacity is high, Workload Optimization Manager will recommend resizing down Heap. If the opposite is true, then Workload Optimization Manager will recommend resizing up Heap.

Heap Scaling Increment

This increment specifies how many units to add or subtract when scaling Heap for an application component.

Attribute	Default Value	
Heap Scaling Increment (MB)	128	


Do not set the increment value to be lower than what is necessary for the Application Component to operate. If the increment is too low, then it's possible there would be insufficient Heap for the Application Component to operate. When reducing allocation, Workload Optimization Manager will not leave an Application Component with less than the increment value. For example, if you use the default 128, then Workload Optimization Manager cannot reduce the Heap to less than 128 MB.

Application Topology

Workload Optimization Manager gives you the ability to create your own <u>Business Applications (on page 325)</u>, <u>Business Transactions (on page 327)</u>, and <u>Services (on page 330)</u> without the need to ingest additional application data into the platform. This is especially useful in environments where there are gaps in the application stack shown in the Workload Optimization Manager supply chain. For example, in the absence of an application monitoring target such as AppDynamics or Dynatrace, you will not see Business Applications in your supply chain. User-created application entities address those gaps.

When you create a new application entity, you identify interrelated application entities and nodes (i.e., the infrastructure that backs the application entities) in your environment for which you want to measure performance. Workload Optimization Manager then links them in a supply chain and represents them as a unified group. You can monitor overall performance for the group in the context of the new application entity, and drill down to the individual entities and nodes for finer details.





Workload Optimization Manager does not perform analysis on any user-created application entity, but it aggregates the underlying risks the same way it does for auto-discovered entities.

After you create an application entity, Workload Optimization Manager counts it in the global supply chain and adds it to the relevant charts (for example, if you created a new Service that has performance risks, you might see it listed in the Top Services chart). Drill down to the newly created entity to monitor its performance. You can also use Search to find the application entity and set it as your scope.

NOTE:

It could take up to 10 minutes to see newly created entities in the supply chain.

Creating Application Entities

1. Navigate to the **Settings** Page.



2. Choose Application Topology.



- 3. Click New Application Topology and then choose Automatic or Manual.
 - Automatic

Create a new application entity composed of tagged entities. For example, create a new Business Application composed of VMs with the "Production" tag.

a. Select the application entity type that you want to create.



- Type an entity name prefix to help you easily identify the application entities that Workload Optimization Manager will create for you.
- c. Specify the tags that will identify the underlying entities.

Manual

Create a new application entity composed of a specific set of application entities and nodes.

- a. Select the application entity type that you want to create.
- b. Give the application entity a name.
- c. Select the underlying application entities and nodes.
- d. Enable or disable Direct Link.
 - Disabled (default)

When **Direct Link** is disabled, Workload Optimization Manager creates a context-based definition of the application entity you are creating and automatically updates that definition as the entity evolves. This allows you to create flexible definitions with minimal effort.

The underlying application entities and nodes that you specified act as "seed entities" for creating the definition. Workload Optimization Manager uses these seed entities to identify the highest entity in the supply chain and any other related entities ("leaf entities"), and then creates a new context-based definition. The result is an application topology that closely matches your environment.

For example, your initial intent might be to create a new Business Application entity composed of several Services (seed entities), so you can monitor performance at the Service level. However, you might not be aware of other entities that could impact performance, making it more time-consuming to identify and resolve performance issues outside of the selected scope. With **Direct Link** disabled, Workload Optimization Manager might discover Application Components and VMs (leaf entities) that back the Services, and then show them in the supply chain. The result is a more complete representation of the Business Application that shows performance risks at each level of the discovered application stack. As the composition of the Business Application changes, Workload Optimization Manager automatically updates the definition so your supply chain view remains current.

- Enabled


When **Direct Link** is enabled, Workload Optimization Manager creates a definition based solely on your selected entities. This option is ideal if you require full control of your definitions. For example, you might have a requirement to limit the scope of your performance monitoring to certain entities.

4. Click Create Definition.

Entity Types - Container Platform

Workload Optimization Manager discovers and monitors the entities that make up your container platform, and recommends actions to assure performance for the applications that consume resources from these entities.





Kubernetes Service


A Kubernetes Service is a logical set of pods that represents a given application. The Service exposes a single entry point for the application process. While the pods that comprise the service are ephemeral, the service is persistent. The Service entity also gives historical tracking of the number of replicas that run to support the Service.

NOTE

For details about Services discovered via APM targets, see Service (on page 330).



Synopsis



Synopsis	
Provides: Response time and transactions to <u>Business Transactions (on page 327)</u> and Business Applications	
Consumes from:	Container pods and the underlying nodes
Discovered through:	Kubeturbo pod that you have deployed in your environment

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Response Time
 - Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).
- Transaction
 - Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

The **Response Time** and **Transaction** charts for a Service show average and peak/low values over time. You can gauge performance against the given SLOs. By default, Workload Optimization Manager estimates SLOs based on monitored values. You can set your own SLO values in policies.

Actions

None

Workload Optimization Manager does not recommend actions for Kubernetes Services, but it does recommend actions for the replicas that back those Services.

For details, see Workload Controller Scale Actions (on page 356).

Kubernetes Service Policies

Policies are required to generate <u>SLO-driven scale actions</u> (on page 356) for Kubernetes Services. You can create policies from the Workload Optimization Manager user interface or by using Custom Resources in your Kubernetes clusters.




In addition to policies, certain requirements must be satisfied in order for Workload Optimization Manager to generate SLO-driven scale actions. For details, see <u>Action Generation Requirements (on page 356)</u>.

NOTE:

When a group of Services applies multiple conflicting policies, Workload Optimization Manager enforces the policy with the most conservative settings.

For Services discovered via APM targets, a different set of policy settings apply. For details, see <u>Service Policies (on page 331)</u>.

Creating Policies From the User Interface



Action Automation and Orchestration

Workload Optimization Manager does not recommend actions for Kubernetes Services, but it does recommend actions for the replicas that back those Services.

To generate these actions, you must turn on horizontal scaling (up and/or down) and specify your desired SLOs.

Attribute	Default Setting/Value
Horizontal Scale Down	Off (Disabled)
Horizontal Scale Up	Off (Disabled)

We recommend action automation under the following circumstances:

- Your applications run as a set of Kubernetes Services backed by a deployment.
- Services deploy via a namespace without quotas.
- Newly provisioned pods are placed on nodes with the same CPU speed.
- You do not have an upstream Kubernetes HPA (Horizontal Pod Autoscaling) enabled for the same workload.



We recommend that you disable automation and manually execute actions under the following circumstances:

- Services deploy via a namespace with quotas.
- Newly created pods are scheduled on nodes with different CPU speeds.
- Services have non-resource constraints that could result in newly provisioned pods staying in the pending state.

Transaction SLO

Transaction SLO is the maximum number of transactions per second that each Application Component replica can handle.

Attribute	Default Setting/Value
Enable Transaction SLO	Off
Transaction SLO	None If you enable SLO, Workload Optimization Manager uses the default value of 10. You can change this to a different value.

■ Response Time SLO

Response Time SLO is the desired weighted average response time (in milliseconds) of all Application Component replicas associated with a Service.

Attribute	Default Setting/Value
Enable Response Time SLO	Off
Response Time SLO [ms]	None If you enable SLO, Workload Optimization Manager uses the default value of 2000. You can change this to a different value.

Minimum and Maximum Replicas

You can adjust the default values based on the characteristics of your applications or if you are planning for capacity. The maximum value also acts as a safeguard against overprovisioning of replicas.

Attribute	Default Setting/Value
Minimum Replicas	1
Maximum Replicas	10000

Creating Policies Using Custom Resources (CRs)

Application owners who do not have access to the Workload Optimization Manager user interface can create the following CRs in their Kubernetes clusters:

- ServicePolicy CR
- ServicePolicyBinding CR

Kubeturbo discovers the settings in these CRs and then displays them as policies in the user interface. Policies in the user interface are read-only since the CRs are the source of truth. Policies are synced with CRs every ten minutes.

ServicePolicy CR

This is a YAML resource that specifies the policy settings that apply to a group of Kubernetes Services (download a sample here).

This CR is a namespaced resource, so there should be a CR in every namespace for the Services, if applicable.

IMPORTANT:

Before creating the ServicePolicy CR, be sure to add this <u>CRD</u> to the Kubernetes cluster. This CRD is mandatory and is intended to ensure the validity of the ServicePolicy CR.

Configure the following:



```
apiVersion: policy.turbonomic.io/vlalpha1
kind: SLOHorizontalScale
metadata:
  name: <Policy_Name>
spec:
  minReplicas: <minReplicas>
  maxReplicas: <maxRelicas>
  objectives:
  - name: ResponseTime
    value: <ResponseTimeSLO>
  - name: Transaction
    value: <TransactionSLO>
behavior:
    scaleUp: <Action_Mode>
    scaleDown: <Action_Mode>
```

Where:

<Policy_Name> is the name of the policy.

In the user interface, this policy will be added to **Settings > Policies**.

- <minReplicas> and <maxRelicas> are values that you set based on the characteristics of your applications or if you are planning for capacity. The maximum value also acts as a safeguard against overprovisioning of replicas.
- <ResponseTimeSLO>

Response Time SLO is the desired weighted average response time (in milliseconds) of all Application Component replicas associated with a Service.

If an SLO value is not specified, the policy will use the default value in the global policy for Services.

To disable the SLO, remove the name-value pair from the CR.

<TransactionSLO>

Transaction SLO is the maximum number of transactions per second that each Application Component replica can handle.

If an SLO value is not specified, the policy will use the default value in the global policy for Services.

To disable the SLO, remove the name-value pair from the CR.

<Action_Mode> specifies the degree of automation for the generated actions.

Choose from the following:

- Turn on scale up and scale down.
- Turn on scale up, turn off scale down.
- Turn on scale down, turn off scale up.

To turn on, set the action acceptance mode to Automatic, Manual, or Recommend. To turn off, set the action acceptance mode to Disabled. See Action Acceptance Modes (on page 529) for details.

We recommend action automation under the following circumstances:

- Your applications run as a set of Kubernetes Services backed by a deployment.
- Services deploy via a namespace without quotas.
- Newly provisioned pods are placed on nodes with the same CPU speed.
- You do not have an upstream Kubernetes HPA (Horizontal Pod Autoscaling) enabled for the same workload.

We recommend that you disable automation and manually execute actions under the following circumstances:

- Services deploy via a namespace with quotas.
- Newly created pods are scheduled on nodes with different CPU speeds.
- Services have non-resource constraints that could result in newly provisioned pods staying in the pending state.



NOTE:

If you turned off horizontal scaling but specified SLOs values in the policy, actions do not generate but SLO values will continue to display in the Response Time and Transaction charts for Services, for your reference. This allows you to gauge performance against those SLOs.

Below is a sample CR:

```
apiVersion: policy.turbonomic.io/vlalphal
kind: SLOHorizontalScale
metadata:
   name: Policy_A
spec:
   minReplicas: 1
   maxReplicas: 10
   objectives:
   - name: ResponseTime
    value: 300
   - name: Transaction
    value: 20
behavior:
   scaleUp: Automatic
   scaleDown: Disabled
```

ServicePolicyBinding CR

This is a YAML resource that binds the policy settings specified in ServicePolicy to the group of Kubernetes services specified in this CR (download a sample here).

IMPORTANT:

Before creating the ServicePolicyBinding CR, be sure to add this <u>CRD</u> to the Kubernetes cluster. This CRD is mandatory and is intended to ensure the validity of the ServicePolicyBinding CR.

Configure the following:

```
apiVersion: policy.turbonomic.io/vlalphal
kind: PolicyBinding
metadata:
   name: <Group_Name>
policyRef:
   kind: SLOHorizontalScale
   name: <Policy_Name>
targets:
   apiVersion: apps/vl
   kind: Service
   name: <Service_Name_1>
   apiVersion: apps/vl
   kind: Service
   name: <Service_Name_2>
```

Where:

- «Group_Name» is the name of the group of Services that will apply the policy. In the user interface, this group will be added to Search > Groups and will be shown in the format <Namespace>/<Group_Name>[Target_Name].
- <Policy_Name> is the policy name defined in the ServicePolicy CR.
 - In the user interface, this policy will be added to **Settings > Policies**.
- Service_Name_1 and Service_Name_2 are the Services belonging to the group. Add more entries as needed. You can specify actual names or use regular expressions.



Below is a sample CR:

apiVersion: policy.turbonomic.io/vlalphal

kind: PolicyBinding

metadata:

name: AH-Service_GP

policyRef:

kind: SLOHorizontalScale

name: Policy_A

targets:

- apiVersion: apps/vl

kind: Service
name: cass-api
- apiVersion: apps/v1


kind: Service

name: cass-(cass|user)

Propagation of Service Policy Settings

Settings in a Service policy propagate to the associated pods and Application Components to establish their relationship and provide context.

For example, assume you created a group of Services called AH-Service_GP and then applied the Service policy Ah-Test_HScale to that group. When you set the scope to this group, Ah-Test_HScale displays as a policy in the entity views for Services, Application Components, and Container Pods. You can click the policy name in any view to see or modify the policy settings.






To prevent conflicts, SLO values in Service policies override any SLOs set in Application Components. In addition, the Response Time and Transaction charts for Application Components show SLOs specified in the Service policy.

Container

An application container is a standalone, executable image of software that includes components to host an application. Because the container instances that support an application can change at any time, containers are considered *ephemeral*.

Synopsis



Synopsis		
Provides:	Resources for the applications to use, including: Virtual CPU Virtual Memory 	
Consumes:	Resources from container pods, virtual machines, and virtual datacenters	
Discovered through:	For Kubernetes, Workload Optimization Manager discovers containers through the Kubeturbo pod that you have deployed in your environment.	
	For Dynatrace and AppDynamics hosted on containers:	
	 Dynatrace: Workload Optimization Manager discovers containers through the metadata of processes. 	



Synopsis		
	-	AppDynamics: Workload Optimization Manager discovers containers through container objects.

Monitored Resources

Workload Optimization Manager monitors the following resources:

Virtual Memory (VMem)

VMem is the virtual memory utilized by a container against the memory limit. If no limit is set, node capacity is used.

VMem Request

If applicable, VMem Request is the virtual memory utilized by a container against the memory request.

■ Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

VCPU Request

If applicable, VCPU Request is the virtual CPU (in mCores) utilized by a container against the CPU request.

VCPU Throttling

VCPU Throttling is the throttling of container virtual CPU that could impact response time, expressed as the percentage of throttling for all containers associated with a Container Spec. In the Capacity and Usage chart for containers, *used* and *utilization* values reflect the actual throttling percentage, while *capacity* value is always 100%.

Actions

None

Workload Optimization Manager does not recommend actions on containers.

Container Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

None

Workload Optimization Manager does not recommend actions on containers.

Action	Default Mode
Resize Container Specs	Manual (automatable)
Scale replicas	Manual (automatable)

For details, see Workload Controller Resize Actions (on page 352).

Consistent Resizing

For groups in user-defined automation policies:

Attribute	Default Setting
Consistent Resizing	Off

When you create a policy for a group of containers and turn on Consistent Resizing, Workload Optimization Manager resizes all the group members to the same size, such that they all support the top utilization of each resource commodity in the group. For example, assume container A shows top utilization of CPU, and container B shows top utilization of memory. Container resize actions would result in all the containers with CPU capacity to satisfy container A, and memory capacity to satisfy container B.



For an affected resize, the Actions List shows individual resize actions for each of the containers in the group. If you automate resizes, Workload Optimization Manager executes each resize individually in a way that avoids disruption to your workloads.

■ For auto-discovered groups:

Workload Optimization Manager discovers Kubernetes groups such as Deployments, ReplicationControllers, ReplicaSets, DaemonSets, and StatefulSets, and automatically enables Consistent Resizing in a read-only policy for each group. If you do not need to resize all the members consistently, create another policy for the group and turn off Consistent Resizing.


Container Spec

A Container Spec is a shared definition for all ephemeral container replicas with like properties. It is a persistent entity that maintains historical data for its ephemeral containers, and all the replicas that have run in the past. Workload Optimization Manager uses historical data to make container sizing decisions. Data includes:

- vCPU used by all container replicas
- vCPU request capacity (if applicable)
- vMem used by all container replicas
- vMem request capacity (if applicable)

In the Workload Optimization Manager supply chain, the count of replicas maps to the count of container entities that a Container Spec encompasses.

Synopsis



Synopsis	
Provides:	N/A
Consumes:	N/A
Discovered through:	Kubeturbo Mediation Pod

Monitored Resources

Workload Optimization Manager monitors the historical usage of any instance of a container running for the workload (assuming the workload name stays the same). Charts show the trend of usage even with restarts or redeployments.



Actions

Workload Optimization Manager can recommend the following actions:

Resize (via Workload Controllers)

A Container Spec retains the historical utilization data of ephemeral containers. Workload Optimization Manager uses this data to make resize decisions that assure optimal utilization of resources. By default, all replicas of the same container for the same workload type resize consistently.

For details, see Workload Controller Resize Actions (on page 352).

Constraint for Sidecar Container Specs

A Kubernetes service might include <u>sidecar</u> Container Specs to provide additional services to a running pod, such as security or logging services. Sidecars injected at pod creation cannot be updated from the parent Workload Controller, causing a resize action to fail.

To prevent the execution of resize actions on injected sidecars, Workload Optimization Manager adds them to a group called "Injected Sidecars/All ContainerSpecs". This group applies a read-only policy that sets the action acceptance mode for resizes to *Recommend*. This means that you can only execute resizes outside of Workload Optimization Manager. The parent Workload Controller will continue to resize non-sidecar Container Specs as usual.

Container Spec Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

The following settings affect tuned scaling:

Setting	Default Mode
vCPU Request Resize Below Min	Recommend
vCPU Limit Resize Above Max	Recommend
vCPU Limit Resize Below Min	Recommend
vMem Request Resize Below Min	Recommend
vMem Limit Resize Above Max	Recommend
vMem Limit Resize Below Min	Recommend

The default mode of *Recommend* means that when resize values in actions fall outside the normal range (as defined in Container Spec policies), Workload Optimization Manager will post the actions for you to review. You can only execute these actions outside Workload Optimization Manager. If you set the action mode to *Disabled*, Workload Optimization Manager will not generate the actions.

For an overview of tuned resizing, see Tuned Resizing (on page 354).

Resize Thresholds

Workload Optimization Manager uses resize thresholds as operational constraints to set up tuned resizing for Container Specs. For an overview of tuned resizing, see <u>Tuned Resizing</u> (on page 354).

Attribute	Default Value
VCPU Request Resize Min Threshold (mCores)	10
VCPU Limit Resize Min Threshold (mCores)	500
VCPU Limit Resize Max Threshold (mCores)	64000
VMEM Request Resize Min Threshold (MB)	10



Attribute	Default Value
VMEM Resize Min Threshold (MB)	10
VMEM Resize Max Threshold (MB)	1048576

Max CPU Throttling Tolerance (%)

This value defines your acceptable level of throttling and directly impacts the resize actions generated on CPU Limits.

Attribute	Default Value
Max CPU Throttling Tolerance (%)	20

A low percentage value indicates more sensitivity to throttling, while a high value indicates more tolerance for throttling and a higher risk of congestion. Workload Optimization Manager generates resize actions to accommodate the value that you defined. A default of up to 20% throttling will be tolerated unless defined otherwise.

Learn more about CPU throttling here.

Increment Constants

Workload Optimization Manager recommends changes in terms of the specified resize increments.

Attribute	Default Value
Increment constant for VCPU Limit and VCPU Request (mCores)	100
Increment constant for VMEM Limit and VMEM Request (MB)	128

For example, assume the vCPU request increment is 100 mCores and you have requested 800 mCores for a container. Workload Optimization Manager could recommend to reduce the request by 100, down to 700 mCores.

For vMem, you should not set the increment value to be lower than what is necessary for the container to operate. If the vMem increment is too low, then it's possible that Workload Optimization Manager would allocate insufficient vMem. For a container that is underutilized, Workload Optimization Manager will reduce vMem allocation by the increment amount, but it will not leave a container with zero vMem. For example, if you set this to 128, then Workload Optimization Manager cannot reduce the vMem to less than 128 MB.

Rate of Resize

(For the default policy only)

Attribute	Default Value
Rate of Resize	High

When resizing resources for a container, Workload Optimization Manager calculates the optimal values for vMem and vCPU. But it does not necessarily make a change to that value in one action. Workload Optimization Manager uses the Rate of Resize setting to determine how to make the change in a single action, as follows:

Low

Change the value by one increment, only. For example, if the resize action calls for increasing vMem, and the increment is set at 128, Workload Optimization Manager increases vMem by 128 MB.

■ Medium

Change the value by an increment that is 1/4 of the difference between the current value and the optimal value. For example, if the current vMem is 2 GB and the optimal vMem is 10 GB, then Workload Optimization Manager will raise vMem to 4 GB (or as close to that as the increment constant will allow).

■ High

Change the value to be the optimal value. For example, if the current vMem is 2 GB and the optimal VMem is 8 GB, then Workload Optimization Manager will raise vMem to 8 GB (or as close to that as the increment constant will allow).



Aggressiveness and Observation Periods

Workload Optimization Manager uses these settings to calculate utilization percentiles for vCPU and vMEM. It then recommends actions to improve utilization based on the observed values for a given time period.

Aggressiveness

Attribute	Default Value
Aggressiveness	99th Percentile

When evaluating vCPU and vMEM performance, Workload Optimization Manager considers resource utilization as a percentage of capacity. The utilization drives actions to scale the available capacity either up or down. To measure utilization, the analysis considers a given utilization percentile. For example, assume a 99th percentile. The percentile utilization is the highest value that 99% of the observed samples fall below. Compare that to average utilization, which is the average of *all* the observed samples.

Using a percentile, Workload Optimization Manager can recommend more relevant actions. This is important in the cloud, so that analysis can better exploit the elasticity of the cloud. For scheduled policies, the more relevant actions will tend to remain viable when their execution is put off to a later time.

For example, consider decisions to reduce the capacity for CPU on a container. Without using a percentile, Workload Optimization Manager never resizes below the recognized peak utilization. For most containers there are moments when peak CPU reaches high levels. Assume utilization for a container peaked at 100% just once. Without the benefit of a percentile, Workload Optimization Manager will not reduce allocated CPU for that container.

With **Aggressiveness**, instead of using the single highest utilization value, Workload Optimization Manager uses the percentile you set. For the above example, assume a single CPU burst to 100%, but for 99% of the samples CPU never exceeded 50%. If you set **Aggressiveness** to 99th Percentile, then Workload Optimization Manager can see this as an opportunity to reduce CPU allocation for the container.

In summary, a percentile evaluates the sustained resource utilization, and ignores bursts that occurred for a small portion of the samples. You can think of this as aggressiveness of resizing, as follows:

- 100th Percentile The least aggressive, recommended for critical workloads that need maximum guaranteed performance at all times.
- 99th Percentile (Default) The recommended setting to achieve maximum performance and savings.
- 90th Percentile Most aggressive, recommended for non-production workloads that can stand higher resource utilization.

■ Max Observation Period

Attribute	Default Value
Max Observation Period	Last 30 Days

To refine the calculation of resource utilization percentiles, you can set the sample time to consider. Workload Optimization Manager uses historical data from up to the number of days that you specify as a sample period. (If the database has fewer days' data then it uses all of the stored historical data.)

A shorter period means there are fewer data points to account for when Workload Optimization Manager calculates utilization percentiles. This results in more dynamic, elastic resizing, while a longer period results in more stable or less elastic resizing. You can make the following settings:

- Less Elastic Last 90 Days
- Recommended Last 30 Days
- More Elastic Last 7 Days

Min Observation Period

Attribute	Default Value
Min Observation Period	1 Day

This setting ensures historical data for a minimum number of days before Workload Optimization Manager will generate an action based on the percentile set in **Aggressiveness**. This ensures a minimum set of data points before it generates the action.



Especially for scheduled actions, it is important that resize calculations use enough historical data to generate actions that will remain viable even during a scheduled maintenance window. A maintenance window is usually set for "down" time, when utilization is low. If analysis uses enough historical data for an action, then the action is more likely to remain viable during the maintenance window.


- More Elastic None
- Recommended 1 Day
- Less Elastic 3 or 7 Days

Workload Controller

A Workload Controller is a Kubernetes controller that watches the state of your pods and then requests changes where needed. Examples of Kubernetes controllers are Deployments and StatefulSets. A single Workload Controller can contain one or more Container Spec entities, and it can be related to one or more running replica pods. Like Container Specs, Workload Controllers are persistent.

You can execute actions to resize Container Specs or scale replicas when you set the scope to a Workload Controller.

Synopsis



Synopsis	
Provides:	N/A
Consumes:	N/A
Discovered through:	Kubeturbo Mediation Pod

Monitored Resources

Workload Optimization Manager monitors quotas (limits and requests) for VCPU and VMem, and associates how much each Workload Controller is contributing to a quota based on all replicas. This allows Workload Optimization Manager to generate rightsizing decisions, and manage the quota as a constraint to rightsizing. Metrics on resource consumption are shown in the Container Spec, Container, and Container Pod views.

Workload Controller Actions

Workload Optimization Manager can recommend the following actions:



Resize or Scale

Actions associated with a Workload Controller resize Container Specs vertically or scale replicas horizontally. This is a natural representation of these actions because the parent controller's Container Specs and number of replicas are modified. The Workload Controller then rolls out the changes in the running environment.

For details, see Workload Controller Resize Actions (on page 352) and Workload Controller Scale Actions (on page 356).

Workload Controller Resize Actions

Actions associated with a Workload Controller resize Container Specs vertically to assure optimal utilization of resources. The Workload Controller then rolls out the changes in the running environment.

Resize Up Actions In Response to CPU Throttling

For vCPU limit resizes, Workload Optimization Manager will recommend a resize up action, even if utilization percentile is low, to address slow response times associated with CPU throttling.

CPU throttling occurs when you configure a CPU limit on a container, which can inadvertently slow your applications' response time. Even if you have more than enough resources on your underlying node, your container workload will still be throttled because it was not configured properly. High response times are directly correlated to periods of high CPU throttling, and this is exactly how Kubernetes was designed to work.

Learn more about CPU throttling here.

Especially for sudden throttling spikes, Workload Optimization Manager will persist the related resize actions so you can evaluate these actions even after the spikes have gone away, and then execute them to prevent spikes from re-occurring. As throttling drops, Workload Optimization Manager will not recommend a resize down action right away, as this could result in subsequent back-and-forth upsize and downsize recommendations. Instead, it evaluates past throttling to decide when a resize down action is finally safe to execute. To ensure the timeliness of these actions and arrive at the optimal resize values to recommend, Workload Optimization Manager calculates fast and slow moving throttling averages, and then displays *smoothed* and *daily* averages in charts.

Smoothed average is an exponential moving average and moving variance method used on CPU throttling data. It allows analysis to generate a vCPU limit resize up action more quickly when throttling is detected, and be conservative on resize down to mitigate introducing throttling.

Action Propagation

Resize actions propagate to application entities and the underlying container infrastructure to show the impact of these actions on the health of your applications and container environment.

Action Merging

Executing several resize actions via Workload Controllers can be very disruptive since pods need to restart with each resize. For replicas of the container scale group(s) related to a single Workload Controller, Workload Optimization Manager consolidates resize actions into one *merged action* to minimize disruptions. When a merged action has been executed (via the associated Workload Controller), all resizes for all related container specifications will be changed at the same time, and pods will restart once.

Action Execution


After you set the scope to Workload Controllers, go to Action Center to see the full list of resize actions that you can execute. This list includes individual and merged actions. You can filter the list to focus on specific actions, such as actions to address resource congestion or vCPU throttling.





By default, resize actions are set in *Manual* mode at the Workload Controller level. This means that Workload Optimization Manager will not execute any action automatically, and you can manually select the actions that you want to execute. If you prefer to execute actions outside Workload Optimization Manager, create Workload Controller policies and set the resize action acceptance mode to *Recommend*. To automate actions, create Workload Controller policies and set the resize action acceptance mode to *Automatic*.

For each action, click DETAILS and expand the Details section to view time series charts that explain the reason for the action. These charts highlight *utilization percentiles* and *smoothed throttling averages* for a given observation period. Workload Optimization Manager uses percentile calculations to make accurate resize decisions.



These charts also:

- Plot daily average percentiles and throttling, for your reference.
- Show projected percentiles after you execute the action. If you have previously executed resize actions on the same Workload Controller, the charts show the resulting improvements in daily average utilization.

Put together, these charts allow you to easily recognize trends that drive Workload Optimization Manager's resize recommendations.



NOTE:

You can set scaling constraints in Container Spec policies to refine the percentile calculations. For details, see <u>Aggressiveness</u> and Observation Periods (on page 350).


Blocking of Action Execution Due to Insufficient Quotas

Workload Optimization Manager treats quotas defined in a namespace as constraints when making resize decisions. If existing actions would exceed the namespace quotas, Workload Optimization Manager recommends actions to resize up the affected namespace quota.

NOTE:

For more information about namespace quotas, see Namespace Monitored Resources (on page 365).

The action details for a Workload Controller include descriptions of the affected Container Spec entities, and how the resources will change for each. If the resize exceeds current namespace quotas, then Workload Optimization Manager blocks the Workload Controller action. The action details list the Namespace actions that block execution of this resize in the **Related Actions** list.




Tuned Resizing

Workload Optimization Manager can automate resizes if the resize values fall within a normal range, and then post more conservative actions when resize values fall outside the range. To do this, you would set specific action acceptance modes and tuned resizing values in policies.

For example, consider resizing vMem limits. As memory demand increases, Workload Optimization Manager can automatically execute vMem limit resizes that fall within the normal range. If the Container Spec requests memory beyond the normal range, Workload Optimization Manager will either ignore the action or post it for you to review, depending on the tuned resizing settings that you configured.

Assume the following tuned scaling settings in policies:





- The **Operational Constraints** settings in the Container Spec policy specify 100 MB to 500 MB as the normal range.
- With the **Resize** action acceptance mode in the Workload Controller policy set to *Automatic*, Workload Optimization Manager will automate *resize up* actions that are below the *max* threshold and *resize down* actions that are above the *min* threshold.

NOTE:

If the action acceptance mode is *Recommend*, Workload Optimization Manager will post the actions for you to review. You can only execute these actions outside Workload Optimization Manager.

- In the Container Spec policy, since the action acceptance mode for vMem Limit Resize Above Max and vMem Limit Resize Below Min is set to Disabled, Workload Optimization Manager will not generate resize actions that fall outside the normal range.
- Since vMEM increment constant is not defined in the Container Spec policy, Workload Optimization Manager uses the
 default value of 128 MB.

With these two policies in effect:

- If a Container Spec with 200 MB of vMEM limit needs to resize to 328 MB, Workload Optimization Manager automatically resizes to 328 MB.
- If a Container Spec with 200 MB of vMEM limit needs to resize to 72 MB, Workload Optimization Manager does not generate the action. vMEM limit remains at 200 MB.

NOTE:

Action policies include scope to determine which entities will be affected by the given policy. It's possible for two or more policies to affect the same entities. As is true for other policy settings, Workload Optimization Manager uses the most conservative settings for the affected entities.

For tuned resizing, the effective action acceptance mode will be the most conservative, and the effective tuned resizing range will be the narrowest range (the lowest *Max* and highest *Min*) out of the multiple policies that affect the given entities. For more information, see <u>Default and User-defined Policies</u> (on page 677).

Downloading Data for Executed Resize Actions

You can view and download data for executed resize actions to gain insight into workloads with performance risks due to resource limits, as well as opportunities to reclaim unused resource requests.

Add the Actions chart to your dashboard.



- 2. Configure the chart. Be sure to set the scope to Workload Controllers to narrow the results, select Tabular as the chart type, and then set the filter to either All Actions or Executed Actions.
- 3. In the chart, click Show All.
- In the page that opens, click the download button at the top-right section of the page. If you set All Actions as the filter, select Executed Actions.
- 5. Open the downloaded file and go to the Resize Workload Controller sheet.

Pay attention to the following columns:

- Namespace, Container Spec, and Container Cluster columns Data in these columns is the most up-to-date at the time of download.
- Change column This column highlights the impact of resize actions on the resources allocated to containers. Each value represents the difference between the Current Value and New Value columns.
- Container Spec column If there is more than one Container Spec in a Workload Controller, you can sort this column to easily identify resize actions on individual Container Specs.
- Impacted Commodity column This column shows if VMem or VCPU was resized. A resize action might show both commodities, which indicates that it is a *merged* action (an action that consolidates resizes related to a single Workload Controller, to minimize disruptions).

Workload Controller Scale Actions

Actions associated with a Workload Controller scale the replicas that back horizontally scalable <u>Kubernetes Services</u> (on page 338) to maintain SLOs for your applications. The Workload Controller then rolls out the changes in the running environment.

For example, when current response time for an application is in direct violation of SLO, Workload Optimization Manager will recommend increasing the number of replicas to improve response time. If applications can meet SLOs using less resources, Workload Optimization Manager will recommend reducing the replica count to improve infrastructure efficiency.

Action Generation Requirements


Workload Optimization Manager generates SLO-driven scale actions under the following conditions:

- Kubernetes Services are discovered by the <u>Kubeturbo</u> pod that you have deployed in your environment.
- Application performance metrics for Services are collected via the Instana (on page 156) target.
- You have created policies for the Services. You can create policies from the user interface or by using Custom Resources (CRs). For details, see <u>Kubernetes Service Policies</u> (on page 339).

Action Visibility


Workload Optimization Manager shows and executes SLO-driven scale actions via Workload Controllers. A single scale action represents the total number of replicas that you need to scale in or out to meet your SLOs.






When you examine an action, Response Time and/or Transaction SLO is indicated as the reason for the action.









Workload Controller Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

Actions associated with a Workload Controller resize Container Specs vertically or scale replicas horizontally. This is a natural representation of these actions because the parent controller's Container Specs and number of replicas are modified. The Workload Controller then rolls out the changes in the running environment.

For details, see Workload Controller Resize Actions (on page 352) and Workload Controller Scale Actions (on page 356).

Action	Default Mode
Resize Container Specs	Manual (automatable)
Scale replicas	Manual (automatable)

Action orchestration is currently not supported.


Container Pod

A container pod is a group of one or more containers with shared storage or network resources. It is the smallest deployable unit of computing that you can create and manage in Kubernetes.

A container pod specifies how to run containers together. Like containers, a container pod is ephemeral.



Synopsis



Synopsis	
Provides:	Resources for containers to use, including:
	■ Virtual CPU
	■ Virtual Memory
Consumes:	Resources from virtual machines and namespaces
Discovered through:	Kubeturbo pod that you have deployed in your environment

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Virtual Memory (VMem)
 - Virtual Memory is the measurement of memory that is in use.
- VMem Request
 - VMem Request is the virtual memory request allocated by a pod against the node allocatable capacity.
- Virtual CPU (VCPU)
 - Virtual CPU is the measurement of CPU that is in use.
- VCPU Request
 - VCPU Request is the virtual CPU request (in mCores) allocated by a pod against the node allocatable capacity.



Actions

Workload Optimization Manager can recommend the following actions:

Move

Move a pod between nodes (VMs) to address performance issues or improve infrastructure efficiency. For example, if a particular node is congested for CPU, you can move pods to a node with sufficient capacity. If a node is underutilized and is a candidate for suspension, you must first move the pods before you can safely suspend the node.

■ Provision/Suspend

When recommending node provision or suspend actions, Workload Optimization Manager will also recommend provisioning pods (based on demand from DaemonSets) or suspending the related pods.

Pod Move Actions

The following items impact the generation and execution of pod move actions:

Constraints

Workload Optimization Manager respects the following constraints when making placement decisions for pods:

- Kubernetes taints for nodes and tolerations for pods are treated as constraints. For example, if a pod has a toleration attribute that restricts it from moving to a certain node, Workload Optimization Manager will not move that pod to the restricted node.
- Workload Optimization Manager imports Kubernetes node labels and treats them as constraints. For example, if a pod
 has a defined node label, Workload Optimization Manager will move that pod to a node with a matching label.
- Workload Optimization Manager recognizes pod affinity and anti-affinity policies.
- You can create placement policies to enforce constraints for pod move actions. For example, you can have a policy that allows pods to only move to certain nodes, or a policy that prevents pods from moving to certain nodes.

For more information, see Creating Placement Policies (on page 673).

Eviction Thresholds

Workload Optimization Manager considers the memory/storage eviction thresholds of the destination node to ensure that the pod can be scheduled after it moves. Eviction thresholds for imagefs and rootfs are reflected as node effective capacity in the market analysis.

Temporary Quota Increases

If a namespace quota is already fully utilized, Workload Optimization Manager temporarily increases the quota to allow a pod to move.

■ Security Context Constraints (SCCs)

Red Hat OpenShift uses <u>SCCs</u> to control permissions for pods. This translates to permissions that users see within the containers of the pods, and the permissions for the processes running inside those pods.

When executing pod move actions, Kubeturbo normally runs with OpenShift cluster administrator permissions to create a new pod and remove the old one. Because of this, the SCCs for the new pod are those that are available to a cluster administrator. It is therefore possible for the new pod to run with an SCC that has higher privileges than the old pod. For example, an old pod might have restricted scc access, while the new one might have anyuid scc access. This introduces a privilege escalation issue.

To prevent privilege escalation when moving pods, Kubeturbo enforces user impersonation, which carries the user-level SCCs of the old pod over to the new pod. To enforce user impersonation, Kubeturbo performs the following tasks:

- Create a <u>user impersonation account</u> for each SCC level.
- Create a <u>service account</u> and treat it as a user account for each SCC level currently running in a given cluster.
- Provide <u>role-based access</u> to SCCs used for impersonation via the service accounts. A service account is allowed to
 use only one SCC resource in the cluster.
- Create a role binding resource to allow service account access to a particular role.

All resources created to enforce user impersonation are removed when Kubeturbo shuts down.

Be aware that by default, an arbitrary pod running in a given cluster does not recognize the namespace it is configured to run in, which is a requirement for user impersonation enforcement. For Kubeturbo to recognize the namespaces for pods, we recommend adding an environment variable named KUBETURBO_NAMESPACE via the downward API. Our standard installation methods add the following environment variable to the Kubeturbo deployment spec.



```
env:
    - name: KUBETURBO_NAMESPACE
    valueFrom:
        fieldRef:
            fieldPath: metadata.namespace
```

With this environment variable, Kubeturbo can successfully create the resources needed to enforce user impersonation. Without this variable, Kubeturbo creates the resources in the namespace called default. This might cause issues if you need to run multiple instances of Kubeturbo in the same cluster. For example, one instance might run as an observer, and another as an administrator. To ensure multiple Kubeturbo instances within the same cluster do not conflict when creating and removing user impersonation resources, run the instances in separate namespaces.

Pod Provision Action in Response to Node Provision

When recommending node provision actions, Workload Optimization Manager also recommends pod provision actions that reflect the projected demand from required DaemonSet pods, and respects the maximum number of pods allowed for a node. This ensures that any application workload can be placed on the new node and stay within the desired range of vMem/vCPU usage, vMem/vCPU request, and number of consumers.


The action details for a pod provision action shows the related node that you need to provision. Click the node name to set it at your scope.



Workload Optimization Manager treats <u>static pods</u> as DaemonSets for the purpose of provisioning nodes. Because a static pod provides a node with a specific capability, it is controlled by the node and is not accessible through the API server. If a node to be provisioned requires a static pod, Workload Optimization Manager generates actions to provision the node and the corresponding static pod.

Workload Optimization Manager creates an auto-generated group of static pods when it discovers a static pod on each node in a cluster. To view all the auto-generated groups, go to Search, select Groups, and then type mirror pods as your search keyword.






Pod Suspension Action in Response to Node Suspension

When recommending node suspension actions, Workload Optimization Manager also recommends suspending the DaemonSet pods that are no longer required to run the suspended nodes.


The action details for a pod suspension action shows the related node that you need to suspend. Click the node name to set it at your scope.



Workload Optimization Manager treats static pods as DaemonSets for the purpose of suspending nodes. Because a static pod provides a node with a specific capability, it is controlled by the node and is not accessible through the API server. If the only workload type left on a node is a static pod, Workload Optimization Manager generates actions to suspend the node and the corresponding static pod.



Workload Optimization Manager creates an auto-generated group of static pods when it discovers a static pod on each node in a cluster. To view all the auto-generated groups, go to Search, select Groups, and then type mirror pods as your search keyword.



Container Pod Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

For details about container pod actions, see Container Pod Actions (on page 361).

Action	Default Mode
Move	Manual

Action orchestration is currently not supported.

Placement Policies

You can create placement policies to enforce constraints for pod move actions. For example, you can have a policy that allows pods to only move to certain nodes, or a policy that prevents pods from moving to certain nodes.


For more information, see Creating Placement Policies (on page 673).

Namespace

A namespace is a logical pool of resources in a Kubernetes environment that manages workloads based on specific requirements or business needs. For example, administrators can pool resources for different organizations within the enterprise, and assign different policies to each pool.



Synopsis



Synopsis	
Provides:	N/A
Consumes:	N/A
Discovered through:	Kubeturbo Mediation Pod

Labels and Annotations

Workload Optimization Manager discovers namespace labels and annotations as tag properties. You can filter namespaces by labels or annotations when you use Search or create Groups.

Monitored Resources

A namespace can include the following compute resource quotas:


- VMem Request Quota
 - VMem Request Quota is the total amount of virtual memory request for all pods allocated to the namespace against the namespace quota.
- VCPU Request Quota
 - VCPU Request Quota is the total amount of virtual CPU request (in mCores) for all pods allocated to the namespace against the namespace quota.
- VMem Limit Quota
 - VMem Limit Quota is the total amount of virtual memory limit for all pods allocated to the namespace against the namespace quota.
- VCPU Limit Quota
 - VCPU Limit Quota is the total amount of virtual CPU limit (in mCores) for all pods allocated to the namespace against the namespace quota.

When configured, these quotas define the capacity for the given namespace. Workload Optimization Manager monitors actual utilization of these quotas against cluster capacity.




Points to consider:

- When you scope to a namespace in the supply chain, you can see utilization data in the Capacity and Usage and Namespace Multiple Resources charts. With this data, you can understand how pods running in the namespace are consuming resources.
- The Capacity and Usage chart shows Capacity as the namespace quotas. Used values are the sum of resource limits and/or requests set for all pods in the namespace.



For a namespace that does not have defined quotas, *Capacity* for the commodity is infinite (as shown in the image below). *Used* values are the sum of resource limits and/or requests set for all pods in the namespace. If these are not set, *Used* value is 0 (zero).



NOTE

If you download the data in the chart, the downloaded file shows infinite capacities as unusually large values (for example, 1,000,000,000 cores instead of the ∞ symbol).

- To see which namespaces use the most cluster resources, set the scope to a container cluster and see the Top Namespaces chart. You can use the data in the chart for showback analysis.
- When you run Optimize Container Cluster plans, Workload Optimization Manager can calculate increased namespace quotas in the plan results. For more information, see <u>Optimize Container Cluster Plan (on page 540)</u>.

Namespace Actions

Workload Optimization Manager can recommend the following actions:


Resize Quota



Workload Optimization Manager treats quotas defined in a namespace as constraints when making resize decisions. If existing actions would exceed the namespace quotas, Workload Optimization Manager recommends actions to resize up the affected namespace quota.

Note that Workload Optimization Manager does not recommend actions to resize *down* a namespace quota. Such an action reduces the capacity that is already allocated to an application. The decision to resize down a namespace quota should include the application owner.

When you have a recommendation to resize namespace quotas, Workload Optimization Manager blocks execution of the resize actions for the affected Workload Containers. The action details show these blocked actions in the **Related Actions** list.



NOTE:

For more information about execution of resize actions via Workload Controllers, see <u>Workload Controller Resize Actions (on page 352)</u>.

Temporary Increases in Namespace Quotas

Workload Optimization Manager can increase namespace quotas temporarily under the following conditions:

- Workload Optimization Manager temporarily increases the quota to allow the clone of the pod that is being moved to be scheduled.
- When executing actions to resize a Workload Controller in a namespace with a defined quota, Workload Optimization Manager can increase the namespace quota temporarily to accommodate new replicas.

When the execution of a resize action requires new replicas, a Kubernetes workload usually has a rolling update strategy defined. Even if the namespace quota is sufficient for the resource requirement of the new replicas, there is a chance that the quota is not enough to accommodate both the old and new replicas, as required by the rolling update. In this case, Kubeturbo calculates and then increases the quota based on the resources required by both the old and new replicas. Kubeturbo reverts the quota to its original size after the new replicas have been scheduled on a node.


Container Cluster

A Container Cluster is a Kubernetes cluster that Workload Optimization Manager discovers through Kubeturbo. With this entity type, Workload Optimization Manager can fully link the entire container infrastructure with the underlying nodes, and then



present all actions on containers and nodes in a single view. This gives you full visibility into the actions that impact the health of your container environment.

Synopsis



Synopsis	
Provides:	N/A
Consumes:	N/A
Discovered through:	Kubeturbo Mediation Pod

Integration with Git-based Software via Argo CD

Workload Optimization Manager integrates with Git-based software via ArgoCD, a GitOps continuous delivery tool that manages ArgoCD Application resources using Custom Resources (CRs). With this integration, Workload Optimization Manager can identify the container cluster resources managed by Argo CD, and then execute resize actions against the Git-based version control software serving as Argo CD's 'source of truth'. Argo CD completes the action by synchronizing changes onto the running environment.

Workload Optimization Manager currently supports the following definitions:

Workload Definition - Path to Version Control Software	Version Control Software	Application Packaging
ArgoCD Application CR in cluster	GitHub or GitLab	None (straight YAMLs)



Workload Definition - Path to Version Control Software	Version Control Software	Application Packaging
ArgoCD ApplicationSet CR in cluster		

For detailed integration instructions, visit this page.


Monitored Resources

Workload Optimization Manager monitors resources for the containers, pods, nodes (VMs), and volumes in a cluster.

Actions

None

Workload Optimization Manager does not recommend actions for a Container Cluster. Instead, it recommends actions for the containers, pods, nodes (VMs), and volumes in the cluster. Workload Optimization Manager shows all of these actions when you scope to a Container Cluster and view the Pending Actions chart.



For actions on nodes:

- For actions to suspend or provision nodes in the public cloud, Workload Optimization Manager includes cost information (investments or savings) attached to those actions. Note that Workload Optimization Manager generates these actions not to optimize costs, but to assure performance and efficiency for your container infrastructure. Workload Optimization Manager reports costs to help you track your cloud spend.
 - To view cost information, set the scope to a cluster in the public cloud and view the Necessary Investments or Potential Savings charts. You can also set the scope to the global cloud environment to see total costs, or to individual container clusters or nodes.
- For VMs/nodes that make up an Azure Kubernetes Service (AKS) cluster, you can manually execute recommended VM Provision and VM Suspend actions. This adjusts the count of nodes in a given node pool, where Provision raises the node count, and Suspend lowers it. You can execute these actions if the cluster is also discovered through an Azure target (along with the KubeTurbo target).
- Node pools and machine sets are ways to deploy and scale compute resources for Kubernetes services hosted in the public cloud and the Red Hat OpenShift 4.x container platform on any infrastructure.

For Kubernetes services in the public cloud, Workload Optimization Manager uses default labels with the following patterns to discover the node pool types within each cluster:

- Azure Kubernetes Service (AKS): agentpool
- Amazon Elastic Kubernetes Service (EKS):

```
//alpha.eksctl.io/nodegroup-name
```


eks.amazonaws.com/nodegroup

Google Kubernetes Engine (GKE): cloud.google.com/gke-nodepool

For Red Hat OpenShift 4.x, Workload Optimization Manager creates node pools based on machine sets.



For both discovered and auto-created node pools, Workload Optimization Manager aggregates and visualizes actions for all the nodes in a pool to help you identify performance issues and optimization opportunities at the node pool level. Use the Top Node Pools chart to see actions and detailed information. By default, this chart displays when you set the scope to your global environment and then click the Container Cluster entity in the supply chain.



The chart shows the number of nodes and aggregated actions for each node pool. For node pools in the public cloud, the chart also shows the costs you would incur if you provision nodes and then scale their volumes, or the savings you would realize if you suspend nodes. To view individual actions, click the button under the Actions column. To see more details, including the full list of nodes for each pool, click the node pool name.

You can automate the execution of these actions through Workload Optimization Manager with Red Hat OpenShift 4.x Machine Operator, or via an Action Script. You can also manually execute node actions for AKS, EKS, or GKE via the cloud provider.

NOTE

The following capabilities will be introduced in a future release:


- Actions to provision or suspend nodes via a plan simulation
- Policies for node pools
- Execution of node actions for AKS, EKS and GKE through Workload Optimization Manager

Cluster Health

To assess the health of each cluster, see the **Top Container Platform Clusters** chart in the predefined Container Platform Dashboard.

For each cluster, the chart shows the sum of resources used by containers and the underlying nodes. Click the **Actions** button to see a list of pending actions.





The **Top Namespaces** chart shows the namespaces that use the most cluster resources. You can use the data in the chart for showback analysis.




Virtual Machine (Kubernetes Node)

In Kubernetes environments, a node is a virtual or physical machine that contains the services necessary to run pods. Workload Optimization Manager represents nodes as Virtual Machine entities in the supply chain.

Workload Optimization Manager can discover node roles and Master Nodes. It creates policies to keep nodes of the same role on unique host or Availability Zone providers, and policies to disable suspension of Master Nodes. Workload Optimization Manager also discovers and displays Node Pools, and Red Hat OpenShift Machine Sets.



Synopsis



Synopsis	
Provides:	Resources to pods
Consumes:	Resources from container clusters
Discovered through:	Kubeturbo Mediation Pod

Monitored Resources

Workload Optimization Manager monitors the following resources:

NOTE: These are resources for nodes that host Kubernetes pods. They are monitored along with the resources from the infrastructure probes, such as vCenter or a public cloud mediation probe.

- VMem
 - VMem is the virtual memory currently used by all containers on the node. The capacity for this resource is the Node Physical capacity.
- VCPU
 - VCPU is the virtual CPU currently used by all containers on the node. The capacity for this resource is the Node Physical capacity.
- Memory Request Allocation
 - Memory Request Allocation is the memory available to the node to support the ResourceQuota request parameter for a given namespace (Kubernetes namespace or Red Hat OpenShift project).
- CPU Request Allocation
 - CPU Request Allocation is the CPU available to the node to support the ResourceQuota request parameter for a given namespace (Kubernetes namespace or Red Hat OpenShift project).
- Virtual Memory Request



Virtual Memory Request is the memory currently guaranteed by all containers on the node with a memory request. The capacity for this resource is the Node Allocatable capacity, which is the amount of resources available for pods and can be less than the physical capacity.

■ Virtual CPU Request

Virtual CPU Request is the CPU currently guaranteed by all containers on the node with a CPU request. The capacity for this resource is the Node Allocatable capacity, which is the amount of resources available for pods and can be less than the physical capacity.

Memory Allocation

Memory Allocation is the memory ResourceQuota limit parameter for a given namespace (Kubernetes namespace or Red Hat OpenShift project).

■ CPU Allocation

CPU Allocation is the CPU ResourceQuota limit parameter for a given namespace (Kubernetes namespace or Red Hat OpenShift project).

Actions

Workload Optimization Manager can recommend the following actions:

Provision

Provision nodes to address workload congestion or meet application demand.

Suspend

Suspend nodes after you have consolidated pods or defragmented node resources to improve infrastructure efficiency.

Reconfigure

Reconfigure nodes that are currently in the NotReady state.

NOTE:

For nodes in the public cloud, Workload Optimization Manager reports the cost savings or investments attached to node and provision actions. For example, you can see the additional costs you would incur if you provision nodes and then scale their volumes, or the savings you would realize if you suspend nodes. Note that performance and efficiency are the drivers of these actions, *not* cost. Cost information is included to help you track your cloud spend. For this reason, you will *not* see costoptimization actions, including recommendations to re-allocate discounts or delete unattached volumes.


To view cost information, set the scope to a node and see the Necessary Investments and Potential Savings charts. You can also set the scope to a <u>container cluster</u> (on page 367) or the global cloud environment to view aggregated cost information.

Node Provision Actions

When recommending node provision actions, Workload Optimization Manager also recommends pod provision actions that reflect the projected demand from required DaemonSet pods, and respects the maximum number of pods allowed for a node. This ensures that any application workload can be placed on the new node and stay within the desired range of vMem/vCPU usage, vMem/vCPU request, and number of consumers.

The action details for a node provision action show the related DaemonSet pods that are required for the node to run. Click a pod name to set it at your scope.





Workload Optimization Manager treats <u>static pods</u> as DaemonSets for the purpose of provisioning nodes. Because a static pod provides a node with a specific capability, it is controlled by the node and is not accessible through the API server. If a node to be provisioned requires a static pod, Workload Optimization Manager generates actions to provision the node and the corresponding static pod.

Node Suspension Actions

When recommending node suspension actions, Workload Optimization Manager also recommends suspending the DaemonSet pods that are no longer required to run the suspended nodes.

The action details for a node suspension action show the related DaemonSet pods that are no longer needed to run the suspended nodes. Click a pod name to set it at your scope.





Workload Optimization Manager treats static pods as DaemonSets for the purpose of suspending nodes. Because a static pod provides a node with a specific capability, it is controlled by the node and is not accessible through the API server. If the only workload type left on a node is a static pod, Workload Optimization Manager generates actions to suspend the node and the corresponding static pod.

Node Reconfigure Actions

Workload Optimization Manager generates node reconfigure actions to notify you of nodes that are currently in the NotReady state.


A reconfigure action should change a node's state to Ready so that Workload Optimization Manager can begin to monitor the health of the node and the associated container pods. This action is read-only and must be executed outside Workload Optimization Manager. As part of action execution, you might need to restart the node or the kubelet agent on the node.

NOTE:


Workload Optimization Manager treats a node as a VM under certain circumstances. For example, it treats a node in vCenter as a VM that can move to a different host if the current host is congested. This means that for a NotReady node in vCenter, it is possible to see a VM move action along with the expected node reconfigure action. Both actions are valid and safe to execute since they achieve two different and non-conflicting results.

For each Kubernetes cluster, Workload Optimization Manager creates an auto-generated group of NotReady nodes. To view all the auto-generated groups, go to Search, select Groups, and then type notready as your search keyword. Click a group to view the individual nodes and the pending reconfigure actions.





When you examine a pending reconfigure action, you can click the link in the 'Entities Impacted by this Node' section to view a list of impacted pods.




These pods are in the Unknown state and are not controllable. In the supply chain and in the list of container pods, these pods display with a gray color to help you differentiate them from other pods.

Kubernetes CPU Metrics

To meet user requirements and align with Kubernetes specifications, Workload Optimization Manager uses millicore (mCore) as the base unit for CPU metrics for your Kubernetes platform.





These include metrics for the following CPU-related commodities:

- vCPU
- vCPU Request
- vCPU Limit Quota
- vCPU Request Quota

Workload Optimization Manager displays these commodities in charts, actions, policies, and plans. For example:

- In the Capacity and Usage chart for container platform entities, capacity and used values for CPU-related commodities are shown in mCores.
- In the supply chain, when you scope to a Workload Controller to view pending <u>resize actions (on page 346)</u> for a container, you will see utilization and resize values in mCores.
- When you create <u>Container Spec policies (on page 348)</u>, resize thresholds and increment constants for CPU-related commodities are set in mCores.
- For an Optimize Container Cluster plan, the <u>plan results (on page 543)</u> for CPU-related commodities are shown in mCores.

For nodes (VMs) and Application Components:

- For nodes stitched to your Kubernetes platform, the base unit for *vCPU Request* is also mCore, since this commodity is provided only to Kubernetes.
- For both nodes and Application Components (standalone or stitched to your Kubernetes platform), the base unit for *vCPU* is MHz, since this is a generic commodity. For example, when you view a pod move action, vCPU metrics for the current and destination nodes for the pod are expressed in MHz.

The following table summarizes the base units of CPU measurement that Workload Optimization Manager uses.

Entity	CPU Commodity			
Littly	vCPU	vCPU Request	vCPU Limit Quota	vCPU Request Quota
Container	mCore	mCore	mCore	mCore



Entity	CPU Commodity			
Entity	vCPU	vCPU Request	vCPU Limit Quota	vCPU Request Quota
Container Spec	mCore	mCore	N/A	N/A
Workload Controller	N/A	N/A	mCore	mCore
Container Pod	mCore	mCore	mCore	mCore
Namespace	mCore	mCore	mCore	mCore
Container Cluster	mCore	mCore	N/A	N/A
Node (VM)	MHz	mCore	N/A	N/A
Application Component	MHz	N/A	N/A	N/A

This feature is available starting in version 3.0.5. For customers updating to version 3.0.5 or later:

- This feature does *not* require you to update your Kubeturbo image after the update.
- For time series charts, metrics generated *after* the update are actual mCore values, but pre-update metrics are the same (unconverted) values in MHz displayed in mCore units. This results in unexpected data in charts immediately after the update.

For example:

If vCPU Limit for a Container Spec was resized from 1300 MHz to 1200 MHz before you updated Workload Optimization Manager, data points in charts correctly show these values in MHz.

Immediately after the update:

- When you view the Virtual CPU chart for the Container Spec, Workload Optimization Manager will show a capacity value of 1200 mCores (which is 1200 MHz in reality) for the last data point before the update, and the equivalent value of 500 mCores for the first data point after the update. This gives the impression of a resize down action between the data points, even if no such action was executed.
- Assume Workload Optimization Manager recommends an action to resize VCPU Limit for the Container Spec from 500 to 700 mCores. When you view the details for this action via the associated Workload Controller, the time series chart will show unexpected data.
 - For the actual recommended action, the data point shows current capacity as 1200 mCores, instead of 500 mCores. The new value after executing the action correctly shows as 700 mCores.
 - For the last resize action before the update, the data point shows the same MHz values (1300 and 1200), but in mCore units.
 - One day after the update, a new data point displays in the chart, indicating that capacity was resized from 1200 mCores to 500 mCores, even if no actual resize action was executed.


Over time, data points with unexpected values will begin to fall out of range and newer data points will reflect actual mCore values.

■ For increment constants in Container Spec policies, the default value of 100 remains unchanged, but the unit changes from MHz to mCores. This means that each resize action will now increase or decrease capacity by 100 mCores, instead of 100 MHz.

Entity Types - Cloud Infrastructure

Workload Optimization Manager discovers and monitors the entities that make up your cloud infrastructure, and recommends actions to assure application performance at the lowest possible cost.





Virtual Machine (Cloud)


A virtual machine (VM) is a software emulation of a physical machine, including OS, virtual memory and CPUs, and network ports. VMs host applications, or they provide resources to container platforms.

NOTE:

Kubernetes nodes are represented as Virtual Machines in the Workload Optimization Manager supply chain. For details about nodes, see <u>Virtual Machine</u> (<u>Kubernetes Node</u>) *(on page 371)*.



Synopsis



Synopsis	
Provides:	Resources for applications to use
Consumes:	Resources from cloud zones or regions
Discovered through:	Public cloud targets

Monitored Resources

For details about monitored resources for cloud VMs, see the following topics:

- AWS Monitored Resources (on page 241)
- Azure Monitored Resources (on page 271)
- GCP Monitored Resources (on page 257)



Cloud VM Actions

For details about cloud VM actions, see the following topics:

- Actions for AWS VMs (on page 381)
- Actions for Azure VMs (on page 383)
- Actions for GCP VMs (on page 385)

Actions for AWS VMs

Workload Optimization Manager can recommend the following actions:

Scale

Change the VM instance to use a different instance type or tier to optimize performance and costs.

See additional information for scale actions below.

Discount-related actions

If you have a high percentage of on-demand VMs, you can reduce your monthly costs by increasing RI coverage. To increase coverage, you scale VMs to instance types that have existing capacity.

If you need more capacity, then Workload Optimization Manager will recommend actions to purchase additional Rls.

Purchase actions should be taken along with the related VM scaling actions. To purchase discounts for VMs at their current sizes, run a <u>Buy VM Reservation Plan (on page 577)</u>.

Stop and Start (also known as 'parking' actions)

Stop a VM for a given period of time to reduce your cloud expenses, and then start it at a later time.

For details, see Parking: Stop or Start Cloud Resources (on page 597).

Controlling Scale Actions for AWS VMs

For scale actions, you can create policies to control the scale actions that Workload Optimization Manager recommends. In those policies, choose from the following options:

- Cloud Scale All execute all scaling actions
- Cloud Scale for Performance only execute scaling actions that improve performance
- Cloud Scale for Savings only execute scaling actions that reduce costs

The default action acceptance mode for these actions is *Manual*. When you examine the pending actions, only actions that satisfy the policy are allowed to execute. All other actions are read-only.

When policy conflicts arise, **Cloud Scale All** overrides the other two scaling options in most cases. For more information, see Default and User-defined Automation Policies (on page 677).

Supported Instance Types for AWS VMs

Workload Optimization Manager considers all supported instance types when making scaling decisions for cloud VMs. If you want your VMs to *only scale to* or *avoid* certain instance types, create policies for those VMs.

You can view the instance types that Workload Optimization Manager supports from the user interface.

- Navigate to Settings > Policies.
- 2. In the Policy Management page, search for and click Virtual Machine Defaults.
- 3. In the Configure Virtual Machine Policy page:
 - a. Scroll down to the bottom of the page.
 - b. Click Add Scaling Constraint.
 - c. Choose Cloud Instance Types.
 - d. Click Edit.

The policy page shows supported tiers for each cloud provider. A tier is a family of instance types, such as *M1* for GCP, *a1* for AWS and *Basic_A1* for Azure. Expand a tier to see individual instance types and resource allocations.



Scaling Prerequisites for AWS VMs

In AWS some instances require VMs to be configured in specific ways before they can scale to those instance types. If Workload Optimization Manager recommends scaling a VM that is not suitably configured onto one of these instances, then it sets the action to *Recommend*, and describes the reason. Workload Optimization Manager will not automate the action, even if you have set the action acceptance mode for that scope to *Automatic*. You can execute the action manually, after you have properly configured the instance.

Note that if you have VMs that you cannot configure to support these requirements, then you can set up a policy to keep Workload Optimization Manager from making these recommendations. Create a group that contains these VMs, and then create policy for that scope. In the policy, exclude instance types by configuring the Cloud Instance Types scaling constraint. For information about excluding instance types, see Cloud Instance Types (on page 399).

The instance requirements that Workload Optimization Manager recognizes are:

Enhanced Network Adapters

Some VMs can run on instances that support Enhanced Networking via the Elastic Network Adapter (ENA), while others can run on instances that do not offer this support. Workload Optimization Manager can recommend scaling a VM that does not support ENA onto an instance that does. However, you must enable ENA on the VM before executing the scaling action. If you scale a non-ENA VM to an instance that requires ENA, then AWS cannot start up the VM after the scaling action.

For information about ENA configuration, visit this page.

■ Linux AMI Virtualization Type

An Amazon Linux AMI can use ParaVirtual (PV) or Hardware Virtual Machine (HVM) virtualization. Workload Optimization Manager can recommend scaling a PV VM to an HVM instance that does not include the necessary PV drivers.

To check the virtualization type of an instance, open the Amazon EC2 console to the Details pane, and review the Virtualization field for that instance.

■ 64-bit vs 32-bit

Not all AWS instance can support a 32-bit VMs. Workload Optimization Manager can recommend scaling a 32-bit VM to an instance that only supports a 64-bit platform.

NVMe Block

Some instances expose EBS volumes as NVMe block devices, but not all VMs are configured with NVMe drivers. Workload Optimization Manager can recommend scaling such a VM to an instance that supports NVMe. Before executing the action, you must install the NVMe drivers on the VM.

In addition, Workload Optimization Manager recognizes processor types that you currently use for your VM. For scale actions, Workload Optimization Manager keeps your VMs on instance types with compatible processors:

GPU-based instances:

Workload Optimization Manager recognizes when your VM is on a GPU-based instance. To ensure the VM always stays on a compatible processor, Workload Optimization Manager does not recommend scale actions.

ARM-based instances

If your VM is on an ARM-based instance, then Workload Optimization Manager will only recommend scaling to other compatible ARM-based instance types.

Scaling Storage for AWS VMs

When a VM needs more storage capacity Workload Optimization Manager recommends actions to scale its volume to an instance that provides more storage. Note that AWS supports both Elastic Block Store (EBS) and Instance storage. Workload Optimization Manager recognizes these storage types as it recommends volume actions.

If the root storage for your VM is Instance Storage, then Workload Optimization Manager will not recommend an action. This is because Instance Storage is ephemeral, and such an action would cause the VM to lose all the stored data.

If the root storage is EBS, then Workload Optimization Manager recommends volume actions. EBS is persistent, and the data will remain after the action. However, if the VM uses Instance Storage for extra storage, then Workload Optimization Manager does not include that storage in its calculations or actions.

Nodes in AWS EMR Clusters

Workload Optimization Manager treats nodes in AWS <u>EMR</u> clusters like regular VMs. As such, it could incorrectly generate scale actions for such nodes. After a node action executes, AWS detects the action as a defect, terminates the node, and replaces



it with a new instance of the initial size. To avoid this issue, we recommend that you disable scale actions for nodes in EMR clusters.

AWS automatically assigns system tags to EMR clusters. To disable scale actions, create a VM group that uses these tags as a filter, and then create a VM policy that disables the 'Cloud Scale All' action type for the VM group.

Actions for Azure VMs

Workload Optimization Manager can recommend the following actions:

Scale

Change the VM instance to use a different instance type or tier to optimize performance and costs.

See additional information for scale actions below.

Discount-related actions

If you have a high percentage of on-demand VMs, you can reduce your monthly costs by increasing Azure reservations coverage. To increase coverage, you scale VMs to instance types that have existing capacity.

If you need more capacity, then Workload Optimization Manager will recommend actions to purchase additional reservations.

Purchase actions should be taken along with the related VM scaling actions. To purchase discounts for VMs at their current sizes, run a <u>Buy VM Reservation Plan (on page 577)</u>.

■ Stop and Start (also known as 'parking' actions)

Stop a VM for a given period of time to reduce your cloud expenses, and then start it at a later time.

For details, see Parking: Stop or Start Cloud Resources (on page 597).

Controlling Scale Actions for Azure VMs

For scale actions, you can create policies to control the scale actions that Workload Optimization Manager recommends. In those policies, choose from the following options:

- Cloud Scale All execute all scaling actions
- Cloud Scale for Performance only execute scaling actions that improve performance
- Cloud Scale for Savings only execute scaling actions that reduce costs

The default action acceptance mode for these actions is *Manual*. When you examine the pending actions, only actions that satisfy the policy are allowed to execute. All other actions are read-only.

When policy conflicts arise, **Cloud Scale All** overrides the other two scaling options in most cases. For more information, see Default and User-defined Automation Policies (on page 677).

Supported Instance Types for Azure VMs

Workload Optimization Manager considers all supported instance types when making scaling decisions for cloud VMs. If you want your VMs to *only scale to* or *avoid* certain instance types, create policies for those VMs.

You can view the instance types that Workload Optimization Manager supports from the user interface.

- Navigate to Settings > Policies.
- 2. In the Policy Management page, search for and click Virtual Machine Defaults.
- 3. In the Configure Virtual Machine Policy page:
 - a. Scroll down to the bottom of the page.
 - b. Click Add Scaling Constraint.
 - c. Choose Cloud Instance Types.
 - d. Click Edit.

The policy page shows supported tiers for each cloud provider. A tier is a family of instance types, such as *M1* for GCP, *a1* for AWS and *Basic_A1* for Azure. Expand a tier to see individual instance types and resource allocations.



Azure Resource Group Discovery

To discover Azure Resource Groups, you can set up the following targets:

- Microsoft Azure service principle targets
- Microsoft Azure Enterprise Agreement (EA) targets

For Azure environments that include Resource Groups, Workload Optimization Manager discovers the Azure Resource Groups and the tags that are used to identify these groups.

In the Workload Optimization Manager user interface, to search for a specific Azure Resource Group, choose **Resource Groups** in the Search Page.

You can set the scope of your Workload Optimization Manager session to an Azure Resource Group by choosing a group in the Search results and clicking **Scope To Selection**.

You can also use Azure tags as filter criteria when you create a custom Workload Optimization Manager resource group. You can choose the Azure Resource Groups that match the tag criteria to be members of the new custom group.

To find the available tags for a specific Azure Resource Group, add the Basic Info chart configured with Related Tag Information to your view or custom dashboard. See <u>Basic Info Charts (on page 623)</u>.

NOTE:

When you inspect Resource Groups, Workload Optimization Manager does not currently show the billed costs for those Resource Groups.

Azure Instance Requirements

In Azure environments, some instance types require workloads to be configured in specific ways, and some workload configurations require instance types that support specific features. When Workload Optimization Manager generates resize actions in Azure, these actions consider the following features:

Accelerated Networking (AN)

In an Azure environment, not all instance types support AN, and not all workloads on AN instances actually enable AN. Workload Optimization Manager maintains a dynamic group of workloads that have AN enabled, and it assigns a policy to that group to exclude any templates that do not support AN. In this way, if a workload is on an instance that supports AN, and that workload has enabled AN, then Workload Optimization Manager will not recommend an action that would move the workload to a non-AN instance.

Azure Premium Storage

Workload Optimization Manager recognizes whether a workload uses Premium Storage, and will not recommend a resize to an instance that does not support Azure Premium Storage.

In addition, Workload Optimization Manager recognizes processor types that you currently use for your workloads. If your workload is on a GPU-based instance, then Workload Optimization Manager will only recommend moves to other compatible GPU-based instance types. For these workloads, Workload Optimization Manager does not recommend resize actions.

IOPS-aware Scaling for Azure VMs

Workload Optimization Manager considers IOPS utilization when making scaling decisions for Azure VMs. To measure utilization, Workload Optimization Manager takes into account a variety of attributes, such as per-disk IOPS utilization, whole VM IOPS utilization, cache settings, and IOPS capacity for the VMs. It also respects IOPS utilization and aggressiveness constraints that you set in VM policies. For details, see <u>Aggressiveness and Observation Periods (on page 397)</u>.

Analysis impacts VM scaling decisions in different ways. For example:

- If your instance experiences IOPS bottlenecks, Workload Optimization Manager can recommend scaling up to a larger instance type to increase IOPS capacity, even if you do not fully use the current VCPU or VMEM resources.
- If your instance experiences underutilization of VMEM and VCPU, but high IOPS utilization, Workload Optimization Manager might not recommend scaling down. It might keep you on the larger instance to provide sufficient IOPS capacity.
- If the instance experiences underutilization of IOPS capacity along with normal utilization of other resources, you might see an action to resize to an instance that is very similar to the current one. If you inspect the action details, you should see that you are changing to a less expensive instance with less IOPS capacity.



Actions for GCP VMs

Workload Optimization Manager can recommend the following actions:

■ Scale

Change the VM instance to use a different instance type or tier to optimize performance and costs.

See additional information for scale actions below.

Discount-related actions

If you have a high percentage of on-demand VMs, you can reduce your monthly costs by increasing Committed Use Discount (CUD) coverage. To increase coverage, you scale VMs to instance types that have existing capacity.

Actions to purchase CUDs will be introduced in a future release.

■ Stop and Start (also known as 'parking' actions)

Stop a VM for a given period of time to reduce your cloud expenses, and then start it at a later time.

For details, see Parking: Stop or Start Cloud Resources (on page 597).

■ Reconfigure

GCP provides a specific set of machine types for each zone in a region. If you create a policy that restricts a VM to certain machine types and the zone it is currently on does not support all of those machine types, Workload Optimization Manager will recommend a reconfigure action as a way to notify you of the non-compliant VM.

For example, assume Zone A does not support machine types for the M1 family. When a VM in that zone applies a policy that restricts it to M1, Workload Optimization Manager will recommend that you reconfigure the VM.

Points to Consider for GCP Scale Actions

- Workload Optimization Manager can generate scaling actions for the following VMs, but cannot execute the actions automatically:
 - VMs with local SSDs

Workload Optimization Manager can recommend scaling to a machine type that supports local SSDs and the number of disks required by the VM, but blocks action execution due to prerequisite steps that you can only perform from GCP. You can view the prerequisite steps when you examine a pending action.

VMs configured with a minimum CPU platform

GCP instance type families can support multiple CPU generations. A specific VM may be configured with a minimum CPU platform to prevent it from scaling to instance types with incompatible CPUs. When you examine a pending action for such a VM, verify that the recommended instance type runs a compatible CPU. Once verified, manually execute the action from GCP.

NOTE:

Workload Optimization Manager does not recognize prioritized attributions you may have set for CUDs. For example, if you have prioritized all your CUD allotments for a single project, Workload Optimization Manager can still recommend actions to apply CUD to other projects in your environment.

- Since all GCP compute tiers have the same net throughput capacity, Workload Optimization Manager will not generate scaling actions in response to net throughput.
- Workload Optimization Manager does not recommend scaling actions for:
 - Spot VMs

NOTE:

Workload Optimization Manager discovers spot VMs, but does not recommend actions or monitor costs for these VMs.

- VMs running on sole-tenant nodes
- VMs with attached GPUs
- VMs in <u>managed instance groups</u>
- VMs running <u>custom machine types</u>



Controlling Scale Actions for GCP VMs

For scale actions, you can create policies to control the scale actions that Workload Optimization Manager recommends. In those policies, choose from the following options:

- Cloud Scale All execute all scaling actions
- Cloud Scale for Performance only execute scaling actions that improve performance
- Cloud Scale for Savings only execute scaling actions that reduce costs

The default action acceptance mode for these actions is *Manual*. When you examine the pending actions, only actions that satisfy the policy are allowed to execute. All other actions are read-only.

When policy conflicts arise, **Cloud Scale All** overrides the other two scaling options in most cases. For more information, see <u>Default and User-defined Automation Policies (on page 677)</u>.

Supported Instance Types for GCP VMs

Workload Optimization Manager considers all supported instance types when making scaling decisions for cloud VMs. If you want your VMs to *only scale to* or *avoid* certain instance types, create policies for those VMs.

You can view the instance types that Workload Optimization Manager supports from the user interface.

- Navigate to Settings > Policies.
- 2. In the Policy Management page, search for and click Virtual Machine Defaults.
- In the Configure Virtual Machine Policy page:
 - a. Scroll down to the bottom of the page.
 - b. Click Add Scaling Constraint.
 - c. Choose Cloud Instance Types.
 - d. Click Edit.


The policy page shows supported tiers for each cloud provider. A tier is a family of instance types, such as *M1* for GCP, *a1* for AWS and *Basic_A1* for Azure. Expand a tier to see individual instance types and resource allocations.

Cloud VM Uptime

For cloud VMs, Workload Optimization Manager includes *uptime* data in its cost calculations. This is especially important for VMs that do not run 24/7 and are charged on-demand rates. With uptime data, Workload Optimization Manager can calculate costs more accurately based on the amount of time a VM has been running.

The Action Details page shows uptime data for these VMs. Workload Optimization Manager calculates uptime based on the VM's age.





Key Concepts

■ Uptime

A percentage value that indicates how long a VM has been running over a period of time (age)

Age

The number of days that a VM has existed since first discovery. For VMs older than 30 days, Workload Optimization Manager displays a value of **30+ days**, but only calculates uptime over the last 30 days.

For newly discovered VMs, age is 0 (zero) on the day of discovery. If the VM is running at the time of discovery, uptime is 100%. Otherwise, uptime is 0% and remains unchanged until the VM is powered on. Workload Optimization Manager recalculates uptime every hour and then refreshes the data shown in the user interface.

Examples

- A VM that was first discovered 5 days (or 120 hours) ago and has been running for a total of 60 hours during that period has a current uptime value of 50%.
- A VM that was first discovered 2 months ago and has been running for a total of 180 hours over the last 30 days (or 720 hours) has a current uptime value of 25%.

Cost Calculations Using Uptime Data

Workload Optimization Manager uses uptime data to calculate estimated on-demand costs for your cloud VMs. For details about calculations, see Estimated On-demand Monthly Costs for Cloud VMs (on page 389).

Uptime data impacts cost calculations, but not the actual scaling decisions that Workload Optimization Manager makes. These decisions rely on other factors, such as resource utilization percentiles and scaling constraints set in policies.




Uptime Data in Charts

Workload Optimization Manager recalculates uptime data every hour and then updates the values shown in charts. The following charts reflect the cost impact of uptime-based calculations:

Potential Savings and Necessary Investment charts

The projected amounts in these charts include on-demand costs for cloud VMs.




When you click **Show All** in these charts and view details for a pending VM action, the **Action Details** page shows ondemand costs before and after you execute the action, factoring in the VM's uptime value. The page also shows the VM's age.




Workload Cost Breakdown chart

This chart shows estimated costs over time, including on-demand costs for VMs.






■ The Entity Information chart shows the latest uptime and age data for a specific cloud VM.



Estimated On-demand Costs for Cloud VMs

Workload Optimization Manager considers a variety of factors when calculating *Estimated On-demand Monthly Cost* for a cloud VM.





AWS VMs and Azure VMs Without License Costs

Cost Calculation

For these VMs, the calculation for Estimated On-demand Monthly Cost can be expressed as follows:

```
On-demand Rate * Usage Not Covered by Discounts * Uptime * 730 = Estimated On-demand Monthly Cost
```

Where:

- On-demand Rate is the hourly cost for a VM's instance type without discount coverage (AWS Rls/Savings Plans or Azure reservations).
 - For AWS, this rate includes all license costs, but not storage or IP. You can obtain on-demand rates via <u>Amazon EC2</u> <u>On-demand Pricing</u>.
 - For Azure, the rate does not include license costs, storage, or IP. You can obtain on-demand rates via <u>Azure Pricing</u> Calculator.

NOTE:

Azure VMs covered by Azure Hybrid Benefit do not have license costs.

- Usage Not Covered by Discounts is the percentage of hourly VM usage not covered by any discount. For example:
 - Discount Coverage = 20% (0.2)
 - Usage Not Covered by Discounts = 80% (0.8)
- **Uptime** is a percentage value that indicates how long a VM has been running since it was first discovered by Workload Optimization Manager. For VMs discovered more than 30 days ago, Workload Optimization Manager only calculates uptime over the last 30 days.

To estimate monthly on-demand costs, Workload Optimization Manager projects the current uptime value into the future. It assumes that future uptime will be similar to the current uptime.

730 represents the number of hours per month that Workload Optimization Manager uses to estimate monthly costs.

The listed items above impact cost calculations, but not the actual scaling decisions that Workload Optimization Manager makes. These decisions rely on other factors, such as resource utilization percentiles and scaling constraints set in policies.

Example

Assume the following data for a pending scale action for an AWS VM:



	Current Values	Values After Action Execution
On-demand Rate	\$0.012/hr	\$0.021/hr
Discount Coverage	50% (0.5)	0% (0.0)
Usage Not Covered by Discounts (calculated based on discount coverage)	50% (0.5)	100% (1.0)



	Current Values	Values After Action Execution
Uptime	95.3% (.953)	

Workload Optimization Manager calculates the following:



Current Estimated On-demand Monthly Cost:

$$0.012 * 0.5 * 0.953 * 730 = 4.1$$


■ Estimated On-demand Monthly Cost *after* executing the action:

$$0.021 * 1.0 * 0.953 * 730 = 15$$

NOTE:

Workload Optimization Manager rounds the calculated values that it displays in the user interface.

Since the Estimated On-demand Monthly Cost is projected to increase from \$4.1/month to \$15/month, Workload Optimization Manager treats the action as an investment and shows an estimated investment of \$11/month.





Azure VMs with License Costs

Cost Calculation

For VMs with license costs, Workload Optimization Manager first calculates the *On-demand Compute Rate*, which it then uses to calculate *Estimated On-demand Monthly Costs*.

1. On-demand Compute Rate Calculation

The calculation for On-demand Compute Rate can be expressed as follows:

```
On-demand Rate - (Reserved License Cost + On-demand License Cost) = On-demand Compute Rate
```

Where:

- On-demand Rate is the hourly cost for a VM's instance type without reservation coverage. This does not include license costs, storage, or IP. You can obtain on-demand rates via Azure Pricing Calculator.
- Reserved License Cost and On-demand License Cost are the hourly costs for the VM's licenses. You can obtain license costs via Azure Pricing Calculator or the Workload Optimization Manager user interface.

From the user interface, set the scope to the Azure VM and then see the Workload Cost Breakdown chart. In the chart, set the time frame to Last 2 Hours, and then:

 Hover over the second to the last bar in the chart to obtain the current On-demand License Cost and Reserved License Cost.



 Hover over the last bar (after the vertical line) in the chart to obtain the On-demand License Cost and Reserved License Cost after you execute actions.





The On-demand Compute Rate and License Cost (On-demand and Reserved) are then used to calculate Estimated On-demand Monthly Costs.

2. Estimated On-demand Monthly Cost Calculation

The calculation can be expressed as follows:

 $(On-demand\ Compute\ Rate\ *\ Usage\ Not\ Covered\ by\ Reservations)\ +\ License\ Cost\ *\ Uptime\ *\ 730\ =\ Estimated\ On-demand\ Monthly\ Cost$

Where:

- Usage Not Covered by Reservations is the percentage of hourly VM usage not covered by any reservation. For example:
 - Reservation Coverage = 20% (0.2)
 - Usage Not Covered by Reservations = 80% (0.8)
- License Cost is the sum of On-demand License Cost and Reserved License Cost.
- Uptime is a percentage value that indicates how long a VM has been running since it was first discovered by Workload Optimization Manager. For VMs discovered more than 30 days ago, Workload Optimization Manager only calculates uptime over the last 30 days

To estimate monthly on-demand costs, Workload Optimization Manager projects the current uptime value into the future. It assumes that future uptime will be similar to the current uptime.

730 represents the number of hours per month that Workload Optimization Manager uses to estimate monthly costs.

The listed items above impact cost calculations, but not the actual scaling decisions that Workload Optimization Manager makes. These decisions rely on other factors, such as resource utilization percentiles and scaling constraints set in policies.

Example


Assume the following data for a pending scale action for an Azure VM with license costs:




	Current Values	Values After Action Execution
On-demand Rate	\$0.45/hr	\$0.218/hr

Current license costs





License costs after action execution



	Current Values	Values After Action Execution	
On-demand License Cost	\$0/hr	\$0.088/hr	
Reserved License Cost	\$0.184/hr	N/A	

- 1. Workload Optimization Manager first calculates the following:
 - Current On-demand Compute Rate:

$$0.45 - (0.184 + 0) = 0.266$$

■ On-demand Compute Rate *after* executing the action:

$$0.218 - (0 + 0.088) = 0.13$$

- 2. Workload Optimization Manager can now calculate Estimated On-demand Monthly Cost based on:
 - On-demand Compute Rate

	Current Values	Values After Action Execution	
On-demand Compute Rate	\$0.266/hr \$0.13/hr		


Usage Not Covered by Reservations and Uptime





	Current Values	Values After Action Execution	
Reservation Coverage	100% (1.0)	0% (0.0)	
Usage Not Covered by Reservations (calculated based on reservation coverage)	0% (0.0)	100% (1.0)	
Uptime	96.1% (.961)		

Workload Optimization Manager calculates the following:



Current Estimated On-demand Monthly Cost:

$$(0.266 * 0.0) + 0.184 * 0.961 * 730 = 129$$

■ Estimated On-demand Monthly Cost *after* executing the action:


$$(0.13 * 1.0) + 0.088 * 0.961 * 730 = 153$$

NOTE:

Workload Optimization Manager rounds the calculated values that it displays in the user interface.

Since the on-demand cost is projected to increase from \$129/month to \$153/month, Workload Optimization Manager treats the action as an investment and shows an estimated investment of \$24/month.





Cloud VM Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

NOTE

The policy settings discussed in this topic only apply to cloud scale actions. For details about settings for parking actions (stop and start), see Parking: Stop or Start Cloud Resources (on page 597).

Action Automation and Orchestration

For details about cloud VM actions, see Cloud VM Actions (on page 381).

Cloud Scale

Action	Default Mode	AWS, Azure, and GCP
Cloud Scale All	Manual	Auto
Cloud Scale for Performance	Manual	Auto
Cloud Scale for Savings	Manual	Auto

Other Actions

Action	Default Mode	AWS and Azure	GCP
Buy discounts	Recommend	Romd	Not yet supported



Action	Default Mode	AWS and Azure	GCP
Provision Kubernetes node (VM)	Manual	Remd	Remd
Suspend Kubernetes node (VM)	Manual	Auto	Auto

Scaling Target Utilization

For VCPU, VMEM, and IO/Net Throughput Utilization:

These advanced settings determine how much you would like a scope of workloads to utilize their resources. These are fixed settings that override the way Workload Optimization Manager calculates the optimal utilization of resources. You should only change these settings after consulting with Technical Support.

While these settings offer a way to modify how Workload Optimization Manager recommends actions, in most cases you should never need to use them. If you want to control how Workload Optimization Manager recommends actions to resize workloads, you can set the aggressiveness per the percentile of utilization, and set the length of the sample period for more or less elasticity on the cloud.

Attribute	Default Value
Scaling Target VCPU Utilization	70
	The target utilization as a percentage of VCPU capacity.
Scaling Target VMEM Utilization	90
	The target utilization as a percentage of memory capacity.
Scaling Target IO Throughput Utilization	70
	The target utilization as a percentage of IO throughput (Read and Write) capacity.
Scaling Target Net Throughput Utilization	70
	The target utilization as a percentage of network throughput (Inbound and Outbound) capacity.

For IOPS Utilization:

Workload Optimization Manager uses this setting in conjunction with aggressiveness constraints to control scaling actions for VMs. You can set the aggressiveness per the percentile of utilization, and set the length of the sample period for more or less elasticity on the cloud.

Attribute	Default Value
Scaling Target IOPS Utilization	70
(Azure VMs only)	For Azure environments, the target percentile value Workload Optimization Manager will attempt to match.

For details on how IOPS utilization affects scaling decisions, see IOPS-aware Scaling for Azure VMs (on page 384).

Aggressiveness and Observation Periods

Workload Optimization Manager uses these settings to calculate utilization percentiles for vCPU, vMEM, and IOPS (Azure VMs only). It then recommends actions to improve utilization based on the observed values for a given time period.

Aggressiveness

Attribute	Default Value
Aggressiveness	95th Percentile

When evaluating performance, Workload Optimization Manager considers resource utilization as a percentage of capacity. The utilization drives actions to scale the available capacity either up or down. To measure utilization, the analysis considers



a given utilization percentile. For example, assume a 95th percentile. The percentile utilization is the highest value that 95% of the observed samples fall below. Compare that to average utilization, which is the average of *all* the observed samples.

Using a percentile, Workload Optimization Manager can recommend more relevant actions. This is important in the cloud, so that analysis can better exploit the elasticity of the cloud. For scheduled policies, the more relevant actions will tend to remain viable when their execution is put off to a later time.

For example, consider decisions to reduce the capacity for CPU on a VM. Without using a percentile, Workload Optimization Manager never resizes below the recognized peak utilization. For most VMs, there are moments when peak CPU reaches high levels, such as during reboots, patching, and other maintenance tasks. Assume utilization for a VM peaked at 100% just once. Without the benefit of a percentile, Workload Optimization Manager will not reduce allocated CPU for that VM.

With **Aggressiveness**, instead of using the single highest utilization value, Workload Optimization Manager uses the percentile you set. For the above example, assume a single CPU burst to 100%, but for 95% of the samples CPU never exceeded 50%. If you set **Aggressiveness** to 95th Percentile, then Workload Optimization Manager can see this as an opportunity to reduce CPU allocation for the VM.

In summary, a percentile evaluates the sustained resource utilization, and ignores bursts that occurred for a small portion of the samples. You can think of this as aggressiveness of resizing, as follows:

- 100th and 99th Percentile More performance. Recommended for critical workloads that need maximum guaranteed
 performance at all times, or workloads that need to tolerate sudden and previously unseen spikes in utilization, even
 though sustained utilization is low.
- 95th Percentile (Default) The recommended setting to achieve maximum performance and savings. This assures
 application performance while avoiding reactive peak sizing due to transient spikes, thus allowing you to take
 advantage of the elastic ability of the cloud.
- 90th Percentile More efficiency. Recommended for non-production workloads that can stand higher resource utilization.

By default, Workload Optimization Manager uses samples from the last 30 days. Use the **Max Observation Period** setting to adjust the number of days. To ensure that there are enough samples to analyze and drive scaling actions, set the **Min Observation Period**.

Max Observation Period

Attribute	Default Value
Max Observation Period	Last 30 Days

To refine the calculation of resource utilization percentiles, you can set the sample time to consider. Workload Optimization Manager uses historical data from up to the number of days that you specify as a sample period. If the database has fewer days' data then it uses all of the stored historical data.

You can make the following settings:

- Less Elastic Last 90 Days
- Recommended Last 30 Days
- More Elastic Last 7 Days

Workload Optimization Manager recommends an observation period of 30 days following the monthly workload maintenance cycle seen in many organizations. VMs typically peak during the maintenance window as patching and other maintenance tasks are carried out. A 30-day observation period means that Workload Optimization Manager can capture these peaks and increase the accuracy of its sizing recommendations.

You can set the value to 7 days if workloads need to resize more often in response to performance changes. For workloads that cannot handle changes very often or have longer usage periods, you can set the value to 90 days.

Min Observation Period

Attribute	Default Value
Min Observation Period	None

This setting ensures historical data for a minimum number of days before Workload Optimization Manager will generate an action based on the percentile set in **Aggressiveness**. This ensures a minimum set of data points before it generates the action.



Especially for scheduled actions, it is important that resize calculations use enough historical data to generate actions that will remain viable even during a scheduled maintenance window. A maintenance window is usually set for "down" time, when utilization is low. If analysis uses enough historical data for an action, then the action is more likely to remain viable during the maintenance window.

- More Elastic None
- Less Elastic 7 Days

Cloud Instance Types

Attribute	Default Value
Cloud Instance Types	None

By default, Workload Optimization Manager considers all instance types currently available for scaling when making scaling decisions for VMs. However, you may have set up your cloud VMs to *only scale to* or *avoid* certain instance types to reduce complexity and cost, improve discount utilization, or meet application demand. Use this setting to identify the instance types that VMs can scale to.

NOTE:

Under most circumstances, when a cloud provider offers a new instance type that is meant to replace an older type, the provider offers it at a lower cost. However, a provider may provide a new instance type with identical costs as the older instance types. If this occurs, and capacity and cost are equal, Workload Optimization Manager cannot ensure that it chooses the newer instance type. To work around this issue, you can create an Action Automation policy that excludes the older instance type.

Click **Edit** to set your preferences. In the new page that displays, expand a **cloud tier** (a family of instance types, such as *a1* for AWS or *B-series* for Azure) to see individual instance types and the resources allocated to them. If you have several cloud providers, each provider will have its own tab.

Select your preferred instance types or cloud tiers, or clear the ones that you want to avoid. After you save your changes, the main page refreshes to reflect your selections.

If you selected a cloud tier and the service provider deploys new instance types to that tier later, then those instance types will automatically be included in your policy. Be sure to review your policies periodically to see if new instance types have been added to a tier. If you do not want to scale to those instance types, update the affected policies.

Consistent Resizing

Attribute	Default Setting
Enable Consistent Resizing	Off

Consistent Resizing for User-defined Automation Policies

When you create a policy for a group of VMs and turn on Consistent Resizing, Workload Optimization Manager resizes all the group members to the same size, such that they all support the top utilization of each resource commodity in the group. For example, assume VM A shows top utilization of CPU, and VM B shows top utilization of memory. A resize action would result in all the VMs with CPU capacity to satisfy VM A, and memory capacity to satisfy VM B.

For an affected resize, the Actions List shows individual resize actions for each of the VMs in the group. If you automate resizes, Workload Optimization Manager executes each resize individually in a way that avoids disruption to your workloads.

Use this setting to enforce the same template across all VMs in a group when resizing VMs on the public cloud. In this way, Workload Optimization Manager can enforce a rule to size all the VMs in a group equally.

Consistent Resizing for Auto-discovered Groups

In public cloud environments, Workload Optimization Manager discovers groups that should keep all their VMs on the same template, and then creates read-only policies for them to implement Consistent Resizing. The details of this discovery and the associated policy vary depending on the cloud provider.

Azure



Workload Optimization Manager discovers Azure availability sets and scale sets.

- For availability sets, Workload Optimization Manager does not enable Consistent Resizing, but it can recommend scale
 actions for individual VMs in the availability set.
 - When a scale action for a VM in an availability set fails due to insufficient resources in the compute cluster, the action remains pending. When you hover over the pending action, you will see a message indicating that action execution has been temporarily disabled due to a previous execution error in the availability set. Workload Optimization Manager assumes that all other VMs in the availability set will fail to scale due to the same resource issue, so it creates a temporary policy that disables action execution for the availability set. Specifically, this policy sets the action acceptance mode for scale actions to *Recommend* and stays in effect for 730 hours (one month). This means that for the duration of the policy, Workload Optimization Manager will continue to generate read-only, non-executable scale actions for individual VMs, so you can evaluate their resource requirements and plan accordingly. You can delete this policy if you need to re-enable action execution in the availability set.
- For scale sets, Workload Optimization Manager automatically enables Consistent Resizing across all the VMs in the group. You can choose to execute all the actions for such a group, either manually or automatically. In that case, Workload Optimization Manager executes the resizes one VM at a time. If you do not need to resize all the members of a given scale set to a consistent template, create another policy for that scope and turn off Consistent Resizing.

AWS

Workload Optimization Manager discovers Auto Scaling Groups and automatically enables Consistent Resizing across all the VMs in each group. You can choose to execute all the actions for such a group, either manually or automatically. In that case, Workload Optimization Manager executes the resizes one VM at a time. If you do not need to resize all the members of a given Auto Scaling Group to a consistent template, create another policy for that scope and turn off Consistent Resizing.

If you select one or all actions for the group either manually or automatically, Workload Optimization Manager will change the Launch Configuration for the Auto Scaling Group but it will not terminate the EC2 instances.

Below are some use cases for employing Consistent Resizing for a group.

- If you have deployed load balancing for a group, then all the VMs in the group should experience similar utilization. In that case, if one VM needs to be resized, then it makes sense to resize them all consistently.
- A common HA configuration on the public cloud is to deploy mirror VMs to different availability zones, where the given application runs on only one of the VMs at a given time. The other VMs are on standby to recover in failover events. Without Consistent Resizing, Workload Optimization Manager would tend to size down or suspend the unused VMs, which would make them unready for the failover situation.

When working with Consistent Resizing, consider these points:

- You should not mix VMs in a group that has a Consistent Resizing policy, with other groups that enable Consistent Resizing. One VM can be a member of more than one group. If one VM (or more) in a group with Consistent Resizing is also in another group that has Consistent Resizing, then both groups enforce Consistent Resizing together, for all their group members.
- If one VM (or more) is in a group with Consistent Resizing turned on, and the same VMs are in a group with Consistent Resizing turned off, the affected VMs assume the ON setting. This is true if you created both groups, or if Workload Optimization Manager created one of the groups for Azure Scale Sets or AWS Auto Scaling Groups.
- For any group of VMs that enables Consistent Resizing, you should not mix the associated target technologies. For example, one group should not include VMs that are managed on both Azure and AWS platforms.
- Charts that show actions and risks assign the same risk statement to all the affected VMs. This can seem confusing. For example, assume one VM needs to resize to address vCPU risk, and 9 other VMs are set to resize consistently with it. Then charts will state that 10 VMs need to resize to address vCPU risks.

Ignore NVMe Constraints

For AWS, Workload Optimization Manager recognizes when a VM instance includes an NVMe driver. To respect NVMe constraints, it will not recommend scaling to an instance type that does not also include an NVMe driver. If you ignore NVMe constraints, then Workload Optimization Manager is free to scale the instance to a type that does not include an NVMe driver.

Attribute	Default Setting
Ignore NVMe Constraints (AWS only)	Off



Instance Store Aware Scaling


Attribute	Default Setting
Instance Store Aware Scaling	Off

The template for your workload determines whether the workload can use an *instance store*, and it determines the instance store capacity. As Workload Optimization Manager calculates a resize or move action, it can recommend a new template that does not support instance stores, or that does not provide the same instance store capacity.

To ensure that resize actions respect the instance store requirements for your workloads, turn on **Instance Store Aware Scaling** for a given VM or for a group of VMs. When you turn this on for a given scope of VMs, then as it calculates move and resize actions, Workload Optimization Manager will only consider templates that support instance stores. In addition, it will not move a workload to a template that provides less instance store capacity.

App Component Spec

In <u>Azure App Service (on page 287)</u> deployments, an App Component Spec represents a set of app instances comprising a single web application. Workload Optimization Manager discovers App Component Specs when you add an Azure target with the necessary permissions.



NOTE

For a list of permissions, see Azure Permissions (on page 275).

Workload Optimization Manager also discovers the *plans* that provide resources to app instances. The supply chain shows these plans as <u>Virtual Machine Specs</u> (on page 402) and links them with App Component Specs to establish their relationship.



Synopsis

Synopsis	
Provides:	App services to end users
Consumes:	Resources from App Service plans
Discovered through:	Azure targets

Monitored Resources

Workload Optimization Manager monitors the following resources:

Response Time

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

■ Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Actions


None

Workload Optimization Manager does not recommend actions for App Component Specs, but it does recommend actions for the underlying Virtual Machine Specs. For details, see <u>Virtual Machine Spec Actions (on page 404)</u>.

Virtual Machine Spec

In <u>Azure App Service (on page 287)</u>, plans define CPU, memory, and storage resources that are available to VM instances to run apps. When you add an Azure target with the necessary permissions, Workload Optimization Manager discovers the plans associated with apps, and shows them as Virtual Machine Specs in the supply chain. Currently, Workload Optimization Manager discovers all plans, except App Service Environment v3 I4, I5, and I6.





NOTE:

For a list of permissions, see Azure Permissions (on page 275).

Points to consider:

- Azure App Service offers several types of apps, including web apps, mobile apps, API apps, and logic apps. Workload Optimization Manager discovers the plans associated with these apps, but only recommends scale actions for plans associated with web apps. If a plan is no longer associated with any type of app, Workload Optimization Manager will recommend that you delete it.
- For web apps, Workload Optimization Manager also discovers the app instances that consume resources from a plan, and shows them as App Component Specs (on page 401) in the supply chain. The supply chain links App Component Specs with Virtual Machine Specs to establish their relationship.
- VM instances underlying a plan scale as a group. For this reason, Workload Optimization Manager represents these VM instances as a single Virtual Machine Spec entity and does *not* monitor them individually. The Entity Information chart for a Virtual Machine Spec shows the current number of VM instances, while resource charts (such as the Virtual CPU and Virtual Memory charts) show aggregated metrics for all VM instances.

Synopsis

Synopsis	
Provides:	Resources to apps (via App Component Specs)
Consumes:	Resources from Azure regions
Discovered through:	Azure targets



Monitored Resources

Workload Optimization Manager monitors the following resources:

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

■ Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Number of Replicas

Number of Replicas is the total number of VM instances underlying an App Service plan.

Actions

Workload Optimization Manager can recommend the following actions:

Scale

Scale Azure App Service plans to optimize app performance or reduce costs, while complying with business policies.

Delete

Delete empty Azure App Service plans as a cost-saving measure. A plan is considered empty if it is not hosting any running apps.

Scale Actions

Workload Optimization Manager supports vertical scaling actions for provisioned App Service plans. These actions change the *size* of all VM instances underlying a plan (for example, from small to large, or large to medium). Horizontal scaling actions, which change the *number* of VM instances underlying a plan, are currently not supported.

Vertical scaling recommendations rely on a variety of factors, including:

- Resource utilization percentiles (on page 406)
- On-demand monthly costs (on page 407)
- VM instance count

Workload Optimization Manager will only recommend vertical scaling actions on plans with six or less VM instances.

- Scaling eligibility
 - Eligible for scaling Basic, Standard, Premium v2, Premium v3, Isolated, Isolated v2
 - Not eligible for scaling Workflow Standard, Elastic Premium, Free, Shared, Dynamic/Serverless
- Azure-enforced constraints, including:
 - Region Only recommend instance types in regions where they are available
 - Server rack Only recommend instance types on server racks where they are available
 - Zone redundancy If zone redundancy is enabled, only recommend instance types that support zone redundancy
 - Deployment slots Only recommend instance types that support the currently configured number of deployment slots that can be added to apps
 - Hybrid connections Only recommend scaling to instance types that support the currently configured number of hybrid connections for a plan

NOTE:

To see the number of deployment slots and hybrid connections configured for a plan, set the scope to the corresponding Virtual Machine Spec and then view the Entity Information chart.

Scaling constraints that you set in Workload Optimization Manager <u>policies (on page 410)</u> for Virtual Machine Specs

For example, you can set a constraint if you want App Service plans to *only scale to* or *avoid* certain instance types. For scale actions, you can create policies to control the scale actions that Workload Optimization Manager recommends. In those policies, choose from the following options:

Cloud Scale All - execute all scaling actions



- Cloud Scale for Performance only execute scaling actions that improve performance
- Cloud Scale for Savings only execute scaling actions that reduce costs

The default action acceptance mode for these actions is *Manual*. When you examine the pending actions, only actions that satisfy the policy are allowed to execute. All other actions are read-only.


When policy conflicts arise, **Cloud Scale All** overrides the other two scaling options in most cases. For more information, see <u>Default and User-defined Automation Policies</u> (on page 677).

Delete Actions

When Workload Optimization Manager discovers an empty plan (i.e., a plan that is not hosting any running apps), it will immediately recommend that you delete the plan as a cost-saving measure. Workload Optimization Manager can recommend deleting provisioned App Service plans, as well as Elastic Premium and Workflow Standard plans.

If a currently empty plan is not deleted and is subsequently discovered as used, Workload Optimization Manager removes the delete action attached to it.

Delete actions include the 'Days Empty' information that indicates how long a plan has been empty.




You can control the delete actions that Workload Optimization Manager recommends, based on the 'Days Empty' value that you set. For example, if you want Workload Optimization Manager to only generate delete actions for plans that have been empty for at least 5 days, perform these steps:

- 1. In the default policy for Virtual Machine Specs, disable delete actions.
- 2. Create a dynamic group of Virtual Machine Specs and set the 'Days Empty' filter to Days Empty > = 5.
- 3. Create a custom Virtual Machine Spec policy, set the scope to the group that you just created, and then *enable* delete actions in that policy.

Actions in Charts

Use the Necessary Investments and Potential Savings charts to view pending Virtual Machine Spec actions. These charts show total monthly investments and savings, assuming you execute all the actions.



Click **Show All** for each chart to review and execute the actions.

The table shows the following:


Actions that are pending for each Virtual Machine Spec



Savings or investments for each Virtual Machine Spec

Utilization Charts for Scale Actions

Workload Optimization Manager uses percentile calculations to measure resource utilization, and drive scaling actions that improve overall utilization and reduce costs. When you examine the details for a pending scaling action on an App Service plan, you will see charts that highlight resource *utilization percentiles* for a given observation period, and the projected percentiles after you execute the action.



The charts also plot *daily average utilization* for your reference. If you have previously executed scaling actions on the App Service plan, you can see the resulting improvements in daily average utilization. Put together, these charts allow you to easily recognize utilization trends that drive Workload Optimization Manager's scaling recommendations.

NOTE:

You can set scaling constraints in Virtual Machine Spec policies to refine the percentile calculations. For details, see <u>Scaling Sensitivity (on page 410)</u>.

Disruptiveness and Reversibility of Scale Actions

Workload Optimization Manager always recommends scaling to a different instance type, so all scaling actions are disruptive and require downtime. You can reverse an action by scaling an App Service plan back to its original instance type.




Estimated On-demand Monthly Costs for Azure App Service Plans

Workload Optimization Manager considers a variety of factors when calculating estimated on-demand monthly costs for Azure App Service plans.

NOTE:

Azure App Service plans appear as Virtual Machine Spec entities in the supply chain.



Cost Calculation

The calculation for estimated on-demand monthly cost can be expressed as follows:

(On-demand Compute Rate * 730) * Number of Instances = Estimated On-demand Monthly Cost Where:

- On-demand Compute Rate is the hourly cost for an App Service plan's instance type.
 You can obtain on-demand rates via App Service Pricing.
- 730 represents the number of hours per month that Workload Optimization Manager uses to calculate monthly costs.
- Number of Instances is the total number of VM instances underlying the App Service plan.



The listed items above impact cost calculations and the scaling decisions that Workload Optimization Manager makes. These decisions also rely on other factors, such as resource utilization percentiles and scaling constraints set in policies.

Example

Assume the following data for a pending action to scale an Azure Service plan from the I2V2 to the I1V1 instance type.

	Current Values	Values After Action Execution
On-demand Compute Rate	\$0.772/hr	\$0.386/hr
Number of Instances	3	3

Workload Optimization Manager calculates the following:

Current estimated on-demand monthly cost:

```
(\$0.772 * 730) * 3 = \$1690.68/Mo.
```

■ Estimated on-demand monthly cost *after* executing the action:

```
(\$0.386 * 730) * 3 = \$845.34/Mo.
```

NOTE:

Workload Optimization Manager rounds the calculated values that it displays in the user interface.

The estimated on-demand monthly cost is projected to decrease from \$1690.68/month to \$845.34/month, as shown in the Details section of the pending action.



Workload Optimization Manager treats the action as a cost-saving measure, and shows total savings of \$845.34/month.




Estimated On-demand Monthly Savings for Empty Azure App Service Plans

Workload Optimization Manager considers an empty App Service plan's on-demand compute rate and VM instance count when calculating the estimated on-demand monthly savings that you would realize when you delete the plan. A plan is considered empty if it is not hosting any running apps.

NOTE:

Azure App Service plans appear as Virtual Machine Spec entities in the supply chain.





Savings Calculation

The calculation for estimated on-demand monthly savings can be expressed as follows:

(On-demand Compute Rate * 730) * Number of Instances = Estimated On-demand Monthly Savings

Where:

- On-demand Compute Rate is the hourly cost for an App Service plan's instance type.
 - You can obtain on-demand rates via App Service Pricing.
- 730 represents the number of hours per month that Workload Optimization Manager uses to calculate monthly savings.
- Number of Instances is the total number of VM instances underlying the App Service plan.

Example

Assume the following data for a pending action to delete an empty Azure Service plan on the P2V2 instance type.

	Current Values
On-demand Compute Rate	\$0.202/hr
Number of Instances	1

Workload Optimization Manager calculates savings as follows:

$$(\$0.202 * 730) * 1 = \$147.46/Mo.$$

NOTE:

Workload Optimization Manager rounds the calculated values that it displays in the user interface.

Workload Optimization Manager shows total savings of \$147.46/month.





Virtual Machine Spec Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

For details about Virtual Machine Spec actions, see Virtual Machine Spec Actions (on page 404).

Action	Default Mode
Cloud Scale All	Manual
Cloud Scale for Performance	Manual
Cloud Scale for Savings	Manual
Delete Virtual Machine Spec	Manual

Scaling Sensitivity

Workload Optimization Manager uses a percentile of utilization over the specified observation period. This gives sustained utilization and ignores short-lived bursts.

Aggressiveness

Attribute	Default Value
Aggressiveness	95th Percentile

Workload Optimization Manager uses these settings to calculate utilization percentiles for vCPU and vMEM.

When evaluating performance, Workload Optimization Manager considers resource utilization as a percentage of capacity. The utilization drives actions to scale the available capacity either up or down. To measure utilization, the analysis considers a given utilization percentile. For example, assume a 95th percentile. The percentile utilization is the highest value that 95% of the observed samples fall below. Compare that to average utilization, which is the average of *all* the observed samples.

Using a percentile, Workload Optimization Manager can recommend more relevant actions. This is important in the cloud, so that analysis can better exploit the elasticity of the cloud. For scheduled policies, the more relevant actions will tend to remain viable when their execution is put off to a later time.

For example, consider decisions to reduce vCPU capacity. Without using a percentile, Workload Optimization Manager never scales below the recognized peak utilization. Assume utilization peaked at 100% just once. Without the benefit of a percentile, Workload Optimization Manager will not reduce resources for the Virtual Machine Spec.

With **Aggressiveness**, instead of using the single highest utilization value, Workload Optimization Manager uses the percentile you set. For the above example, assume a single burst to 100%, but for 95% of the samples, utilization never exceeded 50%. If you set **Aggressiveness** to 95th Percentile, then Workload Optimization Manager can see this as an opportunity to reduce resource allocation.

In summary, a percentile evaluates the sustained resource utilization, and ignores bursts that occurred for a small portion of the samples. You can think of this as aggressiveness of resizing, as follows:

99th or 100th Percentile - More performance. Recommended for critical Virtual Machine Specs that need maximum guaranteed performance at all times, or those that need to tolerate sudden and previously unseen spikes in utilization, even though sustained utilization is low.



- 95th Percentile (Default) The recommended setting to achieve maximum performance and savings. This assures
 performance while avoiding reactive peak sizing due to transient spikes, thus allowing you to take advantage of the
 elastic ability of the cloud.
- 90th Percentile More efficiency. Recommended for Virtual Machine Specs that can stand higher resource utilization.
 By default, Workload Optimization Manager uses samples from the last 14 days. Use the Max Observation Period setting to adjust the number of days.

■ Max Observation Period

Attribute	Default Value
Max Observation Period	Last 14 Days

To refine the calculation of resource utilization percentiles, you can set the sample time to consider. Workload Optimization Manager uses historical data from up to the number of days that you specify as a sample period. If the volume has fewer days' data then it uses all of the stored historical data.

Choose from the following settings:

- Less Elastic Last 30 Days
- Recommended Last 14 Days
- More Elastic Last 3 or 7 Days

Min Observation Period

Attribute	Default Value
Min Observation Period	None

This setting ensures historical data for a minimum number of days before Workload Optimization Manager will generate an action based on the percentile set in **Aggressiveness**. This ensures a minimum set of data points before it generates the action.

Especially for scheduled actions, it is important that resize calculations use enough historical data to generate actions that will remain viable even during a scheduled maintenance window. A maintenance window is usually set for "down" time, when utilization is low. If analysis uses enough historical data for an action, then the action is more likely to remain viable during the maintenance window.

Choose from the following settings:

- More Elastic None
- Less Elastic 1, 3, or 7 Days

Cloud Instance Types

Attribute	Default Value
Cloud Instance Types	None

By default, Workload Optimization Manager considers all instance types currently available for scaling when making scaling decisions for Virtual Machine Specs. However, you may have set up your Virtual Machine Specs to *only scale to* or *avoid* certain instance types to reduce complexity and cost, improve discount utilization, or meet application demand. Use this setting to identify the instance types that Virtual Machine Specs can scale to.

Click **Edit** to set your preferences. In the new page that displays, expand a **cloud tier** (a family of instance types, such as *Basic*) to see individual instance types and the resources allocated to them.

Select your preferred instance types or cloud tiers, or clear the ones that you want to avoid. After you save your changes, the main page refreshes to reflect your selections.

If you selected a cloud tier and the service provider deploys new instance types to that tier later, then those instance types will automatically be included in your policy. Be sure to review your policies periodically to see if new instance types have been added to a tier. If you do not want to scale to those instance types, update the affected policies.



Scaling Target Utilization

The utilization that you set here specifies the percentage of the existing capacity that Workload Optimization Manager will consider to be 100% of capacity.

Attribute	Default Value
VCPU	70
VMEM	90
Storage	90

These advanced settings determine how much you would like a scope of workloads to utilize their resources. These are fixed settings that override the way Workload Optimization Manager calculates the optimal utilization of resources. You should only change these settings after consulting with Technical Support.

While these settings offer a way to modify how Workload Optimization Manager recommends actions, in most cases you should never need to use them. If you want to control how Workload Optimization Manager recommends actions to resize workloads, you can set the aggressiveness per the percentile of utilization, and set the length of the sample period for more or less elasticity on the cloud.


Database Server (Cloud)

In AWS public cloud environments, a Database Server is a relational database that you have configured using AWS Relational Database Service (RDS). Workload Optimization Manager discovers RDS instances through your AWS targets, and then generates scaling actions as needed.

NOTE:

Azure SQL Databases discovered by Workload Optimization Manager appear as *Database* entities in the supply chain. For details, see <u>Database</u> (Cloud) (on page 431).

Synopsis



AWS RDS

Synopsis	
Provides:	Database services to cloud applications and end users
Consumes:	Compute and storage resources in the availability zone
Discovered through:	AWS targets



Permissions

Workload Optimization Manager requires the following permissions for AWS RDS Database Servers:

- Monitoring permissions:
 - cloudwatch:GetMetricData
 - pi:GetResourceMetrics
 - rds:DescribeDBInstances
 - rds:DescribeDBParameters
 - rds:ListTagsForResource
 - rds:DescribeOrderableDBInstanceOptions
- Action execution permissions:
 - rds:ModifyDBInstance
 - rds:StartDBInstance
 - rds:StopDBInstance

For the full list of permissions, see AWS Permissions (on page 242).

Monitored Resources

Workload Optimization Manager monitors the following resources:

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

■ Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

■ DB Cache Hit Rate

DB cache hit rate is the measurement of Database Server accesses that result in cache hits, measured as a percentage of hits versus total attempts. A high cache hit rate indicates efficiency.

Connection

Connection is the measurement of database connections utilized by applications.

Actions

Workload Optimization Manager can recommend the following actions:

■ Stop and Start (also known as 'parking' actions)

Stop a Database Server for a given period of time to reduce your cloud expenses, and then start it at a later time.

■ Scale

Scale compute and storage resources to optimize performance and costs.

Stop and Start Actions for Database Servers

Workload Optimization Manager supports 'parking' actions for cloud resources. These actions *stop* your cloud resources for a given period of time to help you reduce your cloud expenses, and then *start* these resources later when you need them. You can enforce parking actions on demand, or automatically via parking schedules and policies.

For details, see Parking: Stop or Start Cloud Resources (on page 597).



Scale Actions for Database Servers

To recommend accurate scaling actions, Workload Optimization Manager analyzes resource utilization percentiles and collects relevant metrics (such as connections utilization) from AWS. It also takes into consideration constraints defined in policies (on page 421).

Consider the following scenarios and actions:

- To address vCPU congestion, Workload Optimization Manager can recommend scaling a Database Server to the instance type that can adequately meet demand at the lowest possible cost. If vCPU is underutilized, it can recommend scaling to a smaller instance type.
- To address IOPS congestion, Workload Optimization Manager can recommend increasing provisioned IOPS or scaling the Database Server to a different storage type. For gp2 storage, it can recommend increasing disk size to increase provisioned IOPS. After executing these actions, Workload Optimization Manager will not recommend new actions for the next six hours, in compliance with AWS's "cooldown" period for EBS storage.
- Workload Optimization Manager analyzes DB cache hit rate before making vMem scaling decisions. To perform its analysis, it collects cache hit rate metrics for Database Servers with Performance Insights enabled.

For Database Servers with cache hit rate metrics, Workload Optimization Manager considers at least 90% cache hit rate to be optimal. This percentage value is not configurable.

- A cache hit rate value equal to or greater than 90% indicates efficiency. For this reason, Workload Optimization
 Manager will not recommend an action even if vMem utilization is high. If vMem utilization is low, it will recommend
 scaling to a smaller instance type.
- When the cache hit rate is below 90%, Workload Optimization Manager will also not recommend an action, provided that vMem utilization remains low. If vMem utilization is high, then it will recommend scaling to a larger instance type.

Notes on Performance Insights and cache hit rate metrics:


- Performance Insights is enabled by default on a majority of AWS Database Servers. In the Workload Optimization
 Manager user interface, you can use Search and then apply the Performance Insights filter to see which Database
 Servers have Performance Insights enabled.
- If Performance Insights is disabled or is not supported for your AWS Database Server engines or regions, Workload
 Optimization Manager will not have cache hit rate metrics to analyze and will therefore not generate actions in direct
 response to vMem utilization. For a list of supported engines and regions, see this AWS page.
- An action to scale to a different instance type in response to vCPU utilization might also include vMem changes, but vMem utilization alone (without cache hit rate metrics) will not drive actions.

Workload Optimization Manager also considers Connections utilization and capacity when making scaling decisions. It collects utilization metrics from CloudWatch and calculates capacity based on the maximum number of simultaneous connections configured for the Database Server. The maximum number varies by Database Server engine type and memory allocation, and is set in the parameter group associated with a Database Server. Workload Optimization Manager currently supports Database Servers associated with parameter groups that use default values. For example, consider a MySQL Database Server that is on a db.t3.large instance type with 8 GB (8589934592 bytes) of memory, and is associated with a parameter group that uses the default value {DBInstanceClassMemory/12582880}. In this case, Workload Optimization Manager calculates capacity as 682 connections (or {8589934592/12582880}). When Workload Optimization Manager generates an action due to vMem underutilization and sees that Connections utilization is only 15% of capacity (or roughly 100 connections), it picks a smaller instance type that is adequate for both the vMem and Connections requirements of the Database Server. For example, it could pick db.t2.small, which provides 2 GB of memory and a maximum of 170 connections.

Scale Actions in Charts

Use the Necessary Investments and Potential Savings charts to view pending Database Server actions. These charts show total monthly investments and savings, assuming you execute all the actions.





Click Show All for each chart to review and execute the actions.

The table lists all the actions that are pending for Database Servers, and the savings or investments for each action.



For details on how Workload Optimization Manager calculates savings or investments, see <u>Estimated On-demand Costs for Cloud Database Servers (on page 419)</u>.

Utilization Charts for Scale Actions

Workload Optimization Manager uses percentile calculations to measure resource utilization more accurately, and drive scaling actions that improve overall utilization and reduce costs. When you examine the details for a pending scale action on a Database Server, you will see charts that highlight *utilization percentiles* for a given observation period, and the projected percentiles after you execute the action.






The charts also plot *daily average utilization* for your reference. If you have previously executed scaling actions on the Database Server, you can see the resulting improvements in daily average utilization. Put together, these charts allow you to easily recognize utilization trends that drive Workload Optimization Manager's scaling recommendations.

You can set scaling constraints in Database Server policies to refine the percentile calculations.






For details, see Scaling Sensitivity (on page 422).

Non-disruptive and Reversible Scaling Actions

Workload Optimization Manager indicates whether a pending action is non-disruptive or reversible to help you decide how to handle the action.




The following table describes the disruptiveness and reversibility of the actions that Workload Optimization Manager recommends:

Action	Disruptive	Reversible
Scaling to a different instance type	Yes	Yes
Scaling up storage amount	No	No



Action	Disruptive	Reversible
Scaling up storage access (provisioned IOPS)	No	Yes
Scaling to a different storage type + Scaling up storage amount	Yes	No
Scaling to a different storage type + Scaling up storage access (provisioned IOPS)	Yes	Yes
Scaling to a different storage type + Scaling up storage amount + Scaling up storage access (provisioned IOPS)	Yes	No

You can set action acceptance modes in policies to specify the degree of automation for these actions.



Unavailable Instance Types

A scale action could fail if the target instance type is unavailable in the availability zone for some reason. Your AWS environment might show the instance type as available, but when the scaling action executes, the following error displays in AWS:

Cannot modify the instance class because there are no instances of the requested class available in the current instance's availability zone. Please try your request again at a later time.

NOTE:


For details about this error, see this AWS page.

When this error occurs, Workload Optimization Manager modifies the default Database Server policy to exclude the instance type from its scaling list. When the Database Server is available again, Workload Optimization Manager adds it back to the scaling list. For details about this list, see <u>Cloud Instance Types</u> (on page 423).



Estimated On-demand Costs for Cloud Database Servers

Workload Optimization Manager considers a variety of factors when calculating *Estimated On-demand Monthly Cost* for an AWS RDS Database Server.



Non-Aurora Database Servers

Cost Calculation

For non-Aurora Database Servers, the calculation for Estimated On-demand Monthly Cost can be expressed as follows:

(On-demand Compute Rate * 730) + (Provisioned Database Storage Rate * Provisioned Database Storage Amount) + (Provisioned IOPS Rate * Provisioned IOPS Amount) = Estimated On-demand Monthly Cost

Where:

- On-demand Compute Rate is the hourly cost for a Database Server's instance type
 You can obtain on-demand rates via <u>Amazon RDS Pricing</u>.
- 730 represents the number of hours per month that Workload Optimization Manager uses to estimate monthly costs.
- Provisioned Database Storage Rate is the hourly cost for a Database Server's provisioned database storage You can obtain provisioned database storage rates via <u>Amazon RDS Pricing</u>.
- Provisioned IOPS Rate is the monthly cost for a Database Server's provisioned IOPS

Provisioned IOPS apply only to Database Servers on Provisioned IOPS SSD (io1) storage. You can obtain information about Provisioned IOPS SSD storage via the RDS User Guide.

You can obtain provisioned IOPS rates via Amazon RDS Pricing.

The listed items above impact cost calculations and the scaling decisions that Workload Optimization Manager makes. These decisions also rely on other factors, such as resource utilization percentiles and scaling constraints set in policies.

Example

Assume the following data for a pending scale action for SQL Server Express Edition (Single A-Z deployment):



	Current Values	Values After Action Execution
On-demand Compute Rate	\$0.024/hr	\$0.048/hr
Provisioned Database Storage Rate	\$0.133/hr	\$0.133/hr
Provisioned Database Storage Amount	20 GB	20 GB
Provisioned IOPS Rate	\$0.00	\$0.00
Provisioned IOPS Amount	0	0

Workload Optimization Manager calculates the following:

■ Current Estimated On-demand Monthly Cost:

```
(0.024 * 730) + (0.133 * 20) + (0.00 * 0) = 20.18
```

■ Estimated On-demand Monthly Cost *after* executing the action:

```
(0.048 * 730) + (0.133 * 20) + (0.00 * 0) = 37.7
```

NOTE:

Workload Optimization Manager rounds the calculated values that it displays in the user interface.

The Estimated On-demand Monthly Cost is projected to increase from \$20.18/month to \$37.7/month, as shown in the Details section of the pending action.



Workload Optimization Manager treats the action as an investment and shows an estimated investment of \$17.52/month.



Aurora Database Servers

Cost Calculation

For Aurora Database Servers, the calculation for Estimated On-demand Monthly Cost can be expressed as follows:

(On-demand Compute Rate * 730) + (Provisioned Database Storage Rate * Provisioned Database Storage Amount) + (I/O Request Rate * (Hourly Billed I/O Operation Count * 730)) = Estimated On-demand Monthly Cost

Where:

- On-demand Compute Rate is the hourly cost for a Database Server's instance type You can obtain on-demand rates via <u>Amazon Aurora Pricing</u>.
- 730 represents the number of hours per month that Workload Optimization Manager uses to estimate monthly costs.
- Provisioned Database Storage Rate is the hourly cost for a Database Server's provisioned database storage You can obtain provisioned database storage rates via <u>Amazon Aurora Pricing</u>.



- I/O Request Rate is the cost per one million read/write I/O requests
 - You can obtain I/O request rates via Amazon Aurora Pricing.
- Hourly Billed I/O Operation Count is the average sum of read and write I/O operations per hour over the last month

The listed items above impact cost calculations. Except for I/O request rate, these items affect the actual scaling decisions that Workload Optimization Manager makes. These decisions also rely on other factors, such as resource utilization percentiles and scaling constraints set in policies.

Example

Assume the following data for a pending scale action for Aurora MySQL-Compatible Edition:

	Current Values	Values After Action Execution
On-demand Compute Rate	\$0.164/hr	\$0.041/hr
Provisioned Database Storage Rate	\$0.10/hr	\$0.10/hr
Provisioned Database Storage Amount	100	100
I/O Request Rate	\$0.20/one million requests	\$0.20/one million requests
Hourly Billed I/O Operation Count	2000	2000

Workload Optimization Manager calculates the following:

■ Current Estimated On-demand Monthly Cost:

```
(0.164 * 730) + (0.10 * 100) + ((0.20 / 1000000) * (2000 * 730)) = 130.01
```

Estimated On-demand Monthly Cost after executing the action:

```
(0.041 * 730) + (0.10 * 100) + ((0.20 / 1000000) * (2000 * 730)) = 40.22
```

NOTE:

Workload Optimization Manager rounds the calculated values that it displays in the user interface.

Since the Estimated On-demand Monthly Cost is projected to decrease from \$130.01/month to \$40.22/month, Workload Optimization Manager treats the action as a cost-saving measure and shows estimated savings of \$89.79/month.

Cloud Database Server Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

For details about cloud Database Server actions, see <u>Cloud Database Server Actions (on page 413)</u> and <u>Non-disruptive and</u> Reversible Scaling Actions (on page 417).

Action	Default Setting/Mode
Database Server Scaling Actions	On
Disruptive irreversible scaling	Recommend
Disruptive reversible scaling	Recommend
Non-disruptive irreversible scaling	Recommend
Non-disruptive reversible scaling	Recommend



Scaling Sensitivity

Workload Optimization Manager uses a percentile of utilization over the specified observation period. This gives sustained utilization and ignores short-lived bursts.

Workload Optimization Manager uses these settings to calculate utilization percentiles for VCPU, VMEM and DB Cache Hit Rate, and IOPS. It then recommends actions to improve utilization based on the observed values for a given time period.

Aggressiveness

Attribute	Default Value
Aggressiveness	95th Percentile

When evaluating performance, Workload Optimization Manager considers resource utilization as a percentage of capacity. The utilization drives actions to scale the available capacity either up or down. To measure utilization, the analysis considers a given utilization percentile. For example, assume a 95th percentile. The percentile utilization is the highest value that 95% of the observed samples fall below. Compare that to average utilization, which is the average of *all* the observed samples.

Using a percentile, Workload Optimization Manager can recommend more relevant actions. This is important in the cloud, so that analysis can better exploit the elasticity of the cloud. For scheduled policies, the more relevant actions will tend to remain viable when their execution is put off to a later time.

For example, consider decisions to reduce capacity. Without using a percentile, Workload Optimization Manager never resizes below the recognized peak utilization. Assume utilization peaked at 100% just once. Without the benefit of a percentile, Workload Optimization Manager will not reduce resources for that Database Server.

With **Aggressiveness**, instead of using the single highest utilization value, Workload Optimization Manager uses the percentile you set. For the above example, assume a single burst to 100%, but for 95% of the samples, utilization never exceeded 50%. If you set **Aggressiveness** to 95th Percentile, then Workload Optimization Manager can see this as an opportunity to reduce resource allocation.

In summary, a percentile evaluates the sustained resource utilization, and ignores bursts that occurred for a small portion of the samples. You can think of this as aggressiveness of resizing, as follows:

- 99th Percentile More performance. Recommended for critical Database Servers that need maximum guaranteed performance at all times, or those that need to tolerate sudden and previously unseen spikes in utilization, even though sustained utilization is low.
- 95th Percentile (Default) The recommended setting to achieve maximum performance and savings. This assures
 performance while avoiding reactive peak sizing due to transient spikes, thus allowing you to take advantage of the
 elastic ability of the cloud.
- 90th Percentile More efficiency. Recommended for Database Servers that can stand higher resource utilization.

By default, Workload Optimization Manager uses samples from the last 14 days. Use the **Max Observation Period** setting to adjust the number of days. To ensure that there are enough samples to analyze and drive scaling actions, set the **Min Observation Period**.

Max Observation Period

Attribute	Default Value
Max Observation Period	Last 14 Days

To refine the calculation of resource utilization percentiles, you can set the sample time to consider. Workload Optimization Manager uses historical data from up to the number of days that you specify as a sample period. If the Database Server has fewer days' data then it uses all of the stored historical data.

You can make the following settings:

- Less Elastic Last 30 Days
- Recommended Last 14 Days
- More Elastic Last 7 Days or Last 3 Days

Workload Optimization Manager recommends an observation period of 14 days so it can recommend scaling actions more often. Since Database Server scaling is minimally disruptive, scaling often should not introduce any noticeable performance risks.

Min Observation Period



Attribute	Default Value
Min Observation Period	None

This setting ensures historical data for a minimum number of days before Workload Optimization Manager will generate an action based on the percentile set in **Aggressiveness**. This ensures a minimum set of data points before it generates the action.

Especially for scheduled actions, it is important that resize calculations use enough historical data to generate actions that will remain viable even during a scheduled maintenance window. A maintenance window is usually set for "down" time, when utilization is low. If analysis uses enough historical data for an action, then the action is more likely to remain viable during the maintenance window.

- More Elastic None
- Less Elastic 1, 3, or 7 Days

Cloud Instance Types

By default, Workload Optimization Manager considers all instance types currently available for scaling when making scaling decisions for Database Servers. However, you may have set up your Database Servers to *only scale to* or *avoid* certain instance types to reduce complexity and cost, or meet demand. Use this setting to identify the instance types that Database Servers can scale to.

NOTE:

Workload Optimization Manager automatically discovers and enforces Database Server tier exclusions configured in your AWS environment. You do not need to configure these tier exclusions in policies. To see a list of tier exclusions that are currently enforced, set the scope to one or several Database Servers and click the **Policies** tab.

Attribute	Default Value
Cloud Instance Types	None

Click **Edit** to set your preferences. In the new page that displays, expand a **cloud tier** (a family of instance types, such as *db.m1*) to see individual instance types and the resources allocated to them.

Select your preferred instance types or cloud tiers, or clear the ones that you want to avoid. After you save your changes, the main page refreshes to reflect your selections.

NOTE:

This policy setting is not available in plans.

If you selected a cloud tier and the service provider deploys new instance types to that tier later, then those instance types will automatically be included in your policy. Be sure to review your policies periodically to see if new instance types have been added to a tier. If you do not want to scale to those instance types, update the affected policies.

Scaling Target Utilization

This is the target utilization as a percentage of capacity.

Attribute	Default Value
VCPU	70
VMEM	90
IOPS	70
Storage Amount	90

These advanced settings determine how much you would like a scope of workloads to utilize their resources. These are fixed settings that override the way Workload Optimization Manager calculates the optimal utilization of resources. You should only change these settings after consulting with Technical Support.




While these settings offer a way to modify how Workload Optimization Manager recommends actions, in most cases you should never need to use them. If you want to control how Workload Optimization Manager recommends actions to resize workloads, you can set the aggressiveness per the percentile of utilization, and set the length of the sample period for more or less elasticity on the cloud.

Volume (Cloud)

A cloud volume is a storage device that you can attach to a VM. You can use an attached volume the same as a physical hard drive.

Synopsis



Synopsis	
Provides: Storage resources for VMs to use, including:	
	■ Storage Access
	■ Storage Amount
	■ IO Throughput



Synopsis	
Consumes:	Storage services provided by zones or regions
Discovered through:	AWS and Azure targets

Monitored Resources

Workload Optimization Manager monitors the following resources:

Storage Amount

Storage Amount is the storage capacity (disk size) of a volume.

Workload Optimization Manager discovers Storage Amount, but does not monitor utilization.

For a Kubeturbo (container) deployment that includes volumes, Kubeturbo monitors Storage Amount utilization for the volumes. You can view utilization information in the Capacity and Usage chart.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the measurement of IOPS capacity that is in use.

■ I/O Throughput

I/O Throughput is the measurement of I/O throughput capacity that is in use.

NOTE:

Currently, Workload Optimization Manager does not monitor resources for GCP volumes. It only monitors their attachment state and then generates delete actions for unattached volumes.

Actions

Workload Optimization Manager can recommend the following actions:

■ Scale

Scale attached volumes to optimize performance and costs.

NOTE

This action is only supported for AWS and Azure volumes.

Delete

Delete unattached volumes as a cost-saving measure. Workload Optimization Manager generates an action immediately after discovering an unattached volume.

Scale Actions

Scale attached AWS/Azure volumes to optimize performance and costs.

NOTE

Currently, Workload Optimization Manager does not generate scale actions for GCP volumes.

Workload Optimization Manager can recommend:

Scaling within the same tier (scale up or down), or from one tier to another

Examples:

- An action to scale down IOPS for a high performance volume, such as Azure Managed Ultra
- An action to scale a volume from the io1 to the gp2 tier

These actions can reduce costs significantly while continuing to assure performance. In addition, they are *non-disruptive* and *reversible*.

NOTE:

For details about action disruptiveness and reversibility, see Non-disruptive and Reversible Scaling Actions (on page 429).

■ Scaling from one tier to another and then within the new tier, in a single action



For example, to achieve higher IOPS performance for VMs that are premium storage capable, you might see an action to scale the corresponding volume from *Standard* to *Premium*, and then scale up volume capacity from *32GB* to *256 GB*. This action increases costs and is *irreversible*, but is more cost effective than scaling up within the original tier.


NOTE:

Not all VM types are premium storage capable. For details, see the Azure Documentation.

When there are multiple disks attached to a volume, every volume scale action can potentially disrupt the same VM multiple times and some of the actions may fail due to concurrency. To mitigate these issues, Workload Optimization Manager identifies all volume actions associated with a particular VM and combines them into a single unit for execution, thus reducing disruptions and the chance of failures due to concurrency. This approach applies to scale actions in *Manual* or *Automated* mode.

You can create policies to control the scaling actions that Workload Optimization Manager generates.

Workload Optimization Manager includes a policy setting that lets you choose between two outcomes – better savings (default) and better reversibility. If you choose reversibility, which can increase costs, Workload Optimization Manager will prioritize actions to change tiers whenever possible.



Set scaling constraints if you want volumes to only scale to or avoid certain tiers. For details, see <u>Cloud Storage Tiers (on page 431)</u>.

Delete Actions

Delete unattached volumes as a cost-saving measure. Workload Optimization Manager generates delete actions for AWS, Azure, and GCP volumes.

NOTE:

If you delete an Azure volume and then later deploy a new one with an identical name, charts will include historical data from the volume that you deleted.

Exceptions for Azure Site Recovery and Azure Backup Volumes

Workload Optimization Manager discovers Azure Site Recovery and Azure Backup volumes when you add Azure targets. Even though these volumes are always unattached, Workload Optimization Manager will never recommend deleting them because they are critical to business continuity and disaster recovery.

To identify Azure Site Recovery volumes, Workload Optimization Manager checks an Azure resource called Recovery Services vault, which includes information specific to the volumes. It also checks for the ASR-ReplicaDisk tag, which Azure automatically assigns to the volumes.

For Azure Backup volumes, Workload Optimization Manager checks for the RSVaultBackup tag.

It is important that you do not remove these tags. If these tags have been removed for some reason, create a volume policy for the affected volumes and disable the *Delete* action in that policy.

Action Execution for Locked Volumes

For Azure environments, Workload Optimization Manager can recommend scale and delete actions for <u>locked volumes</u>, but the lock level configured for the volumes may prevent some actions from executing.

- For volumes with the ReadOnly lock, both scale and delete actions are not executable.
- For volumes with the CanNotDelete lock, delete actions are not executable, but scale actions are executable.



You must sign in to Azure and then remove the locks for the affected volumes before you can execute actions. To identify the specific locks that you need to remove, open the Action Details page for a pending volume action and see the **Execution Prerequisites** section.

Volume Actions in Charts

Use the Necessary Investments and Potential Savings charts to view pending volume actions. These charts show total monthly investments and savings, assuming you execute all the actions.






Click Show All for each chart to review and execute the actions.

The table shows the following:

- Actions that are pending for each volume
- Savings or investments for each volume
- For Delete actions in the Potential Savings chart:



Number of days a volume has been unattached

This information helps you decide whether to take the action.

Workload Optimization Manager polls your cloud volumes every 6 hours, and then records their state (attached or unattached) at the time of polling. It does not account for changes in state between polls.

For newly unattached volumes, Workload Optimization Manager shows a dash symbol (-) if a volume has been unattached within the last 6 hours. A value of 0 (zero) means that a volume has been unattached within the last 24 hours.

Once Workload Optimization Manager discovers an unattached volume, it immediately recommends that you delete it. If a currently unattached volume is not deleted and is subsequently discovered as attached, Workload Optimization Manager removes the *Delete* action attached to it, and then resets the unattached period.


NOTE:

For volumes that have been deleted from the cloud provider and are no longer discoverable, Workload Optimization Manager removes them from its records after 15 days.

To see the last known VM attached to the volume, click **DETAILS**.

For Scale actions in the Potential Savings or Necessary Investments chart:






- Whether actions are non-disruptive or reversible
- Changes the actions will effect (for example, changes in tiers and/or resource allocations)

When you click the **DETAILS** button for a scaling action, you will see utilization charts that help explain the reason for the action.

Utilization Charts for Volume Scaling Actions



Workload Optimization Manager uses percentile calculations to measure IOPS and throughput more accurately, and drive scaling actions that improve overall utilization and reduce costs. When you examine the details for a pending scaling action on a volume, you will see charts that highlight resource *utilization percentiles* for a given observation period, and the projected percentiles after you execute the action.

The charts also plot *daily average utilization* for your reference. If you have previously executed scaling actions on the volume, you can see the resulting improvements in daily average utilization. Put together, these charts allow you to easily recognize utilization trends that drive Workload Optimization Manager's scaling recommendations.


NOTE

You can set scaling sensitivity in volume policies to refine the percentile calculations. For details, see <u>Scaling Sensitivity (on page 430)</u>.



Non-disruptive and Reversible Scaling Actions

Workload Optimization Manager indicates whether a pending action is non-disruptive or reversible.



Non-disruptive


Executing storage scaling actions can sometimes be disruptive if the VM must be rebooted to execute a storage change. For example, Azure Standard and Premium scaling actions are *disruptive*. When a storage action is disruptive, expect a single reboot (usually 2-3 minutes of downtime).

The following scaling actions are non-disruptive:

- Scaling IOPS and throughput on Azure Ultra storage
- All scaling actions on AWS storage

■ Reversible

Executing storage scaling actions can sometimes be irreversible if the volume must grow in size to subsequently increase IOPS or throughput capacity. In this case, shrinking that volume's size later would not be possible. If you prefer reversible volume actions, create a volume policy and choose **Better Reversibility**.



Cloud Volume Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.



Action Automation and Orchestration

For details about cloud volume actions, see Cloud Volume Actions (on page 425).

Action	Default Mode
Scale	Manual
Delete	Manual

Prefer Savings Over Reversibility

Executing storage scaling actions can sometimes be irreversible if the volume must grow in size to subsequently increase IOPS or throughput capacity. In this case, shrinking that volume's size later would not be possible. If you prefer reversible volume actions, create a volume policy and choose **Better Reversibility**.

Scaling Sensitivity

Workload Optimization Manager uses a percentile of utilization over the specified observation period. This gives sustained utilization and ignores short-lived bursts.

Aggressiveness

Attribute	Default Value
Aggressiveness	95th Percentile

Workload Optimization Manager uses Aggressiveness when evaluating IOPS and throughput.

When evaluating performance, Workload Optimization Manager considers resource utilization as a percentage of capacity. The utilization drives actions to scale the available capacity either up or down. To measure utilization, the analysis considers a given utilization percentile. For example, assume a 95th percentile. The percentile utilization is the highest value that 95% of the observed samples fall below. Compare that to average utilization, which is the average of *all* the observed samples.

Using a percentile, Workload Optimization Manager can recommend more relevant actions. This is important in the cloud, so that analysis can better exploit the elasticity of the cloud. For scheduled policies, the more relevant actions will tend to remain viable when their execution is put off to a later time.

For example, consider decisions to reduce capacity. Without using a percentile, Workload Optimization Manager never scales below the recognized peak utilization. Assume utilization peaked at 100% just once. Without the benefit of a percentile, Workload Optimization Manager will not reduce resources for that volume.

With **Aggressiveness**, instead of using the single highest utilization value, Workload Optimization Manager uses the percentile you set. For the above example, assume a single burst to 100%, but for 95% of the samples, utilization never exceeded 50%. If you set **Aggressiveness** to 95th Percentile, then Workload Optimization Manager can see this as an opportunity to reduce resource allocation.

In summary, a percentile evaluates the sustained resource utilization, and ignores bursts that occurred for a small portion of the samples. You can think of this as aggressiveness of resizing, as follows:

- 99th or 100th Percentile More performance. Recommended for critical volumes that need maximum guaranteed performance at all times, or those that need to tolerate sudden and previously unseen spikes in utilization, even though sustained utilization is low.
- 95th Percentile (Default) The recommended setting to achieve maximum performance and savings. This assures
 performance while avoiding reactive peak sizing due to transient spikes, thus allowing you to take advantage of the
 elastic ability of the cloud.
- 90th Percentile More efficiency. Recommended for volumes that can stand higher resource utilization.

By default, Workload Optimization Manager uses samples from the last 30 days. Use the **Max Observation Period** setting to adjust the number of days.

Max Observation Period

Attribute	Default Value
Max Observation Period	Last 30 Days



To refine the calculation of resource utilization percentiles, you can set the sample time to consider. Workload Optimization Manager uses historical data from up to the number of days that you specify as a sample period. If the volume has fewer days' data then it uses all of the stored historical data.

Choose from the following settings:

- Less Elastic Last 90 Days
- Recommended Last 30 Days
- More Elastic Last 7 Days

Min Observation Period

Attribute	Default Value
Min Observation Period	None

This setting ensures historical data for a minimum number of days before Workload Optimization Manager will generate an action based on the percentile set in **Aggressiveness**. This ensures a minimum set of data points before it generates the action.

Especially for scheduled actions, it is important that resize calculations use enough historical data to generate actions that will remain viable even during a scheduled maintenance window. A maintenance window is usually set for "down" time, when utilization is low. If analysis uses enough historical data for an action, then the action is more likely to remain viable during the maintenance window.

Choose from the following settings:

- More Elastic None
- Less Elastic 1, 3, or 7 Days

Scaling Target IOPS/Throughput Utilization

This is the target utilization as a percentage of capacity.

Attribute	Default Value
Scaling Target IOPS/Throughput Utilization	70

Cloud Storage Tiers

By default, Workload Optimization Manager considers all storage tiers currently available for scaling when making scaling decisions for volumes. However, you may have set up your cloud volumes to *only scale to* or *avoid* certain tiers to reduce complexity and cost, or meet demand. Use this setting to identify the tiers that volumes can scale to.

Attribute	Default Value
Cloud Storage Tiers	None

Click **Edit** to set your preferences. In the new page that displays, select your preferred cloud tiers or clear the ones that you want to avoid. After you save your changes, the main page refreshes to reflect your selections.

Database (Cloud)

Workload Optimization Manager discovers SQL Databases and dedicated SQL pools from your Azure targets, and represents them as Database entities in the supply chain.

NOTE:

AWS RDS databases appear as *Database Server* entities in the supply chain. For details, see <u>Database Server</u> (Cloud) (on page 412).

SQL Databases



Workload Optimization Manager discovers the resources on *individual databases* that are managed under both the DTU (Database Transaction Unit) and vCore pricing models.

- DTU Pricing Model

In the DTU model, Azure bundles CPU, memory, and IOPS as a single DTU metric. Workload Optimization Manager actions on these databases consider both DTU and storage utilization.

vCore Pricing Model

In the vCore model, analysis can track CPU, memory, IOPS, and throughput metrics in isolation. Workload Optimization Manager actions on these databases are driven by CPU, memory, IOPS, throughput and storage utilization.


NOTE:

For more information about the DTU and vCore models, see the Azure documentation.

■ <u>Dedicated SQL Pools</u> (for Azure Synapse Analytics)

A dedicated SQL pool represents a collection of analytic resources that Azure provisions when you use Synapse SQL. Compute capacity for a dedicated SQL pool is expressed in Data Warehousing Units (DWU). DWU represents CPU, memory, and IO Throughput bundled as a single commodity.

Synopsis





Synopsis	
Provides:	Transactions to end users and analytic resources to Azure Synapse Analytics
Consumes:	■ DTU Pricing Model:
	DTU and storage resources in an Azure region
	■ vCore Pricing Model:
	vCPU, vMem, IOPS, throughput, and storage resources in an Azure region
	■ Dedicated SQL Pool:
	DWU and storage resources in an Azure region
Discovered through:	Azure targets

Database Groups

We highly recommend creating groups in Workload Optimization Manager so you can manage SQL databases and dedicated SQL pools with ease. When you set the scope to a particular group, you can evaluate pending actions, view metrics, and assign policies as usual. You can also view the status of individual members. For example, you can see if a dedicated SQL pool is currently active or suspended.

To create groups, go to **Settings > Groups**, and then click **New Group**. In the page that displays, choose **Dynamic** (recommended) and then set the Pricing Model filter as follows:

- **DTU** and/or **vCore** use to create a group of SQL databases
- **DWU** use to create a group of dedicated SQL pools

Monitored Resources

The resources that Workload Optimization Manager can monitor depend on the pricing model in place for the given database entity.

- DTU Pricing Model
 - DTU

DTU is the measurement of compute capacity for the database. DTU represents CPU, memory, and IOPS/IO Throughput bundled as a single commodity.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

- vCore Pricing Model
 - Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

- Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

- I/O Throughput

I/O Throughput is the measurement of an entity's throughput to the underlying storage.

- Dedicated SQL Pool
 - DWU

DWU (Data Warehousing Unit) is the measurement of compute capacity for the dedicated SQL pool. DWU represents CPU, memory, and IO Throughput bundled as a single commodity.

Storage Amount



Storage Amount is the measurement of storage capacity that is in use.

Connection

Connection is the measurement of database connections utilized by applications.

Actions

Workload Optimization Manager can recommend the following actions:

Scale (SQL Database)

■ DTU Pricing Model

Scale DTU and storage resources to optimize performance and costs.

vCore Pricing Model

Scale vCPU, vMem, IOPS, throughput and storage resources to optimize performance and costs.

Suspend (Dedicated SQL Pool)

Suspend an idle dedicated SQL pool (used for Azure Synapse Analytics) to reduce compute costs.

NOTE

Currently, Workload Optimization Manager does not generate actions to start a suspended pool. You can manually start a pool from Azure.

Scale Actions for SQL Databases

Workload Optimization Manager database scaling actions aim to increase resource utilization and reduce costs while complying with business policies.

Workload Optimization Manager drives scaling actions based on the utilization of resources, and treats the following limits as constraints when it makes scaling decisions:

Maximum concurrent sessions

This is the maximum number of database connections at a time.

Maximum concurrent workers

This is the maximum number of database processes that can handle queries at a time.


Points to consider:

- Workload Optimization Manager will *not* recommend:
- Scaling from one pricing model to another
 - Scaling vCore databases to instance types running Gen4 hardware. This hardware generation has been retired and pricing information can no longer be retrieved via the Azure API.
 - Scaling vCore databases on the serverless compute tier
 - Scaling provisioned memory for vCore databases on the Hyperscale service tier. VMem utilization data is currently unavailable for Hyperscale due to an issue in the Azure API.
- On DTU databases, a single action can scale both DTU and storage. On vCore databases, a single action can scale vCPU,
 vMem, IOPS, throughput, and storage.
- In some cases, Workload Optimization Manager might recommend scaling up storage, even if there is no storage pressure on the database, to take advantage of storage provided at no extra cost. For example, Workload Optimization Manager might recommend scaling from the S3 to the S0 tier because of low DTU and storage utilization. Since the S0 tier includes 250 GB of storage at no extra cost, Workload Optimization Manager will also recommend scaling up to this storage amount. If you want to scale DTU but keep the storage amount unchanged, adjust the values for aggressiveness (percentile) and observation period in your database policies.

Utilization Charts for Scale Actions

Workload Optimization Manager uses percentile calculations to measure resource utilization, and drive scaling actions that improve overall utilization and reduce costs. When you examine the details for a pending scaling action on a database, you will see charts that highlight resource *utilization percentiles* for a given observation period, and the projected percentiles after you execute the action.





The charts also plot *daily average utilization* for your reference. If you have previously executed scaling actions on the database, you can see the resulting improvements in daily average utilization. Put together, these charts allow you to easily recognize utilization trends that drive Workload Optimization Manager's scaling recommendations.

NOTE

You can set scaling constraints in database policies to refine the percentile calculations. For details, see <u>Aggressiveness and Observation Period</u> (on page 439).


Non-disruptive and Reversible Scaling Actions

All scaling actions shown in the Action Center view and Action Details page are non-disruptive and reversible.

For actions to scale vCore databases from General Purpose or Business Critical to Hyperscale, there are certain caveats associated with reversing such actions. To learn more, see the <u>Azure documentation</u>.

Suspend Actions for Dedicated SQL Pools

When Workload Optimization Manager discovers an idle dedicated SQL pool (i.e., a pool with no active connections for a specific period of time), it will immediately recommend that you suspend the pool as a cost-saving measure. This action stops the compute instance for the SQL pool, but keeps storage running. In the Action Details page for a specific action, the compute cost is 0 (zero) *after* suspension, while storage cost remains the same.






NOTE:

To calculate the current compute cost, Workload Optimization Manager retrieves the hourly on-demand cost from Azure and then multiplies the result by 730, which represents the number of hours per month that the product uses to estimate monthly costs.

If a currently idle pool is not suspended and is subsequently discovered as active, Workload Optimization Manager removes the suspend action attached to it.

Suspend actions include the 'Idle Time' information that indicates how long a dedicated SQL pool has been idle. By default, Workload Optimization Manager will generate suspend actions if dedicated SQL pools have been idle for at least one hour.




You can control the suspend actions that Workload Optimization Manager generates, based on your preferred idle time value.

For example, if you want Workload Optimization Manager to only generate suspend actions for dedicated SQL pools that have been idle for at least one day, perform these steps:

- 1. Create a dynamic group of Databases and set the 'Hours Idle' filter to Hours Idle < = 24.
- 2. Create a custom Database policy, set the scope to the group that you just created, and then *disable* suspend actions in that policy.

Actions in Charts

Use the Necessary Investments and Potential Savings charts to view pending database actions. These charts show total monthly investments and savings, assuming you execute all the actions.



Click Show All for each chart to review and execute the actions.

The table shows the following:


Actions that are pending for each database



Savings or investments for each database

Estimated On-demand Costs for Cloud Databases

Workload Optimization Manager considers a variety of factors when calculating *Estimated On-demand Monthly Cost* for an Azure SQL Database.



Azure SQL DTU Databases

Cost Calculation

For Azure SQL DTU Databases, the calculation for Estimated On-demand Monthly Cost can be expressed as follows:

 $(On-demand\ Compute\ Rate\ *\ 730))$ + $(Provisioned\ Database\ Storage\ Rate\ *\ (Provisioned\ Database\ Storage\ Amount\ -\ Performance\ Level\ Included\ Storage))$ = Estimated On-demand Monthly Cost

Where:

- On-demand Compute Rate is the hourly cost for a Database's instance type
 - You can obtain on-demand rates via Azure SQL Database Pricing.
- 730 represents the number of hours per month that Workload Optimization Manager uses to estimate monthly costs.
- Provisioned Database Storage Rate is the cost for 1 GB / mo. of a Database's provisioned storage
 - You can obtain provisioned database storage rates via Azure SQL Database Pricing.
- Performance Level Included Storage is the storage amount included in the price of the selected Performance Level of a DTU Database

You can obtain information on DTU storage limits via DTU Storage Limits.

The listed items above impact cost calculations and the scaling decisions that Workload Optimization Manager makes. These decisions also rely on other factors, such as resource utilization percentiles and scaling constraints set in policies.

Example

Assume the following data for a pending scale action for an Azure SQL DTU Database:

	Current Values	Values After Action Execution
On-demand Compute Rate	\$0.20125/hr	\$0.020125/hr



	Current Values	Values After Action Execution
Provisioned Database Storage Rate	\$0.221 per 1 GB/Mo.	\$0.221 per 1 GB/Mo.
Performance Level Included Storage	250 GB	250 GB
Provisioned Database Storage Amount	300 GB	250 GB

Workload Optimization Manager calculates the following:

■ Current Estimated On-demand Monthly Cost:

```
(\$0.20125 * 730) + (\$0.221 * (300 - 250)) = \$157.96/Mo.
```

■ Estimated On-demand Monthly Cost *after* executing the action:

```
(\$0.020125 * 730) + (\$0.221 * (250 - 250)) = \$14.69/Mo.
```

NOTE:

Workload Optimization Manager rounds the calculated values that it displays in the user interface.

The Estimated On-demand Monthly Cost is projected to decrease from \$157.96/month to \$14.69/month, as shown in the Details section of the pending action.

COST IMPACT ③	CURRENT	AFTER ACTIONS
Compute Cost	\$146.91/mo	\$14.69/mo
Storage Cost 1	\$11.05/mo	\$0.00/mo
Total Cost	\$157.96/mo	\$14.69/mo
Total Savings		\$143.27/mo

Workload Optimization Manager treats the action as a saving, and shows an estimated savings of \$143.27/month.

COST IMPACT	CURRENT	AFTER ACTIONS
Compute Cost	\$146.91/mo	\$14.69/mo
Storage Cost 🐧	\$11.05/mo	\$0.00/mo
Total Cost	\$157.96/mo	\$14.69/mo
Total Savings \$143.27/mo		

Azure SQL vCore Databases

Cost Calculation

For Azure SQL vCore Databases, the calculation for Estimated On-demand Monthly Cost can be expressed as follows:

 $(On-demand\ Compute\ Rate\ *\ 730)\ +\ (SQL\ License\ Rate\ *\ 730)\ +\ (Provisioned\ Database\ Storage\ Rate\ *\ (Provisioned\ Database\ Storage\ Amount\ +\ Log\ Space\ Allocated))\ =\ Estimated\ On-demand\ Monthly\ Cost$

Where:

- On-demand Compute Rate is the hourly cost for a Database's instance type
 You can obtain on-demand rates via <u>Azure SQL Database Pricing</u>.
- 730 represents the number of hours per month that Workload Optimization Manager uses to estimate monthly costs.
- SQL License Rate is the hourly cost for a Database's SQL license



You can obtain SQL license rates via Azure SQL Database Pricing.

Note: "Pay as you go" prices in the link above represent the sum of compute and license costs, while "Azure Hybrid Benefit Price" values represent compute costs only.

- Provisioned Database Storage Rate is the cost for 1 GB / mo. of a Database's provisioned storage
 - You can obtain provisioned database storage rates via Azure SQL Database Pricing.
- Log Space Allocated is the log storage space automatically allocated to single Database instance by Azure.
 - Note: Log storage space is considered in database cost calculations, but not reflected in Storage capacity.

You can obtain provisioned database storage rates via Azure SQL Database Pricing.

The listed items above impact cost calculations and the scaling decisions that Workload Optimization Manager makes. These decisions also rely on other factors, such as resource utilization percentiles and scaling constraints set in policies.

Example

Assume the following data for a pending scale action for an Azure SQL vCore Database:

	Current Values	Values After Action Execution
On-demand Compute Rate	\$1.068/hr	\$0.304/hr
SQL License Rate	\$0.799728/hr	\$0.199932/hr
Provisioned Database Storage Rate	\$0.115/hr	\$0.115/hr
Provisioned Database Storage Amount	32 GB	5 GB

Workload Optimization Manager calculates the following:

Current Estimated On-demand Monthly Cost:

```
(\$1.068 * 730) + (\$0.799728 * 730) + (\$0.115 * (32 + 9.6)) = \$1368.23/Mo.
```

■ Estimated On-demand Monthly Cost *after* executing the action:

```
(\$0.304 * 730) + (\$0.199932 * 730) + (\$0.115 * (5 + 1.5)) = \$368.62/Mo.
```

NOTE:

Workload Optimization Manager rounds the calculated values that it displays in the user interface.

Since the Estimated On-demand Monthly Cost is projected to decrease from \$1368.23/month to \$368.62/month, Workload Optimization Manager treats the action as a cost-saving measure and shows estimated savings of \$999.61/month.

Cloud Database Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

For details about cloud database actions, see Cloud Database Actions (on page 434).

Action	Default Setting
Cloud DB Scale	Manual
Database Suspend Actions	On, Manual

Scaling Sensitivity

Workload Optimization Manager uses a percentile of utilization over the specified observation period. This gives sustained utilization and ignores short-lived bursts.



Workload Optimization Manager uses these settings to calculate utilization percentiles for DTU and storage. It then recommends actions to improve utilization based on the observed values for a given time period.

Aggressiveness

Attribute	Default Value
Aggressiveness	95th Percentile

When evaluating performance, Workload Optimization Manager considers resource utilization as a percentage of capacity. The utilization drives actions to scale the available capacity either up or down. To measure utilization, the analysis considers a given utilization percentile. For example, assume a 95th percentile. The percentile utilization is the highest value that 95% of the observed samples fall below. Compare that to average utilization, which is the average of *all* the observed samples.

Using a percentile, Workload Optimization Manager can recommend more relevant actions. This is important in the cloud, so that analysis can better exploit the elasticity of the cloud. For scheduled policies, the more relevant actions will tend to remain viable when their execution is put off to a later time.

For example, consider decisions to reduce capacity. Without using a percentile, Workload Optimization Manager never resizes below the recognized peak utilization. Assume utilization peaked at 100% just once. Without the benefit of a percentile, Workload Optimization Manager will not reduce resources for that database.

With **Aggressiveness**, instead of using the single highest utilization value, Workload Optimization Manager uses the percentile you set. For the above example, assume a single burst to 100%, but for 95% of the samples, utilization never exceeded 50%. If you set **Aggressiveness** to 95th Percentile, then Workload Optimization Manager can see this as an opportunity to reduce resource allocation.

In summary, a percentile evaluates the sustained resource utilization, and ignores bursts that occurred for a small portion of the samples. You can think of this as aggressiveness of resizing, as follows:

- 99th Percentile More performance. Recommended for critical databases that need maximum guaranteed performance at all times, or those that need to tolerate sudden and previously unseen spikes in utilization, even though sustained utilization is low.
- 95th Percentile (Default) The recommended setting to achieve maximum performance and savings. This assures performance while avoiding reactive peak sizing due to transient spikes, thus allowing you to take advantage of the elastic ability of the cloud.
- 90th Percentile More efficiency. Recommended for databases that can stand higher resource utilization.

By default, Workload Optimization Manager uses samples from the last 14 days. Use the **Max Observation Period** setting to adjust the number of days.

Max Observation Period

Attribute	Default Value
Max Observation Period	Last 14 Days

To refine the calculation of resource utilization percentiles, you can set the sample time to consider. Workload Optimization Manager uses historical data from up to the number of days that you specify as a sample period. If the database has fewer days' data then it uses all of the stored historical data.

You can make the following settings:

- Less Elastic Last 30 Days
- Recommended Last 14 Days
- More Elastic Last 7 Days or Last 3 Days

Workload Optimization Manager recommends an observation period of 14 days so it can recommend scaling actions more often. Since Azure SQL DB scaling is minimally disruptive, with near-zero downtime, scaling often should not introduce any noticeable performance risks.

NOTE:

For more information about Azure scaling downtimes, see the <u>Azure documentation</u>.

Min Observation Period



Attribute	Default Value
Min Observation Period	None

This setting ensures historical data for a minimum number of days before Workload Optimization Manager will generate an action based on the percentile set in **Aggressiveness**. This ensures a minimum set of data points before it generates the action.

Especially for scheduled actions, it is important that resize calculations use enough historical data to generate actions that will remain viable even during a scheduled maintenance window. A maintenance window is usually set for "down" time, when utilization is low. If analysis uses enough historical data for an action, then the action is more likely to remain viable during the maintenance window.

- More Elastic None
- Less Elastic 7 Days

Cloud Instance Types

By default, Workload Optimization Manager considers all instance types currently available for scaling when making scaling decisions for databases. However, you may have set up your cloud databases to *only scale to* or *avoid* certain instance types to reduce complexity and cost, or meet demand. Use this setting to identify the instance types that databases can scale to.

Attribute	Default Value
Cloud Instance Types	None

Click **Edit** to set your preferences. In the new page that displays, expand a **cloud tier** (a family of instance types, such as *Premium*) to see individual instance types and the resources allocated to them.

Select your preferred instance types or cloud tiers, or clear the ones that you want to avoid. After you save your changes, the main page refreshes to reflect your selections.

NOTE:

This policy setting is not available in plans.

If you selected a cloud tier and the service provider deploys new instance types to that tier later, then those instance types will automatically be included in your policy. Be sure to review your policies periodically to see if new instance types have been added to a tier. If you do not want to scale to those instance types, update the affected policies.

Scaling Target Utilization

The utilization that you set here specifies the percentage of the existing capacity that Workload Optimization Manager will consider to be 100% of capacity.

The settings you make depend on the pricing model in place for the workloads in the policy scope. To meet a target DTU utilization, the workloads must be members of a DTU pricing model. To meet individual VCPU, VMEM, or IOPs/Throughput targets, the workloads must be members of a vCore pricing model.

Attribute	DTU Pricing: Default Value	vCore Pricing: Default Value
Scaling Target DTU Utilization	70	N/A
VCPU	N/A	70
VMEM	N/A	90
IOPs/Throughput	N/A	70
Storage Amount Utilization	90	90

These advanced settings determine how much you would like a scope of workloads to utilize their resources. These are fixed settings that override the way Workload Optimization Manager calculates the optimal utilization of resources. You should only change these settings after consulting with Technical Support.




While these settings offer a way to modify how Workload Optimization Manager recommends actions, in most cases you should never need to use them. If you want to control how Workload Optimization Manager recommends actions to resize workloads, you can set the aggressiveness per the percentile of utilization, and set the length of the sample period for more or less elasticity on the cloud.

Zone

A zone represents an Availability Zone in your public cloud account or subscription. A zone is a location within a given region that serves as a datacenter to host the workloads that you run in your environment.

Synopsis



Synopsis	
Provides:	Compute and storage resources to VMs
Consumes:	Region resources
Discovered through:	Public cloud targets

Monitored Resources

Workload Optimization Manager monitors the following resources:

Templates

The templates and template families that each zone or region delivers. This includes template capacity and cost for workload resources.

Account Services

These include storage modes, services the accounts offer for enhanced metrics, and services for different storage capabilities.

(AWS only) Relational Database Services (RDS)



The RDS capabilities each cloud account provides.

Storage Tiers

Workload Optimization Manager discovers the storage tier that supports your workloads, and uses the tier pricing to calculate storage cost.

Billing

Workload Optimization Manager discovers the billing across the zones and regions to predict costs in the future, and to track ongoing costs. This includes comparing on-demand pricing to discount billing.

Virtual Memory

The percentage utilized of memory capacity for all the workloads in the zone.

Virtual CPU

The percentage utilized of VCPU capacity for all the workloads in the zone.

Storage Access

For environments that measure storage access, the percentage utilized of access capacity for the zone.

Storage Amount

The percentage utilized of storage capacity for the zone.

■ IO Throughput

For environments that measure IO throughput, the percentage utilized of throughput capacity for the zone.

Net Throughput

For environments that measure Net throughput, the percentage utilized of throughput capacity for the zone.

Actions

None


Workload Optimization Manager does not recommend actions for a cloud zone.

Region

A Region represents a geographical area that is home to one or more Availability Zones. Regions are often isolated from each other, and you can incur a cost for data transfer between them.



Synopsis



Synopsis	
Provides:	Host and storage resources to zones
Consumes:	N/A
Discovered through:	Public cloud targets

Monitored Resources

Workload Optimization Manager does not monitor resources directly from the region, but it does monitor the following resources, aggregated for the zones in a region:

- Virtual Memory
 - The percentage utilized of memory capacity for workloads in the zones.
- Virtual CPU
 - The percentage utilized of VCPU capacity for workloads in the zones.
- Storage Access
 - For environments that measure storage access, the percentage utilized of access capacity for the zones.
- Storage Amount
 - The percentage utilized of storage capacity for the zones.
- IO Throughput
 - For environments that measure IO throughput, the percentage utilized of throughput capacity for the zones.
- Net Throughput
 - For environments that measure Net throughput, the percentage utilized of throughput capacity for the zones.

Actions


None



Workload Optimization Manager does not recommend actions for a cloud region.

Entity Types - On-prem Infrastructure

Workload Optimization Manager discovers and monitors the entities that make up your on-prem infrastructure, and recommends actions to assure performance for the applications that consume resources from these entities.



Virtual Machine (On-prem)


A virtual machine (VM) is a software emulation of a physical machine, including OS, virtual memory and CPUs, and network ports. VMs host applications, or they provide resources to container platforms.

NOTE:

Kubernetes nodes are represented as Virtual Machines in the Workload Optimization Manager supply chain. For details about nodes, see <u>Virtual Machine</u> (Kubernetes Node) (on page 371).



Synopsis



A VM gains its budget by selling resources to the applications it hosts. If utilization is high enough, Workload Optimization Manager can allocate more resources to the VM, provision another instance, or move the VM to a host that has more resources. If utilization falls off, the VM loses budget. On the public cloud, if the budget isn't enough to pay for the host services, Workload Optimization Manager can post an action to suspend the VM.

Resources for hosted applications to use, including:
■ VMEM
■ VCPU
■ Processing Units (IBM PowerVM)
■ Virtual Processors (IBM PowerVM)
■ VStorage
■ IOPS
■ Latency
■ Physical host resources, including CPU and memory
■ Storage



Synopsis	
Discovered through:	Hypervisor targets

Monitored Resources

Workload Optimization Manager monitors the following resources:

Virtual Memory (VMem)

Virtual Memory is the measurement of memory that is in use.

■ Virtual CPU (VCPU)

Virtual CPU is the measurement of CPU that is in use.

Processing Unit (PU)

For PowerVM, processing unit is a unit of measurement for shared processing power across one or more virtual processors. One shared processing unit on one virtual processor accomplishes approximately the same work as one dedicated processor.

Virtual Processor (VP)

For PowerVM, virtual processor (VP) is the guest OS representation of the capacity of the VM. VPs have a one to one correlation with PUs, meaning 1 VP being utilized in a VM equates to 1 PU being used; however, VPs do not have to equal to PUs on a system. VPs are a virtual representation, therefore they can be overprovisioned.

Virtual Storage

Virtual storage is the measurement of virtual storage capacity that is in use.

Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Latency

Latency is the measurement of storage latency.

For VMs discovered via vCenter, the following resources are also monitored:

■ Energy

Energy is the measurement of electricity consumed by a given entity over a period of time, expressed in watt-hours (Wh).

Carbon Footprint

Carbon footprint is the measurement of carbon dioxide equivalent (CO2e) emissions for a given entity. Workload Optimization Manager measures carbon footprint in grams.

Actions

Workload Optimization Manager can recommend the following actions:

■ Resize

Resize resource capacity, reservation, or limit to improve performance.

Resize resource capacity

Change the capacity of a resource that is allocated for the VM. For example, a resize action might recommend increasing the VMem available to a VM. Before recommending this action, Workload Optimization Manager verifies that the VM's cluster can adequately support the new size. If the cluster is highly utilized, Workload Optimization Manager will recommend a move action, taking into consideration the capacity of the new cluster and compliance with existing placement policies.

For hypervisor targets, Workload Optimization Manager can resize vCPU by changing the VM's socket or cores per socket count. For details, see <u>VCPU Scaling Controls (on page 457)</u>.

Resize resource reservation

Change the amount of a resource that is reserved for a VM. For example, a VM could have an excess amount of memory reserved. That can cause memory congestion on the host – A resize action might recommend reducing the amount reserved, freeing up that resource and reducing congestion

Resize resource limit



Change the limit that is set on the VM for a resource. For example, a VM could have a memory limit set on it. If the VM is experiencing memory shortage, an action that decreases or removes the limit could improve performance on that VM.

When multiple resize actions that relate to the same vCenter VM are accepted (manually or automated), they execute together to avoid multiple restarts for the same VM. For example, a VM has both a vCPU resize action and a vMEM resize action. When selecting both actions for execution, the actions combine into the fewest vCenter tasks to minimize the disruption on the VM instead of one set of tasks per action. Only the VMware vCenter integration supports this functionality at this time.

■ Resize PU / Resize VP (IBM PowerVM)

Resize PU (processing units) or VP (virtual processor) to optimize LPAR processing unit allocation and virtual processor capacity based on historical demand collected from the HMC.

Workload Optimization Manager does not support native execution of Resize PU (processing units) and Resize VP (virtual processor) actions. However, actions can be executed using external automation platforms through Action Orchestration workflows such as Action Scripts or Webhooks.

The following policy settings affect the resize actions that Workload Optimization Manager generates:

- Min/Max Observation Period
 - Observation period settings only apply to Resize VP actions.
 - For details, see Aggressiveness and Observation Periods (on page 454).
- Increment Constant for Processing Unit
 - Change the increment constant value to use for VM PU resize actions. PUs can be a decimal value in a VM setting.
 - For details, see Increment Constant for Processing Unit (on page 454).
- Increment Constant for Virtual Processors
 - Change the increment constant value to use for VM VP resize actions. VPs must be an integer value in a VM setting.
 - For details, see Increment Constant for Virtual Processors (on page 454).

Move

Move a VM due to high resource utilization on VM or host, excess IOPS or latency in VStorage, workload placement violation, underutilized host (move VM before suspending host).

■ Reconfigure

Change a VM's configuration to comply with a policy.

For hypervisor targets, Workload Optimization Manager can reconfigure VMs that violate vCPU scaling policies. For details, see VCPU Scaling Controls (on page 457).

Tuned Scaling for On-prem VMs

For resizing VMs, Workload Optimization Manager includes tuned scaling action settings. These settings give you increased control over the action acceptance mode for various resize actions. With this feature, you can automate resize actions within a normal range (the tuned scaling range), and direct Workload Optimization Manager to take more conservative actions when resizes are outside the range.

For example, consider resizing VMs to add more memory. As memory demand increases on a VM, Workload Optimization Manager can automatically allocate more memory. If the hosted application is in a runaway state (always requesting more memory) and ultimately falls outside of the normal range, Workload Optimization Manager will not automate memory resize for the VM.

To configure tuned scaling:

- 1. Create a VM policy.
- 2. Under **Action Automation**, configure the action acceptance mode for the various resize actions.
 - VCPU Resize Up
 - VCPU Resize Down
 - VCPU Resize Above Max
 - VCPU Resize Below Min
 - VMEM Resize Up




- VMEM Resize Down
- VMEM Resize Above Max
- VMEM Resize Below Min

NOTE:

Resize Up and **Resize Down** settings are for conditions within the tuned scaling range, while **Above Max** and **Below Min** settings are for outlying conditions.

- 3. Under **Operational Constraints**, specify the tuned scaling range.
 - VCPU Resize Max Threshold
 - VCPU Resize Min Threshold
 - VMEM Resize Max Threshold
 - VMEM Resize Min Threshold

For example, assume the following settings:



As VCPU utilization for a VM changes over time, Workload Optimization Manager handles resize actions as follows.

Current	Resize Request	Action Acceptance Mode	Result
6 VCPUs	Resize up to 8 VCPUs	Automatic Since the VM will have 8 VCPUs after the requested resize, which is within the VCPU Resize Max threshold of 8, Workload Optimization Manager executes the VCPU Resize Up action automatically.	8 VCPUs
8 VCPUs	Resize up to 10 VCPUs	Manual Since the VM will have 10 VCPUs after the requested	10 VCPUs (if you executed the pending action)



Current	Resize Request	Action Acceptance Mode	Result
		resize, which is above the VCPU Resize Max threshold of 8, Workload Optimization Manager posts the VCPU Resize Up action (as a pending action) and provides the option to execute that action through the user interface.	
10 VCPUs	Resize down to 2 VCPUs	Manual Since the VM will have 2 VCPUs after the requested resize, which is within the VCPU Resize Min threshold of 2, Workload Optimization Manager posts the VCPU Resize Down action (as a pending action) and provides the option to execute that action through the user interface.	2 VCPUs (if you executed the pending action)
2 VCPUs	Resize down to 1 VCPU	Not Generated Since the VM will have 1 VCPU after the requested resize, which is below the VCPU Resize Min threshold of 2, Workload Optimization Manager does not generate the VCPU Resize Down action to comply with the policy.	2 VCPUs

Action policies include scope to determine which entities will be affected by the given policy. It's possible for two or more policies to affect the same entities. As is true for other policy settings, tuned scaling uses the most conservative settings for the affected entities. The effective action acceptance mode will be the most conservative, and the effective tuned scaling range will be the narrowest range (the lowest MAX and highest MIN) out of the multiple policies that affect the given entities. For more information, see <u>Default and User-defined Policies</u> (on page 677).

You can schedule automation policies to take effect during a certain window of time. You can include tuned scaling settings in a scheduled window, the same as you can schedule other policy settings. For more information, see Policy Schedule (on page 687).

On-prem VM Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

For details about on-prem VM actions, see On-prem VM Actions (on page 447).

Action	Default Mode	vCenter	Hyper-V	PowerVM
Move	Manual	Auto	Auto	N/A



Action	Default Mode	vCenter	Hyper-V	PowerVM
Reconfigure	Recommend	Remd	Romd	N/A
Start	Manual	Auto	Auto	N/A
Storage Move	Recommend	Auto	With VMM: Auto Otherwise: Remd	N/A
Provision (Kubernetes nodes only)	Manual	Romd	Romd	N/A
Suspend (Kubernetes nodes only)	Manual	Auto	Auto	N/A
PU Resize Up	Recommend	N/A	N/A	Remd
PU Resize Down	Recommend	N/A	N/A	Remd
VP Resize Up	Recommend	N/A	N/A	Remd
VP Resize Down	Recommend	N/A	N/A	Remd
vCPU Resize Up*	Manual	Auto	Auto	N/A
vCPU Resize Above Max*	Recommend	Auto	Auto	N/A
vCPU Resize Down*	Manual	Auto	Auto	N/A
vCPU Resize Below Min*	Recommend	Auto	Auto	N/A
vMem Resize Up*	Manual	Auto	Auto	N/A
vMem Resize Above Max*	Recommend	Auto	Auto	N/A
vMem Resize Down*	Manual	Auto	Auto	N/A
vMem Resize Below Min*	Recommend	Auto	Auto	N/A

^{*} Workload Optimization Manager uses these settings, in conjunction with <u>resize operational constraints (on page 453)</u>, to set up <u>tuned scaling (on page 448)</u> for on-prem VMs.

You can use Action Scripts (on page 692) and third-party orchestrators (such as ServiceNow) for action orchestration.

Non-disruptive Mode

VM actions include the modifier, **Enforce Non Disruptive Mode**. When you enable this modifier, Workload Optimization Manager ensures that a resize action in *Automatic* or *Manual* mode will not require a reboot or any other disruption to the affected VM. If the action will disrupt the VM, Workload Optimization Manager posts the action in *Recommend* mode.

Attribute	Default Setting
Enforce Non-disruptive Mode	Off



This setting has no effect on actions set to *Recommend* mode. Workload Optimization Manager will continue to post those actions for you to evaluate.

You can enforce non disruptive mode in the default VM policy, and then schedule action policies to automate resize actions during downtimes. Be aware that scheduled actions do not respect the enforced non disruptive mode — Scheduled resize actions will execute during the scheduled window even if they require a reboot. This is useful for setting up certain action behaviors, but you must be aware that enforced non disruptive mode has no effect on scheduled actions.

NOTE:

When you configure a schedule window for a VM resize action, to ensure Workload Optimization Manager will execute the action during the scheduled time, you must turn off the **Enforce Non Disruptive Mode** setting for that scheduled policy. Even if you turn the setting off for the global policy, you still must turn the setting off for your scheduled policy. Otherwise Workload Optimization Manager will not execute the resize action.

Shared Nothing Migration


If you have enabled both storage and VM moves, Workload Optimization Manager can perform shared-nothing migrations, which move the VM and the stored VM files simultaneously. For example, assume a VM on a host also uses local storage on that host. In that case, Workload Optimization Manager can move that VM and move its data to a different datastore in a single action.

Attribute	Default Setting
Shared-nothing Migration	Off

Currently, the following targets support shared-nothing migrations:

- vSphere, versions 5.1 or greater
- VMM for Hyper-V 2012 or later

Because of this feature's potential impact on performance, it is turned off by default. Workload Optimization Manager recommends enabling it only on VMs that need it. To do this, you must first set the action acceptance mode for VM and storage moves to either *Manual* or *Automatic*, and then enable the feature in a VM policy.



If a policy that enables this feature conflicts with a more conservative policy, the latter policy wins. For example, if compute move is set to *Manual*, storage move is set to *Recommend*, and shared-nothing migration is turned on, shared-nothing migration is in effect but remains in *Recommended* state.

NOTE:

Workload Optimization Manager does not simulate shared-nothing migrations in plans.



Resize Thresholds (Operational Constraints)

Workload Optimization Manager uses these settings to set up **tuned scaling** actions for on-prem VMs. Tuned scaling gives you increased control over the action mode for various resize actions. With this feature, you can automate resize actions within a normal range (the tuned scaling range), and direct Workload Optimization Manager to take more conservative actions when resizes are outside the range.

For details about tuned scaling, see Tuned Scaling for On-prem VMs (on page 448).

Attribute	Default Value
VCPU Resize Max Threshold (in Cores)	64
	Tuned Scaling Range Upper Limit
VCPU Resize Min Threshold (in Cores)	1
	Tuned Scaling Range Lower Limit
VMEM Resize Max Threshold (MB)	131072
	Tuned Scaling Range Upper Limit
VMEM Resize Min Threshold (MB)	512
	Tuned Scaling Range Lower Limit

Resize VStorage

The default setting disables resize actions. This is usually preferred because VStorage resize requires that you reformat the storage. The increment constant takes effect if you enable resizing.

Attribute	Default Setting/Value
Resize VStorage	Disabled
Increment constant for VStorage [GB]	None If you enable resize, Workload Optimization Manager uses the default value of 1024. You can change this to a different value.

vCPU Scaling Controls

For details, see VCPU Scaling Controls (on page 457).

Resize Increments

These increments specify how many units to add or subtract when resizing the given resource allocation for a VM.

Attribute	Default Value
Increment constant for VMEM [MB]	1024
Increment constant for VStorage [GB]	1024

NOTE:

vCPU resize increments are configured in conjunction with vCPU scaling controls. For details, see <u>VCPU Scaling Controls (on page 457)</u>.

For VMem, you should not set the increment value to be lower than what is necessary for the VM to operate. If the VMem increment is too low, then it's possible that Workload Optimization Manager would allocate insufficient VMem for the machine to operate. For a VM that is under utilized, Workload Optimization Manager will reduce VMem allocation by the increment amount, but it will not leave a VM with zero VMem. For example, if you set this to 1024, then Workload Optimization Manager cannot reduce the VMem to less than 1024 MB.



Increment Constant for Processing Units

For PowerVM, processing unit is a unit of measurement for shared processing power across one or more virtual processors. One shared processing unit on one virtual processor accomplishes approximately the same work as one dedicated processor.

Workload Optimization Manager recommends VM PU resize actions in multiples of this increment constant value. For example, if Workload Optimization Manager determines that a VM with 1.0 PU needs 1.2 PU and the increment is set to 0.5, then a resize up action is not generated. Increasing this increment reduces the frequency of resize actions so that when they appear the change is more significant.

Attribute	Default Value
Increment constant for processing units	0.1

Increment Constant for Virtual Processors

For PowerVM, virtual processor (VP) is the guest OS representation of the capacity of the VM. VPs have a one to one correlation with PUs, meaning 1 VP being utilized in a VM equates to 1 PU being used; however, VPs do not have to equal to PUs on a system. VPs are a virtual representation, therefore they can be overprovisioned.

Workload Optimization Manager recommends VM VP resize actions in multiples of this increment constant value. For example, if Workload Optimization Manager determines that a VM with 2 VPs needs 1 VP and the increment is set to 2, then a resize down action is not generated. Increasing this increment reduces the frequency of resize actions so that when they appear the change is more significant.

Attribute	Default Value
Increment constant for virtual processors	1

Aggressiveness and Observation Periods

Workload Optimization Manager uses these settings to calculate utilization percentiles for vCPU, vMEM, IOPS, and VPs. It then recommends actions to improve utilization based on the observed values for a given time period.

Aggressiveness

Attribute	Default Value
Aggressiveness	75th Percentile

When evaluating performance, Workload Optimization Manager considers resource utilization as a percentage of capacity. The utilization drives actions to scale the available capacity either up or down. To measure utilization, the analysis considers a given utilization percentile. For example, assume a 75th percentile. The percentile utilization is the highest value that 75% of the observed samples fall below. Compare that to average utilization, which is the average of all the observed samples.

Using a percentile, Workload Optimization Manager can recommend more relevant actions. For scheduled policies, the more relevant actions will tend to remain viable when their execution is put off to a later time.

For example, consider decisions to reduce the capacity for CPU on a VM. Without using a percentile, Workload Optimization Manager never resizes below the recognized peak utilization. For most VMs, there are moments when peak CPU reaches high levels, such as during reboots, patching, and other maintenance tasks. Assume utilization for a VM peaked at 100% just once. Without the benefit of a percentile, Workload Optimization Manager will not reduce allocated CPU for that VM.

With **Aggressiveness**, instead of using the single highest utilization value, Workload Optimization Manager uses the percentile you set. For the above example, assume a single CPU burst to 100%, but for 75% of the samples CPU never exceeded 50%. If you set **Aggressiveness** to 75th Percentile, then Workload Optimization Manager can see this as an opportunity to reduce CPU allocation for the VM.

In summary, a percentile evaluates the sustained resource utilization, and ignores bursts that occurred for a small portion of the samples.

By default, Workload Optimization Manager uses samples from the last 30 days. Use the **Max Observation Period** setting to adjust the number of days. To ensure that there are enough samples to analyze and drive scaling actions, set the **Min Observation Period**.

Max Observation Period



Attribute	Default Value
Max Observation Period	Last 90 Days

To refine the calculation of resource utilization percentiles, you can set the sample time to consider. Workload Optimization Manager uses historical data from up to the number of days that you specify as a sample period. If the database has fewer days' data then it uses all of the stored historical data.

You can make the following settings:

- Less Elastic Last 90 Days
- Recommended Last 30 Days
- More Elastic Last 7 Days

Workload Optimization Manager recommends an observation period of 30 days following the monthly workload maintenance cycle seen in many organizations. VMs typically peak during the maintenance window as patching and other maintenance tasks are carried out. A 30-day observation period means that Workload Optimization Manager can capture these peaks and increase the accuracy of its sizing recommendations.

You can set the value to 7 days if workloads need to resize more often in response to performance changes. For workloads that cannot handle changes very often or have longer usage periods, you can set the value to 90 days.

■ Min Observation Period

Attribute	Default Value
Min Observation Period	None

Especially for scheduled actions, it is important that resize calculations use enough historical data to generate actions that will remain viable even during a scheduled maintenance window. A maintenance window is usually set for "down" time, when utilization is low. If analysis uses enough historical data for an action, then the action is more likely to remain viable during the maintenance window.

- More Elastic None
- Less Elastic 7 Days

Rate of Resize

When resizing resources for a VM, Workload Optimization Manager calculates the optimal values for VMem, VCPU, and VStorage. But it does not necessarily make a change to that value in one action. Workload Optimization Manager uses the Rate of Resize setting to determine how to make the change in a single action.

NOTE:

In Workload Optimization Manager 3.7.1, the Rate of Resize default value changed from 2 to 3. If you have changed your default setting to 1 or want to keep the current default setting of 2, create a new policy scoped to all on-prem VMs and configure the Rate of Resize to your desired setting.

Attribute	Default Value
Rate of Resize	High (3)

■ Low

Change the value by one increment, only. For example, if the resize action calls for increasing VMem, and the increment is set at 1024, Workload Optimization Manager increases VMem by 1024 MB.

Medium

Change the value by an increment that is 1/4 of the difference between the current value and the optimal value. For example, if the current VMem is 2 GB and the optimal VMem is 10 GB, then Workload Optimization Manager will raise VMem to 4 GB (or as close to that as the increment constant will allow).

■ High

Change the value to be the optimal value. For example, if the current VMem is 2 GB and the optimal VMem is 8 GB, then Workload Optimization Manager will raise VMem to 8 GB (or as close to that as the increment constant will allow).



Consistent Resizing

Attribute	Default Setting
Enable Consistent Resizing	Off

When you create a policy for a group of VMs and turn on Consistent Resizing, Workload Optimization Manager resizes all the group members to the same size, such that they all support the top utilization of each resource commodity in the group. For example, if you have deployed load balancing for a group, then all the VMs in the group should experience similar utilization. In that case, if one VM needs to be resized, then it makes sense to resize them all consistently.

Assume VM A shows top utilization of CPU, and VM B shows top utilization of memory. A resize action would result in all the VMs with CPU capacity to satisfy VM A, and memory capacity to satisfy VM B.

NOTE:

If the VMs in the group have different core speeds, then CPU scaling actions might not be consistent. For example, if you set the maximum target CPU size to 2, Workload Optimization Manager might recommend resizing to more than 2 CPUs to account for the VMs with slower cores.

To avoid this problem, be sure that the group only includes VMs with the same core speed.

For an affected resize, the Actions List shows individual resize actions for each of the VMs in the group. To avoid the possibility of resizing VMs disruptively at the same time, you must create automation policies with non-overlapping schedules. For example, if VMs A and B are in the same consistent resizing group, create two policies that resize the VMs at different times of the day.

- For Policy 1, set the scope to a group containing VM A and enable resize automation between, say, 01:00 and 01:45.
- For Policy 2 set the scope to a group containing VM B and enable resize automation between 02:00 and 02:45.

When working with Consistent Resizing, consider these points:

- You should not mix VMs in a group that has a Consistent Resizing policy, with other groups that enable Consistent Resizing. One VM can be a member of more than one group. If one VM (or more) in a group with Consistent Resizing is also in another group that has Consistent Resizing, then both groups enforce Consistent Resizing together, for all their group members.
- For any group of VMs that enables Consistent Resizing, you should not mix the associated target technologies. For example, one group should not include VMs that are on Hyper-V and vCenter platforms.
- Charts that show actions and risks assign the same risk statement to all the affected VMs. This can seem confusing. For example, assume one VM needs to resize to address vCPU risk, and 9 other VMs are set to resize consistently with it. Then charts will state that 10 VMs need to resize to address vCPU risks.

Placement Policies

Workload Optimization Manager supports placement policies for on-prem VMs, as follows:

- You can create placement policies to enforce constraints for VM placements.
 - For example, the VMs in a consumer group can only run on a host that is in the provider group. You can limit the number of consumers that can run on a single provider for hosts in the provider group, only 2 instances of VMs in the consumer group can run on the same host. Or no more than the specified number of VMs can use the same storage device.
- For VMs that require paid licenses, you can create placement policies that set up certain hosts to be the VMs' preferred license providers. Workload Optimization Manager can then recommend consolidating VMs or reconfiguring hosts in response to changing demand for licenses.

For more information, see Creating Placement Policies (on page 673).

NOTE:


For VMM targets, Cisco automatically imports your Availability Sets, representing them as placement policies for the affected infrastructure. To see these availability sets, go to the **Settings > Policies** page and click **Imported Placement Policies**.

For more information, see Importing Workload Placement Policies (on page 673).



vCPU Scaling Controls

Workload Optimization Manager represents the compute capacity of a VM in MHz and vCPUs. The following diagram shows how a VM with four vCPUs can be configured differently in terms of sockets and cores.



Workload Optimization Manager can resize the compute capacity by changing the number of sockets or cores per socket, depending on:

- The policy assigned to the VM
 - On-prem VM policies (on page 450) include vCPU Scaling Controls that give you granular control over how VM compute resources are resized to maintain performance or reconfigured to comply with your operational policies. You can create policies for different VM groups based on their resource needs and characteristics, and decide whether to automate resize and reconfigure actions in those policies.
- The hypervisor that manages the VM
 - Hypervisor targets have varying degrees of support for vCPU Scaling Controls. VMware vSphere supports all scaling controls, while Hyper-V and Nutanix AHV provide limited support. For details, see the *Hypervisor Support* section below.

vCPU Scaling Control Modes and Options

Workload Optimization Manager provides **simple** and **advanced** controls to automate compute resource management actions in compliance with your policies. It also provides a **legacy** control based on units of MHz.

The controls you choose depend on your operational policies regarding the VM configuration of sockets and cores per socket, and your choice of hypervisor. For example, your operational policies may dictate a certain VM configuration that must be respected when resizing a VM's compute resources. Changing sockets is the least disruptive, but for some workloads, it may be preferable to change cores per socket due to socket licensing or operating system constraints. For larger VMs where Non-Uniform Memory Access (NUMA) must be considered for performance reasons, it may be preferable to balance vCPUs across host sockets.

The following tables explain the exact operation for each mode.

Simple Controls

Simple controls change compute resources based on units of vCPU.

vCPU Scaling Option	Unit	Sockets	Cores Per Socket	Resize Action	Reconfigure Action
Change virtual CPUs	vCPUs	Workload Optimization Manager decides	Reconfigured to 1 core per socket	 Non-disruptive if hot-add is enabled and VM sockets are increasing Disruptive if VM cores per socket does not equal 1, even if 	Disruptive



vCPU Scaling Option	Unit	Sockets	Cores Per Socket	Resize Action	Reconfigure Action
				hot-add is enabled	

Advanced Controls

Advanced controls allow you to change sockets or cores per socket, and configure additional options.

vCPU Scaling Option	Unit	Sockets	Cores Per Socket	Resize Action	Reconfigure Action
Change sockets	1 socket	Workload Optimization Manager decides	Preserve VM cores per socket	Non-disruptive if hot-add is enabled and VM sockets are increasing	Not generated
Change sockets	1 socket	Workload Optimization Manager decides	User-specified VM cores per socket	 Non-disruptive if hot-add is enabled Disruptive if VM cores per socket does not match user-specified value 	Disruptive if VM cores per socket does not match user-specified value
Change cores per socket	1 core per socket	Preserve VM sockets	Workload Optimization Manager decides	Disruptive	Not generated
Change cores per socket	1 core per socket	Match host sockets	Workload Optimization Manager decides	Disruptive	 Non-disruptive if hot-add is enabled and VM sockets are increasing Disruptive if cores per socket is changed
Change cores per socket	1 core per socket	User-specified VM sockets	Workload Optimization Manager decides	Disruptive	 Non-disruptive if hot-add is enabled and VM sockets are increasing Disruptive if cores per socket is changed

Legacy Controls

Legacy controls change compute resources based on units of MHz.



vCPU Scaling Option	Unit	Sockets	Cores Per Socket	Resize Action	Reconfigure Action
MHz legacy behavior	MHz	Workload Optimization Manager decides	 Assumes 1 core per socket Execution preserves actual cores per socket 	Non-disruptive if hot-add is enabled and VM sockets are increasing	Not generated

Points to consider:

- If non-disruptive mode (on page 451) is enabled, disruptive actions are not automated and must be executed manually.
- Older Guest OSes and applications may be sensitive to changes in the vCPU architecture that could result in power-on issues or kernel panics/BSODs. Some workloads require manual help with such changes, so always test certain classes of applications and guest operating systems before enabling any automation that changes the vCPU architecture. Use the Workload Optimization Manager knowledge of the application domain and Guest OS to scope them out of policies.

Scaling Option: Change Virtual CPUs

In this scaling option, Workload Optimization Manager adds or removes compute resources in increments of vCPUs. To achieve this, it changes the number of VM sockets and enforces 1 core per socket (if not already enforced).


- If a VM requires a change to compute resources, Workload Optimization Manager generates a resize vCPU action that assumes 1 core per socket. If the VM currently does not have 1 core per socket, Workload Optimization Manager reconfigures it to 1 core per socket as part of action execution.
- If a VM is already optimally sized, but its current cores per socket is not 1, Workload Optimization Manager generates a reconfigure vCPU action to change cores per socket to 1, thereby bringing the VM into compliance with the policy.

This scaling option is ideal under the following scenarios:

- Your environment has a large number of small VMs where precise vCPU scaling is the priority.
- You have VMs that already have 1 core per socket and require on-demand upsizes on these VMs to be non-disruptive.


For example, a VM currently has 1 socket and 2 cores per socket, and applies a policy that changes vCPU in increments of 1.

■ If Workload Optimization Manager determines that the VM needs to increase compute capacity by 1 vCPU (i.e., from 2 to 3 vCPUs), a resize up action changes sockets from 2 to 3, and cores per socket from 2 to 1.



When the same VM needs to reduce compute capacity by 1 vCPU (i.e., from 3 to 2 vCPUs), a resize down action changes sockets from 3 to 2.





Scaling Option: Change Sockets

In this scaling option, Workload Optimization Manager adds or removes compute resources by changing VM sockets.

- If a VM requires a change to compute resources, Workload Optimization Manager generates a resize vCPU action that considers the current cores per socket value (if the 'Preserve existing VM cores per socket' option is set) or uses the user-specified cores per socket value. If the VM's current cores per socket value violates a policy (i.e., does not match the user-specified value), Workload Optimization Manager reconfigures the VM's cores per socket value as part of action execution, thereby bringing the VM into compliance with the policy, while at the same time providing the required change to compute resources.
- If a VM is already optimally sized, but its current cores per socket value violates a policy (i.e., does not match the user-specified value, if set), Workload Optimization Manager generates a reconfigure vCPU action to change cores per socket to the user-specified value, thereby bringing the VM into compliance with the policy.

Change Sockets and Preserve VM Cores Per Socket

In this scaling option, Workload Optimization Manager adds or removes compute resources by changing VM sockets in increments of 1, and preserves VM cores per socket.


This scaling option is ideal under the following scenarios:

- You require Workload Optimization Manager to leave the VM cores per socket configuration unchanged for operational policy reasons (such as compliance with an application support contract policy).
- You have VMs that need to upsize non-disruptively to meet rising application demand.
- You have VMs with even numbers of cores per socket and are required to scale in even increments of vCPUs.


For example, a VM currently has 1 socket and 4 cores per socket, and applies a policy that changes sockets and preserves VM cores per socket. Workload Optimization Manager has determined that the VM requires a change in compute capacity of 1 vCPU.

■ To increase compute capacity by 1 vCPU, a resize up action adds 1 socket. Because this new socket must have 4 cores to preserve VM cores per socket, the end result is 2 sockets with a total of 8 vCPUs.





It is not possible to reduce compute capacity by 1 vCPU because the VM is already at the smallest achievable size. Therefore, no action generates.



Change Sockets and Specify Cores Per Socket

In this scaling option, Workload Optimization Manager adds or removes compute resources by changing VM sockets in increments of 1, and reconfigures VM cores per socket according to the value that you specify.


This scaling option is ideal under the following scenarios:

- You require any odd number vCPUs for a VM to be an even number, by setting an even number of cores per socket.
- You want a quick, script-less bulk disruptive conversion of VMs to a specific cores per socket without negatively impacting compute capacity (vCPUs).
- You have older Guest OSes and applications that are sensitive to vCPU architecture changes that could result in power-on issues or kernel panics/BSODs. Some workloads require manual help with such changes so always test certain classes of applications and OSes before enabling any automation that changes the vCPU architecture. Use the Workload Optimization Manager knowledge of the application domain and Guest OS to scope them out of policies.


For example, a VM currently has 1 socket and 4 cores per socket, and applies a policy that changes sockets and enforces the user-specified 1 core per socket. Workload Optimization Manager has determined that the VM is already optimally sized, so a resize action is not necessary.

 Since the VM is in violation of policy, Workload Optimization Manager changes sockets from 1 to 4, and cores per socket from 4 to 1.





When the VM is compliant with policy, no action generates.



Scaling Option: Change Cores Per Socket

In this scaling option, Workload Optimization Manager adds or removes compute resources by changing the VM cores per socket.

- If a VM requires a change to compute resources, Workload Optimization Manager generates a resize vCPU action that considers the current socket value (if the 'Preserve existing VM sockets' option is set), respects the user-specified socket value, or matches VM sockets to the host socket value. If the VM's current socket value violates a policy (i.e., does not match the user-specified or host socket value), Workload Optimization Manager reconfigures the VM's socket value as part of action execution, thereby bringing the VM into compliance with the policy while at the same time providing the required change to compute resources.
- If a VM is already optimally sized, but its current socket value violates a policy, Workload Optimization Manager generates a reconfigure vCPU action to change the sockets to the user-specified or host socket value, thereby bringing the VM into compliance with the policy.

Older Guest OSes and applications may be sensitive to vCPU architecture changes that could result in power-on issues or kernel panics/BSODs. Some workloads require manual help with such changes so always test certain classes of applications and OSes before enabling any automation that changes the vCPU architecture. Use the Workload Optimization Manager knowledge of the application domain and Guest OS to scope them out of policies.

Change Cores Per Socket and Preserve VM Sockets

In this scaling option, Workload Optimization Manager adds or removes compute resources by changing the VM cores per socket in increments of 1, and preserves VM sockets.

This scaling option is ideal under the following scenarios:

 You require Workload Optimization Manager to leave the VM sockets configuration unchanged for operational policy reasons (such as socket-based licensing or compliance with an application support contract policy).




- You have VDI VMs that are at their maximum Guest OS socket limitation, but require more compute resources.
- You have VMs that are configured with NUMA considerations.

NOTE:


You can also use the 'Match Host Sockets' scaling option (discussed below) for NUMA sensitive VMs.

For example, a VM currently has 1 socket and 4 cores per socket, and applies a policy that changes cores per socket and preserves VM sockets. Workload Optimization Manager has determined that the VM requires a change in compute capacity of 1 vCPU.

■ To increase compute capacity by 1 vCPU, a resize up action changes cores per socket from 4 to 5.



To reduce compute capacity by 1 vCPU, a resize down action changes cores per socket from 4 to 3.



Change Cores Per Socket and Match Host Sockets

In this scaling option, Workload Optimization Manager reconfigures VM sockets to match the number of host sockets, thereby balancing vCPUs evenly across physical sockets. It also changes VM cores per socket to maintain the same compute capacity (vCPU).


This scaling option is ideal under the following scenarios:

- You have large VMs that may realize a performance benefit from reflecting the physical host CPU architecture within the Guest OS so that the application can optimize thread memory access to within a NUMA node.
- You have NUMA sensitive VMs that are migrating between hosts with different CPU architectures. Workload Optimization Manager can place the VMs on the best host and then generate an action to reconfigure the VMs to match the host sockets automatically. You can attach a schedule to the policy to automate disruptive reconfigure actions within a maintenance window.

For example, a VM currently has 1 socket and 4 cores per socket, and is on a host with 1 socket. The VM applies a policy that changes cores per socket and matches host sockets. Workload Optimization Manager has determined that the VM is already optimally sized, so a resize action is not necessary.



When the host socket value changes from 1 to 2, the VM is suddenly in violation of policy. To bring the VM into compliance while maintaining the same vCPU capacity (since the VM is already optimally sized), Workload Optimization Manager must distribute 4 cores between 2 sockets. The end result is 2 sockets and 2 cores per socket.



Change Cores Per Socket and Specify Sockets


In this scaling option, Workload Optimization Manager reconfigures VM sockets according to the value that you specify, and changes VM cores per socket to maintain the same compute capacity (vCPU).

This scaling option is ideal if you have VMs that require a specific socket value for operational policy reasons (such as socket-based licensing or compliance with an application support contract policy).


For example, a VM currently has 1 socket and 2 cores per socket, and applies a policy that changes cores per socket and enforces the user-specified 2 sockets. Workload Optimization Manager has determined that the VM is already optimally sized, so a resize action is not necessary.

■ Since the VM is in violation of policy, Workload Optimization Manager changes sockets from 1 to 2, and cores per socket from 2 to 1.





When the VM is compliant with policy, no action generates.



Scaling Option: Change MHz Legacy Behavior

In this scaling option, Workload Optimization Manager adds or removes compute resources in increments of MHz (1800 MHz by default).

If a VM requires a change to compute resources, Workload Optimization Manager generates a resize vCPU action that assumes 1 core per socket, regardless of the VM's actual cores per socket.

If Workload Optimization Manager discovers the actual number of cores per socket as part of action execution, it adjusts the action accordingly.

For example, a VM currently has 4 vCPUs with 2 sockets and 2 cores per socket. Workload Optimization Manager may generate an action to resize from 4 to 5 vCPUs. However, as part of action execution, the VM socket count changes from 2 to 3, so the end result is 6 vCPUs. Conversely, the same VM may have an action to resize from 4 to 3 vCPUs, but nothing changes as part of action execution.

Hypervisor Support

For **VMware vSphere**, Workload Optimization Manager supports all vCPU scaling options, including changing a VM's number of sockets or cores per socket. Increasing the number of sockets is non-disruptive if CPU hot-add is enabled on a VM, while reducing the socket count always requires a restart and is therefore disruptive.

For Hyper-V and Nutanix AHV, cores per socket and hot-add features have varying degrees of support.

vCPU Scaling Option	vSphere	Hyper-V	Nutanix AHV (Single Core)	Nutanix AHV (Multi Core)
Change virtual CPUs	Supported	Supported	Supported	Not supported by hypervisor



vCPU Scaling Option	vSphere	Hyper-V	Nutanix AHV (Single Core)	Nutanix AHV (Multi Core)
Change sockets – Preserve existing VM cores per socket	Supported	Supported	Supported	Supported
Change sockets - User specified cores per socket	Supported	Not supported by hypervisor	Not supported by hypervisor	Not supported by hypervisor
Change cores per socket - Preserve existing VM sockets	Supported	Not supported by hypervisor NOTE: Workload Optimization Manager assumes one core per socket and only changes sockets.	Not supported by Workload Optimization Manager	Not supported by Workload Optimization Manager
Change cores per socket - Match host sockets				
Change cores per socket - User specified sockets				

Tie Breakers

When a single VM applies multiple conflicting policies, Workload Optimization Manager uses the following tie breakers that follow the principle of least disruptive and most conservative:

vCPU Scaling Control

"Sockets" wins over "Cores per socket" wins over "Virtual CPU" wins over "MHz legacy behavior".

NOTE:

Policies created before the introduction of vCPU scaling controls (i.e., any policy before version 3.3.7) will continue to use the "MHz legacy behavior" option but will not be enforced when policy conflicts arise. You can remove these policies or update them to use the newer scaling controls.

Sockets setting

"Preserve existing VM cores per socket" wins over "User-specified core per socket".

Cores Per Socket setting

"Preserve existing VM sockets" wins over "User-specified socket" wins over "Match host sockets".

User-specified value

The lowest value wins.

Increment Size value

The lowest value wins.

For example, assume a VM belonging to two groups that apply different policies. Policy A changes cores per socket and matches host sockets, while Policy B changes sockets and preserves cores per socket. In this scenario, the VM applies Policy B. Changing sockets wins over changing cores per socket because it is less disruptive.

To see which policies are in effect after the tie-break decision, set the scope to a VM or group of VMs and then click the Policies tab.

Policy Cookbook

Tips:

- Use the following filters when searching for or creating VM groups:
 - Number of vCPUs
 - Number of Sockets
 - Cores per Socket
 - Target Type



- Hot-Add Enabled
- For the least disruptive on-demand upsize of vCPU, enable hot-add on the VM and change sockets while preserving cores per socket.
- For the most precise compute resource management, change cores per socket.
- For NUMA considerations, change cores per socket and match host sockets.
- Check Guest OS application and license compatibility when changing vCPU architecture and before automating actions.

How to...

Manage VM compute capacity by changing the number of vCPUs in increments of 2.

A VM will be reconfigured if required to use 1 core per socket, and resized by changing sockets. Actions are disruptive if the VM does not already have 1 core per socket or if hot-add is not enabled.

- 1. Create a group of VMs that can have 1 core per socket and scale in sockets.
- 2. Assign the group a policy with the following settings:
 - vCPU Scaling Controls
 - · Change: Virtual CPU
 - · Increment size: 2
 - (Optional) vCPU Resize Min/Max Threshold
- Reconfigure all odd-numbered vCPU VMs to be even-numbered, and then manage compute in even numbers of CPUs.

A VM will be reconfigured if required to use 2 cores per socket, and resized by changing sockets. Actions are disruptive if the VM does not already have 2 cores per socket or if hot-add is not enabled.

- 1. Create a group of VMs that can have 2 cores per socket and scale in sockets.
- 2. Assign the group a policy with the following settings:
 - vCPU Scaling Controls
 - · Change: Sockets
 - User specified cores per socket: 2
 - (Optional) vCPU Resize Min/Max Threshold
- Ensure that large VMs always balance their vCPU cores across all physical host sockets (for example, NUMA VMs and Database Server VMs).

A VM will be reconfigured if its socket count does not match the host socket count. The cores per socket count may be adjusted to maintain the overall compute capacity (number of vCPUs). Resize actions are disruptive because cores per socket will change. Reconfigure actions are non-disruptive if VM sockets are increasing, hot-add is enabled, and there are no changes to cores per socket.

- 1. Create a group of VMs using the filters that you require to identity typically larger VMs.
- 2. Assign the group a policy with the following settings:
 - vCPU Scaling Controls
 - · Change: Cores per socket
 - · Sockets: Match host sockets
 - (Optional) vCPU Resize Min/Max Threshold
- Keep VMs to 2 sockets only and manage compute by changing cores.

VMs in the group will be reconfigured to 2 sockets if required, and resized by changing the cores per socket count while keeping the sockets fixed at 2, thus ensuring compliance with socket-based licensing. Resize actions are disruptive because cores per socket will change. Reconfigure actions are non-disruptive if VM sockets are increasing, hot-add is enabled, and there are no changes to cores per socket.


- 1. Create a VM group containing the socket-licensed VMs.
- 2. Assign the group a policy with the following settings:
 - vCPU Scaling Controls
 - · Change: Cores per socket
 - User specified sockets: 2
 - (Optional) vCPU Resize Min/Max Threshold




Database Server (On-prem)

For on-prem, a Database Server is a database discovered through one of the associated database application targets or through APM solutions.

Synopsis





AppDynamics

Database Server Target

Synopsis			
Provides:	 Response Time, Transactions, DBmem, Cache Hit Rate, and TransactionLog to end users Connections to Application Components 		
Consumes:	VM resources, including VCPU, VMem, and VStorage		
Discovered through:	 AppDynamics targets Database Server targets Dynatrace MySQL and SQL Server processes NewRelic Infrastructure Integration (NRI): MySqI, SQL Server, MongoDB, OracleDB 		

Monitored Resources

Workload Optimization Manager monitors the following resources:

Virtual Memory (VMem)
 Virtual Memory is the measurement of memory that is in use.



Transaction

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.

Database Memory (DBMem)

Database memory (or DBMem) is the measurement of memory utilized by a Database Server.

Connection

Connection is the measurement of database connections utilized by applications.

DB Cache Hit Rate

DB cache hit rate is the measurement of Database Server accesses that result in cache hits, measured as a percentage of hits versus total attempts. A high cache hit rate indicates efficiency.

Actions

Workload Optimization Manager can recommend the following actions:

Resize

Resize the following resources:

Connections

Workload Optimization Manager uses connection data to generate memory resize actions for on-prem Database Servers.

Database memory (DBMem)

Actions to resize database memory are driven by data on the Database Server, which is more accurate than data on the hosting VM. Workload Optimization Manager uses database memory and cache hit rate data to decide whether resize actions are necessary.

A high cache hit rate value indicates efficiency. The optimal value is 100% for on-prem (self-hosted) Database Servers, and 90% for cloud Database Servers. When the cache hit rate reaches the optimal value, no action generates even if database memory utilization is high. If utilization is low, a resize down action generates.

When the cache hit rate is below the optimal value but database memory utilization remains low, no action generates. If utilization is high, a resize up action generates.

Transaction log

Resize actions based on the transaction log resource depend on support for virtual storage in the underlying hypervisor technology.

Currently, Workload Optimization Manager does not support resize actions for Oracle and Database Servers on the Hyper-V platform (due to the lack of API support for virtual storage).

On-prem Database Server Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

Action	Default Mode
Resize	Manual
Resize DBMem (Up/Down)	Manual

You can use Action Scripts (on page 692) and third-party orchestrators (such as ServiceNow) for action orchestration.

Transaction SLO

Transaction SLO determines the upper limit for acceptable transactions per second. When the number of transactions reaches the given value, Workload Optimization Manager sets the risk index to 100%.



Attribute	Default Setting/Value
Enable Transaction SLO	Off
Transaction SLO	None
	If you enable SLO, Workload Optimization Manager uses the default value of 10. You can change this to a different value.

Response Time SLO

Response time SLO determines the upper limit for acceptable response time (in milliseconds). If response time reaches the given value, Workload Optimization Manager sets the risk index to 100%.

Attribute	Default Setting/Value
Enable Response Time SLO	Off
	Workload Optimization Manager estimates SLO based on monitored values.
Response Time SLO [ms]	None If you enable SLO, Workload Optimization Manager uses the default value of 2000. You can change this to a different value.

DBMem Utilization

The utilization that you set here specifies the percentage of the existing capacity that Workload Optimization Manager will consider to be 100% of capacity.

Attribute	Default Value
DBMem Utilization (%)	100

For example, a value of 80 means that Workload Optimization Manager considers 80% utilization to be 100% of capacity. Workload Optimization Manager recommends actions that avoid utilization beyond the given value.

DBMem Scaling Increment

This increment specifies how many units to add or subtract when scaling DBMem.

Attribute	Default Value
DBMem Scaling Increment (MB)	128


Do not set the increment value to be lower than what is necessary for the database server to operate. If the increment is too low, then it's possible there would be insufficient DBMem. When reducing allocation, Workload Optimization Manager will not leave a database server with less than the increment value. For example, if you use the default 128, then Workload Optimization Manager cannot reduce DBMem to less than 128 MB.

Volume (On-prem)

On-prem volumes represent VM disks discovered by hypervisor targets. A VM will have one volume for each configured disk and another volume (representing the configuration) that always moves with Disk 1.



Synopsis



Synopsis	
Provides:	Storage resources for VMs to use
	Set the scope to a volume and view the Entity Information chart to see a list of VM-related files (such as VMDKs) contained in the volume.
	Set the scope to a VM to see a list of volumes attached to the VM.
Consumes:	Datacenter resources
Discovered through:	Hypervisor targets

Actions

Workload Optimization Manager can recommend the following actions:

Move

Move a VM's volume (virtual storage) due to excess utilization of the current datastore, or for more efficient utilization of datastores in the environment.

Points to consider:

- The default global policy includes a setting that directs Workload Optimization Manager to use relevant metrics when analyzing and recommending actions for volumes. For details, see <u>Enable Analysis of On-prem Volumes (on page</u> 679).
- Workload Optimization Manager will not recommend moving a volume to a datastore that is currently in maintenance mode. Any volume in that datastore should move to an active datastore (for example, via vMotion).

■ Reconfigure

Reconfigure a VM's volume (virtual storage) to comply with placement policies.



On-prem Volume Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Placement Policies

By default, all on-prem volumes associated with a storage will move together rather than independently. You can create placement policies to place individual volumes on groups of storage. To ensure successful placement, be sure to also turn on the setting Enable Analysis of On-prem Volumes in the default global policy.

For more information, see <u>Creating Placement Policies</u> (on page 673) and <u>Enable Analysis of On-prem Volumes</u> (on page 679)

Action Automation and Orchestration

Action	Default Mode
Move	Manual

Cloud Storage Tiers

This policy setting works with plans that simulate migration of on-prem volumes to the cloud. When you create the policy, be sure to set the scope to on-prem volumes and then select the cloud storage tiers that they can migrate to. Workload Optimization Manager treats these tiers as constraints when you run a Migrate to Cloud plan that includes the volumes defined in the policy.

Attribute	Default Value
Cloud Storage Tiers	None

Click **Edit** to set your preferences. In the new page that displays, expand a **cloud tier** (a family of instance types, such as *Premium*) to see individual instance types.

Select your preferred instance types or cloud tiers, or clear the ones that you want to avoid. After you save your changes, the main page refreshes to reflect your selections.

Virtual Data Center (Private Cloud)

A virtual data center (vDC) is a collection or pool of resources that groups the resources around specific requirements or business needs. In private cloud environments, Workload Optimization Manager discovers the infrastructure that provides resources to the cloud, and the workloads that run on the cloud. To manage these resources, private clouds organize the infrastructure into Provider and Consumer virtual data centers.

NOTE:

Different targets use different names to refer to virtual data centers. In the Workload Optimization Manager supply chain, these entities are all represented by Consumer and Provider VDCs, as follows:


Workload Optimization Manager	vCenter Server	VMM
Consumer VDC	Resource Pool (Child)	Tenant or TenantQuota
Provider VDC	Resource Pool (Root)	Cloud

Provider Virtual Data Centers

A provider virtual data center (vDC) is a collection of physical resources (hosts and data stores) within a cloud stack. The cloud administrator has access to these resources, and defines the data center members. A Provider vDC is created to manage resources that will be allocated to external customers through one or more Consumer vDCs.



Synopsis



A Provider vDC gains its budget by selling resources to the Consumer vDCs that it hosts. If utilization falls off, the data center loses budget. Ultimately, if the budget isn't enough to pay for the services it consumes, Workload Optimization Manager will recommend decommissioning the Provider vDC.

Synopsis	
Provides:	Physical resources (hosts and datastores) to Consumer vDCs
Consumes:	Hosts and datastores from the physical infrastructure
Discovered through:	Private Cloud Stack Managers

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Memory (Mem)
 - Memory is the measurement of memory that is reserved or in use.
- CPI
 - CPU is the measurement of CPU that is reserved or in use.
- Storage
 - Storage is the utilization of the storage attached to the entity.

Actions

None


Workload Optimization Manager does not recommend actions for a Virtual Data Center. Instead, it recommends actions for the entities that provide resources to the Virtual Data Center.



Consumer Virtual Data Centers

A Consumer Virtual Data center (vDC) is a collection of resources that are available for external customers to manage workload through the private cloud. It is an environment customers can use to store, deploy, and operate virtual systems. Consumer Data centers use the resources supplied by a Provider Data center.

Synopsis



A Consumer vDC gains its budget as a function of its activity. The higher the utilization of the vDC, the more Workload Optimization Manager assumes the vDC is selling its services to a user. If utilization is high enough on a Consumer vDC, Workload Optimization Manager can increase resources for the vDC. If utilization falls off, Workload Optimization Manager can reduce resource capacity, or ultimately recommend terminating the vDC.

Workload Optimization Manager can also resize VMs through the Consumer vDC in response to changes in VM utilization.

Synopsis	
Provides:	Resources to host virtual systems
Consumes:	Provider vDC
Discovered through:	Cloud Stack Managers

While users can see some of the physical resources that support the Consumer vDC, consumer-level users cannot modify these physical resources. Users of Consumer vDCs make changes to how the virtual devices are deployed in that environment, but they must ask the Provider vDC administrator to add more physical resources to be used by the Consumer vDC. Likewise, Workload Optimization Manager can change resources on the VMs running in the vDC, but it does not make any changes to physical resources through this vDC.

Monitored Resources

Workload Optimization Manager monitors the following resources:

Memory (Mem)



Memory is the measurement of memory that is reserved or in use.

CPU

CPU is the measurement of CPU that is reserved or in use.

Storage

Storage is the utilization of the storage attached to the entity.

Actions


Workload Optimization Manager does not recommend actions to perform on a Consumer vDC. Instead, it recommends actions to perform on the entities running in the Provider vDC.

Business User

For Virtual Desktop Infrastructure (VDI) environments, a Business User is a user account that is entitled to launch one or more active VDI sessions. As it discovers desktop pools, Workload Optimization Manager creates Business User entities for each user that is entitled to a pool. One business user can be entitled to more than one desktop pool.

To properly work with Business User entities, Workload Optimization Manager discovers user information through the LDAP server that manages users for the VDI environment. Note that the account Workload Optimization Manager uses to connect to the LDAP server must be trusted for the same domains as are the users in your environment.

Synopsis



The Supply Chain shows relationships of Business Users to Desktop Pools and also to VMs. One Business User can have access to multiple Desktop Pools. When a Business User has an active session, the Supply Chain shows a direct link between the user and the VM that hosts the session. However, Workload Optimization Manager does not consider this direct connection when analyzing compute resources. Instead, Business Users utilize Desktop Pool resources, and the Desktop Pools use compute resources from the underlying Virtual Datacenters.



Synopsis	
Provides:	N/A
Consumes:	Resources from the underlying desktop pools, including:
	■ Sessions
	■ Pool Memory
	■ Pool Storage
	■ Pool CPU
	When a Business User has an active session, the supply chain shows it in relation to the VM that hosts the session. The Business User consumes the VM's compute resources to support the session requirements for ImageCPU, ImageMem, and ImageStore resources.
Discovered through:	The LDAP server that manages these users
	You can specify the LDAP server as part of the target configuration, or Workload Optimization Manager can discover it in association with the VDI target.

Monitored Resources

Workload Optimization Manager monitors the following resources:

- ImageCPU
 - ImageCPU is the measurement of CPU that is utilized by a user's desktop images, expressed as a percentage of CPU capacity.
- ImageMem
 - ImageMem is the measurement of memory that is utilized by a user's desktop images, expressed as a percentage of memory capacity.
- ImageStorage
 - ImageStorage is the measurement of storage that is utilized by a user's desktop images, expressed as a percentage of storage capacity.

Business User Actions

Workload Optimization Manager can recommend the following actions:

Move

Move a Business User between desktop pools to address:

- Resource congestion on the image
 - When utilization is consistently near capacity for image resources, Workload Optimization Manager can recommend moving a Business User to a desktop pool that serves larger images.
- Resource congestion on the desktop pool
 - When utilization is consistently near capacity for the desktop pool, Workload Optimization Manager can recommend moving a Business User to a desktop pool that has more available resources.

NOTE:

To support moves, you must configure placement policies that merge *similarly configured* desktop pools. For details, see <u>Desktop Pool Placement Policies</u> (on page 480).

Business User Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

For details about Business User actions, see **Business User Actions** (on page 476).



Action	Default Mode
Move	Recommend

Image Target Utilization

Workload Optimization Manager tracks utilization of desktop image resources for the Business Users in your Virtual Desktop Infrastructure (VDI) environment.

Attribute	Default Value
Image CPU Target Utilization	70
	The target utilization as a percentage of CPU capacity.
Image MEM Target Utilization	90
	The target utilization as a percentage of memory capacity.
Image Storage Target Utilization	90
	The target utilization as a percentage of storage capacity.

Aggressiveness and Observation Period

Workload Optimization Manager uses these settings to calculate utilization percentiles. It then recommends actions to improve utilization based on the observed values for a given time period.

Aggressiveness

Attribute	Default Value
Aggressiveness	95th Percentile

When evaluating utilization of compute and storage resources, Workload Optimization Manager considers a given utilization percentile. For example, assume a 95th percentile. The maximum utilization would be the highest value that 95% of the observed samples fall below.

Using a percentile, Workload Optimization Manager can recommend more relevant actions, so that analysis can better exploit elasticity in your environment. A percentile evaluates the sustained resource utilization, and ignores bursts that occurred for a small portion of the samples. You can think of this as aggressiveness of resizing, as follows:

- 100th Percentile The least aggressive, recommended for critical workloads that need maximum guaranteed performance at all times.
- 95th Percentile (Default) The recommended setting to achieve maximum performance and savings.
- 90th Percentile The most aggressive, recommended for non-production workloads that can stand higher resource utilization.

Max Observation Period

Attribute	Default Value
Max Observation Period	Last 7 Days

To refine the calculation of resource utilization, you can set the sample time to consider. Workload Optimization Manager uses historical data from up to the number of days that you specify as a sample period. (If the database has fewer days' data then it uses all of the stored historical data.)

A shorter period means there are fewer data points to account for when Workload Optimization Manager calculates utilization percentiles. This results in more dynamic, elastic moves to different Desktop Pools, while a longer period results in more stable or less elastic moves. You can make the following settings:


- Less Elastic Last 90 Days
- More Elastic Last 30 Days
- (Default) Most Elastic Last 7 Days



Desktop Pool

For Virtual Desktop Infrastructure (VDI) environments, a desktop pool is a collection of desktops that users can select from. The desktop pool can provide logical grouping of desktops according to user roles, assignment type (dedicated or floating), and the source of resources (physical host or VM).

Synopsis



The desktop pool gets compute and storage resources from the underlying Virtual Datacenter. For VMware Horizon View, the VDI architecture includes one or more vCenter Server instances. When it discovers the Horizon View target, Workload Optimization Manager also discovers the supporting vCenter Server instances, and their corresponding Virtual Datacenters. These are the source of compute and storage resources for the associated desktop pools.

Synopsis	
Provides:	Resources for Business Users to use, including:
	■ Pool Memory
	■ Pool CPU
	 Active Sessions
Consumes:	■ Compute and storage resources from the associated Virtual Datacenters
	 Sessions from the underlying View Pod
Discovered through:	VDI management targets
	For VMware Horizon View, the target is the View Connection Server.

Monitored Resources

Workload Optimization Manager monitors the following resources:

Pool CPU

Pool CPU is the measurement of CPU that is utilized by active sessions in a desktop pool.



Pool Memory

Pool memory is the measurement of memory that is utilized by active sessions in a desktop pool.

Pool Storage

Pool storage is the measurement of storage that is utilized by active sessions in a desktop pool.

Active Sessions

Active sessions is the number of active sessions in a desktop pool, expressed as a percentage of the pool's capacity.

Total Sessions

Total sessions is the number of active and disconnected (non-terminated) sessions in a desktop pool, expressed as a percentage of the pool's capacity.

Actions

None

Workload Optimization Manager does not recommend actions for a desktop pool. It recommends actions for the Business Users running active sessions in the pool.

Desktop Pool Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

None

Workload Optimization Manager does not recommend actions for a desktop pool. It recommends actions for the Business Users running active sessions in the pool.

Observation Settings

Workload Optimization Manager uses these settings to decide whether to move Business Users from one desktop pool to another.

Daily Observation Windows

Attribute	Default Value
Daily observation windows	3 windows per day

When evaluating utilization of pool resources, Workload Optimization Manager divides each day into different observation windows, calculates an average for each, and uses the highest value. In this way, Workload Optimization Manager can account for high-use periods in the day to base calculations off of the most representative usage of the desktop images.

Assume three observation windows:

Window	Time range	Average utilization
W1	00:00 - 08:00	10%
W2	08:00 - 16:00	80%
W3	16:00 - 24:00	40%

Average utilization for this day *without* the benefit of observation windows would be 44%. By using observation windows we can see that the representative utilization of pool resources is closer to 80%. That is because Workload Optimization Manager discovers an average utilization of 80% during the high-usage time of day.

When calculating whether to move business users from one desktop pool to another, Workload Optimization Manager averages the observation windows over the time you set for the Max Observation Period. For this reason, you should try to set up observation windows that capture the best representation of work habits amongst your business users.

Max Observation Period



Attribute	Default Value
Max Observation Period	Last 7 Days

To refine the calculation of resource utilization, you can set the sample time to consider. Workload Optimization Manager uses historical data from up to the number of days that you specify as a sample period. (If the Workload Optimization Manager database has fewer days' data, then it uses all of its stored historical data.)

A shorter period means there are fewer data points to account for when Workload Optimization Manager calculates utilization. This results in more dynamic, elastic resizing, while a longer period results in more stable or less elastic resizing. You can make the following settings:

- Less Elastic Last 30 Days
- Recommended Last 7 Days
- More Elastic Last 3 Days

Pool Utilization

These settings affect the actions Workload Optimization Manager recommends as it manages business users and active accounts on the desktop pool. Workload Optimization Manager recommends actions that avoid using these resources beyond the given settings.

Attribute	Default Value
Pool CPU Utilization	95
Pool Mem Utilization	95
Pool Storage Utilization	95

The values you set here specify what percentage of the existing capacity that Workload Optimization Manager will consider to be 100% of capacity. For example, setting 70 for Desktop Pool Pool CPU Utilization means that Workload Optimization Manager considers 70% utilization of that CPU to be 100% of capacity and 35% utilization to be 50% of capacity.

Placement Policies

Under some circumstances, you can have Business Users who need larger desktop images. This appears as users with high utilization of the image resources. In this case, Workload Optimization Manager can recommend moving the Business Users to a different desktop pool that serves up larger images.

To support moving Business Users, you must create a placement policy that merges desktop pools. Be sure to merge only desktop pools that are *similarly configured* – they should run the same operating system and applications, and differ only in allocated memory and/or CPU.

To merge desktop pools:

- Create a new placement policy.
- 2. Choose Merge as the policy type.
- For the consumer type to merge, choose **Desktop Pool**.
- 4. Choose the pools that you want to merge.
- Save the policy.


For more information, see Creating Placement Policies (on page 673).

View Pod

For Virtual Desktop Infrastructure (VDI) environments, a View Pod groups together a given set of Desktop Pools.



Synopsis



Synopsis	
Provides:	Active Sessions
Consumes:	N/A
Discovered through:	VDI Management targets
	For VMware Horizon View, the target is the View Connection Server.

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Active Sessions
 - Active sessions is the number of active sessions in a desktop pool, expressed as a percentage of the pool's capacity.
- Total Sessions

Total sessions is the number of active and disconnected (non-terminated) sessions in a desktop pool, expressed as a percentage of the pool's capacity.

Actions

None

Workload Optimization Manager does not recommend actions for a view pod. Instead, it recommends actions for the Business Users that are running active sessions.

Active Session Capacity for View Pods

Each View Pod entity has a set capacity of active sessions. By default, Workload Optimization Manager assumes a capacity of 8,000. So that Workload Optimization Manager can generate reliable actions for Business User entities, you must set this capacity to match the active session capacity that your Horizon administrator has deployed for the given view pod.

Once you know the correct active session capacity for your view pod, create an automation policy that sets the capacity. For complete information about creating automation policies, see <u>Creating Automation Policies (on page 680)</u>. For information about view pod policies, see <u>View Pod Policies (on page 482)</u>.

Create a new automation policy.

Navigate to the Settings Page and choose **Policies**. Then click **NEW AUTOMATION POLICY**, and select View Pod as the policy type. Be sure to name the new policy.



2. Set the policy scope to your view pod.

To define its scope, you assign a group to the policy. You will have to create the group for this view pod:

- Expand the SCOPE section and then click ADD VIEW POD GROUPS.
- Choose the group that contains only the view pod you want to configure.

If it has already been created, choose the group from the list. If the group does not appear, click **NEW GROUP** to create a static group that includes only the view pod you want to configure. For more information about creating groups, see <u>Creating Groups</u> (on page 669).

Choose the group you want and click SELECT. This returns you to the Configure View Pod Policy fly-out.

Set the view pod capacity.

Expand the **UTILIZATION CONSTRAINTS** section and click **ADD UTILIZATION CONSTRAINT**. From the drop-down list, choose Active Sessions Capacity. In the capacity field, enter the capacity that you have calculated for your desktop pools.

4. Save your work

When you're done, be sure to click SAVE AND APPLY.

View Pod Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

None

Workload Optimization Manager does not recommend actions for a view pod. Instead, it recommends actions for the Business Users that are running active sessions.

Active Sessions Capacity

This setting controls the number of active sessions a given view pod can support.

Attribute	Default Value
Active Sessions Capacity	8000

For each view pod, you should set this value to match the active session capacity that has been deployed in your VDI environment for the given view pod. For more information, see Active Session Capacity for View Pods (on page 481).

Host

For on-prem environments, a host is a server that runs processes, including hypervisor processes to host virtual workloads. Note that a host is not necessarily a physical piece of hardware. A VM can be set up as a server that runs a hypervisor, and in turn it can host other VMs within its processing space. However, it is typical to use physical hardware as your hosts.


NOTE:

To support vSAN storage in your environment, you can deploy HCl Hosts. Workload Optimization Manager discovers the vSAN as a storage entity that consumes resources from the underlying hosts. For more information, see <u>vSAN Storage (on page 492)</u>.

On the public cloud a host is an availability zone. This is where your cloud workloads run. For details, see Zone (on page 442).



Synopsis



A host gains its budget by selling resources to the workloads that run on it. The more workloads running on a host, the more budget the host has to purchase storage and datacenter resources. If utilization of a host is high enough, Workload Optimization Manager can recommend that you provision a new one. If utilization falls off, the host loses budget. Ultimately, if the budget is not enough to pay for the services it consumes, Workload Optimization Manager will recommend to suspend or power off the host.

Synopsis		
Provides:	Host resources for VMs to use, including: Memory CPU IO throughput Net (network throughput)	
	 Swap Ballooning (sharing of memory among hosted VMs) CPU Ready Queue 	
Consumes: Discovered through:	Datacenter resources (physical space, cooling, etc.) and storage Hypervisor targets	
	For some hypervisor vendors, the host is the target, and for others the hosts are managed by the specified target.	

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Memory (Mem)
 - Memory is the measurement of memory that is reserved or in use.
- CPU
 - CPU is the measurement of CPU that is reserved or in use.
- IO



IO is the utilization of a host's IO adapters.

Net

Net is the utilization of data through the host's network adapters.

Swap

Swap is the measurement of a host's swap space that is in use.

Balloon

Balloon is the measurement of memory that is shared by VMs running on a host.

■ CPU Ready

CPU Ready is the measurement of a host's ready queue capacity that is in use.

For hosts discovered via vCenter targets, the following resources are monitored:

Energy

Energy is the measurement of electricity consumed by a given entity over a period of time, expressed in watt-hours (Wh).

Carbon Footprint

Carbon footprint is the measurement of carbon dioxide equivalent (CO2e) emissions for a given entity. Workload Optimization Manager measures carbon footprint in grams.

Actions

Workload Optimization Manager can recommend the following actions:

Start

Start a suspended host when there is increased demand for physical resources.

Provision

Provision a new host in the environment when there is increased demand for physical resources. Workload Optimization Manager can then move workloads to that host.

Suspend

When physical resources are underutilized on a host, move existing workloads to other hosts and then suspend the host.

■ Reconfigure

Workload Optimization Manager generates this action in response to changing demand for software licenses. For details, see <u>License Policy (on page 676)</u>.

NOTE:

Workload Optimization Manager discovers VMware HA configurations in clusters, and considers the reserved resources in its calculations. For tolerated host failures, or a reserved percentage of cluster resources, Workload Optimization Manager automatically sets utilization constraints for that cluster. If you configure a failover host, Workload Optimization Manager reserves that host for HA and will not move VMs to it.

DRS Automation Settings

Workload Optimization Manager automatically discovers DRS automation settings for vSphere hosts managed through vCenter. When you set the scope to a vSphere host and then view the Entity Information chart, the following information displays:

Vendor Automation Mode

The chart shows the automation mode discovered from vCenter - Not Automated, Partially Automated, or Fully Automated.

Vendor Migration Level

Workload Optimization Manager assigns a vendor migration level based on the migration level discovered from vCenter. The chart only shows the assigned migration level (i.e., the Workload Optimization Manager Vendor Migration Level).

Workload Optimization Manager Vendor Migration Level	vCenter Migration Level
1 (Conservative)	5
2 (Less Conservative)	4



Workload Optimization Manager Vendor Migration Level	vCenter Migration Level
3 (Moderate)	3
4 (Less Aggressive)	2
5 (Aggressive)	1

Host Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

For details about host actions, see Host Actions (on page 484).

Action	Default Mode	vCenter	Hyper-V	UCS (blades only)	PowerVM
Start	Recommend	Auto	Remd	Auto	N/A
Suspend	Recommend	Auto	Remd	Auto	N/A
Provision	Recommend	Remd	Remd	Auto	N/A
Reconfigure	Recommend	Romd	Remd	Rcmd	N/A

You can use Action Scripts for action orchestration.

For ServiceNow:

- Host provision actions will not generate a CR.
- For host suspend actions to succeed, it must be enabled in the given hypervisor, and there must be no VMs currently running on that host.

Maintenance Automation Avoidance

Attribute	Default Setting
Maintenance Automation Avoidance	30 minutes

The Maintenance Automation Avoidance setting applies to vCenter environments with DRS clusters. Workload Optimization Manager uses this setting when:

- Workload Optimization Manager actions to move VMs from one host to another are automated.
- The DRS <u>automation level</u> is *Fully Automated*, regardless of <u>migration threshold</u>.

NOTE:

Workload Optimization Manager automatically discovers DRS automation levels and migration thresholds and displays them in the Entity Information chart for hosts.

■ Host maintenance is in effect.

This setting prevents action conflicts between Workload Optimization Manager and DRS.

When a host enters maintenance mode, DRS starts to move VMs on the host to other hosts to prepare for maintenance. In response, Workload Optimization Manager clears all pending actions to and from the host. For example, assume a cluster with Host_01, Host_02, and Host_03. When Host_01 enters maintenance mode, Workload Optimization Manager removes the following pending actions from the system:

Move a VM on Host_01 to Host_02.

This prevents a potential conflict with a DRS action that moves the VM to Host_03.



Move a VM on Host_02 to Host_01.

Since Host_02 and Host_03 are not in maintenance mode, Workload Optimization Manager might recommend moving the VM from Host_02 to Host_03 as an alternative action.

In addition, Workload Optimization Manager treats a host entering or in maintenance mode as uncontrollable and stops generating actions for the host. The host remains uncontrollable after it leaves maintenance mode, but is within the Maintenance Automation Avoidance period that you specified. During rolling host maintenance operations on DRS clusters, where hosts undergo maintenance on a staggered basis, this gives DRS a window (30 minutes by default) to move VMs from hosts entering maintenance to hosts that have recently left maintenance, thereby avoiding any potential conflict.

When the Maintenance Automation Avoidance period is over, Workload Optimization Manager treats the host as controllable and resumes action generation. At this stage, it is assumed that all critical DRS activities on the host have been completed, so Workload Optimization Manager actions should be safe to execute.

The following table summarizes Workload Optimization Manager's response at various stages of maintenance.

Maintenance Status	DRS Activities	Host Status in Workload Optimization Manager	Workload Optimization Manager Pending Actions	Workload Optimization Manager New Actions
Host is entering maintenance mode.	Increased number of DRS activities moving VMs away from the host entering maintenance	X Uncontrollable (Maintenance)	# Removed from the system	X Not generated
Host is in maintenance mode.	Maintenance tasks on the host	X Uncontrollable (Maintenance)	N/A	X Not generated
Host has left maintenance mode but is within the Maintenance Automation Avoidance window.	Increased number of DRS activities moving VMs away from other hosts entering maintenance	X Uncontrollable (Maintenance)	N/A	X Not generated
Host has left maintenance mode and is outside the Maintenance Automation Avoidance window.	Minimal number of DRS activities on the host	# Controllable	N/A	# Generated

Points to consider:

- You can set a different Maintenance Automation Avoidance value that aligns with your host maintenance practices. For example, if moving VMs back to a host typically takes an hour, specify a value of 60.
- You can set a global value in the default policy for hosts, or specific values in automation policies that you create for your clusters.
- For rolling maintenance of hosts in a cluster, where hosts undergo maintenance on a staggered basis, there could be a point in the process where some or all hosts are uncontrollable. This means that Workload Optimization Manager cannot recommend actions to alleviate pressure on overburdened hosts. As such, these hosts could lose performance while they are uncontrollable.
- This setting has no effect on clusters where the DRS automation level is *Manual* or *Partially Automated*. As soon as a host enters maintenance mode, Workload Optimization Manager automates the first action to move a VM to another host, and then stops recommending actions. After the host leaves maintenance mode, Workload Optimization Manager automates actions to manage the performance of the cluster as normal.

Utilization Constraints

Utilization constraints affect the actions Workload Optimization Manager recommends as it manages your environment. Workload Optimization Manager recommends actions that avoid using these resources beyond the given settings. The values



you set here specify what percentage of the existing capacity that Workload Optimization Manager will consider to be 100% of capacity.

Attribute	Default Value
Memory Overprovisioned Percentage	1000
Net Throughput	50
Ready Queue Utilization	50
Memory Utilization	100
IO Throughput	50
CPU Overprovisioned Percentage	1000
CPU Utilization	100
Swapping Utilization	20

For example:

- Setting 50 for Net Throughput means that Workload Optimization Manager considers 50% utilization of that throughput to be 100% of capacity and 25% utilization to be 50% of capacity
- Setting 1000 for Memory Overprovisioned Percentage means that overprovisioning memory by 5 times the physical capacity shows up as 50% utilization of the Mem Overprovisioned capacity in Workload Optimization Manager
- Setting 100 for Memory Utilization means that Workload Optimization Manager capacity reflects the physical capacity for this resource

Desired State

The desired state for your environment is an n-dimensional sphere that encompasses the fittest conditions your environment can achieve.

Attribute	Default Value
Diameter	10
Center	70

The multiple dimensions of this sphere are defined by the resource metrics in your environment. Metric dimensions include VMem, storage, CPU, etc. While the metrics on the devices in your environment can be any value, the desired state, this n-dimensional sphere, is the subset of metric values that assures the best performance while achieving the most efficient utilization of resources that is possible.

The Desired State settings define the center of the sphere as well as its diameter. This is a way for you to customize what Workload Optimization Manager considers to be the desired state.

Setting the center of the sphere chooses the priority for Workload Optimization Manager analysis. If you set the balance in favor of efficiency, Workload Optimization Manager tends to place more VMs on fewer physical hosts, and to give them storage capacity from fewer data stores. As a result, high utilization can have more impact on QoS. With a balance in favor of performance, Workload Optimization Manager tends to spread virtual loads across more physical devices. This can result in the provisioning of excess resources.

The diameter setting determines the range of deviation from the center that can encompass the desired state. If you specify a large diameter, Workload Optimization Manager will have more variation in the way it distributes workload across hosting devices.

As you move each slider, a tooltip displays the numerical value of the setting. **Center** indicates the percentage of resource utilization you want, within the range you specify as **Diameter**. For example, if you want utilization of 75%, plus or minus 10%, then you would set **Center** = 75 and **Diameter** = 20. Workload Optimization Manager recommends actions that tend toward this desired state much as possible, given the dependencies within the current environment.



NOTE:

The setting for Target Utilization can have an effect on plans that you run. If you disable provisioning and suspension for hosts and datastores, then you should always set Center and Diameter to their default values.

Placement Policies

You can create placement policies that merge multiple clusters into a single logical group for the purpose of workload placement.

For example, you can merge three host clusters in a single provider group. This enables Workload Optimization Manager to move workload from a host in one of the clusters to a host in any of the merged clusters to increase efficiency in your environment.

For more information, see Creating Placement Policies (on page 673).

NOTE


For vCenter, Cisco automatically imports any vSphere Host DRS rules when DRS is enabled, and displays them on the **Settings** > **Policies** page under **Imported Placement Policies**.

For more information, see Importing Workload Placement Policies (on page 673).

Chassis

A chassis houses the servers that are part of a computing fabric. It provides compute, memory, storage, and bandwidth resources.

Synopsis



Synopsis	
Provides:	Chassis resources (physical space, cooling, etc.)
Consumes:	N/A
Discovered through:	Fabric Manager targets

NOTE:

When Workload Optimization Manager discovers that blade servers housed in a particular chassis have been designated as vCenter hosts, the supply chain stitches the blade servers and chassis to the corresponding vCenter data center to establish their relationship. When you set the scope to that data center and view the Health chart, you will see the blade servers in the list of hosts. In addition, when the data center is included in a merge policy (a policy that merges data centers for the purpose of VM placement), the VMs in the blade servers apply the policy, allowing them to move between data centers as necessary.

Monitored Resources

Workload Optimization Manager monitors the following resources:

Power

Power is the measurement of electricity consumed by a given entity, expressed in watts.

Cooling

Cooling is the percentage of the acceptable temperature range that is utilized by the entity. As the temperature nears the high or low running temperature limits, this percentage increases.



Actions

None

Workload Optimization Manager does not recommend actions for a chassis.


Data Center

A data center is the sum of VMs, hosts, datastores, and network devices that are managed by a given hypervisor target. A data center provides compute, memory, storage, and bandwidth resources.

NOTE:

For public cloud environments, a data center is the cloud region. The hosts that get resources from the data center are availability zones within that region. For details, see Region (on page 443) and Zone (on page 442).

Synopsis



Synopsis	
Provides:	Compute, memory, storage, and bandwidth resources
Consumes:	N/A
Discovered through:	Hypervisor targets

NOTE:

When Workload Optimization Manager discovers that blade servers housed in a particular chassis have been designated as vCenter hosts, the supply chain stitches the blade servers and chassis to the corresponding vCenter data center to establish their relationship. When you set the scope to that data center and view the Health chart, you will see the blade servers in the list of hosts. In addition, when the data center is included in a merge policy (a policy that merges data centers for the purpose of VM placement), the VMs in the blade servers apply the policy, allowing them to move between data centers as necessary.

Monitored Resources

Workload Optimization Manager does not monitor resources directly from the data center, but it does monitor the following resources, aggregated for the hosts in a data center:

- Memory (Mem)
 - Memory is the measurement of memory that is reserved or in use.
- CPU



CPU is the measurement of CPU that is reserved or in use.

IO

IO is the utilization of a host's IO adapters.

Ne

Net is the utilization of data through the host's network adapters.

Swap

Swap is the measurement of a host's swap space that is in use.

Balloon

Balloon is the measurement of memory that is shared by VMs running on a host.

CPU Ready

CPU Ready is the measurement of a host's ready queue capacity that is in use.

For vCenter targets, the following resources are also monitored:

Energy

Energy is the measurement of electricity consumed by a given entity over a period of time, expressed in watt-hours (Wh).

Carbon Footprint

Carbon footprint is the measurement of carbon dioxide equivalent (CO2e) emissions for a given entity. Workload Optimization Manager measures carbon footprint in grams.

Actions

None

Workload Optimization Manager does not recommend actions for a data center. Instead, it recommends actions for the entities running in the data center.

Data Center Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Operational Constraints

Workload Optimization Manager <u>calculates</u> (on page 627) carbon footprint using industry standards that take into account energy consumption, datacenter efficiency, and carbon intensity data. You can create Data Center policies to adjust the calculations according to the requirements of your data centers. For example, a data center in a particular location might have different requirements than data centers in other locations. After you adjust the calculations via policies, Workload Optimization Manager can accurately report your organization's carbon footprint.

Attribute	Default Value
Carbon Intensity (CI)	.25 (g/Wh)
Power Usage Effectiveness (PUE)	1.5

- Carbon Intensity (CI) is a measurement of how 'clean' electricity is. It refers to how many grams of carbon dioxide (CO2) are released to produce 1 watt-hour (Wh) of electricity. Electricity that is generated using fossil fuels is more carbon intensive, as the process by which it is generated creates CO2 emissions. Renewable energy sources, such as wind, hydro, or solar power produce next to no CO2 emissions, so their carbon intensity value is much lower and often zero.
- Power Usage Effectiveness (PUE) is a ratio that describes how efficiently a computer data center uses energy; specifically, how much energy is used by the computing equipment. PUE is the ratio of the total amount of energy used by a computer data center facility to the energy delivered to computing equipment. The closer PUE is to 1, the more efficient the computer data center.



Placement Policies


For vCenter environments, you can create placement policies that merge data centers to support cross-vCenter moves. In this case, where a data center corresponds to a given vCenter target, the merged clusters can be in different data centers. In this case you must create two merge policies; one to merge the affected data centers, and another to merge the specific clusters.

For more information, see Creating Placement Policies (on page 673).

Storage

Workload Optimization Manager represents storage as Datastores. A Datastore is a logical grouping of one or more physical storage devices that serve workload storage requirements.

Synopsis



A Datastore gains its budget by selling resources to the VMs it serves. If utilization of a Datastore is high enough, Workload Optimization Manager can recommend that you provision a new one.

Synopsis		
Provides:	Host resources for VMs to use, including: Storage Amount IOPS Latency	
Consumes:	Disk arrays (or aggregates)	
Discovered through:	Hypervisor and Storage Controller targets	

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Storage Amount
 - Storage Amount is the measurement of storage capacity that is in use.
- Storage Provisioned
 - Storage provisioned is the utilization of the entity's capacity, including overprovisioning.
- Storage Access (IOPS)

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

NOTE:

When it generates actions, Workload Optimization Manager does not consider IOPS throttling that it discovers on storage entities. Analysis uses the IOPS it discovers on Logical Pool or Disk Array entities.

Latency

Latency is the measurement of storage latency.



Storage Actions

Workload Optimization Manager can recommend the following actions:

Move

For high utilization of physical storage, move datastore to a different disk array (aggregate).

Provision

For high utilization of storage resources, provision a new datastore.

Resize

Increase or decrease the datastore capacity.

■ Start

For high utilization of storage resources, start a suspended datastore.

Suspend

For low utilization of storage resources, move served VMs to other datastores and suspend this one.

Delete

Delete a datastore or volume that has been suspended for a period of time.


Storage resize actions use Workload Optimization Manager tuned scaling settings. This gives you increased control over the action acceptance mode Workload Optimization Manager will use for the affected actions. For an overview of tuned scaling, see <u>Tuned Scaling for On-prem VMs (on page 448)</u>.

You can create placement policies to enforce constraints for storage move actions. For example, you can have a policy that allows storage to only move to certain disk arrays, or a policy that prevents storage from moving to certain disk arrays.

For more information, see <u>Creating Placement Policies (on page 673)</u>.

vSAN Storage

Overview



For environments that use hyperconverged infrastructure to provide storage on a vSAN, Workload Optimization Manager can discover the storage provided by a host cluster as a single Storage entity. This Storage entity represents the full storage capacity that is provided by that host cluster.

Workload Optimization Manager supports VMware vSAN, but does not support stretched VSAN clusters. Adding stretched clusters can cause the generation of incorrect storage recommendations and actions.

Workload Optimization Manager supports VMware vSAN.



vSAN Storage Capacity

When you consider vSAN capacity, you need to compare Raw Capacity with Usable Capacity.

- Raw Capacity
- Workload Optimization Manager discovers Raw Capacity configured in vCenter and uses it to calculate Usable Capacity.
 Raw Capacity displays in the Entity Information chart.
- Usable Capacity

Workload Optimization Manager calculates Usable Capacity and then uses the calculated value to drive scaling actions. Workload Optimization Manager can recommend scaling the Storage Amount, Storage Provisioned, or Storage Access capacity. Usable Capacity displays in the Capacity and Usage chart.

Usable Capacity Calculation

To calculate Usable Capacity, Workload Optimization Manager considers a variety of attributes, including:

- Raw Capacity and Largest Host Capacity
 - Workload Optimization Manager compares the Raw Capacity for all the hosts in the cluster and then uses the largest value as Largest Host Capacity.
- RAID Factor

Workload Optimization Manager calculates RAID Factor based on the *Failures to Tolerate* (FTT) value and *Redundancy Method* that it discovers. FTT specifies how many failures a given cluster can tolerate, while Redundancy Method specifies the RAID level for the cluster.

FTT	Redundancy Method	RAID Factor
0	RAID1	1
1	RAID1	1/2
2	RAID1	1/3
1	RAID5/6	3/4
2	RAID5/6	2/3

NOTE:

If discovery fails for some reason, Workload Optimization Manager uses a RAID Factor of 1.

Host Capacity Reservation, Slack Space Percentage, and Compression Ratio

You can control the values for these attributes in storage policies. For details about these attributes and their effect on usable capacity calculations, see Hyper-converged Infrastructure Settings (on page 497).

The calculation for Usable Capacity can be expressed as:

```
Usable Capacity = (Raw Capacity - Largest Host Capacity * Host Capacity Reservation) * Slack Space Perce ntage * RAID Factor * Compression Ratio
```

If the result of the calculation is zero or a negative value, Workload Optimization Manager sets the Usable Capacity to 1 MB.

Capacity and Usage Chart for vSAN Storage

The **Capacity and Usage** chart for vSAN storage shows two Storage Amounts - *Consumed* (bought) and *Provided* (sold). This is because vSAN storage can buy and sell commodities to hosts.

For the Provided Storage Amount, the Capacity value corresponds to Usable Capacity, while the Used value indicates utilization.

Entity Information Chart for vSAN Storage

The Entity Information chart includes the following information:

■ HCI Technology Type



The technology that supports this storage cluster. For this release, Workload Optimization Manager supports VMware vSAN technology.

Capacity

Workload Optimization Manager displays rounded values for the following, which might be slightly different from the values it discovers from vCenter:

- Raw Capacity
 - The sum of the Raw Capacity that each storage capacity device provides.
- Raw Free Space
 - How much of the Raw Capacity is not currently in use.
- Raw Uncommitted Space
 - In terms of Raw Capacity, how much space is available according to your thin/thick provisioning.
- Redundancy Method and Failures to Tolerate

Redundancy Method specifies the RAID level employed for the cluster. RAID level impacts how much Usable Capacity you can see for a given Raw Capacity. You can use a RAID calculator to determine how the RAID level impacts your Usable Capacity.

Failures to Tolerate specifies how many capacity device failures a given cluster can tolerate. In practical terms, this means how many hosts can come down at the same time, without affecting storage. This value should match the RAID level.

Actions to Add vSAN Capacity

To scale up storage amount, you add additional hosts that are configured to include their storage in the vSAN array.

When you scope the session to the vSAN storage, you can see actions to scale:

- Storage Amount
- Storage Provisioned
- Storage Access

The action to scale up the storage indicates the amount of storage you need to add. It appears as a recommended action. In fact, to add storage you must add a new host.

When you scope the session to hosts that provide the capacity devices to the storage, you can see the following actions that are related to scaling up the storage capacity:

- Scale up StorageAmount for Storage [MyVsanStorageCluster]
- Provision Host [VSAN_HostName]

The action to provision a host includes details about the storage cluster. Because you need to manually add hosts to your onprem environment, this appears as a recommended action.

Planning With vSAN Storage

For *Hardware Replace* and *Custom* plans, you can use HCl Host templates to add vSAN capacity. These represent the hosts that add storage capacity to a vSAN cluster. For more information, see HCl Host Template Settings (on page 713).

Under certain circumstances, *Add Virtual Machines* plans can fail to place workloads, or it can fail to generate actions to increase storage capacity by provisioning new hosts.

- If you scope the plan to a user-created group that only provides vSAN storage, or to a discovered storage cluster group, then the plan can fail to place VMs with multiple volumes. This can occur for VMs that use conventional storage (not vSAN) along with vSAN storage.
- If you scope the plan to a vSAN host group and add VMs, the plan can fail to increase storage capacity by provisioning new hosts. For example, assume you scope the plan to a vSAN host group and add 20 VMs to the environment. In that case, you need hosts to provide compute capacity for the VMs, and you also need hosts to provide storage capacity. The plan can represent the compute provisioning correctly, but it can incorrectly fail to add more storage capacity to the vSAN.
- If the vSAN RAID type is Raid6/FTT=2, if you scope the plan to any vSAN groups then the plan will fail to place any of the VMs.



Storage Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

The following are the storage actions and automation support for environments that do not include Disk Array Storage Controllers as targets. For details about these actions, see <u>Storage Actions (on page 492)</u>.

Action	Default Mode	vCenter	Hyper-V
Delete (Volume)	Recommend	Romd	Romd
Suspend	Manual	Romd	Remd
Delete (Datastore)	Disabled	Romd	Remd
Move	Recommend	Romd	Remd
Provision	Recommend	Remd	Remd
Start	Recommend	Remd	Remd
Resize (Up, Down, Above Max, or Below Min - using tuned scaling)	Recommend	Remd	Remd

For datastores on disk arrays:

Action	Default Mode	Dell Compellent	HP 3Par	NetApp ONTAP	VNX	VMAX	Nutanix	Pure Storage
Delete (Volume)	Recommend	Romd	Not supported	Remd	Romd	Romd	Remd	Romd
Suspend	Manual	Remd	Remd	Remd	Romd	Romd	Remd	Remd
Delete (Datastore)	Disabled	Remd	Not supported	Remd	Romd	Romd	Remd	Romd
Move	Recommend	Remd	Not supported	Remd	Romd	Remd	Remd	Remd
Provision	Recommend	Remd	Remd	Remd	Romd	Romd	Remd	Rcmd
Start	Recommend	Remd	Rcmd	Remd	Romd	Romd	Rcmd	Rcmd
Resize (Up, Down, Above Max, or Below Min - using tuned scaling)	Recommend	Remd	Remd	Remd	Remd	Remd	Remd	Remd

You can use Action Scripts for action orchestration.

For ServiceNow:

- Storage suspend and vSAN storage resize actions will not generate a CR.
- Currently Workload Optimization Manager can only execute a CR for storage provision actions on Pure and Dell Compellent storage.



Utilization Constraints

Utilization constraints affect the actions Workload Optimization Manager recommends as it manages your environment. Workload Optimization Manager recommends actions that avoid using these resources beyond the given settings. The values you set here specify what percentage of the existing capacity that Workload Optimization Manager will consider to be 100% of capacity.

Attribute	Default Value
Storage Amount Utilization	90
Storage Provisioned Utilization	100
IOPS Utilization	100
Latency Utilization	100

For example, setting 90 for Storage Amount Utilization means that Workload Optimization Manager considers 90% utilization of the physical storage to be 100% of capacity.

Storage Settings

Attribute	Default Setting/Value
Storage Overprovisioned Percentage	200
IOPS Capacity	50000
Storage Latency Capacity [ms]	100
Minimum Wasted Files [KB]	1000
Directories to Ignore	\.dvsData.* \.snapshot.* \.vSphere-HA.* \.naa.* \.etc.* lost\ +found.*
Files to Ignore	Empty String

Storage Overprovisioned Percentage

Storage Overprovisioned Percentage sets how much overprovisioning Workload Optimization Manager assumes when recommending actions for VM datastores. For example, if a datastore has a 30 GB capacity, and Storage Overprovisioned Percentage is set to 200, Workload Optimization Manager will treat the datastore as though it has a capacity of 60 GB, or 200% of the actual datastore capacity.

■ IOPS Capacity

IOPS Capacity is the IOPS setting for individual datastores. To set a specific capacity for one group of datastores, select that group as the property scope and override the global setting for that scope.

Note that IOPS capacity for a disk array takes precedence – Datastores that are members of a disk array always have the IOPS capacity that is set to the disk array.

Workload Optimization Manager considers these settings when calculating utilization percentage. For example, assume IOPS Capacity of 500 for datastores. If utilization on a datastore is 250 IOPS, then the datastore is at 50% of capacity for that metric.

Storage Latency Capacity

This sets the maximum storage latency to tolerate on a datastore, in ms. The default setting is 100 ms.

Workload Optimization Manager measures the latency experienced by all VMs and hosts that access the datastore. Assume a default setting of 100 ms. If a datastore exhibits latency of 50 ms, then the Workload Optimization Manager will show latency utilization of 50%.

For VMAX environments, Workload Optimization Manager discovers SLO for storage latency that you set in VMAX and uses it in analysis. However, if you set a higher storage latency value in a Workload Optimization Manager policy, analysis will use that value instead.

Minimum Wasted Files



You can make settings to control how Workload Optimization Manager tracks and reports on wasted storage in your environment. Wasted storage is any disk space devoted to files that are not required for operations of the devices or applications in your environment. Wasted storage may indicate opportunities for you to free up disk space, and provide more storage capacity to running VMs and applications.

If there are groups of datastores you don't want to track for wasted storage, set the given scope and disable datastore browsing there. If you prefer not to use Workload Optimization Manager resources to track wasted storage, leave the global setting checked.

The settings for **Directories to Ignore** and **Files to Ignore** specify directories and files that Workload Optimization Manager will not consider when looking for wasted data storage space. Separate items in these lists with the OR bar ("|").

Scaling Constraints

Rate of Resize

Workload Optimization Manager uses the Rate of Resize setting to determine how to make storage resize changes in a single action.

Attribute	Default Value
Rate of Resize	High (3)

Low

Change the value by one increment only.

Medium

Change the value by an increment that is 1/4 of the difference between the current value and the optimal value.

High

Change the value to be the optimal value.

This default value ensures that resizing to the desired state can be achieved in a single action. This is more efficient than smaller, incremental resizes.

Increment Constant for Storage Amount

This setting controls how many GB to add or subtract when resizing the allocation for a datastore.

Attribute	Default Value
Increment Constant for Storage Amount [GB]	100 GB

Hyperconverged Infrastructure Settings

Workload Optimization Manager considers these settings when calculating capacity and utilization for hyperconverged environments.

Attribute	Default Setting/Value
Host Capacity Reservation	1
Host IOPS Capacity	50000
Slack Space Percentage	25
Compression Ratio	1
Usable Space Includes Compression	Off

NOTE:

Workload Optimization Manager uses Host Capacity Reservation, Slack Space Percentage, and Compression Ratio to calculate vSAN usable capacity and drive scaling actions. For more information about usable capacity and how it is calculated, see <u>vSAN Storage (on page 492)</u>.

Host Capacity Reservation



When a host must be taken out of service for maintenance, vSphere will evacuate the data from that host and move it to other hosts in the cluster to maintain the integrity of the replication demanded by the storage policy. For this to happen, there must be enough free raw capacity available to accept the data being evacuated.

Workload Optimization Manager uses this setting to determine how many hosts worth of capacity it should subtract from the raw capacity amount before calculating usable capacity. This is not the same as redundancy. It does not specify how the array distributes data to maintain integrity.

Host IOPS Capacity

In addition to calculating usable capacity, Workload Optimization Manager needs an estimate of datastore IOPS capacity (storage access). Workload Optimization Manager uses the value that you set to provide an estimate of effective IOPS capacity for each host in the cluster. Total IOPS capacity is the number of hosts in the cluster multiplied by Host IOPS Capacity.

Slack Space Percentage

It is recommended that a vSAN datastore never be filled to prevent vSphere from moving objects/files around the cluster to balance the datastore across all the hosts.

Workload Optimization Manager reduces usable capacity by the percentage that you set.

Compression Ratio

vSAN supports both deduplication and compression, which may increase the amount of usable capacity on the datastore. Workload Optimization Manager does not try to predict the deduplication or compression ratio, but you can choose to include a compression ratio into the usable capacity calculation. This captures the ratio achieved both by compression and deduplication.

The compression ratio that you set acts as a multiplier on the raw capacity to calculate usable capacity. For example, a compression ratio of 2 would double the amount of usable capacity. The default value of 1 means no compression.

■ Usable Space Includes Compression

Turn this on if you want Workload Optimization Manager to consider the compression ratio when calculating storage utilization and capacity. Whether this is on or off, Workload Optimization Manager always considers compression when calculating utilization of StorageProvisioned.

Placement Policies

Workload Optimization Manager supports placement policies for storage and storage clusters.

- You can create placement policies to enforce constraints for storage move actions. For example, you can have a policy that allows storage to only move to certain disk arrays, or a policy that prevents storage from moving to certain disk arrays.
- You can create placement policies that merge multiple clusters into a single logical group for the purpose of workload placement.


For more information, see <u>Creating Placement Policies (on page 673)</u>.

Logical Pool

A logical pool represents storage resources that are managed together and presented as a single storage system. Workload Optimization Manager analysis identifies performance and efficiency opportunities for a logical pool. For example, it can recommend moving resources into or out of a logical pool, or aggregating resource capacity within the pool.



Synopsis



Synopsis	
Provides:	Storage resources
Consumes:	Disk array resources
Discovered through:	Storage targets

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Storage Amount
 - Storage Amount is the measurement of storage capacity that is in use.
- Storage Provisioned
 - Storage provisioned is the utilization of the entity's capacity, including overprovisioning.
- Storage Access (IOPS)
 - Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.
- Latency
 - Latency is the measurement of storage latency.

Logical Pool Actions

Workload Optimization Manager can recommend the following actions:

- Resize
- Provision
- Move
- Start



Suspend

Logical Pool Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

Action	Default Mode		
Suspend	Disabled		
Start	Disabled		
Resize	Recommend		
Move	Disabled		
Provision	Disabled		

Storage Settings

Attribute	Default Value
Storage Latency Capacity [ms]	100
Storage Overprovisioned Percentage	200
IOPS Capacity	50000

■ Storage Latency Capacity

This sets the maximum storage latency to tolerate on a logical pool, in ms. The default setting is 100 ms.

■ Storage Overprovisioned Percentage

Storage Overprovisioned Percentage sets how much overprovisioning Workload Optimization Manager assumes when recommending actions for logical pools.

■ IOPS Capacity

IOPS Capacity is the IOPS setting for individual logical pools.

NOTE:


Workload Optimization Manager discovers storage latency and IOPS capacities that you set in your environment (for example VMAX) and uses them in its analysis. These capacities will be overridden by values that you set in Workload Optimization Manager policies.

Disk Array

A Disk Array (an aggregate) is a data storage system made up of multiple disk drives. For example, a RAID is an aggregate that implements redundancy and other data management features. A disk array provides storage volumes to serve the storage requirements of physical machines. It uses the resources of one storage controller, which manages the disk array operation.



Synopsis



Synopsis	
Provides:	Storage resources for datastores to use, including: Storage Amount Storage Provisioned IOPS (storage access operations per second) Latency (capacity for disk latency in ms)
Consumes from:	Storage Controllers
Discovered through:	Storage Controller targets

Monitored Resources

Workload Optimization Manager monitors the following resources:

NOTE:

Not all targets of the same type provide all possible commodities. For example, some storage controllers do not expose CPU activity. When a metric is not collected, the corresponding chart in the user interface will not display data.

- Storage Amount
 - Storage Amount is the measurement of storage capacity that is in use.
- Storage Provisioned
 - Storage provisioned is the utilization of the entity's capacity, including overprovisioning.
- Storage Access (IOPS)
 - Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.
- Latency
 - Latency is the measurement of storage latency.

Disk Array Actions

Workload Optimization Manager can recommend the following actions:

Provision



For high utilization of the disk array's storage, provision a new disk array. This action can only be executed outside Workload Optimization Manager.

Start

For high utilization of disk array, start a suspended disk array. This action can only be executed outside Workload Optimization Manager.

Suspend

For low utilization of the disk array's storage, move VMs to other datastores and suspend volumes on the disk array. This action can only be executed outside Workload Optimization Manager.

Move

(Only for NetApp Cluster-Mode) For high utilization of Storage Controller resources, Workload Optimization Manager can move an aggregate to another storage controller. The storage controllers must be running.

For high IOPS or latency, a move is always off of the current disk array. All the volumes on a given disk array show the same IOPS and Latency, so moving to a volume on the same array would not fix these issues.

Move VM

For high utilization of Storage on a volume, Workload Optimization Manager can move a VM to another volume. The new volume can be on the current disk array, on some other disk array, or on any other datastore.

For high IOPS or latency, a move is always off of the current disk array. All the volumes on a given disk array show the same IOPS and Latency, so moving to a volume on the same array would not fix these issues.

Move Datastore

To balance utilization of disk array resources, Workload Optimization Manager can move a datastore to another array.

Disk Array Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

The following table describes the default action acceptance modes for disk array actions and automation support for environments that have Disk Array Storage Controllers as targets.

Action	Default Mode	Dell Compellent	HP 3Par	NetApp ONTAP	VMAX	VNX	Nutanix	Pure Storage	XTremIO
Move	Disabled			Romd					
Provision	Recommend	Remd	Romd	Remd			Remd	Remd	
Resize (up)	Recommend	Rcmd	Romd	Romd	Romd	Romd	Remd	Romd	
Start	Recommend								
Suspend	Disabled								

Action Automation for NetApp Storage Systems

For NetApp storage systems, the actions Workload Optimization Manager can automatically perform depend on the NetApp version you are running, and whether the system is running in cluster mode:

Automated Action	Cluster-Mode
Move VM between datastores, on the same disk array	Yes
Move VM between datastores on different disk arrays	Yes



Automated Action	Cluster-Mode
Move Datastore between disk arrays on the same storage controller	Yes
Move Datastore between disk arrays on different storage controllers	Yes
Resize Storage	Yes
Resize Disk Array	No – Resize up, only

In addition, for a system running in Cluster-Mode, Workload Optimization Manager can recommend moving an aggregate to another storage controller.

Utilization Constraints

Utilization constraints affect the actions Workload Optimization Manager recommends as it manages your environment. Workload Optimization Manager recommends actions that avoid using these resources beyond the given settings. The values you set here specify what percentage of the existing capacity that Workload Optimization Manager will consider to be 100% of capacity.

Attribute	Default Value
Storage Amount Utilization	90

Storage Settings

Set capacity for specific storage resources.

Attribute	Default Value
IOPS Capacity	5000
A generic setting for disk array IOPS capacity (see Disk Array IOPS Capacity below).	
VSeries LUN IOPS Capacity	5000
7.2k Disk IOPS Capacity	800
10k Disk IOPS Capacity	1200
15k Disk IOPS Capacity	1600
SSD Disk IOPS Capacity	50000
Disk Array IOPS Capacity	10000
Storage Overprovisioned Percentage	200
Storage Latency Capacity [ms]	100

NOTE:

Workload Optimization Manager discovers storage latency and IOPS capacities that you set in your environment (for example VMAX) and uses them in its analysis. These capacities will be overridden by values that you set in Workload Optimization Manager policies.

■ IOPS Capacity

The capacity of IOPS (IO operations per second) that your storage devices can support. Workload Optimization Manager considers these settings when calculating utilization percentage. For example, assume IOPS Capacity of 5000 for a disk array. If utilization on the array is 2500 IOPS, then the disk array is at 50% of capacity for that metric.



Note that the IOPS setting for an array will determine IOPS calculations for all the storage on that array. If you made different IOPS settings for individual datastores hosted by the array, Workload Optimization Manager ignores the datastore settings and uses the disk array settings.

Various Disk IOPS Capacity settings (SSD Disk IOPS, 7.2k Disk IOPS, etc)

IOPS capacity settings for the different types of physical drives that are discovered on a disk array. If the storage controller exposes the types of disks in the array, Workload Optimization Manager uses multiples of these values to calculate the IOPS capacity of the disk array.

Disk Array IOPS Capacity

Some disk arrays do not expose data for their individual disks — This is typical for flash arrays, or arrays that aggregate storage utilization across multiple tiers. Workload Optimization Manager uses this setting for the IOPS capacity of such disk arrays. Set it to the global scope to specify IOPS capacity for all disk arrays. To override this setting, set a disk array or group of disk arrays as the property scope, and then set the value you want for **IOPS Capacity**.

NOTE:

The user interface shows a disk array entity for any array that is discovered through a valid disk array or storage controller target. It also shows *placeholder* disk arrays for disk arrays that are not discovered through a configured target. For example, you might have disk arrays that Workload Optimization Manager does not natively support. Or you might have storage that is not hosted by any disk array. Such *placeholder* disk array entities appear with the string "DiskArray-" prefixed to their names. The user interface allows you to set IOPS Capacity to these placeholders, but those settings have no effect. To set IOPS Capacity for that storage, you must set it to the individual datastores.

■ Storage Overprovisioned Percentage


This setting indicates how much overprovisioning Workload Optimization Manager assumes when recommending actions for disk arrays. For example, if a disk array has a 30 TB capacity, and Storage Overprovisioned Percentage is set to 200, Workload Optimization Manager will treat the datastore as though it has a capacity of 60 TB, or 200% of the actual disk array capacity.

If the disk array is returning good Data Reduction Rates (DRR) in excess of the Storage Overprovisioned Percentage, actions to provision disk array may be generated. Consider increasing the percentage upwards closer to the real DRR. For example, if DRR is 12 to 1, the percentage could be closer to 1200.

Storage Controller

A Storage Controller is a device that manages one or more disk arrays. The storage controller provides CPU cycles to perform storage management tasks for each disk array it manages.

Synopsis



A storage controller gains its budget by selling resources to the disk arrays it manages. If utilization of the storage controller's CPU resources is high enough, Workload Optimization Manager can recommend that you provision a new one and move disk arrays (aggregates) to it.

Synopsis	
Provides:	CPU resources to manage disk arrays.
Consumes:	NA
Discovered through:	Workload Optimization Manager directly accesses storage controller targets.



Monitored Resources

Workload Optimization Manager monitors the following resources:

■ CPU

CPU is the measurement of CPU that is reserved or in use.

Storage Amount

Storage Amount is the measurement of storage capacity that is in use.

NOTE:

In NetApp environments, the storage controller shows 100% utilization when there are no more disks in a SPARE state that the storage controller can utilize in an aggregate. This does not indicate that the storage controller has no capacity.

Actions

Workload Optimization Manager can recommend the following actions:

Provision

For high utilization of the storage controller's CPU, provision a new storage controller, and then move disk arrays to it.

Storage Controller Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

Actions for individual Disk Array Storage Controllers:

Action	Default Mode	Dell Compellent	HP 3Par	NetApp ONTAP	VNX	VMAX	Nutanix	Pure Storage	XTremIO
Provision	Disabled	Remd	Rcmd	Remd	Remd	Remd	Rcmd	Remd	Remd

Utilization Constraints

Utilization constraints affect the actions Workload Optimization Manager recommends as it manages your environment. Workload Optimization Manager recommends actions that avoid using these resources beyond the given settings. The values you set here specify what percentage of the existing capacity that Workload Optimization Manager will consider to be 100% of capacity.

Attribute	Default Value	
Storage Amount Utilization	90	
	Maximum allowed utilization of storage that is managed by the Storage Controller.	
CPU Utilization	100	
	Maximum allowed utilization of Storage Controller CPU (from 20 to 100).	

Storage Settings

Set capacity for specific storage resources.

Attribute	Default Value
IOPS Capacity	5000
Storage Latency Capacity [ms]	100




10 Module

An IO Module connects the compute resources on a chassis to the fabric domain via the Fabric Interconnect. It provides the servers on the chassis with Net resources. Typical installations provide two IO Modules per chassis.

Workload Optimization Manager supports IO Modules when you have installed the Fabric Control Module license.

Synopsis



Synopsis	
Provides:	Net resources
Consumes from:	Chassis and Fabric Interconnect
Discovered through:	Fabric Manager targets

Monitored Resources

Workload Optimization Manager monitors the following resources:

Net Throughput

Net Throughput is the rate of message delivery over a port.

Actions

None


Workload Optimization Manager does not recommend actions for an IO Module.

Switch

A switch connects servers in a computing fabric to the fabric's network and storage resources. It provides network bandwidth to the servers in the platform.



Synopsis



Synopsis	
Provides:	Net resources
Consumes:	N/A
Discovered through:	Fabric Manager targets (such as UCS)

Monitored Resources

Workload Optimization Manager monitors the following resources:

- Net Throughput
 - Net Throughput is the rate of message delivery over a port.
- PortChannel

PortChannel is the amalgamation of ports with a shared net throughput and utilization.

Actions

Workload Optimization Manager can recommend the following actions:

Resize

Resize PortChannel for a switch to increase bandwidth.

Switch Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

Action Automation and Orchestration

For environments that have Fabric Managers as targets:

Action	Default Mode	Cisco UCS
Resize	Recommend	Romd
Start	Recommend	Remd



Action	Default Mode	Cisco UCS
Provision	Recommend	Remd
Suspend	Disabled	Romd
Move	Disabled	Romd


Utilization Constraints

Utilization constraints affect the actions Workload Optimization Manager recommends as it manages your environment. Workload Optimization Manager recommends actions that avoid using these resources beyond the given settings. The values you set here specify what percentage of the existing capacity that Workload Optimization Manager will consider to be 100% of capacity.

Attribute	Default Value
Switch Net Throughput	70

Workload Optimization Manager Actions

After you deploy your targets, Workload Optimization Manager starts its analysis of your environment. This holistic analysis identifies problems and the actions you can take to *resolve* and *avoid* these problems. Workload Optimization Manager then generates a set of actions for that particular analysis and displays it in Action Center for you to investigate.



To get the best results from Workload Optimization Manager, execute these actions promptly and consider automating as many of them as possible. You can execute these actions from the user interface or outside Workload Optimization Manager. To automate these actions, create an <u>automation policy (on page 680)</u> or change action acceptance to *Automatic* in the <u>default policies (on page 678)</u>.


At first glance, individual actions might appear trivial and it is instinctively convenient to ignore them. It is important to keep in mind that executing a single action can impact other workloads in a meaningful way, helping move these other workloads closer to their desired state. However, if you find that a recommended action is not acceptable (for example, if it violates existing business rules), you can set up a policy with your preferred action.

In some cases, actions can introduce disruptions that you want to avoid at all costs. For example, during critical hours, Workload Optimization Manager might execute a resize action on a mission critical resource, which then requires that resource to restart. It is important to anticipate these disruptions and plan accordingly. For example, you can create a group for all critical resources and then schedule the execution of actions to off-peak hours or weekends.



Working With Action Center


When you start using Workload Optimization Manager, all the actions that the product generates appear as pending. Use Action Center to review and execute pending actions.



Viewing Action Center

Action Center displays in areas of the product that reference actions, providing a consistent view and experience. Here are some ways you can view Action Center.


The Action button on the main menu provides easy access to all the current pending actions.



Action Center in this view is its own dedicated page. Bookmark the page or share it with interested parties.

■ To focus on actions for a specific entity type, click the entity type in the supply chain, and then click the **Actions** tab.






You can launch Action Center from action-focused charts, such as the Pending Actions, Top Utilized, and Potential Savings charts.




After you run a plan (on page 531), click an Actions tab to open Action Center.






Action Center Features


Action Center provides a comprehensive view of actions. The following features are available to help you work with actions with ease.

















Action Handling

Workload Optimization Manager will never execute actions automatically, unless you tell it to. If you examine the default policies that ship with the product, you will notice that these policies do not enable automation on any action. Workload Optimization Manager gives you full control over all automation decisions.



At first, your goal may be to evaluate all the actions in Action Center and then execute those that result in immediate improvements in performance and resource utilization. Over time, you develop and fine-tune your action-handling process to meet productivity goals and respond to changing business needs. This process could lead to the following key decisions:

Disabling actions that should never execute, such as those that violate business rules



- Workload Optimization Manager will not consider recommending disabled actions when it performs its analysis.
- Allowing certain actions to execute automatically, such as those that assure performance on mission-critical resources Automation simplifies your task, while ensuring that workloads continue to have adequate resources to perform optimally. As such, it is important that you set the goal of automating as many actions as possible. This requires evaluating which actions are safe to automate, and on which entities.
- Continuing to let Workload Optimization Manager post certain actions so you can execute them on a case-by-case basis For example, certain actions might require the approval of specific individuals. In this case, you would want Workload Optimization Manager to post those actions for review and only execute the actions that receive an approval.
 - These are the actions that you would look for in Action Center. These actions stop showing after you execute them, if you disable or automate them, or if the environment changes in the next market analysis such that the actions are no longer needed.

Action Details

The Action Details page provides a comprehensive set of information to help you understand why Workload Optimization Manager recommends an action and what you would gain if you execute it.




The Action Details page for a specific action has a unique URL (or deep link) that you can share with interested parties. To get the URL, click the 'share' icon at the top-right section of the page and then copy the URL displayed in the address bar of the new tab.



Utilization Charts

Workload Optimization Manager uses percentile calculations to measure resource utilization more accurately, and drive actions that improve overall utilization and reduce costs for cloud workloads. When you examine the details for an entity or pending action, you will see charts that highlight resource utilization percentiles for a given observation period, and the projected percentiles after you execute the action.





The charts also plot *daily average utilization* for your reference. If you have previously executed scaling actions on the entity, you can see the resulting improvements in daily average utilization. Put together, these charts allow you to easily recognize utilization trends that drive Workload Optimization Manager's recommendations.

Notes:

- You can set constraints in policies to refine the percentile calculations.
- After you execute an action, it might take some time for the charts to reflect the resulting improvements.

Entities with Utilization Charts

Utilization charts display for actions on the following entity types:

Entity Type	Monitored Resources		Notes	
Entity Type	Percentile Utilization	Average Utilization		
Virtual Machine	■ vCPU ■ vMem	■ vCPU ■ vMem	For on-prem VMs, you will see either a VCPU or VMem chart, depending on the commodity that needs to scale. For cloud VMs and VMs in Migrate to Cloud plans, both charts display.	
			These charts also appear when you scope to a given VM (on-prem or cloud) and view the Details page. They also appear in Migrate to Cloud plan results.	
Virtual Machine Spec	■ vCPU ■ vMem	vCPUvMemStorageNumber of replicas	See <u>Virtual Machine Spec</u> <u>Actions (on page 404)</u> .	
Database (cloud)	■ DTU Pricing Model - DTU • vCore Pricing Model - vCPU - vMem - IOPS - Throughput	■ DTU Pricing Model - DTU - Storage • vCore Pricing Model - vCPU - vMem - IOPS	See Cloud Database Actions (on page 434).	



Entity Type	Monitored Resources		Notes
Entity Type	Percentile Utilization	Average Utilization	
		ThroughputStorage	
Database Server (cloud)	■ vCPU ■ vMem ■ IOPS	■ vCPU ■ vMem ■ IOPS	See Cloud Database Server Actions (on page 413).
Volume (cloud)	■ IOPS ■ Throughput	■ IOPS ■ Throughput	These charts also appear when you scope to a given volume and view the Details page. See Cloud Volume Actions
Workload Controller	 vCPU limits and requests vMem limits and requests 	 vCPU limits, throttling, and requests vMem limits and requests 	(on page 425). See Container Actions (on page 346).

Action Details - vCPU Resizes for On-prem VMs

The Action Details page provides a comprehensive set of information to help you understand why Workload Optimization Manager recommends a vCPU resize down action and the impact of this action on the VM and its host.

Actions to resize down vCPU can result in significant performance improvements in environments where CPU Ready on virtualization hosts is high.






Addressing CPU Ready Issues by Resizing Down vCPU

CPU Ready is a measurement of how long a VM is waiting for access to the host's physical CPU. In VMware environments, a CPU Ready value of 5% (or 1000 milliseconds) is considered a performance risk for general purpose VMs. As the VM and its application increase in priority/performance requirements, the acceptable CPU Ready value decreases.

To identify risks related to CPU Ready in your environment, add the Top Clusters by Utilization chart to your dashboard and then sort the chart data by CPU Ready.



As you examine the pending actions for these clusters, check for actions to resize down VM vCPU and then prioritize them for execution. These actions offer the greatest opportunity to resolve CPU Ready issues.

Actions by Entity Type

Workload Optimization Manager generates actions based on how entity types use or provide resources, and what each entity type supports.

The following tables show the actions that each entity type supports:

Application Entity Types

Entity Type	Supported Actions	
Business Application	None	
	Workload Optimization Manager does not recommend actions for a Business Application, but it does recommend actions for the underlying Application Components and infrastructure. The Pending Actions chart for a Business Application lists these actions, thus providing visibility into the risks that have a direct impact on the Business Application's performance.	
Business Transaction	None Workload Optimization Manager does not recommend actions for a Business Transaction, but it does recommend actions for the underlying Application Components and infrastructure. The Pending Actions chart for a Business Transaction lists these actions, thus providing visibility into the risks that have a direct impact on the Business Transaction's performance.	
Service	For APM Services:	
	None	



Entity Type	Supported Actions			
	Workload Optimization Manager does not recommend actions for Services discovered via APM targets, but it does recommend actions for the underlying Application Components and nodes. The Pending Actions chart for Services list these actions, thus providing visibility into the risks that have a direct impact on their performance.			
	For Kubernetes Services:			
	None			
	Workload Optimization Manager does not recommend actions for Kubernetes Services, but it does recommend actions for the replicas that back those Services.			
	For details, see Workload Controller Scale Actions (on page 356).			
Application Component	Resize			
	Resize the following resources to maintain performance:			
	■ Thread Pool			
	Workload Optimization Manager generates thread pool resize actions. These actions are recommend-only and can only be executed outside Workload Optimization Manager.			
	■ Connections			
	Workload Optimization Manager uses connection data to generate memory resize actions for on-prem Database Servers.			
	■ Heap			
	Workload Optimization Manager generates Heap resize actions if an Application Component provides Heap and Remaining GC Capacity, and the underlying VM or container provides VMem. These actions are recommend-only and can only be executed outside Workload Optimization Manager.			
	NOTE:			
	Remaining GC capacity is the measurement of Application Component uptime that is <i>not</i> spent on garbage collection (GC).			
	The resources that Workload Optimization Manager can resize depend on the processes that it discovers from your Applications and Databases targets. Refer to the topic for a specific target to see a list of resources that can be resized.			

Container Platform Entity Types

Entity Type	Supported Actions
Service	None
	Workload Optimization Manager does not recommend actions for Kubernetes Services, but it does recommend actions for the replicas that back those Services.
	For details, see Workload Controller Scale Actions (on page 356).
Container	None
	Workload Optimization Manager does not recommend actions on containers.
Container Spec	Resize (via Workload Controllers)
	A Container Spec retains the historical utilization data of ephemeral containers. Workload Optimization Manager uses this data to make resize decisions that assure optimal utilization of resources. By default, all replicas of the same container for the same workload type resize consistently.
	For details, see Workload Controller Resize Actions (on page 352).
Namespace	Resize Quota



Entity Type	Supported Actions
	Workload Optimization Manager treats quotas defined in a namespace as constraints when making resize decisions. If existing actions would exceed the namespace quotas, Workload Optimization Manager recommends actions to resize up the affected namespace quota.
	Note that Workload Optimization Manager does not recommend actions to resize down a namespace quota. Such an action reduces the capacity that is already allocated to an application. The decision to resize down a namespace quota should include the application owner.
	For details, see Namespace Actions (on page 366).
Workload Controller	Resize or Scale
	Actions associated with a Workload Controller resize Container Specs vertically or scale replicas horizontally. This is a natural representation of these actions because the parent controller's Container Specs and number of replicas are modified. The Workload Controller then rolls out the changes in the running environment.
	For details, see <u>Workload Controller Resize Actions (on page 352)</u> and <u>Workload Controller Scale Actions (on page 356)</u> .
Container Pod	■ Move
	Move a pod between nodes (VMs) to address performance issues or improve infrastructure efficiency. For example, if a particular node is congested for CPU, you can move pods to a node with sufficient capacity. If a node is underutilized and is a candidate for suspension, you must first move the pods before you can safely suspend the node.
	■ Provision/Suspend When recommending node provision or evappend actions. Workload Optimization
	When recommending node provision or suspend actions, Workload Optimization Manager will also recommend provisioning pods (based on demand from DaemonSets) or suspending the related pods.
	For details, see Container Pod Actions (on page 361).
Container Cluster	None
	Workload Optimization Manager does not recommend actions for a Container Cluster. Instead, it recommends actions for the containers, pods, nodes (VMs), and volumes in the cluster. Workload Optimization Manager shows all of these actions when you scope to a Container Cluster and view the Pending Actions chart.
Kubernetes node (VM)	A Kubernetes node (cloud or on-prem) is represented as a Virtual Machine entity in the supply chain.
	■ Provision
	Provision nodes to address workload congestion or meet application demand. Suspend
	Suspend nodes after you have consolidated pods or defragmented node resources to improve infrastructure efficiency.
	■ Reconfigure Reconfigure nodes that are currently in the NotReady state.
	NOTE:
	For nodes in the public cloud, Workload Optimization Manager reports the cost savings or investments attached to these actions.
	For details, see Node Actions (on page 373).



Cloud Infrastructure Entity Types

Entity Type	Supported Actions
Virtual Machine (Cloud)	For details about cloud VM actions, see the following topics: Actions for AWS VMs (on page 381) Actions for Azure VMs (on page 383) Actions for GCP VMs (on page 385)
Virtual Machine Spec	 Scale Scale Azure App Service plans to optimize app performance or reduce costs, while complying with business policies. Delete Delete empty Azure App Service plans as a cost-saving measure. A plan is considered empty if it is not hosting any running apps.
	For details, see <u>Virtual Machine Spec Actions (on page 404)</u> .
App Component Spec	None Workload Optimization Manager does not recommend actions for App Component Specs, but it does recommend actions for the underlying Virtual Machine Specs. For details, see Virtual Machine Spec Actions (on page 404).
Database (Cloud)	Scale (SQL Database) ■ DTU Pricing Model Scale DTU and storage resources to optimize performance and costs. ■ vCore Pricing Model Scale vCPU, vMem, IOPS, throughput and storage resources to optimize performance and costs. Suspend (Dedicated SQL Pool) Suspend an idle dedicated SQL pool (used for Azure Synapse Analytics) to reduce compute costs. NOTE: Currently, Workload Optimization Manager does not generate actions to start a suspended pool. You can manually start a pool from Azure. For details, see Cloud Database Actions (on page 434).
Database Server (Cloud)	 Stop and Start (also known as 'parking' actions) Stop a Database Server for a given period of time to reduce your cloud expenses and then start it at a later time. Scale Scale compute and storage resources to optimize performance and costs. For details, see Cloud Database Server Actions (on page 413) and Parking: Stop or Start Cloud Resources (on page 597).
Volume (Cloud)	 Scale Scale attached volumes to optimize performance and costs. Delete Delete unattached volumes as a cost-saving measure. Workload Optimization Manager generates an action immediately after discovering an unattached volume. For details, see Cloud Volume Actions (on page 425).
Zone	None



Entity Type	Supported Actions
	Workload Optimization Manager does not recommend actions for a cloud zone.
Region	None

On-prem Infrastructure Entity Types

Entity Type	Supported Actions
Virtual Machine (On-prem)	■ Resize
	Resize resource capacity, reservation, or limit to improve performance. Resize PU / Resize VP (IBM PowerVM)
	Resize PU (processing units) or VP (virtual processor) to optimize LPAR processing unit allocation and virtual processor capacity based on historical demand collected from the HMC. Move
	Move a VM due to high resource utilization on VM or host, excess IOPS or latency in VStorage, workload placement violation, underutilized host (move VM before suspending host).
	■ Reconfigure
	Change a VM's configuration to comply with a policy.
	For hypervisor targets, Workload Optimization Manager can reconfigure VMs that violate vCPU scaling policies. For details, see VCPU Scaling Controls (on page 457) .
	For details, see On-prem VM Actions (on page 447).
Volume (On-prem)	■ Move
	Move a VM's volume (virtual storage) due to excess utilization of the current datastore, or for more efficient utilization of datastores in the environment.
	Points to consider:
	 The default global policy includes a setting that directs Workload Optimization Manager to use relevant metrics when analyzing and recommending actions for volumes. For details, see <u>Enable Analysis of On-prem Volumes</u> (on page 679).
	 Workload Optimization Manager will not recommend moving a volume to a datastore that is currently in maintenance mode. Any volume in that datastore should move to an active datastore (for example, via vMotion).
	■ Reconfigure
	Reconfigure a VM's volume (virtual storage) to comply with placement policies.
Database Server (On-prem)	Resize
	Resize the following resources:
	Connections
	Workload Optimization Manager uses connection data to generate memory resize actions for on-prem Database Servers. • Database memory (DBMem)
	Actions to resize database memory are driven by data on the Database Server, which is more accurate than data on the hosting VM. Workload Optimization Manager uses database memory and cache hit rate data to decide whether resize actions are necessary.



Entity Type	Supported Actions
	A high cache hit rate value indicates efficiency. The optimal value is 100% for on- prem (self-hosted) Database Servers, and 90% for cloud Database Servers. When the cache hit rate reaches the optimal value, no action generates even if database memory utilization is high. If utilization is low, a resize down action generates.
	When the cache hit rate is below the optimal value but database memory utilization remains low, no action generates. If utilization is high, a resize up action generates.
	■ Transaction log
	Resize actions based on the transaction log resource depend on support for virtual storage in the underlying hypervisor technology.
	Currently, Workload Optimization Manager does not support resize actions for Oracle and Database Servers on the Hyper-V platform (due to the lack of API support for virtual storage).
Virtual Data Center	None
	Workload Optimization Manager does not recommend actions for a Virtual Data Center. Instead, it recommends actions for the entities that provide resources to the Virtual Data Center.
Business User	Move
	Move a Business User between desktop pools to address:
	 Resource congestion on the image
	When utilization is consistently near capacity for image resources, Workload Optimization Manager can recommend moving a Business User to a desktop pool that serves larger images.
	 Resource congestion on the desktop pool
	When utilization is consistently near capacity for the desktop pool, Workload Optimization Manager can recommend moving a Business User to a desktop pool that has more available resources.
	NOTE:
	To support moves, you must configure placement policies that merge <i>similarly</i> configured desktop pools. For details, see <u>Desktop Pool Placement Policies (on page 480)</u> .
Desktop Pool	None
	Workload Optimization Manager does not recommend actions for a desktop pool. It recommends actions for the Business Users running active sessions in the pool.
View Pod	None
	Workload Optimization Manager does not recommend actions for a view pod. Instead, it recommends actions for the Business Users that are running active sessions.
Host	■ Start
	Start a suspended host when there is increased demand for physical resources.
	■ Provision
	Provision a new host in the environment when there is increased demand for physical resources. Workload Optimization Manager can then move workloads to that host.
	■ Suspend
	When physical resources are underutilized on a host, move existing workloads to other hosts and then suspend the host.
	■ Reconfigure



Entity Type	Supported Actions
	Workload Optimization Manager generates this action in response to changing demand for software licenses. For details, see <u>License Policy (on page 676)</u> .
	For details, see <u>Host Actions (on page 484)</u> .
Chassis	None
	Workload Optimization Manager does not recommend actions for a chassis.
Data Center	None
	Workload Optimization Manager does not recommend actions for a data center. Instead, it recommends actions for the entities running in the data center.
Storage	■ Move
	For high utilization of physical storage, move datastore to a different disk array (aggregate). Provision
	For high utilization of storage resources, provision a new datastore. Resize
	Increase or decrease the datastore capacity. Start
	For high utilization of storage resources, start a suspended datastore. Suspend
	For low utilization of storage resources, move served VMs to other datastores and suspend this one.
	■ Delete
	Delete a datastore or volume that has been suspended for a period of time. For details, see <u>Storage Actions (on page 492)</u> .
Logical Pool	■ Resize
	■ Provision
	■ Move ■ Start
	■ Start ■ Suspend
Disk Array	■ Provision
DISK ATTAY	For high utilization of the disk array's storage, provision a new disk array. This action can only be executed outside Workload Optimization Manager.
	For high utilization of disk array, start a suspended disk array. This action can only be executed outside Workload Optimization Manager.
	■ Suspend
	For low utilization of the disk array's storage, move VMs to other datastores and suspend volumes on the disk array. This action can only be executed outside Workload Optimization Manager.
	■ Move
	(Only for NetApp Cluster-Mode) For high utilization of Storage Controller resources, Workload Optimization Manager can move an aggregate to another storage controller. The storage controllers must be running.
	For high IOPS or latency, a move is always off of the current disk array. All the volumes on a given disk array show the same IOPS and Latency, so moving to a volume on the same array would not fix these issues. Move VM



Entity Type	Supported Actions
	For high utilization of Storage on a volume, Workload Optimization Manager can move a VM to another volume. The new volume can be on the current disk array, on some other disk array, or on any other datastore.
	For high IOPS or latency, a move is always off of the current disk array. All the volumes on a given disk array show the same IOPS and Latency, so moving to a volume on the same array would not fix these issues.
	■ Move Datastore
	To balance utilization of disk array resources, Workload Optimization Manager can move a datastore to another array.
Storage Controller	Provision
	For high utilization of the storage controller's CPU, provision a new storage controller, and then move disk arrays to it.
IO Module	None
	Workload Optimization Manager does not recommend actions for an IO Module.
Switch	Resize
	Resize PortChannel for a switch to increase bandwidth.

Action Categories

Workload Optimization Manager groups entries in the Actions List by different categories. These categories do not strictly define the severity of an issue, but they indicate the nature of the issue.

Compliance

A virtual environment can include policies that limit availability of resources. It's possible that the environment configuration violates these defined policies. In such cases, Workload Optimization Manager identifies the violation and recommends actions that bring the entity back into compliance.

Efficiency

Efficient utilization of resources is an important part of running in the desired state. Running efficiently maximizes your investment and reduces cost. When Workload Optimization Manager discovers underutilized resources, it recommends actions to consolidate your operations. For example, it can recommend that you move certain VMs onto a different host, and then suspend the original host.

Performance

Ultimately, the reason to manage workloads in your environment is to assure performance and meet productivity goals. Workload Optimization Manager can recommends actions when it detects conditions that directly put performance at risk. You can consider these critical conditions, and you should execute the recommended actions as soon as possible.

Prevention

Workload Optimization Manager constantly monitors conditions, and works to keep your environment running in a desired state. As it finds issues that risk moving the environment out of this state, it recommends preventive actions. You should attend to these issues, and perform the associated actions. If you do not, the environment may drift away from the desired state, and performance may be put at risk.



Action Types

Workload Optimization Manager performs the following general types of actions:

- Buy Purchase cloud instances at a <u>discounted (on page 113)</u> rate to reduce on-demand costs
- Delete Remove unused entities (for example, datastores on disk arrays or unattached volumes)
- Move Move an entity from one provider to another to address performance issues or improve infrastructure efficiency
- Optimization Increase discount coverage for cloud workloads to reduce on-demand costs
- Provision Add resource providers to the environment to increase capacity
- Reconfigure Correct a misconfiguration to bring an entity into compliance
- Scale/Resize Change the resources allocated to workloads to meet demand
- Start Start a stopped/suspended entity
- Stop/Suspend Pause an entity for a period of time to increase efficient use of resources

For information on the actions that Workload Optimization Manager generates for specific entities, see <u>Actions by Entity Type</u> (on page 518).

Placement

Placement actions determine the best provider for a consumer. These include initial placement for a new entity, and move actions that change a consumer to use a different provider. For example, moving a VM assigns it to a different host. Moving a VM's storage means the VM will use a different datastore.

Placement Constraints

When making placement decisions, Workload Optimization Manager checks for placement constraints to limit the set of providers for a given consumer. It respects automatic placement constraints, including cluster boundaries and DRS rules. It also considers user-configured constraints defined in a placement policy to ensure compliance to specific business requirements.

Reviewing the constraints on an entity helps you understand the actions that Workload Optimization Manager recommends. If an action seems questionable to you, then you should look at the constraints on the affected entities. It's possible that some policy or constraint is in effect, and it keeps Workload Optimization Manager from recommending a more obvious action. For details, see Entity Placement Constraints (on page 130).

You can run plans to see what happens if you turn off constraints, or disable or enable certain placement policies.

Effective CPU Capacity

CPU processor speed is not necessarily an effective indicator of CPU capacity. For example, processor architecture can make a slower CPU have a greater effective capacity. Newer models of machines can often have fewer cores or less clock speed, but still have a higher effective capacity.

When placing VMs on hosts in the on-prem environment, Workload Optimization Manager discovers the effective CPU capacity of your hosts. This increases the accuracy of placement calculations so that newer, more efficient hosts will show a greater effective capacity than less efficient hosts that might have larger or faster processors.

To discover the effective capacity, Workload Optimization Manager uses benchmark data from spec.org. This benchmark data maps to effective capacity settings that Workload Optimization Manager uses to make placement calculations.

You can see a catalog of these benchmark data and choose from listed processors when you edit Host templates. For more information, see <u>Selecting CPUs from the Catalog (on page 712)</u>.

Shared-Nothing Migration Actions

If you have enabled both storage and VM moves, Workload Optimization Manager can perform shared-nothing migrations, which move the VM and the stored VM files simultaneously. For details, see <u>Shared-Nothing Migration (on page 452)</u>.

Cross-vCenter vMotion

VMware vSphere 6.0 introduces functionality that enables migration of virtual machines between different vCenter Server instances. Workload Optimization Manager supports this capability through *Merge* placement policies (see <u>Creating Placement</u>



<u>Policies (on page 673)</u>). It considers cross-vCenter locations when calculating placement, and can recommend or execute moves to different vCenter servers.

Moves on the Public Cloud

On the public cloud you do not place workloads on physical hosts. In the Workload Optimization Manager Supply Chain, the Host nodes represent availability zones. Workload Optimization Manager can recommend moving a workload to a different zone, if such a move can reduce your cloud cost. These moves recognize constraints, such as availability of instances types and discounts (on page 113) in the given zones.

In AWS environments, a VM can use Elastic Block Stores (EBS) or Instance Storage. If the VM's root storage is EBS, then Workload Optimization Manager can recommend a VM move. However, because Instance Storage is ephemeral and a move would lose the stored data, Workload Optimization Manager does not recommend moving a VM that has Instance Storage as its root storage.

If a VM is running within a billing family, then Workload Optimization Manager only recommends moving that VM to other regions within that billing family.

In AWS environments that use RIs, Workload Optimization Manager recognizes Availability Zones that you have specified for your RI purchases. For move and resize actions, Workload Optimization Manager gives precedence to these RIs in the given zone. All else being equal for a given zone, if you have Zone RIs with reserved capacity and RIs that do not reserve capacity, Workload Optimization Manager will use the Zone RI first.

Scaling

Scaling actions update capacity in your environment. For vertical scaling, Workload Optimization Manager increases or decreases the capacity of resources on existing entities. For horizontal scaling it provisions new providers. For example, provisioning a host adds more compute capacity that is available to run VMs. Provisioning a VM adds capacity to run applications.

Workload Optimization Manager can provision the following:

- Containers
- VMs
- Hosts
- Storage
- Storage Controllers (only for planning scenarios)
- Disk Arrays

Under certain circumstances, Workload Optimization Manager can also recommend that you provision a virtual datacenter.

Discount Optimization

To reduce your cloud costs, Workload Optimization Manager can recommend scaling VMs to instance types that are charged discounted rates.

NOTE:

Under most circumstances, when a cloud provider offers a new instance type that is meant to replace an older type, the provider offers it at a lower cost. However, a provider may provide a new instance type with identical costs as the older instance types. If this occurs, and capacity and cost are equal, Workload Optimization Manager cannot ensure that it chooses the newer instance type. To work around this issue, you can create an Action Automation policy that excludes the older instance type.

■ Discount Utilization (on page 665)

This chart shows how well you have utilized your current discount <u>inventory</u> (on page 663). The desired goal is to maximize the utilization of your inventory and thus take full advantage of the discounted pricing offered by your cloud provider.

■ Discount Coverage (on page 661)

This chart shows the estimated percentage of VMs covered by discounts. If you have a high percentage of on-demand VMs, you should be able to reduce your monthly costs by increasing coverage. To increase coverage, you scale VMs to instance types that have existing capacity.



■ Discount Inventory (on page 663)

This chart lists the cloud provider discounts discovered in your environment.

Discount optimization actions are not executed by Workload Optimization Manager users. They reflect capacity reassignments performed by your cloud provider.

Configuration

These are reconfigure and resize actions. Reconfigure actions can add necessary network access, or reconfigure storage. Resize actions allocate more or less resource capacity on an entity, which can include adding or reducing VCPUs or VMem on a VM, adding or reducing capacity on a datastore, and adding or reducing volumes in a disk array.

Workload Optimization Manager can reconfigure the following:

- VMs
- Containers
- Storage
- Disk Arrays
- Virtual Datacenters

Start/Buy

Workload Optimization Manager can recommend that you start a suspended entity to add capacity to the environment. It can also recommend purchasing cloud provider <u>discounts (on page 113)</u> to reduce costs for your current workload.

Stop

Stop actions suspend entities without removing them from the environment. Suspended capacity is still available to be brought back online, but is currently not available for use. Suspended resources are candidates for termination.

Workload Optimization Manager can suspend the following:

- Application Components
- Container Pods
- Disk Arrays
- Hosts
- Storage (on-prem)
- Virtual datacenter

Delete

Delete actions affect storage. For example, Workload Optimization Manager might recommend that you delete wasted files to free up storage space, or delete unused storage in your cloud environment to reduce storage costs.

Wasted Storage in Azure Environments

In Azure environments, Workload Optimization Manager can identify unmanaged storage as unattached volumes, recommend that you remove this unused storage, and then show *estimated* savings after you remove this storage and no longer pay for it. The savings that Workload Optimization Manager shows are estimates based on the overall cost for that storage, since Azure does not provide specific values for the cost per volume or cost for the amount of storage that is in use for a given volume. If the estimated savings appear unusually high, then you should identify which storage the actions will remove, and review your billing to calculate the costs with more precision.



Action Acceptance Modes

Action acceptance modes specify the degree of automation for the generated actions. For example, in some environments you might not want to automate resize down of VMs because that is a disruptive action. You would use action acceptance modes in a policy to set that business rule.

Workload Optimization Manager supports the following action acceptance modes:

- Recommend Recommend the action so that a user can execute it outside Workload Optimization Manager
- Manual Recommend the action, and provide the option to execute that action through the Workload Optimization Manager user interface
- Automatic Execute the action automatically

For automated resize or move actions on the same entity, Workload Optimization Manager waits five minutes between each action to avoid failures associated with trying to execute all actions at once. Any action awaiting execution stays in queue. For example, if a VM has both vCPU and vMem resize actions, Workload Optimization Manager could resize vCPU first. After this resize completes, it waits five minutes before resizing vMem.

The Pending Actions charts only count actions in Recommend or Manual mode.

Automated actions appear in the following charts:

- All Actions chart on the Home Page and the On-prem Executive Dashboard
- Accepted Actions chart on the Home Page

Setting Action Acceptance Modes

There are two ways to configure action acceptance modes:

- Change the action acceptance mode in a <u>default policy (on page 678)</u>.
- Create an <u>automation policy (on page 680)</u>, scope the policy to specific entities or groups, and then select the action acceptance mode for each action.

Workload Optimization Manager allows you to create dynamic groups to ensure that entities discovered in the future automatically add to a group and apply the policy of that group. If a conflict arises as a result of an entity belonging to several groups, the entity applies the policy with the most conservative action.

Action Acceptance Overrides


Under some conditions, Workload Optimization Manager changes the action acceptance mode of an action from *Manual* to *Recommend*.

Workload Optimization Manager makes this change as a safeguard against executing actions that the underlying infrastructure cannot support. For example, assume you have VM move actions set to *Manual*. Then assume Workload Optimization Manager analysis wants to move a VM onto a host that is already utilized fully. In this case, there would be other actions to move workloads *off* of the given host to make room for this new VM. However, because moves are *Manual*, the host might not be properly cleared off yet. In that case, Workload Optimization Manager changes actions to move workloads *to* the host from *Manual* to *Recommend*.

For cloud environments, some instances require workloads to be configured in specific ways before they can move to those instance types. If Workload Optimization Manager recommends moving a workload that is not suitably configured onto one of these instances, then it changes the action acceptance mode from *Manual* to *Recommend*, and then describes the reason.



Plans: Looking to the Future



Use the Plan Page to run simulations for what-if scenarios that explore possibilities such as:

- Reducing cost while assuring performance for your workloads
- Impact of scaling resources
- Changing hardware supply
- Projected infrastructure requirements
- Optimal workload distribution to meet historical peaks demands
- Optimal workload distribution across existing resources

How Plans Work

To run a plan scenario, Workload Optimization Manager creates a snapshot copy of your real-time market and modifies that snapshot according to the scenario. It then uses the Economic Scheduling Engine to perform analysis on that plan market. A scenario can modify the snapshot market by changing the workload, adding or removing hardware resources, or eliminating constraints such as cluster boundaries or placement policies.

As it runs a plan, Workload Optimization Manager continuously analyzes the plan market until it arrives at the optimal conditions that market can achieve. When it reaches that point, the Economic Scheduling Engine cannot find better prices for any of the resources demanded by the workload – the plan stops running, and it displays the results as the plan's desired state. The display includes the resulting workload distribution across hosts and datastores, as well as a list of actions the plan executed to achieve the desired result.

For example, assume a scenario that adds virtual machines to a cluster. To run the plan, Workload Optimization Manager takes a snapshot of the current market, and adds the VMs to the specified cluster. Workload Optimization Manager then runs analysis on the plan market, where each entity in the supply chain shops for the resources it needs, always looking for a better price – looking for those resources from less-utilized suppliers. This analysis continues until all the resources are provided at the best possible price.




The results might show that you can add more workload to your environment, even if you reduce compute resources by suspending physical machines. The recommended actions would then indicate which hosts you can take offline, and how to distribute your virtual machines among the remaining hosts.

Idle Workloads

Plans calculate optimal placement and optimal resource allocation for the given workload. However, plans do not include *idle* workloads. This is because an idle VM shows no utilization, so the plan cannot determine optimal placement or what percentage of allocated resources that workload will require when it restarts.

Plan Management



The Plan Management Page is your starting point for creating new plans, viewing saved plans, and deleting saved plans that you don't need anymore. To display this page, click **Plan** in the Workload Optimization Manager navigation bar.

Create new plans

To create a new plan, click the **NEW PLAN** button. See Setting Up Plan Scenarios (on page 531).

View saved plans

After you create and run a plan, Workload Optimization Manager saves it and then shows it in the Plan Management Page. You can open the saved plan to review the results, or you can change its configuration and run it again.

NOTE:

You can also view saved plans from the Search page, under the Plans category.

Delete saved plans

To delete a saved plan, turn on the plan's checkbox and then click the **Delete** button.

Configure nightly plans

Workload Optimization Manager runs nightly plans to calculate headroom for the clusters in your on-prem environment. For each cluster plan, you can set which VM template to use in these calculations. See <u>Configuring Nightly Plans (on page 596)</u>.

Setting Up Plan Scenarios

A plan scenario specifies the overall configuration of a plan. Creating the plan scenario is how you set up a what-if scenario to see the results you would get if you changed your environment in some way.

This topic walks you through the general process of setting up a plan scenario.



1. Plan Entry Points

You can begin creating a plan scenario from different places in the user interface:


From the Plan Page

Navigate to the Plan Page and click **NEW PLAN**. This plan has no scope. You will specify the scope after selecting the plan type.



■ From the Home Page

To start a plan scenario from the **Home Page**, you must first go to the **Search** page to set the scope.



Set the scope to a specific Account, Billing Family, VM Group, or Region to start an Optimize Cloud plan.

Cloud scope

If you set the scope to a specific Account, Billing Family, VM Group, or Region, you can start an Optimize Cloud or Buy VM Reservations plan.

On-prem scope

If you set the scope to a specific Cluster, Datacenter, Group, Storage Cluster, or Virtual Datacenter, you can start any plan. You may need to go through additional steps, depending on your chosen plan type. For example, if you scope to a cluster and choose the Add Virtual Machines plan type, the plan wizard prompts you to select the most suitable templates for the VMs you plan to add to the cluster.

Container cluster scope

If you set the scope to a specific Container Platform Cluster, you can start an Optimize Container Cluster or Migrate Container Workloads plan.

For details, see Scoping the Workload Optimization Manager Session (on page 124).


After setting the scope, the Plan button appears in the Home Page.





2. Plan Types

Select from the list of plan types. For more information, see Plan Scenarios and Types (on page 537).




Workload Optimization Manager opens the appropriate plan wizard.

3. Plan Wizards


Each plan type includes a wizard to guide you through creating the scenario. The wizard leads you through the required configuration steps to create a plan that answers a specific question. After you make the required settings, you can skip ahead and run the plan, or continue through all the optional steps.





4. Plan Scope

All plans require a scope. For example, to configure an Optimize Cloud plan, you set the scope to all or specific cloud providers or accounts.



It usually helps to focus on a subset of your environment. For a very large environment, scoped plans run faster.


To narrow the scope, select a group from the list on the left side of the page. The page then refreshes to include only the entities belonging to that group.

Use Search or Filter to sort through a long list.

5. Additional Plan Information


The wizard prompts you for any additional information required to run the plan. For example, for a Hardware Refresh plan, you need to identify the hosts that will replace the scoped hosts. For a Migrate to Cloud plan, you need to identify the cloud service provider, region, or group you want the scoped workloads to migrate to.





6. Run the Plan

After you provide the minimum required information for running a plan, the wizard shows you the following options:



- Run Plan: Immediately run the plan.
- Next: [Step]: Continue with the rest of the wizard and then run the plan.
- Skip to Configuration: Skip the rest of the wizard and go to the Plan Page to:
 - Customize the plan settings.
 - See a preview of the plan scenario.
 - Run the plan.

NOTE: For a custom plan, the only option available is **Configure Plan**. Click this button to open the Plan Page, configure the plan settings, and then run the plan.


7. The Plan Page

The Plan Page first displays if you skip the wizard or as soon as you run a plan.

For a plan with a large scope, it might take some time before you see the results. You can navigate away from the Plan Page and check the status in the Plan Management Page. You can also cancel a plan that is in progress.

The Plan Page shows the following sections:





Plan Page Sections	Description
A. Plan name	Workload Optimization Manager automatically generates a name when you create a new plan. Change the name to something that helps you recognize the purpose of this plan.
B. Plan scope	Review the scope that you set in a previous step. NOTE: It is not possible to change the scope of the plan in the Plan Page. You will need to start over if you want a different scope. To start over, go to the top-right section of the page, click the More options icon (), and then select New Plan.
C. Configuration toolbar	Configure additional settings for the plan. You can name the plan, change workload demand and the supply of resources, and specify other changes to the plan market. The toolbar items that display depend on the plan you are creating.
D. Configuration summary	Review the plan's configuration settings. You can remove any setting by clicking the x mark on the right. Use the toolbar on top to change the settings. As you make changes to the plan scenario, those changes immediately appear in the Configuration summary.
E. Additional	See what else you can do with the plan.
options	■ Upload : (For Azure only) Upload the results of a Migrate to Cloud plan to the Azure Migrate portal. For details, see <u>Uploading the Results to Azure (on page 575)</u> .
	■ Run / Run Again:
	 If a plan has not run, click Run and then check the plan results.
	 If the plan has run and you want to run it again with a different set of configuration settings, click Run Again. This runs the plan scenario against the market in its current state.
	■ : Click to see more options.



Plan Page Sections	Description
	New Plan Reset view Delete plan New Plan: Configure a new plan. You can choose this option if you want to change the scope of the current plan, which requires that you start over and configure a new plan. Reset view: Restore charts to their default views. For example, if you changed the commodities displayed in the Optimized Improvements or Comparison charts, you can discard those changes by choosing this option. Delete plan: Choose if you no longer need the plan.
F. Plan results	Review the results in the charts provided.
	For a plan that has not run, you will see a Scope Preview chart and a one-time message instructing you to run the plan.


8. Plan Management

All the plans you have created display in the Plan Management Page (on page 531).

Plan Scenarios and Types

To simulate different plan scenarios, Workload Optimization Manager provides the following general types of plans:





Optimize Container Cluster

Run an Optimize Container Cluster plan to identify performance and efficiency opportunities for a single Kubernetes cluster. The results show the optimal number of nodes you need to assure performance for your existing workloads, and the impact of actions on the health of your container workloads and infrastructure.

Migrate Container Workloads

Run a Migrate Container Workloads plan to simulate the migration of container workloads from one cluster to another. The plan compares results from a 'lift-and-shift only' scenario against a Workload Optimization Manager optimized plan. The results further highlight the actions you need to take to maintain and optimize workload performance in the new cluster.

Optimize Cloud

For the scope of your public cloud environment that you want to examine, run a plan to see all the opportunities you have to reduce cost while assuring performance for your workloads. This includes suggestions to buy discounts (on page 113), comparisons of template and storage usage, and a comparison of current to optimized cost.



Buy VM Reservations

Run the Buy VM Reservations plan to see the most cost-effective discount (on page 113) purchases that will continue to assure performance for your cloud VMs.

Migrate to Cloud

A Migrate to Cloud plan simulates migration of on-prem VMs to the cloud, or migration of VMs from one cloud provider to another.

NOTE:

For migrations within your on-prem environment, use the Virtual Machine Migration plan type.

Optimize On-prem

See the effects of executing certain actions, such as scaling virtual machines, suspending hosts, or provisioning storage, to your on-prem environment.

Add Virtual Machines

Adding virtual machines increases the demand that you place on your environment's infrastructure. You can set up a plan to add individual VMs or groups of VMs in your environment, or based on templates.

Hardware Refresh

Choose hosts that you want to replace with different hardware. For example, assume you are planning to upgrade the hosts in a cluster. How many do you need to deploy, and still assure performance of your applications? Create templates to represent the upgraded hosts and let the plan figure out how many hosts you really need.

To increase the accuracy of the plan results, Workload Optimization Manager analysis considers a cluster's overall resource utilization over the last ten days. The platform identifies the day within those ten days when percentile utilization for the cluster reached 90%, and then uses each VM's actual utilization data *on that day* to perform its analysis.

NOTE:

If you configure a Hardware Refresh plan to use a baseline snapshot, the plan will use that snapshot's data instead of the cluster's percentile data.

Host Decommission

If your environment includes underutilized hardware, you can use a plan to see whether you can decommission hosts without affecting the workloads that depend on them.

Virtual Machine Migration

Use this plan type to simulate workload migrations within your on-prem environment.

You can see whether you have enough resources to move your workload from its current provider group to another. For example, assume you want to decommission one datacenter and move all its workload to a different datacenter. Does the target datacenter have enough physical resources to support the workload move? Where should that workload be placed? How can you calculate the effect such a change would have on your overall infrastructure?

To calculate this information, create a plan that:

- Limits the plan scope to two datacenters (or clusters) the one you will decommission, and the one that will take on the extra workload
- Removes all the hardware from the decommissioned datacenter
- Calculates workload placement across datacenter (or cluster) boundaries
- Does not provision new hardware to support the workload

Merge Clusters

See the effects of merging two or more clusters. For example, you can see if merging the clusters would require provisioning additional storage to support current demand, or if ignoring cluster boundaries would improve performance and efficiency.



Alleviate Pressure


Choose a cluster that shows bottlenecks or other risks to performance, and check to see the minimal changes you can make by migrating some workloads to another cluster. The cluster that is showing risks is a *hot* cluster, and the cluster you will migrate to is a *cold* cluster.

Custom Plan

With a custom plan, you skip directly to the plan configuration after specifying the plan scope, and set up whatever type of scenario you want.

You would also choose Custom Plan if you need to run plans that include containers and container pods.

Optimize Container Cluster Plan



Run an Optimize Container Cluster plan to identify performance and efficiency opportunities for a single Kubernetes cluster. The results show the optimal number of nodes you need to assure performance for your existing workloads, and the impact of actions on the health of your container workloads and infrastructure. For example, you can see how container resize actions change the limits and requests allocated per namespace, or how node provision/suspend actions impact allocatable capacity for the cluster. For a cluster in the public cloud, the results also include the cost impact of node actions.

You can scope the plan to a:


- Standalone container cluster
- Container cluster in an on-prem or public cloud environment
- Container cluster stitched to applications via Data Ingestion Framework (DIF)

Scoping to a group within a Kubernetes cluster (such as a group of nodes) is currently not supported.




Configuring an Optimize Container Cluster Plan

You can start an Optimize Container Cluster plan when you open the Plan page or set the scope to a Kubernetes cluster. For an overview of setting up plan scenarios, see <u>Setting Up Plan Scenarios</u> (on page 531).



1. Scope

Select a Kubernetes cluster to optimize.



Scoping to a group within a Kubernetes cluster (such as a group of nodes) is currently not supported.

NOTE:

After selecting a cluster, you can skip the next step (**Optimization Settings**) and run the plan. Workload Optimization Manager runs the **Full Optimization** scenario in this case.

2. Optimization Settings

Choose from the given optimization scenarios.



4	Optimization Settings	×
•	Full Optimization See how many nodes are required if applying all actions.	
0	Optimize Container Spec Size Update only containers spec sizes to assure performance. Best for application owners.	
0	Optimize Cluster Resources, Placement and Nodes Move, provision and suspend container pods, provision and suspend nodes (Virtual Machines) without impact on container or node size to assure performance. Best for DevOps and	nd SREs

■ Full Optimization

Workload Optimization Manager will recommend all relevant actions to optimize the cluster. For example, it can recommend provisioning nodes or resizing containers to meet application demand, or moving pods from one node to another to reduce congestion.

Workload Optimization Manager can recommend the following actions:

- Resize namespace compute resource quotas
- Resize container limits and requests
- Move pods
- Provision or suspend nodes
- Scale volumes

NOTE:

For a cluster in the public cloud, Workload Optimization Manager shows the cost impact of actions on nodes and volumes, to help you track your cloud spend. Workload Optimization Manager only reports the costs attached to these actions, and does *not* perform cost analysis on the cluster.

For a cluster in an on-prem environment, Workload Optimization Manager can also recommend the following actions:

- Move VMs
- Provision or suspend hosts
- Provision or suspend storage

Optimize Container Spec Size

Workload Optimization Manager will only recommend resizing container limits and requests. This is ideal for application owners who manage the containers that their applications run on, but not the underlying container infrastructure.

Optimize Cluster Resources, Placement, and Nodes

Workload Optimization Manager will recommend *all* relevant actions, *except* resizing container limits and requests. This is ideal for teams who oversee the health of your container infrastructure, and want to evaluate the impact of *not* rightsizing workloads.

After selecting an optimization scenario, you can:

Run the plan.

Or

Choose Skip to Configuration to configure additional settings. See the next section for details.

(Optional) Additional Plan Settings

You can fine tune your selected optimization scenario or include additional scenarios before you run the plan.

Enable or disable actions

Fine tune your optimization scenario by enabling or disabling actions for containers, pods, or nodes. For example, you may have selected **Full Optimization**, but only for containers, nodes, and pods that are allowed to move. In this case, you would disable move actions for the pods that should never move.

For clusters in on-prem environments, you can also enable or disable actions for hosts and storage.



IMPORTANT:

To avoid seeing inaccurate plan results, do not disable all actions.

Add pods

See resource changes if you add more pods to the cluster. For example, you might need to provision nodes to accommodate the new pods.


Select an existing pod within or outside the selected Kubernetes cluster, and then specify how many copies to add. The plan simulates adding pods with the same resources as the selected pod.

Remove pods or nodes

See the effect of removing pods or nodes from the cluster. For example, pod density could improve significantly if you remove pods that you no longer need, or certain pods might become unplaced if you remove nodes.

Working with Optimize Container Cluster Plan Results

After the plan runs, you can view the results to see how the plan settings you configured affect your environment.



General Guidelines


Familiarize yourself with these common terms that appear in the plan results:

- A container pod represents the compute demand from a running pod.
- A Kubernetes node (virtualized or bare metal) is represented as a VM.
- Used (or Usage) values represent actual resource consumption. For example, a node that consumes 100 MB of memory
 has a used value of 100 MB.
- Utilization values represent used/usage values against capacity. For example, a node that consumes 100 MB of memory against a total capacity of 500 MB has a utilization value of 20%.



Optimize Container Cluster Summary

RESULTS OVERVIEW PLAN ACTIONS (258)



This chart shows how your container environment and the underlying resources will change after you execute the actions that the plan recommends. The chart shows the following information:

Container Pods

Count of active container pods in the plan.

Virtual Machines

Count of active nodes in the plan. This chart does not count "non-participating" entities in the real-time market, such as suspended nodes.

Pod Density

Average number of pods per node.

For the total number of pods against the node capacity (maximum pods per node), see the **Number of Consumers** data in the following charts:

- Nodes (VMs) Optimized Improvements
- Nodes (VMs) Comparison
- Container Cluster Optimized Improvements
- Container Cluster Comparison

Cluster CPU Capacity

Total CPU capacity for the cluster. The 'After Plan' result indicates how much CPU capacity will result in the optimal number of nodes required to run workloads.

Cluster Memory Capacity

Total memory capacity for the cluster. The 'After Plan' result indicates how much memory capacity will result in the optimal number of nodes required to run workloads.

Cluster Allocatable CPU

Total amount of cluster CPU <u>available</u> for pod requests. The 'After Plan' result indicates how much of the allocatable CPU capacity will change if you provision or suspend nodes.

Cluster Allocatable Memory



Total amount of cluster memory <u>available</u> for pod requests. The 'After Plan' result indicates how much of the allocatable memory capacity will change if you provision or suspend nodes.

■ Cluster CPU Overcommitment

(Only for containers with CPU limits) This indicates whether the CPU limits exceed the capacity of the underlying nodes. A value greater than 100% indicates overcommitment. Workload Optimization Manager manages cluster resources by actual utilization and limit rightsizing so that you can run more workloads with less risk.

Workload Optimization Manager only calculates overcommitment in plans. The calculation can be expressed as:

Overcommitment = Sum of CPU limits for all containers / Sum of CPU capacity for all nodes


Cluster Memory Overcommitment

(Only for containers with memory limits) This indicates whether the memory limits exceed the capacity of the underlying nodes. A value greater than 100% indicates overcommitment. Workload Optimization Manager manages cluster resources by actual utilization and limit rightsizing so that you can run more workloads with less risk.

Workload Optimization Manager only calculates overcommitment in plans. The calculation can be expressed as:

Overcommitment = Sum of memory limits for all containers / Sum of memory capacity for all nodes

Optimize Container Cluster Actions



This chart summarizes the actions that you need to execute to achieve the plan results. For example, you might need to resize limits and requests for containers (via the associated Workload Controllers) to address performance issues. Or, you might need to move pods from one node to another to reduce congestion.

Smarter redistribution and workload rightsizing also drive cluster optimization, resulting in the need to provision node(s) based on application demand, or to defragment node resources to enable node suspension.

Workload Optimization Manager can recommend the following actions:

- Resize namespace compute resource quotas
- Resize container limits and requests

NOTE:

Executing several container resize actions can be very disruptive since pods need to restart with each resize. For replicas of the container scale group(s) related to a single Workload Controller, Workload Optimization Manager consolidates resize actions into one *merged action* to minimize disruptions. When a merged action has been executed (via the associated Workload Controller), all resizes for all related container specifications will be changed at the same time, and pods will restart once.

- Move pods
- Provision or suspend nodes
- Scale volumes

NOTE:


For a cluster in the public cloud, Workload Optimization Manager shows the cost impact of actions on nodes and volumes, to help you track your cloud spend. Workload Optimization Manager only reports the costs attached to these actions, and does *not* perform cost analysis on the cluster. See the Optimized Savings and Optimized Investments charts for more information.



For an on-prem cluster, Workload Optimization Manager can also recommend the following actions:

- Move VMs
- Provision or suspend hosts
- Provision or suspend storage


Optimized Savings



For a cluster in the public cloud, Workload Optimization Manager shows the savings you would realize if you execute the actions (such as node suspension) that the plan recommends to increase infrastructure efficiency. Note that efficiency is the driver of this action, *not* cost. Cost information is included to help you track your cloud spend.

The chart shows total monthly savings. Click Show All to view the actions with cost savings.

Optimized Investments




For a cluster in the public cloud, Workload Optimization Manager shows the costs you would incur if you execute the node and volume scaling actions that the plan recommends to address performance issues. For example, if some applications risk losing performance, Workload Optimization Manager can recommend provisioning nodes to increase capacity. This chart shows how these actions translate to an increase in expenditure. Note that performance and efficiency are the drivers of these actions, *not* cost. Cost information is included to help you plan for the increase in capacity.

The chart shows total monthly investments. Click **Show All** to view the actions that require investments.




Nodes (VMs) Optimized Improvements



This chart compares the following before and after the plan:


- Utilization of the following for all nodes:
 - vMem
 - vCPU
 - vMem Request
 - vCPU Request
- Number of pods consuming resources against the maximum pod capacity for all the nodes

Nodes (VMs) Comparison



This chart compares node resource utilization (one metric at a time) before and after the plan.

Namespace Quotas Optimized Improvements




This chart shows pod utilization of resource quotas defined in namespaces. Resource quotas include:

- CPU Limit Quota
- Memory Limit Quota
- CPU Request Quota
- Memory Request Quota

For namespaces without defined quotas, utilization is 0 (zero).

With or without quotas, you can see the sum of pod limits and requests per namespace. Go to the top-right section of the Plan Results page, click the download button, and select **Namespace**. Utilization data in the downloaded file shows these limits and requests. You can also compare usage values in the Namespaces Comparison chart.

Namespaces Comparison




This chart compares namespace quota usage (one metric at a time) before and after the plan.


Use this chart to see how container resizing changes the limits and requests allocated per namespace, whether you leverage quotas or not.



To achieve the 'After Plan' results, click **Show All**. In the Details page that opens, go to the Name column and then click the namespace link. This opens another page with a list of pending actions for the namespace.



Namespace Resources Comparison




This chart shows how much cluster resources per namespace are utilized by pods. Utilization can be expressed as follows:

 ${\tt Utilization = Sum \ of \ actual \ vMem/vCPU \ used \ by \ pods \ / \ vMem/vCPU \ capacity \ for \ the \ cluster}$

This information helps you understand which namespaces use the most cluster resources. You can also use it for showback analysis. vMem and vCPU utilized by pods in the namespaces would change when the number of nodes changes as a result of executing the plan actions.

This chart is especially useful if you do not have resource quotas defined in your namespaces.

Container Cluster Optimized Improvements



This chart shows the following, assuming you execute all actions in the plan:

- Changes to the utilization of cluster resources
- Overcommitment values

Container Cluster Comparison



This chart compares the following before and after the plan:

- Utilization of cluster resources (one metric at a time)
- Overcommitment values

Optimized Improvements for Hosts, Storage, and Virtual Machines

Use these charts if you ran the plan on an on-prem Kubernetes cluster. These charts show how the utilization of resources would change assuming you accept all of the actions listed in the Plan Actions chart



Hosts, Storage Devices, and Virtual Machines Comparison


Use these charts if you ran the plan on an on-prem Kubernetes cluster. These charts show how the utilization of a particular commodity (such as memory or CPU) for each entity in the plan would change if you execute the recommended actions.

NOTE:

For the Storage Devices Comparison chart, if you set the view to **VM Per Storage** and click **Show all**, the total number of VMs sometimes does not match the number in the Summary chart. This happens if there are VMs in the plan that use multiple storage devices. The Storage Devices Comparison chart counts those VMs multiple times, depending on the number of storage devices they use, while the Plan Summary chart shows the actual number of VMs.

Downloading Plan Results

To download results for nodes, namespaces, or the container cluster, click the download button at the top-right section of the Plan Results page.



You can also download the plan results shown in individual charts. Click the **Show All** button for a chart, and then the download button at the top-right section of the Details page.



For charts that display infinite capacities (for example, the Namespaces Comparison chart), the downloaded file shows an unusually high value, such as 1,000,000,000 cores, instead of the ∞ symbol.



Re-Running the Plan

You can run the plan again with the same or a different set of configuration settings. This runs the plan scenario against the market in its current state, so the results you see might be different, even if you did not change the configuration settings.

Use the toolbar on top of the Configuration section to change the configuration settings.

NOTE:

It is not possible to change the scope of the plan in the Plan Page. You will need to start over if you want a different scope. To start over, go to the top-right section of the page, click the More options icon (), and then select **New Plan**.

When you are ready to re-run the plan, click Run Again on the top-right section of the page.

Migrate Container Workloads Plan

Run a Migrate Container Workloads plan to simulate the migration of container workloads from one cluster to another. For example, when you are ready to deploy workloads in your test cluster to production, you can run this plan to evaluate resource requirements in the production cluster. You might also have a need to decommission an existing cluster or consolidate workloads in different clusters into a single cluster, both of which require moving existing workloads to a new cluster. Run this plan to see if all workloads can be placed in the new cluster.

The destination cluster (i.e., the cluster that you choose for migration) can be a:

- Standalone container cluster
- Container cluster in an on-prem or public cloud environment. For cloud environments, cost information is included in the plan results.
- Container cluster stitched to applications via Data Ingestion Framework (DIF)

The plan results show the impact of workload migration on the destination cluster, based on two migration scenarios:

	BEFORE MIGRATION	LIFT & SHIFT	
Workload Controllers	69	71	71
Container Pods	141	145	145
Virtual Machines	7	7	5
Pod Density	20.1 : 1	20.7 : 1	29 : 1
Cluster CPU Capacity	17 Cores	27 Cores	17 Cores
Cluster CPU Allocatable	17 Cores	17 Cores	17 Cores
Cluster CPU Request	4.6 Cores	4.6 Cores	3.85 Cores
Cluster CPU Limit	773.81 Cores	269.81 Cores	270.22 Cores
Cluster CPU Overcommitment	4551.8 %	999.3 %	1589.5 %
Cluster Memory Capacity	39.94 GB	61.94 GB	39.94 GE
Cluster Memory Allocatable	39.45 GB	39.45 GB	39.45 GE
Cluster Memory Request	5.82 GB	5.83 GB	5.83 GE
Cluster Memory Limit	27.72 GB	22.05 GB	15.81 GB
Cluster Memory Overcommitment	69.4 %	35.6 %	39.6 %

■ Lift & Shift

The Lift & Shift scenario migrates your container workloads based on the resources currently available in the destination cluster.

Optimized

The Optimized scenario identifies opportunities to optimize performance in the destination cluster. For example, after analyzing historical resource utilization, Workload Optimization Manager might recommend resizing limits and requests for



containers (via the associated Workload Controllers) to maintain performance. If you were to migrate workloads based on the resources currently available in the destination cluster, then your applications could risk losing performance.

NOTE:

The plan results do not show data for the source cluster.

The results further highlight the actions you need to take to maintain and optimize workload performance in the destination cluster.

Configuring a Migrate Container Workloads Plan

You can begin creating a plan scenario from two places in the user interface:


- From the Plan Page (Recommended)
 - On the left menu, click Plan to open the Plan Page. Click New Plan, and then select Migrate Container Workloads.
- From the supply chain

To start a plan scenario from the supply chain, set the scope to a container cluster and then click **Plan** at the top-right corner of the page.

For an overview of setting up plan scenarios, see Setting Up Plan Scenarios (on page 531).

1. Scope

Select the container workloads that you want to migrate.




Container workloads are grouped by namespace. Expand a namespace to see individual Workload Controllers that manage workloads, and the number of container replicas for each Workload Controller. You can adjust the number of replicas in a later step. For example, you can add replicas to meet workload demand.

To define your scope, select individual namespaces and/or Workload Controllers, from one or several clusters. For example, if you are migrating workloads in two clusters, select the namespaces in those clusters.

To find specific workloads, type a keyword in the Search bar or click **Add Filter**. You can filter workloads by container cluster, namespace, tag, or Workload Controller.

2. Where to Migrate

Choose the destination cluster for the container workloads you selected.





You can migrate to a:


- Standalone container cluster
- Container cluster in an on-prem or public cloud environment
- Container cluster stitched to applications via Data Ingestion Framework (DIF)

After selecting a cluster, you can:

Run the plan.

Or

Choose Skip to Configuration to configure additional settings, including:



- Removing existing replicas from the destination cluster. You may need to do this to make room for the workloads you
 are migrating.
- Adjusting the number of replicas for the Workload Controllers in scope. For example, you may need to add replicas to meet workload demand.

Working with Migrate Container Workloads Plan Results

After the plan runs, you can view the results to see the impact of workload migration on the *destination* cluster. The results do *not* show data for the *source* cluster (i.e., the cluster that currently hosts the workloads).

General Guidelines

Familiarize yourself with these common terms that appear in the plan results:

- A container pod represents the compute demand from a running pod.
- A Kubernetes node (virtualized or bare metal) is represented as a VM.
- Used (or Usage) values represent actual resource consumption. For example, a node that consumes 100 MB of memory has a used value of 100 MB.
- Utilization values represent used/usage values against capacity. For example, a node that consumes 100 MB of memory against a total capacity of 500 MB has a utilization value of 20%.



Migrate Container Workloads Summary

	BEFORE MIGRATION	LIFT & SHIFT	
Workload Controllers	69	71	71
Container Pods	141	145	145
Virtual Machines	7	7	5
Pod Density	20.1 : 1	20.7 : 1	29 : 1
Cluster CPU Capacity	17 Cores	27 Cores	17 Cores
Cluster CPU Allocatable	17 Cores	17 Cores	17 Cores
Cluster CPU Request	4.6 Cores	4.6 Cores	3.85 Cores
Cluster CPU Limit	773.81 Cores	269.81 Cores	270.22 Cores
Cluster CPU Overcommitment	4551.8 %	999.3 %	1589.5 %
Cluster Memory Capacity	39.94 GB	61.94 GB	39.94 GB
Cluster Memory Allocatable	39.45 GB	39.45 GB	39.45 GB
Cluster Memory Request	5.82 GB	5.83 GB	5.83 GB
Cluster Memory Limit	27.72 GB	22.05 GB	15.81 GB
Cluster Memory Overcommitment	69.4 %	35.6 %	39.6 %

Table Columns

Table columns shows the following information for the destination cluster:

- Before Migration
 - This column shows the state of the destination cluster before workload migration.
- Lift & Shift
 - The Lift & Shift scenario migrates your container workloads based on the resources currently available in the destination cluster.
- Optimized

The Optimized scenario identifies opportunities to optimize performance in the destination cluster. For example, after analyzing historical resource utilization, Workload Optimization Manager might recommend resizing limits and requests for containers (via the associated Workload Controllers) to maintain performance. If you were to migrate workloads based on the resources currently available in the destination cluster, then your applications could risk losing performance.

Table Rows

Table rows show the following information for the destination cluster:

Row	Description			
Workload Controllers	Count of active Workload Controllers. This chart does not count "non-participating" entities in the real-time market, such as inactive Workload Controllers.			
Container Pods	Count of active (running) container pods.			
Virtual Machines	Count of active Kubernetes nodes (virtualized or bare metal). This chart does not count "non-participating" nodes in the real-time market, such as suspended nodes.			
Pod Density	Average number of pods per node. The 'Optimized' result shows if you can improve density by increasing the number of pods per node.			




Row	Description	
	For the total number of pods against the node capacity (maximum pods per node), see the Number of Consumers data in the following charts:	
	 Nodes (VMs) Optimized Improvements 	
	■ Container Platform Cluster Optimized Improvements	
Cluster CPU Capacity	Total CPU capacity for the cluster. The 'Optimized' result indicates how much CPU capacity will result in the optimal number of nodes required to run workloads.	
Cluster CPU Allocatable Total amount of cluster CPU <u>available</u> for pod requests. The 'Optimized' result indicates how a allocatable CPU capacity will change if you provision or suspend nodes.		
Cluster CPU Total CPU Request capacity for the cluster. Request		
Cluster CPU Limit	Total CPU Limit capacity for the cluster.	
Cluster CPU Overcommitment	(Only for containers with CPU limits) This indicates whether the CPU limits exceed the capacity of the underlying nodes. A value greater than 100% indicates overcommitment. Workload Optimization Manager manages cluster resources by actual utilization and limit rightsizing so that you can run more workloads with less risk.	
	Workload Optimization Manager only calculates overcommitment in plans. The calculation can be expressed as:	
	Overcommitment = Sum of CPU limits for all containers / Sum of CPU capacity for all nodes	
Cluster Memory Capacity	Total memory capacity for the cluster. The 'Optimized' result indicates how much memory capacity will result in the optimal number of nodes required to run workloads.	
Cluster Memory Allocatable	Total amount of cluster memory <u>available</u> for pod requests. The 'Optimized' result indicates how much of the allocatable memory capacity will change if you provision or suspend nodes.	
Cluster Memory Request	Total Memory Request capacity for the cluster.	
Cluster Memory Limit	Total Memory Limit capacity for the cluster.	
Cluster Memory Overcommitment	(Only for containers with memory limits) This indicates whether the memory limits exceed the capacity of the underlying nodes. A value greater than 100% indicates overcommitment. Workload Optimization Manager manages cluster resources by actual utilization and limit rightsizing so that you can run more workloads with less risk.	
	Workload Optimization Manager only calculates overcommitment in plans. The calculation can be expressed as:	
	Oversommitment - Cum of memory limits for all senteinous /	
	Overcommitment = Sum of memory limits for all containers /	

Plan Actions

Workload Optimization Manager shows separate tabs for **Lift & Shift** and **Optimized** migration actions. You can download the list of actions as a CSV file.





These tabs show the actions that you need to execute to achieve the plan results. For example, you might need to resize limits and requests for containers (via the associated Workload Controllers) to address performance issues. Or, you might need to move pods from one node to another to reduce congestion.

Smarter redistribution and workload rightsizing also drive actions, resulting in the need to provision node(s) based on application demand, or to defragment node resources to enable node suspension.


Workload Optimization Manager can recommend the following actions:

Entity	Lift & Shift Actions	Optimized Actions		
Workload Controller	None	Resize container limits and requests See "Workload Controller Resize Actions" below for additional details.		
Namespace	None	Resize quotas (if container resize actions would exceed the namespace quotas)		
Pod	 Move Provision (if node provision is required) Reconfigure 	 Move Provision (if node provision is required) Suspend (if node suspension is required) Reconfigure 		
Node (VM)	ProvisionMove on-prem nodes	ProvisionSuspendMove on-prem nodes		
Cloud volume	Scale	Scale		
On-prem storage	ProvisionSuspend	■ Provision ■ Suspend		
On-prem host	ProvisionSuspend	■ Provision ■ Suspend		

Additional information:

Workload Controller Resize Actions

When you expand an action on a Workload Controller, you will see charts that track VCPU and VMem utilization for the impacted Container Spec. With these charts, you can easily recognize the utilization trends that Workload Optimization Manager analyzed to make accurate resize decisions.




For more information about these charts, see Utilization Charts (on page 515).

Executing several container resize actions can be very disruptive since pods need to restart with each resize. For replicas of the container scale group(s) related to a single Workload Controller, Workload Optimization Manager consolidates resize actions into one *merged action* to minimize disruptions. When a merged action has been executed (via the associated Workload Controller), all resizes for all related container specifications will be changed at the same time, and pods will restart once.

Pod Constraints

A Migrate Container Workloads plan evaluates pod constraints on the source cluster when making placement decisions for pods. The plan enforces taints, tolerations, and nodeSelector specifications if there are matching constraints in the destination cluster. If these constraints cannot be achieved in the destination cluster, the plan ignores them to guarantee placement.

The plan always enforces affinity and anti-affinity constraints, which could result in unplaced pods in the destination cluster. If this happens, the plan generates reconfigure actions for the unplaced pods and shows a notification in the plan results.




Click **Show Details** to see the list of pods and the reasons for their non-placement. The charts in the plan results do not count these pods.

Savings

For a destination cluster in the public cloud, Workload Optimization Manager shows the savings you would realize if you execute the actions that the plan recommends. The results show separate charts for the **Lift and Shift** and **Optimized** scenarios, so you can compare the impact of actions on your cloud expenses.





For example, in both scenarios, the plan might recommend scaling volumes to new tiers to address performance issues. If these new tiers happen to be more cost-effective than the current tiers, then the actions are treated as cost-saving measures. For the optimized scenario, the plan might also recommend suspending certain nodes to increase infrastructure efficiency, which could introduce additional savings.

Note that application performance and infrastructure efficiency are the drivers of these actions, *not* cost optimization. Cost information is included to help you track your cloud expenses.

The charts show total monthly savings. Click Show All to view the actions with cost savings.


NOTE:

An empty chart indicates that no savings will be realized after you execute the recommended actions.

Investments

For a destination cluster in the public cloud, Workload Optimization Manager shows the costs you would incur if you execute the actions that the plan recommends. The results show separate charts for the **Optimized** and **Lift and Shift** scenarios, so you can compare the impact of actions on your cloud expenses.





For example, if some applications risk losing performance, the plan might recommend provisioning nodes to increase capacity. The charts show how node provision actions translate to an increase in expenditure. You can use cost information in the charts as you seek approval to execute these actions.


The charts show total monthly investments. Click Show All to view the actions that require investments.

NOTE:

An empty chart indicates that no investments are required to execute the recommended actions.

Nodes (VMs) Optimized Improvements

This chart compares the following before and after the plan:



- Utilization of the following resources for all nodes:
 - vMem




- vCPU
- vMem Request
- vCPU Request
- Number of pods consuming resources against the maximum pod capacity for all the nodes

Use this chart to identify nodes that are candidates for suspension, or resources with unusual utilization. You can also use this chart to drill down to a specific resource. Click **Show All** for more details.

Namespace Quotas Optimized Improvements

This chart shows pod utilization of resource quotas defined in namespaces. Resource quotas include:




- CPU Limit Quota
- Memory Limit Quota
- CPU Request Quota
- Memory Request Quota

The chart highlights utilization improvements as a result of namespace resizing.

For namespaces without defined quotas, utilization is 0 (zero).

Container Platform Cluster Optimized Improvements

This chart shows the following, assuming you execute all actions in the plan:



- Changes to the utilization of cluster resources
- Overcommitment values



Optimized Improvements for Hosts and Storage

Use these charts if you ran the plan on an on-prem cluster. These charts show how the utilization of resources would change assuming you accept all of the actions that the plan recommends.

Downloading Plan Results

You can download the plan results shown in individual charts. Click the **Show All** button for a chart, and then the download button at the top-right section of the Details page.

Re-Running the Plan

You can run the plan again with the same or a different set of configuration settings. This runs the plan scenario against the market in its current state, so the results you see might be different, even if you did not change the configuration settings. Use the toolbar on top of the Configuration section to change the configuration settings.


NOTE:

It is not possible to change the scope of the plan in the Plan Page. You will need to start over if you want a different scope. To start over, go to the top-right section of the page, click the More options icon (), and then select **New Plan**.

When you are ready to re-run the plan, click Run Again on the top-right section of the page.

Optimize Cloud Plan

Run the Optimize Cloud plan to see how you can maximize savings while still assuring performance for your applications and workloads. This plan identifies ways to optimize your costs by choosing the best templates (most adequate compute resources), regions, accounts, or resource groups to host your workloads. The plan also identifies workloads that can change over to discounted pricing, and it compares your current costs to the costs you would get after executing the plan recommendations.






Configuring an Optimize Cloud Plan

For an overview of setting up plan scenarios, see Setting Up Plan Scenarios (on page 531).

1. Scope

You can scope by:



Accounts

Choose an AWS account or Azure subscription for the plan's scope. If you choose an Account for the scope, then the plan will not recommend discount purchases. To optimize discount purchases for a limited scope, choose a Billing Family.

Billing Families

Include discount purchases in the planning for a scope that is limited to a single billing family. The plan calculates discount purchases through the billing family's master account.

Cloud Providers

See how you can optimize all your AWS or Azure workloads.

Resource Groups

Workload Optimization Manager discovers Azure resource groups. You can select one or more resource groups for the plan scope.

Regions

Focus the plan on a provider's region.

2. Optimization Settings



Choose from the given optimization options. Note that if you set a plan's scope to a resource group, Workload Optimization Manager will optimize services without recommending discount purchases.

If your goal is to purchase discounts for VMs at their current sizes, use the Buy VM Reservations plan type. For details, see <u>Buy VM Reservations Plan (on page 577)</u>.




NOTE:

If you turn on the **Disable All Actions** setting in the global default policy and then run an Optimize Cloud plan with VM scaling and discount purchases enabled, the plan results show inaccurate discount recommendations.

Turn off **Disable All Actions** to resolve this issue. Be aware that after you turn off this setting, it will take Workload Optimization Manager a week to reflect accurate results in Optimize Cloud plans.

3. Reserved Instances Settings



For Plan RI Inventory, the discounts for the current scope are selected by default. Click Edit to make changes.

For **RI Purchase Profile**, the settings that you have set up for real-time analysis are selected by default. You can change the settings to see how they affect costs.

Offering Class

For AWS environments, choose the offering class that corresponds to the RI types that you typically use in your environment.

■ Term

For AWS and Azure environments, choose the payment terms you contract for your discounts. TERM can be one of **1 Year** or **3 Year**. Typically, longer term payment plans cost less per year.

Payment

The payment option that you prefer for your AWS RIs:

- All Upfront You make full payment at the start of the RI term.
- Partial Upfront You make a portion of the payment at the start of the term, with the remain cost paid at an hourly rate.
- No Upfront You pay for the RIs at an hourly rate, for the duration of the term.

Working With Optimize Cloud Plan Results


After the Optimize Cloud plan runs, you can view the results to see how you can maximize savings or make other improvements to your cloud environment.



The plan results:

- Compare current to optimized costs, including on-demand compute, discounted compute, on-demand database, and storage costs
- Compare current and optimized breakdowns of templates used
- Compare breakdowns of storage tiers in use
- Project the discount coverage (how many workloads are covered by discounted pricing) and utilization (percentage of discounts that are active)
- Show the cost benefit of moving workloads from on-demand to discounted pricing

Viewing the Results



The plan results include the following charts:

■ Cloud Cost Comparison

This chart highlights any difference in cost as a result of optimization. For example, undersized VMs risk losing performance and should therefore scale up. This could contribute to an increase in cost. On the other hand, oversized VMs can scale down to less expensive instances, so cost should go down. The values under the % column indicate the percentage of VMs that are affected by optimization cost calculations.

Workload Optimization Manager can also recommend that you purchase discounts to reduce costs. The analysis looks at workload history to identify workloads that can move from on-demand to discounted pricing. This considers the count of workloads in a family, plus their hours of active-state condition, to arrive at the discounts you should purchase. Since discounted costs are incurred at the account level, the Cloud Cost Comparison chart will present discounted costs or charges when you scope to an account or group of accounts (including a billing family).

For AWS clouds, Workload Optimization Manager can get the information it needs to display license costs for database instances. For Azure clouds, Workload Optimization Manager does not display database license costs because Azure does not make that information available.

Workload Mapping

This chart shows the types of tiers you currently use, compared to the tiers the plan recommends, including how many of each type, plus the costs for each.



To see a detailed breakdown of the template costs, click SHOW CHANGES at the bottom of the chart.


Volume Tier Summary

This chart shows the current distribution of volumes that support your workloads, and the optimized distribution if you execute the actions that the plan recommends.

The difference in the result reflects the number of unattached volumes. To see a list of unattached volumes, click **Show changes** at the bottom of the chart.

Discount Inventory

This chart lists the cloud provider discounts discovered in your environment. For a tabular listing, click **Show All** at the bottom of the chart. In the tabular listing, you can see if a discount expired before the specified purchase date.




Recommended RI Purchases

Workload Optimization Manager can recommend purchasing instance types at a discounted rate to help you increase the percentage of VMs covered by discounted pricing and reduce on-demand costs. This chart shows your pending purchases. Download the list of purchases and then send it your cloud provider or representative to initiate the purchase process.

NOTE:

Purchase actions should be taken along with the related VM scaling actions. To purchase discounts for VMs at their current sizes, run a <u>Buy VM Reservation Plan (on page 577)</u>.

Currently, Workload Optimization Manager can recommend purchase actions for AWS and Azure. Purchase actions for GCP will be introduced in a future release.



Click Show All to see a table with details for each discount.


The table shows the properties, up-front cost, and break-even period for each discount. The break-even period is the time at which savings will exceed the up-front cost, rounded to the month. The Cost Impact column indicates the monthly savings you would realize when you buy a specific discount.



When you choose one or more check boxes, the total count, up-front cost, and savings appear at the top.

Viewing Plan Actions


Click the Plan Actions tab on top of the page to view a list of actions that you need to execute to achieve the plan results.



Re-Running the Plan

You can run the plan again with the same or a different set of configuration settings. This runs the plan scenario against the market in its current state, so the results you see might be different, even if you did not change the configuration settings.

Use the toolbar on top of the Configuration section to change the configuration settings.



Actions

Use this to enable or disable automatic Scale actions for the virtual machines in the plan.

RI Settings
 See Reserved Instance Settings (on page 564).


NOTE:

It is not possible to change the scope of the plan in the Plan Page. You will need to start over if you want a different scope. To start over, go to the top-right section of the page, click the More options icon (!), and then select **New Plan**.

When you are ready to re-run the plan, click Run Again on the top-right section of the page.



Migrate to Cloud Plan



A Migrate to Cloud plan simulates migration of on-prem VMs to the cloud, or migration of VMs from one cloud provider to another. This plan focuses on optimizing performance and costs by choosing the most suitable cloud resources for your VMs and the volumes they use. To further optimize your costs, the plan can recommend moving workloads from on-demand to discounted pricing, and purchasing more discounts.

The plan calculates costs according to the billing and price adjustments that you have negotiated with your cloud provider. Costs include compute, service (such as IP services), and license costs. The plan also calculates discount purchases for VMs that can benefit from discounted pricing.

NOTE:

If your instance of Workload Optimization Manager is inoperative for a period of time, that can affect the cost calculations. To calculate costs for a VM that it will migrate to the cloud, Workload Optimization Manager considers the VM's history. For example, if the VM has been stable for 16 of the last 21 days, then Workload Optimization Manager will plan for that VM to use a discount. In this way, the plan calculates the best cost for the migration. However, if Workload Optimization Manager is inoperative for any time, that can impact the historical data such that the plan will *not* recognize a VM as stable, even though it is.

Points to consider:

- AWS includes EC2 Spot Instances that offer steep discounts. A plan that migrates from AWS to Azure will not migrate VMs that run on Spot Instances.
- Do not use this plan type to migrate within the same cloud provider (for example, moving VMs from one Azure subscription to another) as a way to test the effect on pricing. The results from such a plan would not be reliable.
- For migrations within your on-prem environment, use the *Virtual Machine Migration* plan type.
- Before migrating, consider turning on a setting in the default global policy that enables metrics collection for on-prem volumes attached to VMs. This allows Workload Optimization Manager to make more accurate placement decisions for the VMs and volumes you are migrating. For details, see Enable Analysis of On-prem Volumes (on page 679).

The plan results show:

- Projected costs
- Actions to execute your migration and optimize costs and performance
- Optimal cloud instances to use, combining efficient purchase of resources with assured application performance
- The cost benefit of moving workloads from on-demand to discounted pricing
- Discounts you should purchase




Configuring a Migrate to Cloud Plan

For an overview of setting up plan scenarios, see Setting Up Plan Scenarios (on page 531).

1. Scope


Select the VMs that you want to migrate. You can select VM groups and/or individual VMs.




If you select an Auto Scaling Group, Workload Optimization Manager simulates migrating the VMs individually, and not as a group.

2. Where to Migrate

Choose a billing account (AWS account or Azure subscription).



Choose a region. Workload Optimization Manager shows all the regions that you can access from your target cloud accounts.






By default, Workload Optimization Manager considers all instance types in the selected region when making placement decisions for the scoped VMs and the volumes they use. However, you may have set up constraints in policies that limit migration to certain instance types. If there are VMs and volumes in your scope that are affected by those policies, Workload Optimization Manager will only consider the instance types defined in the policies.

3. Licensing (OS Migration Profile)

Select an OS Profile for this migration.



On the cloud, instances usually include an OS platform to run processes on the VM. As you migrate VMs to the cloud, you can specify the OS you prefer to run. You can keep the same OS that the original VM has, or map it to a different OS.

■ Include OS cost

As Workload Optimization Manager calculates placement for the migrated workloads, it will include costs for instances that provide the same OS that the VM already has.

BYOL (Bring your own license)

This is the same as the **Include OS cost** option, except the plan does not include OS licensing costs in any of the cost calculations for on-cloud placement.

Custom OS


For each of the listed OS types, map the migrated VM to the OS you choose. The OS types are:

- Linux Any open source distribution of Linux. For the migration, Workload Optimization Manager will choose instances
 that provide the Linux platform that the cloud service provider delivers as a free platform. Note that this is always
 BYOL, because it assumes a free OS license.
- RHEL (Red Hat Enterprise Linux)
- SLES (SUSE Linux Enterprise Server)
- Windows

If you enable **BYOL** for RHEL, SLES, or Windows, Workload Optimization Manager assumes that you are paying for the OS license, and will not include the license cost in the plan results. If you do not enable **BYOL**, Workload Optimization Manager gets the license cost from the service provider and includes that cost in the plan results.



4. Reserved Instances Settings



For Plan RI Inventory, the discounts for the current scope are selected by default. Click Edit to make changes.

For **RI Purchase Profile**, the settings that you have set up for real-time analysis are selected by default. You can change the settings to see how they affect costs.

Offering Class

For AWS environments, choose the offering class that corresponds to the RI types that you typically use in your environment.

■ Term

For AWS and Azure environments, choose the payment terms you contract for your discounts. TERM can be one of **1 Year** or **3 Year**. Typically, longer term payment plans cost less per year.

Payment


The payment option that you prefer for your AWS RIs:

- All Upfront You make full payment at the start of the RI term.
- Partial Upfront You make a portion of the payment at the start of the term, with the remain cost paid at an hourly rate.
- No Upfront You pay for the RIs at an hourly rate, for the duration of the term.

Working With Migrate to Cloud Plan Results

The Migrate to Cloud plan results show the cloud resources and costs for the VMs you plan to migrate, and the actions required for migration.





Workload Optimization Manager shows results for two migration scenarios:

I ift & Shift

Lift & Shift migrates your VMs to cloud instances that match their current resource allocations.

Optimized

As Workload Optimization Manager runs the plan, it looks for opportunities to optimize cost and performance. For example, it might discover overprovisioned VMs after analyzing the historical utilization of VM resources. If you were to migrate such VMs to instances that match their current allocations, then you would spend more than necessary. For an optimized migration, Workload Optimization Manager can recommend migrating to less expensive instances while still assuring performance, and then show the resulting savings. In addition, when you examine the actions for an optimized migration, you will see charts that plot the historical utilization data used in the analysis.

Results Overview

The Results Overview section shows the following:

Unplaced VMs

If the plan's scope includes VMs that cannot be migrated, the results include a notification indicating the number of VMs. Click **Show Details** to see the list of VMs and the reasons for their non-placement.



The charts in the plan results do not count these VMs.

Workload Optimization Manager displays adjusted CPU values for unplaced VMs. These values are the actual metrics used in analysis and are calculated using <u>benchmark data</u>. CPU values shown in other places (such as the Capacity and Usage chart) are unadjusted values obtained from targets.

Cloud Cost Comparison Chart

This chart highlights any difference in cost as a result of optimization. For example, undersized VMs risk losing performance and should therefore scale up. This could contribute to an increase in cost. On the other hand, oversized VMs can scale down to less expensive instances, so cost should go down. The values under the % column indicate the percentage of VMs that are affected by optimization cost calculations.




CLOUD COST COMPARISON sws-US West (N. California)				
	LIFT & SHIFT (1)	OPTIMIZED ()	DIFFERENCE	%
Virtual Machines with performance risks	99 out of 684	0 out of 687	99	-
Virtual Machines with efficiency opportunities 🌘	588 out of 684	0 out of 687	588	
On-Demand Compute Cost 🔞	\$113,460 /mo	\$23,214 /mo	-\$90,246 /mo	₹ 79.5 9
Reserved Compute Cost	\$9,816 /mo	\$19,229 /mo	\$9,413 /mo	▲ 95.9 9
Storage Cost	\$32,183 /mo	\$40,397 /mo	\$8,214/mo	▲ 25.5 9
Total Cost	\$155,459 /mo	\$82,840 /mo	-\$72,619 /mo	₹46.79

NOTE:

For Azure, the results do not include the license cost for the migrated VMs.

■ Virtual Machine Mapping Chart


This chart gives a breakdown of the instance types that the plan recommends for the migration, including how many of each is needed.



Click **Show Changes** to see a table with details for each VM in the plan. The table maps VMs to instance types. It also shows the properties and monthly cost for each instance type, and indicates whether Workload Optimization Manager recommends buying discounts. Under the **Actions** column, click **Details** to compare Lift & Shift and Optimized actions.

■ Volume Tier Summary Chart

This chart gives a breakdown of the volume types that the plan recommends for the migration, including how many of each is needed.



Click **Show Changes** to see a table with details for each volume in the plan. The table maps the volumes you plan to migrate to the volume types that Workload Optimization Manager recommends. It also shows the properties and monthly cost for each volume type. Under the **Actions** column, click **Details** to compare Lift & Shift and Optimized actions.

Recommended RI Purchases Charts




Workload Optimization Manager can recommend purchasing instance types at a discounted rate to help you increase the percentage of VMs covered by discounted pricing and reduce on-demand costs. This chart shows your pending purchases. Download the list of purchases and then send it your cloud provider or representative to initiate the purchase process.

NOTE:

Purchase actions should be taken along with the related VM scaling actions. To purchase discounts for VMs at their current sizes, run a <u>Buy VM Reservation Plan (on page 577)</u>.

Currently, Workload Optimization Manager can recommend purchase actions for AWS and Azure. Purchase actions for GCP will be introduced in a future release.



To identify VMs that are good candidates for discounted pricing, Workload Optimization Manager analysis considers the history of a VM (by default, the last 21 days), and it looks for:

- Activity
 - If the VM's VCPU utilization percentile is 20% or higher, then Workload Optimization Manager considers it an active VM.
- Stability

If there have been no start, stop, or resize actions for the VM for 16 of the last 21 days, then Workload Optimization Manager considers it stable.

If the current discount inventory cannot support the VM, or if supporting it would exceed your desired coverage, then Workload Optimization Manager can recommend purchasing additional discounts.

Click Show All to see a table with details for each discount.

The table shows the properties, up-front cost, and break-even period for each discount. The break-even period is the time at which savings will exceed the up-front cost, rounded to the month. The Cost Impact column indicates the monthly savings you would realize when you buy a specific discount.

When you choose one or more check boxes, the total count, up-front cost, and savings appear at the top.

Click **Details** under the **Actions** column to compare Lift & Shift and Optimized actions.

NOTE:

The plan assumes that a discount will always be less expensive than its on-demand counterpart. However, this is not always the case. There might be billing details from service providers that could lead to recommendations to move to a discounted instance type that is more expensive than running on demand.


Plan Actions

Workload Optimization Manager shows separate tabs for **Lift & Shift** and **Optimized** migration actions. You can download the list of actions as a CSV file.





For *Optimized* migrations, when you expand an action on a VM, you will see charts that track VCPU and VMem utilization for that VM. With these charts, you can easily recognize the utilization trends that Workload Optimization Manager analyzed to determine the most efficient instance for the VM.



For more information about these charts, see Utilization Charts (on page 515).

Uploading Plan Results to Azure Migrate

Workload Optimization Manager can upload the plan results and additional plan information to the Azure Migrate portal as part of your migration process. This feature is only available for plans that simulate on-prem VM migration to an Azure region.

Uploaded information includes:

- Basic information for the on-prem VMs, including OS Name and Machine Name
- Target Azure region, VM size, and storage type

NOTE:

Azure Migrate does not support automatic selection of OS Disk or manual selection of Ultra Storage disk tiers as part of a migration plan.

- Discount recommendations
- OS license recommendations (based on the licensing option that you selected for the plan)

NOTE:

The Azure Migrate portal displays standardized information provided by third-party migration assessment solutions, including Workload Optimization Manager. Microsoft might not support displaying some information unique to Workload Optimization Manager.




Before uploading the results, be sure to complete the following tasks:

- 1. Create a project in the Azure Migrate portal.
- 2. Add Workload Optimization Manager as a migration assessment solution to the project.
- 3. Set the necessary permissions in the Azure Migrate portal. For details about permissions, see <u>Azure Service Principal and Subscription Permissions</u> (on page 275).

Consult the Azure documentation for information on completing these tasks.

When you are ready to upload:

1. Click **Upload** at the top-right corner of the Plan Page.



2. Specify the following:

Migration Plan Type

Choose to migrate either the 'Lift & Shift' or 'Optimized' results.

Plan Destination (Migrate Project)

Select from the list of Azure Migrate projects. These are the projects belonging to the Azure subscription that you selected for the plan. If you have not created a project for the subscription, go to the Azure Migrate portal and create one.

WARNING:

Uploading to a project with existing plan results overwrites those results.

The upload will fail if another upload targeted at the same destination is already in progress.

Click Submit.

The Plan Page updates to display the upload status. Refresh the page periodically to check:

- If the upload task completed without problems
- Any upload issues for individual entities
- 4. When the upload is complete, log in to the Azure Migrate portal and go to the project you selected as the plan destination.

The project should now display the uploaded information. Use the migration tools identified for the project to start the actual migration.

NOTE

Repeat the upload procedure if you re-ran the plan and want to upload the new results.



Re-Running the Plan


You can run the plan again with the same or a different set of configuration settings. This runs the plan scenario against the market in its current state, so the results you see might be different, even if you did not change the configuration settings. Use the toolbar on top of the Configuration section to change the configuration settings.

NOTE:

It is not possible to change the scope of the plan in the Plan Page. You will need to start over if you want a different scope. To start over, go to the top-right section of the page, click the More options icon (), and then select **New Plan**.

When you are ready to re-run the plan, click Run Again on the top-right section of the page.

Buy VM Reservations Plan



Run the Buy VM Reservations plan to see discount purchase opportunities that can significantly reduce on-demand costs for your cloud VMs. When calculating purchases, Workload Optimization Manager evaluates all purchasing options for your selected scope and usage data for the VMs in that scope. It then compares your current costs to the costs you would get after executing the plan recommendations.


Currently, Workload Optimization Manager can recommend purchase actions for AWS and Azure. Purchase actions for GCP will be introduced in a future release.

Configuring a Buy VM Reservations Plan

For an overview of setting up plan scenarios, see Setting Up Plan Scenarios (on page 531).



1. Scope



You can scope by:

Accounts

Choose AWS accounts or Azure subscriptions for the plan's scope.

Billing Families

Include discount purchases for a billing family. The plan calculates discount purchases through the billing family's master account.

Cloud Providers


See purchase opportunities for your AWS or Azure environment.

■ Regions

Focus the plan on a cloud provider's region.



2. RI Settings



Purchase RIs

Allow the plan to buy discounts based on the following configurations:

Profile

The settings that you have set up for real-time analysis are selected by default. You can change the settings to see how they affect costs.

- Offering Class

For AWS environments, choose the offering class that corresponds to the RI types that you typically use in your environment.

Term

For AWS and Azure environments, choose the payment terms you contract for your discounts. TERM can be one of **1 Year** or **3 Year**. Typically, longer term payment plans cost less per year.

- Payment

The payment option that you prefer for your AWS RIs:

- All Upfront You make full payment at the start of the RI term.
- Partial Upfront You make a portion of the payment at the start of the term, with the remain cost paid at an hourly
- No Upfront You pay for the RIs at an hourly rate, for the duration of the term.

Virtual Machine Usage

Specify the time frame you want the plan to use when it calculates your discount purchases.

Terminated Virtual Machines

- Only use data from active VMs Select this option if you terminate your VMs permanently.
- Use data from active and deleted VMs (Support CI/CD pipeline) Select this option if you want to use data from a CI/CD pipeline that regularly deploys and terminates VMs.




Discount Inventory

Select your discount inventory for the plan. You can use the default selection or any of the available discounts for your scope.

Working With Buy VM Reservations Plan Results

After the Buy VM Reservations runs, you can view the results to see discount and optimization opportunities for your cloud environment.



Viewing the Results

The plan results include the following charts:

■ Cloud Cost Comparison

This chart highlights changes to your existing discount coverage and utilization if you execute all the actions that the plan recommends. Actions include increasing coverage or purchasing additional instance types at a discounted rate. Your cloud provider will adjust discount allocations when the actions have completed.


- Analysis evaluates ways to increase your current discount coverage so you can take full advantage of discounted pricing.
- The plan can recommend purchase actions to reduce your costs further. The analysis looks at historical VM usage and
 uptime to arrive at the number of instance types you should purchase.

You can compare current and after-action costs, including on-demand compute, discounted compute, and total costs. Purchase actions increase your discounted compute cost, but can lower your on-demand compute cost significantly as discount coverage increases. The end result is a reduction to your total cost.

Virtual Machine Mapping

This chart shows the instance types for the VMs included in the plan.






Click **Show Changes** to see details for each VM with discount coverage changes. The table maps VMs to instance types, and shows how changes in discount coverage can reduce on-demand cost.


Discount Inventory

This chart lists the cloud provider discounts discovered in your environment. For a tabular listing, click **Show All** at the bottom of the chart. In the tabular listing, you can see if a discount expired before the specified purchase date.



■ Recommended RI Purchases

Workload Optimization Manager can recommend purchasing instance types at a discounted rate to help you increase the percentage of VMs covered by discounted pricing and reduce on-demand costs. This chart shows your pending purchases. Download the list of purchases and then send it your cloud provider or representative to initiate the purchase process.



Click Show All to see a table with details for each discount.




The table shows the properties, up-front cost, and break-even period for each discount. The break-even period is the time at which savings will exceed the up-front cost, rounded to the month. The Cost Impact column indicates the monthly savings you would realize when you buy a specific discount.

When you choose one or more check boxes, the total count, up-front cost, and savings appear at the top.

Viewing Plan Actions

Click the Plan Actions tab on top of the page to view a list of actions that you need to execute to achieve the plan results.



Re-Running the Plan

You can run the plan again with the same or a different set of configuration settings. This runs the plan scenario against the market in its current state, so the results you see might be different, even if you did not change the configuration settings.

Use the toolbar on top of the Configuration section to change the configuration settings.

- RI Settings
 - Update your purchase settings to see how they impact results. For example, you can configure a longer timeframe so that the plan can include additional VM usage data in its analysis. For details, see <u>Purchase Rls (on page 579)</u>.
- Discount Inventory
 - Use the default selection or any of the available discounts for your scope.


NOTE:

It is not possible to change the scope of the plan in the Plan Page. You will need to start over if you want a different scope. To start over, go to the top-right section of the page, click the More options icon (), and then select **New Plan**.

When you are ready to re-run the plan, click Run Again on the top-right section of the page.



Alleviate Pressure Plan



Use the Alleviate Pressure plan to find out how to migrate workloads from a stressed or *hot* cluster over to a cluster with more headroom. This plan shows the minimal changes you need to make to reduce risks on the hot cluster.

The plan results:

- Show the actions to migrate workloads from the hot cluster to the cold one
- Compare the current state of your clusters to the optimized state
- Show resulting headroom for both the hot and the cold clusters
- Show trends of workload-to-inventory over time for both clusters

Alleviate Pressure plans make use of the headroom in your clusters. Headroom is the number of VMs the cluster can support, for CPU, Memory and Storage.

To calculate cluster capacity and headroom, Workload Optimization Manager runs nightly plans that take into account the conditions in your current environment. The plans use the Economic Scheduling Engine to identify the optimal workload distribution for your clusters. This can include moving your current VMs to other hosts within the given cluster, if such moves would result in a more desirable workload distribution. The result of the plan is a calculation of how many more VMs the cluster can support.

To calculate VM headroom, the plan simulates adding VMs to your cluster. The plan assumes a certain capacity for these VMs, based on a specific VM template. For this reason, the count of VMs given for the headroom is an approximation based on that VM template.

To specify the templates these plans use, you can configure the nightly plans for each cluster. For more information, see Configuring Nightly Plans (on page 596)



NOTE:


To execute, this plan must ignore certain constraints. The plan ignores cluster constraints to allow migrating workloads from the hot cluster to the cold one. It also ignores network constraints, imported DRS policies, and any Workload Optimization Manager that would ordinarily be in effect.

Configuring an Alleviate Pressure Plan

For an overview of setting up plan scenarios, see Setting Up Plan Scenarios (on page 531).


1. Scope

The wizard first gives you a list for you to choose the hot cluster. This is the cluster that shows risks to performance. The list sorts with the most critical clusters first, and it includes the calculated headroom for CPU, Memory, and Storage in each cluster.



2. Cold Cluster

After you select the hot cluster, choose the cold cluster.



Working With Alleviate Pressure Plan Results

After the plan runs, you can view the results to see how the migration of workloads off of your hot cluster affects your environment.





Viewing the Results

The results include the following charts:

Plan Actions

You can see a list of actions to reduce the pressure on the hot cluster. It's typical to see actions to move workloads from the hot cluster over to the cold cluster. If some VMs are overprovisioned, you might see actions to reduce the capacity for those workloads.

Hosts Optimized Improvements

This chart compares the current state of the hot cluster to its state after executing the plan actions. It displays the resource utilization of the cluster's hosts both before and after the plan.

Headroom

With these charts, you can compare the headroom between the hot and cold clusters.

Virtual Machines vs Hosts and Storage

This chart shows the total number of virtual machines, hosts, and storage in your on-prem environment, and tracks the data over time. Chart information helps you understand and make decisions around capacity and utilization, based on historical and projected demand.

Re-Running the Plan

You can run the plan again with the same or a different set of configuration settings. This runs the plan scenario against the market in its current state, so the results you see might be different, even if you did not change the configuration settings.

Use the toolbar on top of the Configuration section to change the configuration settings.





The toolbar items that display are similar to the toolbar items for a custom plan. For details, see <u>Configuring a Custom Plan (on page 586)</u>.


NOTE:

It is not possible to change the scope of the plan in the Plan Page. You will need to start over if you want a different scope. To start over, go to the top-right section of the page, click the More options icon (), and then select **New Plan**.

When you are ready to re-run the plan, click Run Again on the top-right section of the page.

Custom Plan

For an overview of setting up plan scenarios, see Settings Up User Plan Scenarios (on page 531).



When you create a custom scenario, you specify the plan scope as an initial step, and then skip the plan wizards and jump straight into setting up the plan parameters. You can name the plan, change workload demand and the supply of resources, and specify other changes to the plan market.


Configuring a Custom Plan

For an overview of setting up plan scenarios, see Setting Up Plan Scenarios (on page 531).

1. Scope

Specify the plan scope and then click **Configure Plan** at the bottom of the page.





2. Plan Configuration

Use the Plan Configuration toolbar to fine-tune your plan settings. You can change workload demand and the supply of resources, and specify other changes to the plan market.



2.1. Add

Add virtual machines, hosts, or storage to your plan. For example, when you add hosts, you increase the compute resources for the plan.




Copy from an Entity or Template

Choose an entity or template to copy. This describes the new entities that Workload Optimization Manager will add to the plan. For example, you can run a plan that adds new VMs to a cluster. If you copy from a template, then the plan adds a new VM that matches the resource allocation you have specified for the given template.

Option 1: Copy from an entity





Option 2: Copy from a template

If no existing template is satisfactory, create one by clicking **New Template**.



NOTE:

Workload Optimization Manager automatically adds any new template you create to the Template Catalog page (Settings > Templates).


It is not possible to use templates for containers or container pods.

Use the **Filter** option to show entities or templates with certain properties (name, number of CPUs, etc.). This makes it easier to sort through a long list.

Number of Copies to Add

After choosing an entity or template, it appears as an entry in the Configuration summary. Then you can set how many copies to add.






2.2. Replace



Replacing virtual machine is a way to change the properties of VMs in your plan market. When you replace workload, you select one or more VMs that you want to change, and then you select a template to use in their place. The list of changed VMs displays in the Configuration Summary. You can delete individual entries from the this summary if necessary.

Replacing hosts or storage is a way to plan for a hardware upgrade. For example, if you replace your hosts or datastores with a more powerful template, the plan might show that you can use fewer hosts or datastores, and it will show the best placement for workloads on those entities. You begin by selecting the entities you want to replace, and when you click **REPLACE** you can then choose a template that will replace them. Note that you can only choose a single template for each set of entities you want to have replaced. You can configure different replacements in the same plan, if you want to use more than one template.

2.3. Remove



Removing virtual machines frees up resources for other workloads to use.

Removing hosts or storage means you have fewer compute or storage resources for your workloads. If you think you have overprovisioned your environment, you can run a plan to see whether fewer hosts or less storage can still support the same workload.



2.4. Actions



See the effect of enabling or disabling actions on the entities included in the plan. For example, you might plan for more workload but know that you don't want to add more hardware, so you disable Provision of hosts for your plan. The results would then indicate if the environment can support the additional workload.

2.5. Ignore Constraints

Choose to ignore constraints (such as placement policies) for VMs in your environment.



By default, VMs are constrained to the cluster, network group, datacenter, or storage group that their hosts belong to. You can choose to ignore these boundaries.

For example, by default a plan does not consider moving VMs to physical hosts outside of the current cluster. If you disable the Cluster constraint for a VM in your plan, then the plan can evaluate the results of hosting those VMs on any other physical machine within the scope of your plan. If the best results come from moving that VM to a different cluster, then the plan will show that result.

NOTE:

If you are adding hosts to a plan, and use host templates, then you must turn on Ignore Constraints.

2.6. Placement Policies

By default, the plan includes all the placement policies that apply to the plan scope. Also, these policies are in their real-time state (enabled or disabled).



You can use these settings to enable or disable existing policies, or you can create new policies to apply only to this plan scenario. For information about creating placement policies, see <u>Placement Policies</u> (on page 673).



2.7. Utilization

Setting utilization by a certain percentage is a way to increase or decrease the workload for the scope of your plan and any entity added to the plan, or for specific groups. Workload Optimization Manager uses the resulting utilization values as the baseline for the plan.




Max Host Utilization levels specify the percentage of the physical resource that you want to make available in the given plan. By default, hosts have utilization set to 100%. For a given plan, you can set the utilization to a lower value. For example, assume you want to simulate High Availability of 25% for some hosts in the plan. In that case, you can select these hosts and set their utilization levels to 75%.

Max Storage utilization levels specify the percentage of the physical resource that you want to make available in the given plan. By default, storage has utilization set to 100%. For a given plan, you can set the utilization to a lower value. For example, assume you have one data store that you want to share evenly for two clusters of VMs. Also assume that you are creating a plan for one of those clusters. In that case, you can set the datastores to 50% utilization. This saves storage resources for the other cluster that will use this storage.

2.8. Baseline

Use these settings to set up the baseline of utilization metrics for your plan.




By default, the plan runs against the current state of your environment. You can set up the plan to add or remove entities, or otherwise affect the plan calculations. But the utilization metrics will be based on the current state of the plan. If you run the same plan multiple times, each run begins with a fresh view of your inventory.

You can select from the list of snapshots to load the utilization statistics from a previous time period into the plan. Use this to run the plan against utilization that you experienced in the past. For example, assume a peak utilization period for the month before the winter holidays. During the holidays you want to plan to add new capacity that can better handle that peak. You would set the baseline to the utilization you saw during that pre-holiday peak.



2.9. Desired State

The desired state is a condition in your environment that assures performance for your workloads, while it utilizes your resources as efficiently as possible and you do not overprovision your infrastructure. Workload Optimization Manager uses default Desired State settings to drive its analysis. You should never change the settings for real-time analysis unless you are working directly with Technical support. However, you can change the settings in a plan to see what effect a more or less aggressive configuration would have in your environment.



You can think of the desired state as an n-dimensional sphere that encompasses the fittest conditions your environment can achieve. The multiple dimensions of this sphere are defined by the resource metrics in your environment. Metric dimensions include VMem, storage, CPU, etc. While the metrics on the entities in your environment can be any value, the desired state, this n-dimensional sphere, is the subset of metric values that assures the best performance while achieving the most efficient utilization of resources that is possible.


The Desired State settings center this sphere on Performance (more infrastructure to supply the workload demand), or on Efficiency (less investment in infrastructure to supply the workload demand). The settings also adjust the diameter of the sphere to determine the range of deviation from the center that can encompass the desired state. If you specify a large diameter, Workload Optimization Manager will have more variation in the way it distributes workload across hosting devices.

For more information, see The Desired State (on page 101).

Working With Custom Plan Results

After the plan runs, you can view the results to see how the plan settings you configured affect your environment.





Viewing the Results

The results include the following charts:

■ Plan Summary Chart

This chart compares your current resources to the resources you would get after executing the plan.

NOTE:

Under some circumstances, this chart might not count "non-participating" entities in the real-time market, such as suspended VMs or hosts in a failover state. The following charts, on the other hand, count all entities in the real-time market, regardless of state:

- Scope Preview chart (displays before you run the plan)
- Optimized Improvements and Comparison charts

If the plan's scope includes VMs that cannot be placed, the results include a notification indicating the number of VMs. Click **Show Details** to see the list of VMs and the reasons for their non-placement.

Click Show all at the bottom of the chart to see savings or investment costs, or to download the chart as a CSV file.

■ Plan Actions Chart

This chart summarizes the actions that you need to execute to achieve the plan results. For example, if you run an Alleviate Pressure plan, you can see actions to move workloads from the hot cluster over to the cold cluster. If some VMs are overprovisioned, you might see actions to reduce the capacity for those workloads.

The text chart groups actions by action type (on page 526). The list chart shows a partial list of actions (on page 508).






To view action details or download the list of actions as a CSV file:

- Click an action type in the text chart or an individual action in the list chart.
- Click Show All at the bottom of the chart.

Optimized Improvements Charts for Hosts, Storage, and Virtual Machines

The Optimized Improvements chart shows how the utilization of resources would change assuming you accept all of the actions listed in the Plan Actions chart.



In many of these charts, you can change the commodities on display. To do this, go to the top-right section of the chart, click the More options icon (), and then select Edit. In the new screen that displays, go to the Commodity section and then add or remove commodities.


To restore the default commodities, use the Reset view option at the top-right section of the page.

 Click Show all at the bottom of the chart to see a breakdown of the current chart data by entity (for example, show CPU, Memory, and IO Throughput utilization for each host), or to download chart data as a CSV file.

Comparison Charts for Hosts, Storage Devices, and Virtual Machines

A Comparison chart shows how the utilization of a particular commodity (such as memory or CPU) for each entity in the plan would change if you execute the actions listed in the Plan Actions chart.





 To change the commodity displayed in the chart, go to the top-right section of a chart and then select from the list of commodities.

To restore the default commodity, go to the top-right section of the page, click the More options icon (i), and then select **Reset view**.

 Click Show all at the bottom of the chart to show a breakdown of the current chart data by entity (for example, show Virtual Memory utilization for each virtual machine), or to download the chart as a CSV file.

NOTE:

For the Storage Devices Comparison chart, if you set the view to **VM Per Storage** and click **Show all**, the total number of VMs sometimes does not match the number in the Plan Summary chart. This happens if there are VMs in the plan that use multiple storage devices. The Storage Devices Comparison chart counts those VMs multiple times, depending on the number of storage devices they use, while the Plan Summary chart shows the actual number of VMs.

Re-Running the Plan

You can run the plan again with the same or a different set of configuration settings. This runs the plan scenario against the market in its current state, so the results you see might be different, even if you did not change the configuration settings.

Use the toolbar on top of the Configuration section to change the configuration settings.



For details about these settings, see Configuring a Custom Plan (on page 586).


NOTE:

It is not possible to change the scope of the plan in the Plan Page. You will need to start over if you want a different scope. To start over, go to the top-right section of the page, click the More options icon (), and then select **New Plan**.

When you are ready to re-run the plan, click Run Again on the top-right section of the page.



Configuring Nightly Plans



Workload Optimization Manager runs nightly plans to calculate headroom for the clusters in your on-prem environment. For each cluster plan, you can:

- 1. View the plan and its template.
- 2. Expand to see template details.
- Set which VM template to use in these calculations.


For information about viewing cluster headroom, see Viewing Cluster Headroom (on page 134).

To calculate cluster capacity and headroom, Workload Optimization Manager runs nightly plans that take into account the conditions in your current environment. The plans use the Economic Scheduling Engine to identify the optimal workload distribution for your clusters. This can include moving your current VMs to other hosts within the given cluster, if such moves would result in a more desirable workload distribution. The result of the plan is a calculation of how many more VMs the cluster can support.

To calculate VM headroom, the plan simulates adding VMs to your cluster. The plan assumes a certain capacity for these VMs, based on a specific VM template. For this reason, the count of VMs given for the headroom is an approximation based on that VM template.

To set templates to use for the nightly plans:

Navigate to the Plan Page and click NIGHTLY PLAN CONFIGURATION.



This displays a list of all the nightly plans. Workload Optimization Manager creates a nightly plan for each cluster.




- 2. Click the plan that you want to configure.
 - A fly-out appears that lists all the available templates.
- 3. Select the template you want for this plan.

Choose the template and click Select.

Park: Stop or Start Cloud Resources

Workload Optimization Manager supports 'parking' actions for cloud resources. These actions *stop* your cloud resources for a given period of time to help you reduce your cloud expenses, and then *start* these resources later when you need them. You can enforce parking actions on demand, or automatically via parking schedules and policies.

When you click Park on the main menu, the user interface displays a list of parkable entities discovered from cloud targets.



The following table describes the current level of support for parking actions.

Supported Entity	Parkable	Not Parkable
VM	VMs discovered via AWS, Azure, and GCP targets	VMs on consistent scaling groups, auto scaling groups, or scale sets
Database Server	AWS RDS instances NOTE: AWS provides guidelines and caveats for parking actions. For example, your accounts will continue to incur certain charges while instances are stopped. For details, visit this AWS page.	AWS RDS clusters and cluster members

Permissions

Be sure that your cloud targets have the required permissions so that Workload Optimization Manager can enforce parking actions. For a full list of permissions, see the following topics:

- AWS Permissions (on page 242)
- Azure Permissions (on page 275)
- GCP Permissions (on page 264)



Notice for Updated Workload Optimization Manager Instances

If you updated your Workload Optimization Manager instance from version 3.5.0 (or older) and noticed that the parking feature is missing in the user interface, perform the following steps in your updated instance:

1. Open charts_vlalpha1_xl_cr.yaml for editing.

vi /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalpha1_xl_cr.yaml

2. In the suspend section, change the value for enabled to true.

```
# Suspend service selector
suspend:
    enabled: true
```

Apply the change.

kubectl apply -f /opt/turbonomic/kubernetes/operator/deploy/crds/charts_v1alpha1_x1_cr.yaml

4. Restart the UI and API pods.

```
kubectl delete pod <ui-podname>
kubectl delete pod <api-podname>
```

How Parking Works

Cloud VMs and Database Servers that become idle for a period of time (for example, after business hours) and those that undergo regular maintenance are ideal for parking. When parking actions are enforced, Workload Optimization Manager reverses any conflicting actions on these entities. For example, when a VM has been started via Workload Optimization Manager and a user stops the VM via the cloud provider, Workload Optimization Manager will start the VM after a subsequent discovery cycle.

When a scaling action is in progress, Workload Optimization Manager postpones a stop or start action until the scaling action completes.

Enforcing Parking Actions

There are several ways to enforce parking actions.

Execute actions on demand.

Use the Parking page to execute parking actions on individual entities. For details, see <u>Executing Parking Actions (on page</u> 599).

Attach a parking schedule to one or several entities.

Use the Parking page to attach a parking schedule to one or several entities. You must create parking schedules as a prerequisite. For details, see <u>Managing Parking Schedules (on page 707)</u> and <u>Scheduling Parking Actions (on page 600)</u>.

NOTE:

When you execute a parking action on demand and the affected entity has an existing schedule, a system prompt notifies you to pause the schedule before executing the action. This prevents potential conflicts between on-demand and scheduled parking actions.

Create parking policies.

Use parking policies to enforce actions dynamically and at scale. For example, you can create a parking policy at the cloud provider level so that all existing and newly discovered parkable entities from a specific cloud provider are parked uniformly.

Use the Policy Management page to create parking policies. For details, see Parking Policies (on page 700).

Parking policies take precedence over the other enforcement methods. For example, if a parking policy dictates that a VM must be running everyday from 9:00 AM to 6:00 PM, and a Workload Optimization Manager user manually stopped the VM from the Parking page at 3:00 PM, the VM will be started to comply with the parking policy.



General Guidelines

Be aware of the following as you manage parking actions.


- To see and download a list of parking (and non-parking) actions that have been executed successfully, add the All Actions chart to your dashboard and use the tabular view.
- Currently, actual savings associated with parking actions are not reflected in the Parking page or the Cumulative Savings chart.

For VMs, the Cost column in the Parking page shows the estimated on-demand monthly cost for a VM, for your reference.

Working with the Parking Page

After discovering parkable cloud VMs and Database Servers, Workload Optimization Manager adds them to the Parking page and shows their state (stopped or running) at the time of discovery. The page shows VMs and Database Servers as separate groups, so you can manage them efficiently.

Use the Parking page to execute parking actions or attach parking schedules to these entities.



NOTE:

Users with the Site Administrator, Administrator, or Automator role can manage the parking actions and settings in the Parking page. Users with other roles have read-only access to the page. For details about roles, see Managing User Accounts (on page 723).

General tasks:

- For a long list of entities, you can type a search keyword or add filters to narrow the results.
- To set an entity as your scope, click the entity name.
- To download the data in the Parking page, click the download button at the top-right section of the page.


Executing Parking Actions

Parking actions can only be executed from the Parking page. The Pending Actions, Potential Savings, and Top Accounts charts in the Home Page only show the non-parking actions that you can execute.

You can execute parking actions in the following ways:

■ For individual entities, use the toggle under the State column to change the currently enforced parking action.





Select one or several entities with the same state, and then click Stop or Start.



In the All Actions chart, the tabular view shows the following information for the parking actions that you executed:



- Execution: Manually Accepted
- Risk Type: Savings (stop actions) or Efficiency Improvement (start actions)

Scheduling Parking Actions

Attach a parking schedule to one or several entities to ensure that parking actions occur automatically at the appropriate times. You must create parking schedules as a prerequisite. For instructions on creating parking schedules, see Managing Parking Schedules (on page 707).


NOTE:

Use <u>parking policies</u> (on page 700) to schedule parking actions at scale. The parking schedules that you set up can be reused in these policies.

Parking actions cannot be scheduled using <u>automation policies</u> (on page 396) for cloud VMs and Database Servers. Automation policies (and the schedules configured in these policies) only apply to scale actions.

To attach a schedule, select one or several entities without a schedule and then select **Attach** from the dropdown at the top-left section of the page. In the Parking Schedule page, choose from a list of previously configured schedules.






If no schedule is suitable or available, create one by clicking **New** at the top-right section of the Parking Schedule page. Be aware that a schedule created this way will immediately apply to the entities in scope. If this is not your preference, create a new schedule by navigating to **Settings > Schedule** and then clicking **New Schedule > Parking Schedule**.

After attaching a schedule, the name of the schedule appears under the **Schedule** column. Click the name to view the settings for that schedule. To edit the settings, navigate to **Settings > Schedule** and then open the schedule for editing.

In the All Actions chart, the tabular view shows the following information for scheduled parking actions that have been executed:



- Execution: Automatically Accepted
- Risk Type: Savings (stop actions) or Efficiency Improvement (start actions)

Changing a Parking Schedule

To change the schedule currently attached to an entity, select the entity and then select **Attach** from the dropdown at the top-left section of the page. In the Parking Schedule page, click **Change Schedule** and then choose from a list of previously configured schedules (or create a new one). When you are done, the new schedule displays under the **Schedule** column.



You can select multiple entities, as long as those entities share the same schedule.




Pausing a Parking Schedule

You can pause schedule enforcement for a given period of time. For example, you can pause during non-typical work hours or when an unanticipated maintenance window requires automation outside Workload Optimization Manager to start and stop workloads. If the entity was running, it keeps running. If it was stopped, it stays stopped.


To pause a parking schedule, select one or several entities with a schedule, and then select **Pause** from the dropdown at the top-left section of the page. In the Pause Schedule page, specify the duration of the pause.



An icon appears before the name of the schedule to indicate that it has been paused.



The parking schedule will resume automatically when the pause period is over. To manually resume the schedule, select the affected entities, and then select **Attach** from the dropdown at the top-left section of the page. In the Parking Schedule page, click **Resume Schedule**.




NOTE:

When you execute a parking action on demand and the affected entity has an existing schedule, a system prompt notifies you to pause the schedule before executing the action. This prevents potential conflicts between on-demand and scheduled parking actions.

Detaching a Parking Schedule

You can detach parking schedules anytime. Select one or several entities with schedules, and then select **Detach** from the dropdown at the top-left section of the page.





Place: Reserve Workload Resources

From the Workload Placement Page, you can set up reservations to save the resources you will need to deploy VMs at a future date. Workload Optimization Manager calculates optimal placement for these VMs and then reserves the host and storage resources that they need.

To reserve VMs, you will need to choose a VM template, specify any placement constraints, set how many instances to reserve, and then indicate whether to reserve now or in the future. Because reserved VMs do not yet exist, they do not participate in the real-time market.

About VM Templates for Reservations

VM templates specify the resource requirements for each reserved VM, including:

- Compute and storage resources allocated to each VM
- Consumed factor. This is the percentage of allocated CPU, memory, or storage that the reserved VM will utilize.

For more information about these templates, see VM Template Settings (on page 710).

About Placement of Reserved VMs

To determine the best placement for the VMs you want to reserve, Workload Optimization Manager runs a plan using the last-generated data in nightly-run headroom plans.

NOTE:

If you have changed your environment by adding targets or changing policies, wait until the next run of headroom plans for the affected scope before you create reservations.

When making placement decisions, Workload Optimization Manager considers the following:

- Placement constraints set in the reservation
- Demand capacity

Workload Optimization Manager calculates demand based on the *resource allocation* and *consumed factor* set in VM templates. For example, if you want to create a reserved VM from a template that assigns 3 GB of virtual memory and a consumed factor of 50%, Workload Optimization Manager calculates 1.5 GB of demand capacity for the reservation.

Overprovisioned capacity

For reserved VMs, this corresponds to the resource allocation set in VM templates. Continuing from the previous example, Workload Optimization Manager assumes 3 GB of overprovisioned capacity for a reserved VM created from a template that assigns 3 GB of virtual memory.

For providers (hosts and storage), Workload Optimization Manager calculates overprovisioned capacity. The default overprovisioned capacity is 1000% for host Mem and CPU, and 200% for storage. A host with 512 GB of memory will have an overprovisioned capacity of 5 TB (5120 GB).

Providers must have sufficient *demand* and *overprovisioned* capacity to place a reservation. Workload Optimization Manager analyzes the current and historical utilization of cluster, host, and storage resources to identify viable providers for the VMs when they are deployed to your on-prem environment. In this way, Workload Optimization Manager can prevent congestion issues after you deploy the VMs.



NOTE:

Workload Optimization Manager persists historical utilization data in its database so it can continue to calculate placements accurately when market analysis restarts.

The initial placement attempt either succeeds or fails.

Successful Initial Placements

If the initial placement attempt is successful, Workload Optimization Manager adds the reserved VM to your inventory.

In the previous example, a reserved VM that requires 1.5 GB of demand capacity and 3 GB of overprovisioned capacity can be placed on a host with 512 GB of memory (5 TB of overprovisioned capacity), assuming no constraints will prevent the placement.

Note that *actual* and *reserved* VMs share the same resources on providers. This means that provider capacity will change as demand from the actual VMs changes. Workload Optimization Manager polls your environment once per day to identify changes in provider capacity. It then evaluates if it can continue to place the reserved VMs *within the same cluster*, and then shows the latest placement status.

For example, if the host for a reserved VM is congested at the time of polling, Workload Optimization Manager might decide to move the VM to another host in the cluster that has sufficient capacity. In this case, the placement status stays the same (**Reserved**). Should you decide to deploy the VM at that point, you need to deploy it to the new host. If, on the other hand, there is no longer a suitable host in the cluster, the placement fails and the status changes to **Placement Failed**. Deploying the VM at that point will result in congestion. Workload Optimization Manager will *not* retry fulfilling the reservation.

Failed Initial Placements

If the initial placement attempt is unsuccessful (for example, if all providers have seen historical congestion), Workload Optimization Manager shows that the placement has failed and will *not* retry fulfilling the reservation.

Current and Future Reservations

You can create a current or future reservation from the Workload Placement Page.

Current Reservation

Workload Optimization Manager calculates placement immediately and then adds the reserved VMs to your inventory if placement is successful.

This reservation stays in effect for 24 hours, or until you delete it.

Future Reservation

Set the reservation for some time in the future.

Workload Optimization Manager does not calculate placement at this time – the future reservation saves the definition, and Workload Optimization Manager will calculate placement at the time of the reservation start date.

This reservation stays in effect for the duration that you set, or until you delete it.

Displaying the Workload Placement Page



To see the reservations that are currently in effect and to create new reservations, click the **PLACE** button in the Navigation Menu.




ALL RESERVATIONS

Workload Placement

orkload Placement





Creating a Reservation

Reservations set aside resources for anticipated workload. While a reservation is in the RESERVED state, Workload Optimization Manager continually calculates placement for the reserved VMs.

To create a reservation:

1. Navigate to the Workload Placement page.



2. Create a new reservation.



In the Workload Placement page, click CREATE RESERVATION.

Workload Optimization Manager displays a list of templates. Choose the template you want, and click **NEXT: CONSTRAINTS**.

3. Optionally, specify placement constraints.

In the Constraints section and choose which constraints to apply to this reservation.

Constraints are optional, but note that these constraints are how you ensure that the template you have chosen is viable in the given locations that Workload Optimization Manager will choose.

The constraints you can choose include:

Scope

Choose the datacenter or host cluster that you will limit the reservation to.

Placement Policy

This list shows all the placement policies have been created as **Workload Optimization Manager Segments**. Choose which placement policies the reservation will respect.

Networks

Workload Optimization Manager discovers the different networks in your environment. Use this constraint to limit workload placement to the networks you choose.



When you are done setting constraints, click NEXT: RESERVATION SETTINGS.

4. Make the reservation settings, and create the reservation.

To finalize the reservation, make these settings:

RESERVATION NAME

The name for the reservation. You should use unique names for all your current reservations. This name also determines the names of the reservation VMs that Workload Optimization Manager creates to reserve resources in your environment. For example, assume the name *MyReservation*. If you reserve three VMs, then Workload Optimization Manager creates three reservation VMs named *MyReservation_0*, *MyReservation_1*, and *MyReservation_2*.

VIRTUL MACHINES COUNT

How many VMs to reserve.

NOTE:

You can include up to 100 VMs in a single reservation.

RESERVATION DATE

The time period that you want the reservation to be active. Can be one of:

Reserve Now

Use this to calculate the ideal placement for a workload that you want to deploy today. Workload Optimization Manager begins planning the reservation immediately when you click **CREATE RESERVATION**. The reservation stays in effect for 24 hours – At that time Workload Optimization Manager deletes the reservation.

Future Reservation

This executes the reservation for the date range you specify. Workload Optimization Manager begins planning the reservation on the day you set for START DATE. The END DATE determines when the reservation is no longer valid. At that time, Workload Optimization Manager deletes the reservation.

When you are finished with the reservation settings, click **CREATE RESERVATION**. Workload Optimization Manager displays the new reservation in the Workload Placement page. Depending on the reservation settings and your environment, the reservation can be in one of the one of the following states:

■ UNFULFILLED

The reservation request is in the queue, waiting for an ongoing reservation request to complete.

INPROGRESS

Workload Optimization Manager is planning the placement of the reservation workloads.

■ FUTURE

Workload Optimization Manager is waiting for the START DATE before it will start to plan the reservation.

■ RESERVED

Workload Optimization Manager has planned the reservation, and it found providers for all the VMs in the reservation. As your environment changes, Workload Optimization Manager continues to calculate the placement for the reservation VMs. If at any time it finds that it cannot place all the VMs, it changes the reservation to PLACEMENT FAILED.

■ PLACEMENT FAILED

Workload Optimization Manager cannot place all the reservation VMs. As your environment changes, Workload Optimization Manager continues to calculate placement for the VMs. If at any time it finds that it can place all the VMs, it changes the reservation to RESERVED.

INVALID


An error occurred while planning the placement of the reservation VMs.

NOTE:

The list of reservations refreshes whenever you open the Workload Placement page. To see changes in reservation state, navigate away from the page, and navigate back to it again.



Managing Reservations



The PLACE page displays the current list of reservations.

- 1. For an entry in the RESERVED state, you can click the entry name to open the Reservation Settings flyout.
- 2. To see details about the provider entities or the data center that is hosting the reserved VMs, click the entity name.
- 3. You can expand items in the list to see some details, or you can click to view the full details.
- 4. To delete a reservation, select it in the list and click the DELETE icon. This cancels the reservation or deployment.

Deploying Workloads to the Reserved Resources

When you reserve resources, you know that they are available for you to deploy actual VMs in your environment.

- 1. Note the placement that your reservation calculated.
 - Expand the reservation entry in the Workload Placement page and note the hosts and storage that provide resources for your VMs.
- Delete the reservation.

Before you deploy the reserved VMs, delete the reservation to free up the Workload Optimization Manager market to manage the placement of the VMs you are about to deploy.

NOTE:


When you delete a reservation from the user interface or API, Workload Optimization Manager only marks the reservation for deletion and waits 48 hours before permanently deleting it. You can permanently delete a reservation by using the API's reservation_force_delete parameter along with a DELETE call to a specific reservation. When reservation_force_delete = true, the system removes the reservation permanently, no matter what state it is in.

3. Deploy the actual VMs.

In your Hypervisor user interface, deploy the VMs to the hosts and storage that you noted. When you are done, Workload Optimization Manager manages their placement the same as it manages the rest of your environment.



Dashboards: Focused Views



Dashboards give you views of your environment that focus on different aspects of the environment's health. At a glance, you can gain insights into service performance health, workload improvements over time, actions performed and risks avoided, and savings in cost. For cloud environments, you can see utilization of discounts, potential savings, required investments, and the cost/performance of specific cloud accounts.

The Dashboards page lists all the dashboards that are available to you, including built-in and custom dashboards that your account can access.

- 1. To view a dashboard, click its name in the list.
- 2. To create a custom dashboard, click NEW DASHBOARD.
- 3. To delete a dashboard, select the dashboard and click the delete button

Built-in dashboards give you overviews of your on-prem, cloud, and container environments, showing how you have improved your environment over time.

NOTE:

In charts that show tables, if the table contains more than 500 cells, then the User Interface disables the option to export the chart as PDF. You can still export the chart as a CSV file to load in a spreadsheet.

Built-in Dashboards

Built-in Dashboards are scorecards of your environment. They demonstrate how well you are improving performance, cost, and compliance, as well as opportunities for further improvements that are available.

Workload Optimization Manager ships with these dashboards:


- On-Prem Executive Dashboard
- Cloud Executive Dashboard
- Container Platform Dashboard

NOTE:

Workload Optimization Manager ships these dashboards with default configurations. To edit a dashboard, you must log in with the administrator user account. Users logged in with that account can add or remove chart widgets, and change widget scopes. For information about editing dashboards, see Creating and Editing Custom Dashboards (on page 612).



On-Prem Executive Dashboard



The On-Prem Executive Dashboard shows the overall performance, capacity, and compliance in your on-prem infrastructure. This includes insights into:

Actions History

- The On-Prem Environment chart widget shows you an overview of your on-prem environment that Workload
 Optimization Manager is managing and controlling. The chart displays the workloads and the infrastructure that
 Workload Optimization Manager discovered.
- The Workload Improvements chart widget shows how the efficiency, performance, and policy risks associated with your workloads have disappeared as you have increased your adoption of Workload Optimization Manager Workload Automation. The chart tracks how your workloads have grown as your execution of actions have increased or decreased as your environment achieves and maintains its desired states over time.
- The All Actions chart widget shows the number of actions that Workload Optimization Manager has generated versus
 the ones executed. This gives you an understanding of where there were more opportunities for improvement that
 were not taken in the past versus those that are available today.

Opportunities

- The Workload by Performance, Workload by Compliance, and Workload by Efficiency chart widgets indicate workload health by showing the risks that are currently in your environment and each classification of those risks. You can click Show Action on the chart to reveal all of the outstanding actions that need to be taken to resolve those risks on your workloads.
- The Necessary Investments and Potential Savings chart widgets together project how the current actions to improve performance, efficiency, and compliance will impact your costs.

Current State

This chart shows the top clusters in your on-prem environment by CPU, memory, and storage capacity or utilization. In the default view, the chart shows the top clusters by CPU headroom (available capacity). It also shows time to exhaustion of cluster resources, which is useful for future planning (for example, you might need to buy more hardware).



 The Virtual Machines vs Hosts and Storage and the Virtual Machines vs Hosts and Storage -Density chart widgets show how your overall density has improved in your on-prem environment. A high count of VMs per host or storage means that your workloads are densely packed.

Cloud Executive Dashboard



The Cloud Executive Dashboard shows your overall cloud expenditures and how you can improve performance and reduce cost. This includes insights into:

Actions History

- The Cloud Environment chart widget shows you an overview of your cloud environment that Workload Optimization
 Manager is managing and controlling. The chart displays the workloads, cloud service providers, and cloud accounts
 that you currently have set up as Workload Optimization Manager targets.
- The Workload Improvements chart widget shows how the efficiency, performance, and policy risks associated with your workloads have disappeared as you have increased your adoption of Workload Optimization Manager Workload Automation. The chart tracks how your workloads have grown as your execution of actions have increased or decreased as your environment achieves and maintains its desired states over time.
- The Cumulative Savings chart widget shows you the cost savings for executed cloud actions compared to the cloud actions that you have not executed (missed savings).

Opportunities

- The Workload by Performance, Workload by Compliance, and Workload by Efficiency chart widgets indicate workload health by showing the risks that are currently in your environment and each classification of those risks. You can click Show Action on the chart to reveal all of the outstanding actions that need to be taken to resolve those risks on your workloads.
- The Necessary Investments and Potential Savings chart widgets together project how the current actions to improve performance, efficiency, and compliance will impact your costs.
- Cloud Estimated Cost chart widget shows estimated monthly costs and investments for the cloud. Monthly cost
 amounts are summarized as amounts with and without actions.

Current State

- The **Top Accounts** chart widget shows all of the cloud accounts in your cloud environment and what the utilization is for each account. You can see the number of workloads, estimated monthly costs, saved by actions, and actions taken. In the default view, the chart shows the top cloud accounts and you can click **Show All** button to see all of the accounts. In the Show All list, you can also download the account cost data as a CSV file or PDF.
- The Cost Breakdown by Tag chart widget shows the tags you have assigned to your cloud resources and the costs
 associated with each of these tagged categories. The Cost Breakdown by Cloud Service Provider chart widget is an
 Expenses chart widget that shows your expenses for each cloud service provider.



Usage of Discounts

Discounts reduce cost by offering a subscription-based payment plan. Workload Optimization Manager discovers these discounts and tracks usage patterns to identify workloads that can take advantage of discounted pricing. The Cloud Executive Dashboard shows whether you are getting the most out of your current discounts.


Discount Coverage (on page 661)

This chart shows the estimated percentage of VMs covered by discounts. If you have a high percentage of ondemand VMs, you should be able to reduce your monthly costs by increasing coverage. To increase coverage, you scale VMs to instance types that have existing capacity.

Discount Inventory (on page 663)

This chart lists the cloud provider discounts discovered in your environment.

Container Platform Dashboard



The Container Platform Dashboard shows the overall performance, capacity, and health of your container infrastructure. This includes insights into:

■ Top Container Platform Clusters

Assess the health of your clusters and sort them by risk level.

■ Top Namespaces

Identify namespaces that are running out of quota, and how much resources each namespace is using in both quotas and actual utilization.

Top Services

Assess the impact of Services on the performance of your applications.



Creating and Editing Custom Dashboards

A custom dashboard is a view that you create to focus on specific aspects of your environment. You can create dashboards that are private to your user account, or dashboards that are visible to any user who logs into your Workload Optimization Manager deployment.

Two common approaches exist for creating custom dashboards:

Scope First

You can create a dashboard in which all of the chart widgets focus on the same scope of your environment. For example, you might want to create a dashboard that focuses on costs for a single public cloud account. In that case, as you add chart widgets to the dashboard, you give them all the same scope.

Data First

You might be interested in a single type of data for all groups of entities in your environment. For example, each chart widget in the dashboard can focus on Cost Breakdown by Cloud Service, but you set the scope of each chart widget to a different cloud region or zone.

Of course, you can mix and match, according to your needs. You can set any scopes or data sources to the chart widgets in a dashboard to set up whatever organization and focus that you want.

NOTE:

If you set a scope to your Workload Optimization Manager session, the specified scope does not affect your custom dashboards. For information about scoped views, see <u>Working With a Scoped View (on page 124)</u>.

Creating a Dashboard

To create a custom dashboard:

1. Navigate to the Dashboards Page.




Click to navigate to the Dashboard Page.

This page lists all dashboards that are available to you. To view a dashboard, click its name in the list.

2. Create a new dashboard.



Click **NEW DASHBOARD** to add a new dashboard to your Workload Optimization Manager session. The dashboard appears with a default name and without chart widgets. The time range in the Time Slider is set to 24 hours by default.



Name the dashboard.

Give a name that describes the dashboard. If you will share the dashboard with all Workload Optimization Manager users, the name will help them decide whether to view it.

4. Add chart widgets to the dashboard.



Add as many chart widgets to the dashboard as you want. See Creating and Editing Chart Widgets (on page 614).

5. Optionally, set the dashboard access.

Click Gear to change the setting.



Dashboard access can be:

- Only Me (default) The dashboard is only available to your Workload Optimization Manager user account.
- All Users Every Workload Optimization Manager user can see this dashboard.

As soon as you create a new dashboard, it appears in the list on the Dashboard Page. Users with access to it can click the dashboard name in the list to view it, create a copy of the dashboard, or print the dashboard.

At any time, if you are an administrator or the dashboard owner, you can view and make the following changes to the dashboard:

- Add, edit, or delete widgets
- Change the dashboard name
- Change the dashboard access setting

For executive dashboards, only an administrator (username=administrator) can edit an executive dashboard.

Editing a Dashboard

If you have created a dashboard, you can change the name of the dashboard, its access settings, and its chart widgets. To change the chart widgets, see <u>Creating and Editing Chart Widgets</u> (on page 614).


1. Navigate to the Dashboards Page.



Click to navigate to the Dashboard Page.

- 2. Click the name of the dashboard that you want to edit.
- 3. Click Gear in the dashboard.

In the Edit Dashboard flyout, change the dashboard name or set the dashboard access.



For the dashboard's access, you can set:

- Only Me The dashboard is only available to your Workload Optimization Manager user account.
- All Users Every Workload Optimization Manager user can see this dashboard.
- When you are done, close the panel.

Your changes take effect when you close the panel.

Deleting a Dashboard

If you are an administrator or the dashboard owner, you can delete a custom dashboard. You cannot delete executive dashboards.

1. Navigate to the Dashboards Page.



Click to navigate to the Dashboard Page.

This page lists all dashboards that are available to you.

2. Delete one or more dashboards.



In the list, choose the check box for each dashboard to delete and click Trash can.

Creating and Editing Chart Widgets

Workload Optimization Manager displays information about your environment in various chart widgets. To focus on the information you need, you can add new chart widgets to scoped views and dashboards, and you can edit existing chart widgets. You can also pull the corners of chart widgets to resize them and change the display order of chart widgets in dashboards.

When you create or edit a chart widget, you can choose various settings. For example, in the Top Utilized chart widget, if you choose Clusters as the Entity Type, you can then choose Utilization as the Data Type and Storage Provisioned as the Commodity.

Creating a Chart Widget

To create a new chart widget:

1. Click Add Widget to open the Widget Gallery.



On a dashboard, click **Add Widget** at the upper-right corner. In a scoped view, click **Add Widget** on the right above the charts.

2. Choose a chart widget in the Widget Gallery.

The Widget Gallery is a list of thumbnail previews of chart widgets.

You can scroll through the gallery or search it. For example, if you type "Health" in the **Search** field, the results are two chart widgets, Health and Workload Health. You can choose chart widgets from these categories:

- Actions and Impact
- Status and Details
- Cloud
- On-Prem

To see the possible displays of a specific chart widget, use the horizontal scroll bar at the bottom of the thumbnail to scroll through the display choices.

To choose a chart widget to add it to your dashboard, click the thumbnail preview.

The Widget Preview window with the Edit flyout opens.

3. Configure the settings for your chart widget.

Chart widget settings determine the data that the chart widget shows.


In the Edit flyout, choose the settings and click **Update Preview** to display the result in the Widget Preview window.

When you are satisfied with your settings, click Save. The chart widget is added to your dashboard.

For information about settings, see Chart Widget Settings (on page 615).

For example:





To delete a chart widget from your dashboard, choose **Delete** in the More options menu at the upper-right corner of the chart widget.

Methods to Access Chart Widget Settings

Two methods exist for accessing the chart widget settings in the Edit flyout:

- You can access the settings in the Edit flyout when you add a chart widget to your dashboard after you click a thumbnail preview.
- For an existing chart widget in a dashboard, you can choose **Edit** in the More options menu.



Chart Widget Settings

Chart widget settings vary according to the type of chart widget. Also, depending on the value that you choose for a setting, more settings appear. The following is a list of frequently used chart widget settings:

Scope

The set of entities in your environment that this chart widget represents. By default, the chart widget scope is set to **Global Environment**.


For every type of chart widget, you have the option to set the chart's scope. To do so:

- Click Click to change scope to open the Select Scope flyout.
- 2. In the Select Scope flyout you can:
 - Select the scope for the chart: entities, groups, or accounts.
 The ACCOUNTS tab is available depending on the type of chart widget.



Your choice appears in the **Scope** field.

- b. Search or refine results with a filter.
- c. Display details for the list of entities, groups or accounts.



Timeframe

The timeframe for historical data or projections in the chart. Choices for the chart's timeframe are: Default, Last 2 Hours, Last 24 Hours, Last 7 Days, Last 30 Days, and Last Year.

If you set the timeframe to **Default**, the dashboard Time Slider controls the timeframe setting. For example, if your dashboard Time Slider is set to one month (1M), then all chart widgets with the Default timeframe in that dashboard are set to one month and show information for one month. Note that the dashboard Time Slider does not override the other specific timeframe settings.

■ Chart Type

The chart widget's display type. Most chart widgets can display horizontal bar or ring charts. Other display choices can include tabular data, band chart, stacked bar, line, or area charts.

NOTE:

For summary charts like horizontal bar and ring charts, when the legend has more than four categories, the remaining categories are represented as a fifth category named "Other."

Entity Type

The type of entities or their data that you want to display in this chart widget. Choices vary (for example, Applications, Hosts, Virtual Data Centers, Storage Devices, and so on).

Commodity

The resources that you want this chart widget to monitor. Some charts can monitor multiple commodities. Choices vary (for example, CPU, Memory, Virtual Storage, and so on).

Chart Types

Workload Optimization Manager provides many different types of charts in the Widget Gallery. To design dashboards, you should be familiar with the data each chart presents. These charts provide information on actions, impact, status of your environment, and details about specific entities, cloud, and on-prem environments.

Actions and Impact Chart Types

These chart widgets provide information on actions, pending actions, risks that you avoided, improvements, and potential savings or investments.



Pending Actions Charts

Pending Actions charts show the actions that Workload Optimization Manager recommends to improve the current state of your environment.

Chart Type


You can set the display to:

- Text
- Ring Chart
- Horizontal Bar
- List

Examples:


■ Text

The text chart shows the number of actions for each action type. It gives a quick visual indication of the kinds of actions that are pending. For details, see Action Types (on page 526).



Ring Chart

The ring chart counts the number of actions for each action type. It gives a quick visual indication of the kinds of actions that are pending. For details, see <u>Action Types (on page 526)</u>.



Horizontal Bar




The horizontal bar chart counts the number of actions for each action type. It gives a quick visual indication of the kinds of actions that are pending. For details, see Action Types (on page 526)



■ List

The list chart shows an abbreviated listing of the actions for the chart's scope. For details about the different actions generated by the product, see <u>Actions (on page 508)</u>.



At the bottom of the chart, click **Show All** to see a full list of pending actions that are in the scope of the chart, along with action details and controls to execute actions. For details, see Working with Action Center (on page 509).

Actions Charts

Actions charts keep a history of pending (not executed) and executed actions. These charts use historical data from the Workload Optimization Manager database. You can set the chart to show hourly, daily, or monthly data points.

Filter

You can filter the chart to show All Actions (pending and executed actions) or only Executed Actions.

Chart Type

You can set the display to:

- Tabular
- Area Chart



- Text
- Stacked Bar Chart

Stacked Bar Chart



For the Stacked Bar Chart, each bar represents a time period. Hover over the bar to see the number of *unique* actions for that time period. In the default view, the bars represent actions per hour in the last 24 hours. The 2:00 PM bar, for example, shows actions between 2:00 PM and 2:59 PM.

A pending action that remains valid for an extended period of time is counted *once* for each hour, day, and month it remains pending. This also applies to pending actions that go away as conditions in the market change, but are generated again in the future. Once a pending action is executed, it is counted once (this time, as an executed action) on the hour, day, and month of execution.

Consider the following scenarios.


- An action was generated at 1:25 PM and then executed two hours later at 3:25 PM.
 - For per-hour views (Last 24 Hours or Default), the action will be counted three times as a pending action in the 1:00 PM and 2:00 PM bars, and as an executed action in the 3:00 PM bar.
 - For per-day (Last 7 or 30 Days) or per-month (Last Year) views, the action will be counted once (as an executed action) on the day or month of execution.
- An action was generated at 6:20 PM but went away (without being executed) in the next hour. The same action was generated again the next day at 9:10 AM and was executed immediately.
 - For per-hour views, the action will be counted twice as a pending action in the 6:00 PM bar and as an executed action in next day's 9:00 AM bar.
 - For per-day views, the action will also be counted twice as a pending action on Day 1 and an executed action on Day 2.
 - For per-month views, the action will be counted once (as an executed action) on the month of execution.

Use the chart to evaluate the rate of action execution, which underscores the importance of executing actions in a timely manner. As pending actions persist, they become more challenging to track and your environment stays in a risky state longer. To reduce potential delays in executing actions, consider action automation.

Tabular Chart

To see the full list of actions, click Show All at the bottom of the chart.





Risks Avoided Charts

As you execute the actions Workload Optimization Manager has recommended, you improve your environment's health and avoid risks to performance or cost. These charts show how many risks you have avoided over time. For example, the charts can show how many over-provisioning and congestion risks you avoided.

Chart Type

You can set the display to:

- Text
- Ring Chart
- Horizontal Bar

Optimized Improvements Charts

Workload Optimization Manager automatically executes or recommends actions, depending on the policies that you set up. For the recommended actions, you can use Optimized Improvements charts to show how utilization of resources would change assuming you accept all of the <u>pending actions (on page 617)</u>.

Entity Type

Entity types you can choose include:

- Business Applications
- Business Transactions
- Services
- Application Components
- Chassis
- Containers
- Container Pods
- Container Specs
- Namespaces
- Workload Controllers
- Data Centers
- Databases
- Database Servers
- Disk Arrays
- IO Modules
- Internet




- Logical Pool
- Networks
- Hosts
- Regions
- Storage Devices
- Storage Controllers
- Switches
- Virtual Data Centers
- Virtual Machines
- Volumes
- Zones

Commodity

Depending on the entity type, you can add different resource commodities that you want to measure. For a chart of Hosts, you can measure commodities such as CPU, Memory, and even network flow between VMs that are on the same host (In-Provider Flow) or on other hosts (In-DPOD or Cross-DPOD Flow).

Display

Optimized Improvements charts show two bar charts for the entities that are in scope – one for current consumption, and the other for the consumption you would expect to see if you execute all the actions. You can hover on the graph for details in a tooltip.



Potential Savings or Investments Charts

These charts show potential savings or necessary investments in your cloud expenditure, assuming you execute all the pending actions that Workload Optimization Manager identifies as a result of its analysis.

For example, if some workloads risk losing performance, Workload Optimization Manager might recommend scaling actions for the virtual machine to increase resources. The Necessary Investments chart shows how these actions translate to an increase in expenditure.

On the other hand, if there are pending actions to scale a virtual machine, which result in reduced monthly costs, the Potential Savings chart shows the reduced cost that would result from those actions.

This chart also track discount optimization actions. VM scaling actions may result in freed up capacity on a discounted instance type, which can now be applied to a different VM. Discount optimization actions reflect the potential savings resulting from reassigning the capacity to a different VM. These actions are not executed by Workload Optimization Manager users. They reflect capacity reassignment performed by your cloud provider.

The projected amounts include on-demand costs for VMs. For information about on-demand cost calculations, see <u>Estimated</u> On-demand Monthly Costs for Cloud VMs (on page 389).



Type

You can choose Potential Savings or Necessary Investments.

Chart Type

You can set the display to:


- Text
- Ring Chart
- Horizontal Bar

For the ring chart, you can click an action type (for example, **Scale Volumes**) in the chart or legend to display a filtered view of the actions list.

Show All

Click **Show all** at the bottom of the chart to see a breakdown of savings or investments by action/entity type and entity. By default, the actions are shown in order of largest amounts so you can easily identify which ones will incur the highest costs or introduce the most savings.

For example, you can see the savings you would realize if you execute all *Scale* actions on the *virtual machines* included in the chart's scope.



The table then breaks down the total savings by individual virtual machines, and includes links to the specific actions that you need to perform to realize those savings.



You can also compare instance types, costs, and discount coverage before and after executing the actions, allowing you to easily identify actions with the most savings.

Status and Details Chart Types

These chart widgets provide information on the status of your environment and details about specific entities.

Health Charts

Health charts show the current status of your environment, by entity type. For example, you can choose to show the health of all hosts in your environment, or the health of all the workloads running on a public cloud region.



Entity Type

Entity types you can choose include:

- Business Applications
- Business Transactions
- Services
- Application Components
- Chassis
- Containers
- Container Pods
- Container Specs
- Namespaces
- Workload Controllers
- Data Centers
- Databases
- Database Servers
- Disk Arrays
- IO Modules
- Internet
- Logical Pool
- Networks
- Hosts
- Regions
- Storage Devices
- Storage Controllers
- Switches
- Virtual Data Centers
- Virtual Machines
- Volumes
- Zones

Chart Type

You can set the display to:

- Text
- Ring Chart
- Horizontal Bar

Basic Info Charts

The Basic Info charts provide an overview of a single entity or individual Azure resource group that you have chosen as your scope.

Type

You can choose:

Entity Information

This chart shows basic information (ID, Name, Type, State, Severity, Target Name, and so on) for the scoped entity or Azure resource group.

Related Tag Information



This chart lists any available tag information for the scoped entity or Azure resource group. For example, in a cloud environment, if a virtual machine has tags applied to it, the chart shows those tags for the virtual machine.

Display

The chart shows the information as Tabular.

Capacity and Usage Charts

These charts list the resources for the selected entity type, showing their allocated capacity and how much of that capacity is in use.

Entity Type

Entity types you can choose include:

- Business Applications
- Business Transactions
- Services
- Application Components
- Containers
- Container Pods
- Container Specs
- Namespaces
- Workload Controllers
- Data Centers
- Database Servers
- Disk Arrays
- Logical Pool
- Networks
- Hosts
- Regions
- Zones
- Storage Devices
- Storage Controllers
- Virtual Machines
- Volumes

Commodity

Depending on the entity type, you can add different resource commodities that you want to measure. For example, for a chart of Virtual Machines, you can measure commodities such as virtual CPU, memory, and storage.

NOTE:

For a cloud database server, the chart might show incorrect *used* values for vMem and Storage Amount after an action executes. It could take up to 40 minutes for the correct values to display.

Display

The chart shows the information as Tabular.

Multiple Resources Charts

Multiple Resources charts show the historical utilization of commodities for the scoped entity or a group of entities. The vertical bar shows the current moment – plots that extend to the right project utilization into the future.



Entity Type

Entity types you can choose include:

- Business Applications
- Business Transactions
- Services
- Application Components
- Containers
- Container Pods
- Container Specs
- Namespaces
- Workload Controllers
- Data Centers
- Database Servers
- Disk Arrays
- Logical Pool
- Networks
- Hosts
- Regions
- Zones
- Storage Devices
- Storage Controllers
- Virtual Machines
- Volumes

Commodity

Depending on the entity type, you can add different resource commodities that you want to measure. For example, for a chart of volumes, you can measure commodities such as IO throughput, storage access, and storage amount.

Show Peaks

Edit the chart and choose the Show Peaks checkbox to include peak information in the chart.

Display

The chart shows the historical utilization and, if chosen, the peak information as a Line chart.


Resources Charts

Resources charts show the utilization of a resource over time, for the entities in the chart's scope. The chart title shows the resource that you are plotting, as well as the chart's current scope.

To see finer details about your environment, you can set up charts that show utilization of specific commodities. For example, you can set up a dashboard with a number of Resources charts with their scopes set to the same cluster. Such a dashboard gives you a detailed look at the health of that cluster. Or you could make a dashboard with each chart scoped to a different cluster, but have all the charts show the same resource utilization.

Ring Chart

For certain entity types (such as hosts, storage, and disk arrays), you will see a ring chart on the left that indicates the current overall utilization of a particular resource. Hover over the ring chart to see the following information:



- Free: Available capacity
- Used: Utilized capacity
- Reserved: Unavailable capacity due to utilization constraints

The sum of Free and Used capacity equals the total allocated capacity.

In addition to showing the currently discovered free and used capacity, Workload Optimization Manager also calculates *Reserved* capacity based on utilization constraints set in policies.

For example, for a cluster with 100 GB of allocated storage, Workload Optimization Manager might discover 80 GB of free capacity, and 20 GB of used capacity. If the cluster is currently applying a storage policy that has a utilization constraint of 90%, then Workload Optimization Manager will show 10 GB of reserved capacity.

Options

Choose **Show Utilization** to see averages and peaks/lows, or **Show Capacity** to see averages and peaks/lows versus capacity. The **Show Summary** option adds a ring chart to the view, showing the current utilization of the selected commodity.

Chart Type

You can set the following types of display:

- Line Chart
 - A line plot showing resource utilization over time. The vertical green bar shows the current moment Plots that extend to the right project utilization into the future.
- Band Chart

Lines plot average capacity and average used. The chart shows a band where its thickness indicates peaks and lows.

Carbon Footprint Chart

Carbon footprint is the measurement of carbon dioxide equivalent (CO2e) emissions for a given entity. Workload Optimization Manager measures carbon footprint in grams.

Workload Optimization Manager collects energy-related data from hosts and VMs at 10-minute intervals, and then uses that data to calculate carbon footprint. When you set the scope to one or several hosts or VM discovered from supported targets, the data that Workload Optimization Manager calculated displays in the Carbon Footprint chart.





NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported entity (see the next section for a list of supported entities).

Workload Optimization Manager also relies on host power data for the supported targets. This data is mandatory for Energy and Carbon Footprint calculations.

Supported Entities

Data is available in the Carbon Footprint chart for hosts and VMs discovered via vCenter targets.

Carbon Footprint Calculation

The calculation for carbon footprint can be expressed as follows:

```
(Energy Consumption) * [(Power Usage Effectiveness) * (Carbon Intensity)] = Carbon Footprint
```

Where:

- Energy Consumption is the consumption data collected from the entity.
- Power Usage Effectiveness (PUE) is a ratio that describes how efficiently a computer data center uses energy; specifically, how much energy is used by the computing equipment. PUE is the ratio of the total amount of energy used by a computer data center facility to the energy delivered to computing equipment. The closer PUE is to 1, the more efficient the computer data center.
- Carbon Intensity (CI) is a measurement of how 'clean' electricity is. It refers to how many grams of carbon dioxide (CO2) are released to produce 1 watt-hour (Wh) of electricity. Electricity that is generated using fossil fuels is more carbon intensive, as the process by which it is generated creates CO2 emissions. Renewable energy sources, such as wind, hydro, or solar power produce next to no CO2 emissions, so their carbon intensity value is much lower and often zero.

By default, PUE is set to 1.5, while CI is set to 0.25 g/Wh. These values appear in the <u>default policy (on page 490)</u> for Data Center entities. You can modify these values directly for a global effect, or set specific values in custom automation policies for Data Centers.


For example, if energy consumption for a host is 50 Wh, carbon footprint will be calculated as follows:

```
(50) * [(1.5) * (.25)] = 18.75 grams of CO2e
```

Connection Chart

Connection is the measurement of database connections utilized by applications.

Workload Optimization Manager collects connection data from Database Servers discovered via Databases, APM, and Cloud targets. When you set the scope to one or several Database Servers, the data that Workload Optimization Manager collected displays in the Connection chart.





NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported Database Server (see the next section for a list of supported Database Servers).

Supported Database Servers

Data is available in the Connection chart for Database Servers discovered via the following targets:

Target	Supported Database Servers
AWS	RDS
Azure	SQL
AppDynamics	MongoDB
Instana	Oracle
MySQL	MySQL
Oracle	Oracle
JBoss	All Database Servers discovered from the target
SQL	SQL
Tomcat	All Database Servers discovered from the target
WebLogic	All Database Servers discovered from the target
WebSphere	All Database Servers discovered from the target

Effect on Memory Resize/Scale Actions

Workload Optimization Manager uses connection data to generate memory resize actions for on-prem Database Servers.

For cloud Database Servers, Workload Optimization Manager uses connection data as a constraint when generating scale actions. For details about scale actions, see <u>Database Server Actions</u> (on page 413).

DB Cache Hit Rate Chart

DB cache hit rate is the measurement of Database Server accesses that result in cache hits, measured as a percentage of hits versus total attempts. A high cache hit rate indicates efficiency.

Workload Optimization Manager collects cache hit rate data from Database Servers discovered via Databases, APM, and Cloud targets. When you set the scope to one or several Database Servers, the data that Workload Optimization Manager collected displays in the DB Cache Hit Rate chart.





NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported Database Server (see the next section for a list of supported Database Servers).

Supported Database Servers

Data is available in the DB Cache Hit Rate chart for Database Servers discovered via the following targets:

Target	Supported Database Servers
AWS	RDS
Azure	SQL
AppDynamics	SQL, Oracle
Dynatrace	SQL
Instana	MySQL, SQL, Oracle
MySQL	MySQL
New Relic	SQL, MySQL
Oracle	Oracle
SQL	SQL

Effect on Memory Resize Actions

Actions to resize database memory are driven by data on the Database Server, which is more accurate than data on the hosting VM. Workload Optimization Manager uses database memory and cache hit rate data to decide whether resize actions are necessary.


A high cache hit rate value indicates efficiency. The optimal value is 100% for on-prem (self-hosted) Database Servers, and 90% for cloud Database Servers. When the cache hit rate reaches the optimal value, no action generates even if database memory utilization is high. If utilization is low, a resize down action generates.

When the cache hit rate is below the optimal value but database memory utilization remains low, no action generates. If utilization is high, a resize up action generates.

DB Memory Chart

Database memory (or DBMem) is the measurement of memory utilized by a Database Server.

Workload Optimization Manager collects memory data from Database Servers discovered via Databases and APM targets. When you set the scope to one or several Database Servers, the data that Workload Optimization Manager collected displays in the DB Memory chart.



NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported Database Server (see the next section for a list of supported Database Servers).

Supported Database Servers

Data is available in the DB Memory chart for Database Servers discovered via the following targets:

Target	Supported Database Servers
AppDynamics	Oracle, MongoDB
Dynatrace	SQL, MySQL
Instana	MySQL, SQL
MySQL	MySQL
Oracle	Oracle
SQL	SQL

Memory Resize Actions

Actions to resize database memory are driven by data on the Database Server, which is more accurate than data on the hosting VM. Workload Optimization Manager uses database memory and cache hit rate data to decide whether resize actions are necessary.

A high cache hit rate value indicates efficiency. The optimal value is 100% for on-prem (self-hosted) Database Servers, and 90% for cloud Database Servers. When the cache hit rate reaches the optimal value, no action generates even if database memory utilization is high. If utilization is low, a resize down action generates.


When the cache hit rate is below the optimal value but database memory utilization remains low, no action generates. If utilization is high, a resize up action generates.

Energy Chart

Energy is the measurement of electricity consumed by a given entity over a period of time, expressed in watt-hours (Wh).

Workload Optimization Manager collects energy-related data from vCenter hosts and VMs at 10-minute intervals. For VMs, the data collected from hosts is used to calculate VM energy consumption. When you set the scope to one or several hosts or VM, the data that Workload Optimization Manager collected or calculated displays in the Energy chart.





NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported entity (see the next section for a list of supported entities).

Workload Optimization Manager also relies on host power data for the supported targets. This data is mandatory for Energy and Carbon Footprint calculations.

Supported Entities

Data is available in the Energy chart for hosts and VMs discovered via vCenter targets.

Calculation of Energy Consumed by VMs

Workload Optimization Manager calculates energy consumption for each VM on a host, based on two types of host energy:

- Host idle energy this is the energy consumed by a host while in an idle state, when no processes are actively executing.
 This includes host overhead energy, which represents energy that is consumed by non-VM resources, such as hypervisors.
 Host idle energy is attributed to all member VMs based on each VM's allocated capacity.
- Host active energy this is the energy consumed by the VMs' operating systems and active processes.
 Host active energy is attributed to all member VMs based on each VM's usage of host CPU.

The calculation can be expressed as follows:

```
(VM Size / Total Size for all VMs) * Host Idle Energy for VMs + (VM CPU Utilization / Total CPU Utilization for all VMs) * Host Active Energy for VMs = VM Energy Consumption (in Wh)
```

NOTE:

Workload Optimization Manager rounds the calculated values.

For example, consider a host with three VMs. Currently, host *idle* energy for VMs is 50 Wh, while host *active* energy for VMs is 20 Wh.

Workload Optimization Manager calculates VM energy consumption as follows:

VM	Size (Cores)	CPU Utilization (%)	VM Energy Consumption (Wh)
VM_01	2	50 (x 2 cores) = 100	(2 / 4) * 50 + (100 / 180) * 20 = 36.1
VM_02	1	80 (x 1 core) = 80	(1 / 4) * 50 + (80 / 180) * 20 = 21.4




VM	Size (Cores)	CPU Utilization (%)	VM Energy Consumption (Wh)
VM_03	1	0 (idle)	(1 / 4) * 50 + (0) * 20 = 12.5
Total	4	180	70

Heap Chart

Heap is the portion of a VM or container's memory allocated to individual applications.

Workload Optimization Manager collects heap data from Application Components discovered via Applications and APM targets. When you set the scope to one or several Application Components, the data that Workload Optimization Manager collected displays in the Heap chart.



The chart shows average and peak/low values over time. Use the selector at the bottom left section of the chart to change the time frame.

NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported Application Component (see the next section for a list of supported Application Components).

Supported Application Components

Data is available in the Heap chart for Application Components discovered via the following targets:

Target	Supported Application Components
AppDynamics	Java applications, .NET, Node.js
Dynatrace	Java applications
Instana	Java applications
JBoss	Java applications
JVM	Java applications
New Relic	Java applications, Node.js
Tomcat	Java applications
WebLogic	Java applications
WebSphere	Java applications



Heap Resize Actions

Workload Optimization Manager generates Heap resize actions if an Application Component provides Heap and Remaining GC Capacity, and the underlying VM or container provides VMem. These actions are recommend-only and can only be executed outside Workload Optimization Manager.

NOTE:

Remaining GC capacity is the measurement of Application Component uptime that is not spent on garbage collection (GC).

Number of Replicas Chart

This chart shows the replicas of Application Components running over a given time period.

Use this chart if:

- SLO-driven scaling is enabled for a Service, and provision or suspend actions are executed by Workload Optimization Manager. These actions adjust the number of replicas to help you meet your SLO goals.
- Kubernetes Horizontal Pod Autoscaler (HPA) is enabled for a Deployment, ReplicaSet, or StatefulSet that is exposed as a Service. Workload Optimization Manager discovers adjustments to the number of replicas made by HPA.

The chart shows following information:

Capacity values

The number of desired pod replicas configured in the Workload Controller that backs the Service. This can be configured in *Deployment, ReplicaSet, StatefulSet, ReplicationController* or *DeploymentConfig.*

The chart plots the maximum observed capacity within the given time period.

Used values


The number of *ready* pods owned by the Workload Controller. Pods in other states (for example, pending pods) are not counted.

The chart plots the *average* used values within the given time period. Hover over the chart to see the minimum and maximum used values.

Remaining GC Capacity Chart

Remaining GC capacity is the measurement of Application Component uptime that is not spent on garbage collection (GC).

Workload Optimization Manager collects GC data from Application Components discovered via Applications and APM targets, and then uses that data to calculate remaining GC capacity. When you set the scope to one or several Application Components, the capacity that Workload Optimization Manager calculated displays in the Remaining GC Capacity chart.



The chart shows average and peak/low values over time. Use the selector at the bottom left section of the chart to change the time frame.

NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported Application Component (see the next section for a list of supported Application Components).



Supported Application Components

Data is available in the Remaining GC Capacity chart for Application Components discovered via the following targets:

Target	Supported Application Components
AppDynamics	Java applications, .NET
Dynatrace	Java applications
Instana	Java applications
JBoss	Java applications
JVM	Java applications
New Relic	Java applications, Node.js
Tomcat	Java applications
WebLogic	Java applications
WebSphere	Java applications


Effect on Heap Resize Actions

Workload Optimization Manager generates Heap resize actions if an Application Component provides Heap and Remaining GC Capacity, and the underlying VM or container provides VMem. These actions are recommend-only and can only be executed outside Workload Optimization Manager.

Response Time Chart

Response Time is the elapsed time between a request and the response to that request. Response Time is typically measured in seconds (s) or milliseconds (ms).

Workload Optimization Manager collects response time data from entities discovered via Applications, Databases, and APM targets. Entities include Business Applications, Business Transactions, Services, Application Components, and self-hosted Database Servers. When you set the scope to any of these entities, the data that Workload Optimization Manager collected displays in the Response Time chart.



The chart shows average and peak/low values over time. Use the selector at the bottom left section of the chart to change the time frame.

NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported entity (see the next section for a list of supported entities).




Supported Entities

Data is available in the Response Time chart for the following entities:


Target	Supported Entities
AppDynamics	Business Application, Business Transaction, Service, Application Component
Datadog	Business Application, Business Transaction, Service, Application Component
Dynatrace	Business Application, Service
Instana	Business Application, Business Transaction, Service, Application Component, Database Server
JBoss	Application Component
JVM	Application Component
MySQL	Database Server
New Relic	Business Transaction, Service, Application Component, Database Server
Oracle	Database Server
SQL	Database Server
Tomcat	Application Component
WebLogic	Application Component
WebSphere	Application Component

Response Time SLOs


To evaluate the performance of your applications and Database Servers, set Response Time SLOs (Service Level Objectives) as an operational constraint in policies. For applications, you can set the SLO at the Business Application, Business Transaction, Service, or Application Component level.



After you create a policy, the SLO value appears as a solid straight line in the Response Time chart. You can then gauge performance against the given SLO.



If you do not set an SLO, Workload Optimization Manager estimates SLO based on historical Response Time data collected from the target, and then displays the estimated value in the Capacity and Usage chart, as Response Time capacity. This estimated value is *not* reflected in the Response Time chart.



NOTE:


When you set an SLO value, Response Time capacity in the Capacity and Usage chart shows as N/A.

Response Time SLOs for Kubernetes Services

When you add a Kubernetes target, Workload Optimization Manager discovers container platform entities, including Kubernetes Services monitored by AppDynamics, Instana, Dynatrace, and New Relic.

To generate actions that adjust pod replicas, Kubernetes Services must be discovered by the Kubeturbo pod that you have deployed in your environment, as well as collect performance metrics via Instana or DIF (Data Ingestion Framework). In addition, Workload Optimization Manager requires that you turn on horizontal scaling and specify Response Time SLOs in policies for the affected Services.





Response Time SLO is the desired weighted average response time (in milliseconds) of all Application Component replicas associated with a Service.

NOTE

If you specified SLOs but turned off horizontal scaling in policies, no actions generate but SLO values will continue to display in the Response Time chart for Services, for your reference. This allows you to gauge performance against those SLOs.

Storage Access Chart

Storage Access, also known as IOPS, is the per-second measurement of read and write access operations on a storage entity.

Workload Optimization Manager collects storage access data from VMs, Database Servers, and storage entities discovered via cloud, on-prem, and storage targets. When you set the scope to these entities, the data that Workload Optimization Manager collected displays in the Storage Access chart.





NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported entity (see the next section for a list of supported entities).

Supported Entities

Data is available in the Storage Access chart for entities discovered via the following targets:

Target Type	Target	Supported Entities
Cloud	AWS	Virtual Machine, Database Server, Volume
	Azure	Virtual Machine, Database Server, Volume
	GCP	Virtual Machine
Fabric	HPE OneView	Virtual Machine, Storage
Hyperconverged	HyperFlex	Storage, Disk Array
	Nutanix	Storage, Disk Array
Hypervisor	Hyper-V	Virtual Machine, Storage
	vCenter	Virtual Machine, Storage
Storage	EMC ScaleIO	Storage, Disk Array
	EMC VMAX	Storage, Disk Array, Logical Pool
	EMC XtremIO	Storage, Disk Array
	HPE 3PAR	Storage, Disk Array, Logical Pool
	IBM FlashSystem	Storage, Disk Array, Logical Pool
	NetApp	Storage, Disk Array
	Pure Storage	Storage, Disk Array

Scale Actions

Workload Optimization Manager considers storage access (IOPS) utilization when recommending scaling actions for <u>cloud VMs</u> (on page 381), <u>cloud Database Servers (on page 413)</u>, and <u>volumes (on page 425)</u>.

Storage Amount Chart

Storage Amount is the measurement of storage capacity that is in use.

Workload Optimization Manager collects storage amount data from VMs, Database Servers, and storage entities discovered via cloud, on-prem, and storage targets. When you set the scope to these entities, the data that Workload Optimization Manager collected displays in the Storage Amount chart.





NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported entity (see the next section for a list of supported entities).

Supported Entities

Data is available in the Storage Amount chart for entities discovered via the following targets:

Target Type	Target	Supported Entities
Cloud	AWS	Virtual Machine, Database Server
	Azure	Virtual Machine
	GCP	Virtual Machine
Fabric	HPE OneView	Storage
Hyperconverged	HyperFlex	Storage, Disk Array
	Nutanix	Storage, Disk Array, Storage Controller
Hypervisor	Hyper-V	Storage
	vCenter	Storage
Storage	EMC ScaleIO	Storage, Disk Array, Storage Controller
	EMC VMAX	Storage, Disk Array, Logical Pool, Storage Controller
	EMC XtremIO	Storage, Disk Array, Storage Controller
	HPE 3PAR	Storage, Disk Array, Logical Pool, Storage Controller
	IBM FlashSystem	Storage, Disk Array, Logical Pool, Storage Controller
	NetApp	Storage, Disk Array, Storage Controller
	Pure Storage	Storage, Disk Array, Storage Controller




Scale Actions

Workload Optimization Manager can recommend scaling <u>cloud VMs (on page 381)</u> and <u>cloud Database Servers (on page 413)</u> to instance types that can adequately meet storage demand at the lowest possible cost. For cloud Database Servers, Workload Optimization Manager can also recommend scaling up storage amount within the same instance type. Note that scaling up storage amount is non-disruptive but irreversible.

Threads Chart

Threads is the measurement of thread capacity utilized by applications.

Workload Optimization Manager collects thread data from Application Components discovered via Applications and APM targets. When you set the scope to one or several Application Components, the data that Workload Optimization Manager collected displays in the Threads chart.



The chart shows average and peak/low values over time. Use the selector at the bottom left section of the chart to change the time frame.

NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported Application Component (see the next section for a list of supported Application Components).

Supported Application Components

Data is available in the Threads chart for Application Components discovered via the following targets:

Target	Supported Application Components
AppDynamics	Java applications, .NET
JBoss	Java applications
JVM	Java applications
New Relic	Java applications
Tomcat	Java applications
WebLogic	Java applications
WebSphere	Java applications

Thread Pool Resize Actions


Workload Optimization Manager generates thread pool resize actions. These actions are recommend-only and can only be executed outside Workload Optimization Manager.

Transaction Chart

Transaction is a value that represents the per-second utilization of the transactions allocated to a given entity.



Workload Optimization Manager collects transaction data from entities discovered via Applications, Databases, and APM targets. Entities include Business Applications, Business Transactions, Services, Application Components, and self-hosted Database Servers. When you set the scope to any of these entities, the data that Workload Optimization Manager collected displays in the Transaction chart.



The chart shows average and peak/low values over time. Use the selector at the bottom left section of the chart to change the time frame.

NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported entity (see the next section for a list of supported entities).

Supported Entities


Data is available in the Transaction chart for the following entities:

Target	Supported Entities
AppDynamics	Business Application, Business Transaction, Service, Application Component, Database Server
Dynatrace	Business Application, Service, Database Server
Instana	Business Application, Business Transaction, Service, Database Server
JBoss	Application Component
MySQL	Database Server
New Relic	Business Transaction, Service, Application Component, Database Server
Oracle	Database Server
SQL	Database Server
Tomcat	Application Component
WebLogic	Application Component
WebSphere	Application Component


Transaction SLOs

To evaluate the performance of your applications and Database Servers, set Transaction SLOs as an operational constraint in policies. For applications, you can set the SLO at the Business Application, Business Transaction, Service, or Application Component level.






After you create a policy, the SLO value appears as a solid straight line in the Transaction chart. You can then gauge performance against the given SLO.



If you do not set an SLO, Workload Optimization Manager estimates SLO based on historical Transaction data collected from the target, and then displays the estimated value in the Capacity and Usage chart, as Transaction capacity. This estimated value is *not* reflected in the Transaction chart.



NOTE:


When you set an SLO value, Transaction capacity in the Capacity and Usage chart shows as N/A.

Transaction SLOs for Kubernetes Services

When you add a Kubernetes target, Workload Optimization Manager discovers container platform entities, including Kubernetes Services managed by AppDynamics, Instana, Dynatrace, and New Relic.



To generate actions that adjust pod replicas, Kubernetes Services must be discovered by the Kubeturbo pod that you have deployed in your environment, as well as collect performance metrics via Instana or DIF (Data Ingestion Framework). In addition, Workload Optimization Manager requires that you turn on horizontal scaling and specify Transaction SLOs in policies for the affected Services.



Transaction SLO is the maximum number of transactions per second that each Application Component replica can handle.


NOTE:

If you specified SLOs but turned off horizontal scaling in policies, no actions generate but SLO values will continue to display in the Transaction chart for Services, for your reference. This allows you to gauge performance against those SLOs.

Transaction Log Chart

Transaction log is the measurement of storage capacity utilized by a Database Server for transaction logging.

Workload Optimization Manager collects transaction log data from Database Servers discovered via Databases and APM targets. When you set the scope to one or several Database Servers, the data that Workload Optimization Manager collected displays in the Transaction Log chart.



NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported Database Server (see the next section for a list of supported Database Servers).

Supported Database Servers

Data is available in the Transaction Log chart for Database Servers discovered via the following targets:

Target	Supported Database Server
AppDynamics	SQL
Oracle	Oracle
SQL	SQL

Transaction Log Resize Actions

Resize actions based on the transaction log resource depend on support for virtual storage in the underlying hypervisor technology.


Currently, Workload Optimization Manager does not support resize actions for Oracle and Database Servers on the Hyper-V platform (due to the lack of API support for virtual storage).

Virtual Storage Chart

Virtual storage is the measurement of virtual storage capacity that is in use.

Workload Optimization Manager collects virtual storage data from VMs discovered via on-prem and APM targets. When you set the scope to one or several VMs, the data that Workload Optimization Manager collected displays in the Virtual Storage chart.





NOTE:

An empty chart could be the result of delayed discovery, target validation failure, unavailable data for the given time frame, or an unsupported entity (see the next section for a list of supported entities).

Supported Entities

Data is available in the Virtual Storage chart for entities discovered via the following targets:

Target Type	Target	Supported Entities
Database	MySQL	Virtual Machine
	Oracle	Virtual Machine
	SQL	Virtual Machine
Fabric	HPE OneView	Virtual Machine
Guest OS Process	SNMP	Virtual Machine
	WMI	Virtual Machine
Hyperconverged	HyperFlex	Virtual Machine
	Nutanix	Virtual Machine
Hypervisor	Hyper-V	Virtual Machine
	vCenter	Virtual Machine

Virtual Storage Actions

Workload Optimization Manager can recommend the following virtual storage actions:

- Move a VM's volume (virtual storage) due to excess utilization of the current datastore, or for more efficient utilization of datastores in the environment.
- Reconfigure a VM's volume (virtual storage) to comply with placement policies.

Top Utilized Charts

Top Utilized charts show the entities or groups with the most utilization.



Entity Type

Entity types you can choose include:

- Accounts (on page 647) (public cloud)
- Business Applications
- Business Transactions
- Services
- Application Components
- Zones
- Chassis
- Clusters (on page 647) (of hosts)
- Containers
- Container Pods
- Container Specs
- Namespaces
- Workload Controllers
- Data Centers
- Databases
- Database Servers
- Disk Arrays
- IO Modules
- Internet
- Logical Pool
- Networks
- Hosts
- Resource Groups (on page 648)
- Regions
- Storage Devices
- Storage Controllers
- Switches
- Virtual Data Centers
- Virtual Machines
- Volumes
- Wasted Files

Data Type

Depending on the entity type (for example, Clusters), you can choose **Headroom** or **Utilization** information in the chart.

Commodity

Depending on the entity type, you can add one or more different resource commodities that you want to measure.

Display


The chart lists the top entities by utilization of the commodities that you or the system has set. Depending on the entity type and scope, you can sort the information. To view the utilization details, hover over the entity to display the tooltip.

To drill down to an entity, click the entity name in the chart. This sets the scope to that entity.

Click the **ACTIONS** button for an entity to examine the actions that are pending for it, and then decide which ones are safe to execute.

Example: A top clusters chart which can be sorted by CPU headroom or CPU exhaustion.





Top Clusters Chart

This chart shows the top clusters in your on-prem environment by CPU, memory, and storage capacity or utilization. In the default view, the chart shows the top clusters by CPU headroom (available capacity). It also shows time to exhaustion of cluster resources, which is useful for future planning (for example, you might need to buy more hardware).

To calculate cluster capacity and headroom, Workload Optimization Manager runs nightly plans that take into account the conditions in your current environment. The plans use the Economic Scheduling Engine to identify the optimal workload distribution for your clusters. This can include moving your current VMs to other hosts within the given cluster, if such moves would result in a more desirable workload distribution. The result of the plan is a calculation of how many more VMs the cluster can support.

Click the **ACTIONS** button for a given cluster to see the actions that Workload Optimization Manager recommends to keep cluster resources in the desired state, and then decide which ones are safe to execute.

Click **Show All** to see all of the clusters. In the Show All list, you can also download capacity data as a CSV file. Click a cluster name to set the scope to that cluster and view more details about its current capacity and health.

Top Accounts Chart

This chart lists the cloud accounts with the largest potential savings. These are the savings you would realize if you execute pending actions for your cloud workloads. Click the **ACTIONS** button to examine these actions and decide which ones are safe to execute. The chart also shows billed costs in the last 30 days.

To set the scope to a particular account, click the account name.

Click **Show all** to view additional information, including the number of actions that have been executed for individual accounts or workloads, along with the resulting savings. If you have multiple cloud providers, each provider will have its own tab. You can download the accounts list as a CSV file.

AWS Accounts

The chart shows the AWS master and member accounts that you have added as targets, including <u>GovCloud (on page 245)</u> accounts. Accounts with a star symbol are master accounts.

For GovCloud accounts, the billed cost is shown as **N/A** since invoicing for these accounts is managed through an associated AWS *standard account*. Adding this standard account as a target is optional. When added, it appears in the Top Accounts chart and shows the total billed cost for the GovCloud accounts and the standard account itself.

NOTE:

Specific RIs can provide savings for multiple accounts. However, individual accounts show the full RI savings, which can result in exaggerated savings for that account.



Azure Accounts

The chart shows the subscriptions discovered via the service principal accounts that you have added as targets, including <u>Azure Government (on page 284)</u> subscriptions.

GCP Accounts

The chart shows the folders and projects discovered via the GCP service accounts that you have added as targets.

If a service account has access to a folder with projects and subfolders, the folder displays as the top-level account. Click **Show All** to see the full resource hierarchy and top-down data. If a service account has access to a project or subfolder but not its parent folder, the project or subfolder displays as the top-level account.

Top Resource Groups Chart

This chart highlights the estimated monthly cost for the top resource groups in your cloud environment and the savings you would realize if you execute the pending actions. Click the **ACTIONS** button to examine these actions and decide which ones are safe to execute. Click a resource group to set the scope to that group.

The chart also counts actions that have been executed for individual groups, and then shows the resulting savings.

Workload Health Charts

Workload Health charts show the health of workloads from the compliance, efficiency improvement, and performance assurance perspectives. These charts use current (real-time) data for the workloads chosen for the chart widget scope.

Chart Type

You can set the display to:

- Text
- Ring Chart
- Horizontal Bar

Breakdown

You can choose:

Workload by Compliance

A virtual environment can include policies that limit availability of resources. It's possible that the environment configuration violates these defined policies. In such cases, Workload Optimization Manager identifies the violation and recommends actions that bring the entity back into compliance.

■ Workload by Efficiency Improvement

Efficient utilization of resources is an important part of running in the desired state. Running efficiently maximizes your investment and reduces cost. When Workload Optimization Manager discovers underutilized workloads, it recommends actions to optimize operations and save money.

Workload by Performance Assurance

Ultimately, the reason to manage workloads in your environment is to assure performance and meet QoS goals. When Workload Optimization Manager detects conditions that directly put QoS at risk, it recommends associated actions to assure performance. You can consider these critical conditions, and you should execute the recommended actions as soon as possible.

Workload Health charts indicate actions that you should consider to improve the health of workloads. To see a list of actions, click **Show Actions** at the bottom of the chart.

Environment Charts

Environment charts provide an overview of your environment. They show the targets that you are managing and count the entities that Workload Optimization Manager has discovered through those targets. For example, you can display the cloud service providers, hypervisors, and the number of workloads.



Environment Type

You can choose one of the following views:

- Hybrid (both on-prem and cloud)
- Cloud
- On-Prem

Display

The chart shows the information as a Text chart type.

Workload Improvements Charts

Workload Improvements charts track the health of workloads in your environment over time, and map the health to the number of actions Workload Optimization Manager has executed in that time period.

In the chart, you can see the significance and value of executed actions:

Workloads Overall

This is the total number of workloads over time.

Workloads with Performance Risks

These are the workloads that are not performing well.

Inefficient Workloads

These are the workloads that are running on under-utilized hosts or are not being utilized.

Workloads Out of Compliance

These are the workloads that are violating a placement policy. Workloads that are not in compliance might be running on a host or placed on storage, for example, that violate a placement policy.

Executed actions

Actions that Workload Optimization Manager executed.

The vertical line shows when the last data point was polled in your environment.

Environment Type

You can choose one of the following views:

- Hybrid (both on-prem and cloud)
- Cloud
- On-Prem

Display

The chart shows the information as a Line chart.

Cloud Chart Types

These chart widgets provide information on the status of your cloud environment.

For many cloud chart widgets that display costs and savings, Workload Optimization Manager uses the billing reports from your cloud service providers to build a picture of your overall costs. The data includes all costs that the service provider includes in the billing report. Workload Optimization Manager parses these reports into the formats that it uses for the cloud chart widgets.

NOTE:

In order for Workload Optimization Manager to access AWS monthly reports, you must have created a Cost and Usage report in your AWS account and you must store it in an S3 bucket.



Billing Breakdown Charts

IMPORTANT:

This chart has been removed from the product and can no longer be added to dashboards. Delete it now and start using the replacement chart, Workload Cost Breakdown.

To delete this chart, click the ellipsis icon (i) at the top right section of the chart and then select **Delete**.

To add the Workload Cost Breakdown chart, click **Add Widget** at the top right section of any dashboard, find and select **Expenses**, go to the Commodity field, and then select **Workload Cost Breakdown**.

Expenses Charts

Workload Optimization Manager uses billing information from your cloud provider to track (on page 112) compute, storage, and license costs for your workloads. Use this chart to manage your costs and see how they evolve over time.

Commodity

You can choose:

Billed Cost by Service Provider

See costs over time for each cloud service provider that you use in your cloud environment.

You can open more than one account from a single service provider. If you are running workloads on different service providers, then this chart shows the distribution of costs across them.

■ Top Billed Cost by Account

The chart shows the <u>cloud accounts</u> (on page 647) with the largest costs. The chart's legend displays up to 20 actual accounts and, if needed, an additional item labeled 'Others' that represents all accounts that are not in the top 20. Hover on a data point to see costs for individual accounts.

■ Top Billed Cost by Service

The chart shows the services with the largest costs. The chart's legend displays up to 20 actual services and, if needed, an additional item labeled 'Others' that represents all services that are not in the top 20. Hover on a data point to see costs for individual services.

■ Workload Cost Breakdown

This chart breaks down costs by the following categories:

- On-Demand Compute
- Spot Compute
- On-Demand Compute License Bundle only applies to Azure VMs and AWS VMs running Windows OS
- On-demand License
- Reserved License
- Storage
- Other cost includes workload costs that are not categorized by Workload Optimization Manager, such as network charges

Points to consider:

- For VMs fully covered by AWS Reserved Instances, Azure reservations, or GCP committed use discounts, on-demand cost is 0 (zero).
- For Azure VMs, the chart shows cost data from the day the VM was discovered by Workload Optimization Manager.
 Cost data before discovery is not available and therefore not reflected in the chart.

Chart Type

You can set the display to:

- Line Chart
- Stacked Bar Chart
- Area Chart



Chart Time Frame

Currently, the chart can display data from the last 7 or 30 days. As you change the time frame, Workload Optimization Manager divides the reported information into the appropriate time units to match that time frame. However, the source remains the same. Changing the time frame does not affect the source data or increase data polling.

Cloud Tier Breakdown Charts

Cloud Tier charts show the cloud tiers that Workload Optimization Manager discovers for the chart widget scope. For example, if the Chart Widget Scope is set to All Cloud VMs and the Entity Type is set to Virtual Machine, the chart shows all the cloud tiers that the workloads use.

Entity Type

You can choose any entity type in the list.

Chart Type

You can set the display to:

- Text
- Ring Chart
- Horizontal Bar

Location Charts

Location charts show cloud provider regions in a world map for which there are discovered workloads. Click on any region to examine more detailed information in a scoped view.

Display

The chart shows the regions in countries in a Map chart.


Cost Breakdown by Tag Charts

Cost Breakdown By Tag charts show the costs for tagged cloud entities that Workload Optimization Manager has discovered in your AWS, Azure, or GCP environment. For the tagged entities in scope, the chart shows how daily costs change over time.

You choose a tag key to track, and then choose which tag values to include in the chart. Each data point aggregates the costs for all the entities with a given tag/value pair. You can display the cost breakdown in a stacked bar chart or an area chart.

For example, in this stacked bar chart, the tag **poolName** is workload-type and the tag **Values** are ptpool, ptpool2, and mixwin.





Scope

To display these charts, add them to the default views in the Home Page or to your custom dashboards. By default, these charts are scoped to your global environment. You can change the scope to view granular data.

Timeframe

Currently, the chart can display data from the last 7 or 30 days.

Chart Type

You can set the display to:

- Area Chart
- Stacked Bar Chart

For more detail, hover over a data point. A tooltip appears to show specific values for that date. Click the legend items to show/hide data for specific values.

Tag Settings

Choose the Tag/Value pairs you want to display in the chart.

Note that tag Key and Value are case insensitive. Each data point in the chart aggregates the costs for all entities with the given tag Key/Value pair, regardless of case.

Key

The tag name that you want to chart. Workload Optimization Manager discovers the tags you have configured in your environment.

You can choose one Key for the chart.

■ Values

The values that you have configured in your environment for the given Key.

You can choose multiple values. To shorten the list of values, type a filter string in the Values field.



Cumulative Savings and Investments Charts

IMPORTANT:

We have enhanced the way we track cumulative savings and investments to accurately report the impact of actions on your cloud expenses. This enhanced tracking begins in version 3.7.3. For cumulative savings and investments before this version, see the **Legacy Cumulative Savings** and **Legacy Cumulative Investments** charts.

Actions for your cloud workloads usually have cost savings or investments attached to them. For example, deleting unattached volumes can lower your costs significantly (savings), while scaling a VM to a different tier to improve performance could incur additional costs (investments). These charts highlight total savings and investments as a result of executing actions. Workload Optimization Manager uses billing data from your cloud provider to calculate savings and investments.

These charts display in the built-in Cloud Executive Dashboard. You can add these charts to the default views in the Home Page or to your custom dashboards.

NOTE:

Billing data from your cloud provider generally takes 1 to 2 days to update fully. Savings and investment figures may change until the data is fully updated.

In the Cloud Executive Dashboard, scoped users can see data for the entire cloud environment.

Scale Actions

Scale actions involve moving an entity to a different compute tier or adjusting the entity's allocated capacity. Currently, Workload Optimization Manager calculates savings and investments when scaling the following entities:

- VMs (AWS, Azure, and GCP)
- Volumes (AWS and Azure)
- Databases (Azure SQL vCore or DTU)
- Virtual Machine Specs (Azure App Service plans)

Workload Optimization Manager calculates savings and investment *per entity*. Calculation is based on the *before-action* and *after-action* costs.

- Before-action cost is the cost of an entity before an action was executed. This is based on the cost snapshot on the day of action execution.
- After-action cost is the cost of an entity as reflected in the daily billing report from the cloud provider.

Savings and investments are the total of all past scaling actions, with the exception that a scale in one direction (such as a scale up) reduces the amounts of previous actions in the opposite direction (such as a scale down), until one or more previous actions have no more effect.

To illustrate, consider three consecutive scale actions for a newly discovered VM and the effect of these actions on the calculated costs. Note that these actions are assumed to have been executed at midnight. Costs are calculated proportionately when actions are executed at other times of the day.

Day	Executed Action	Before-action Cost	After-action Cost	Investments	Savings
01	Scale up	\$2	\$5	\$5 - \$2 = \$3	\$0
02	Scale down	\$5	\$4	\$4 - \$2 = \$2	\$5 - \$4 = \$1
03	Scale down	\$4	\$2	\$2 - \$2 = \$0	\$5 - \$2 = \$3

Investment is the difference between the after-action cost on a particular day and the lowest ever before-action cost up to that day (\$2 for all three days in the example). Savings is the difference between the largest ever before-action cost up to a particular day (\$5 on Days 02 and 03) and the after-action cost on that day.

NOTE

When the result of the calculation is a negative amount, Workload Optimization Manager considers savings or investments to be \$0.



Workload Optimization Manager reads the daily billing report from the cloud provider to determine the current daily cost of an entity. Calculation also takes into account workload uptime (for VMs) and the effect of consecutive scale actions on the same workload.

Points to consider:

- Calculation can adjust to varying VM uptime and discount coverage over time.
- Calculation stops for terminated entities or entities that Workload Optimization Manager no longer discovers.
- Calculation stops if there is a cost change in the entity that is not the result of a Workload Optimization Manager action.

Delete Actions

Delete actions always result in savings. Currently, Workload Optimization Manager calculates savings when deleting the following entities:

- Unattached volumes (AWS, Azure, and GCP)
- Empty Virtual Machine Specs (Azure App Service plans)

Workload Optimization Manager checks the daily cost of an entity on the day the entity was deleted, and uses that cost to calculate savings from that day onwards. The daily bill from the cloud provider is not used to calculate savings.

Chart Settings

Click the More options icon (i), and then select **Edit** to modify the following settings:

Scope

By default, the charts are scoped to your global environment. You can change the scope to one or several accounts, billing families, groups, or entities.

- Timeframe
 - Last 7 Days or Last 30 Days Each data point in the chart shows total savings or investments from previous days until
 the given day.
 - Last Year Each data point in the chart shows total savings or investments from previous months until the given month.
- Chart Type

You can set the display to:

- Text and Bar Chart
- Text and Area Chart
- Stacked Bar Chart
- Area Chart
- Text
- Type

Switch between the **Cumulative Savings** and **Cumulative Investments** views. You can also change the displayed data to just **Savings** or **Investments** if you do not wish to see how the savings or investment costs accumulate over time.

■ Group By

This setting breaks down data points by the selected group. By default, no group is selected. Each data point only shows the total cumulative values for a given day or month, depending on the selected timeframe.

The following groups are supported:

- Account Cloud accounts discovered in your environment
- Action Type Scale and delete actions
- Cloud Service Provider AWS, Azure and GCP
- Entity Type Virtual Machine, Volume, Database (Azure only), Virtual Machine Spec (Azure only)
- Region Regions for the entities
- Resource Group (Azure only) Available resource groups in your environment

For example, if you selected Account:

- The chart represents each account as a distinct color.
- When you hover on a data point, the chart shows a list of accounts, ordered from largest to smallest cumulative values.



- The chart legend shows the individual accounts. Click an account to show/hide values for that account.
- The chart and legend show up to 20 accounts and, if needed, an additional item labeled 'Others' that represents all accounts that are not in the top 20.

Show All

Click Show All at the bottom of the chart to view and download data in tabular format.

Legacy Cumulative Savings and Investments Charts

IMPORTANT:

These charts show cumulative savings and investments before version 3.7.3. We enhanced the tracking of cumulative savings and investments in version 3.7.3, and data from this enhanced tracking is available in the **Cumulative Savings** and **Cumulative Investments** charts.

Actions for your cloud workloads usually have cost savings or investments attached to them. For example, deleting unattached volumes can lower your costs significantly (savings), while scaling a VM to a different tier to improve performance could incur additional costs (investments).

These charts highlight:

- Total realized savings and investments as a result of executing actions
- Total missed savings and investments when actions are not executed

Information in these charts can help shape your action handling policies. For example, you can start automating actions so you don't miss opportunities to assure performance at the lowest possible cost.

Scope

These charts display in the built-in Cloud Executive Dashboard and are scoped to your global environment. You can change the scope to view granular data. You can also add these charts to the default views in the Home Page or to your custom dashboards.

Another way to view granular data is to set the scope (in the supply chain or by using Search) to one or several accounts, billing families, groups, or workloads.

Scale Actions

For actions to scale workloads (VMs, Database Servers, databases, or volumes), Workload Optimization Manager calculates savings and investment *per workload* based on the hourly cost of the workload price difference, taking into account workload uptime (on page 386) and the effect of consecutive scale actions on the same workload.

Calculated investments and savings are the total of all past scaling actions, with the exception that a scale in one direction reduces the amounts of previous actions in the opposite direction, until one or more previous actions have no more effect.

To illustrate:

Consider three consecutive scale actions for a VM and their effect on the calculation.

- 1. A cost increase of \$1.00 counts as an investment of \$1.00.
- A subsequent cost decrease of \$0.25 is factored in as:
 - Savings of \$0.25 to the total amount in the Cumulative Savings chart
 - An investment of \$0.75 to the total amount in the Cumulative Investments chart
- 3. Another cost decrease of \$1.00 is factored in as:
 - Savings of \$1.25 to the total amount in the Cumulative Savings chart
 - An investment of \$0.00 to the total amount in the Cumulative Investments chart

By the time the third action was executed, the initial \$1.00 investment has been "undone" (investment amount is \$0.00) and is no longer considered when calculating savings and investments for the VM.

- Calculation can adjust to varying VM uptime and discount coverage over time.
- Calculation stops for terminated entities or entities that Workload Optimization Manager no longer discovers.
- Calculation stops if there is a cost change in the entity that is not the result of a Workload Optimization Manager action.



Volume Delete Actions

For actions to delete volumes, Workload Optimization Manager calculates savings accumulated over one year since volume deletion, based on the hourly cost of the deleted volume. It also estimates missed savings based on the hourly cost of the workload price difference and the number of hours that pending actions remain in the system.

Chart Type

You can set the display to:

- Text and Bar Chart
- Text and Area Chart
- Stacked Bar Chart
- Area Chart
- Text

You can edit the chart to switch between the **Cumulative Savings** and **Cumulative Investments** views. You can also change the displayed data to just **Savings** or **Investments** if you do not wish to see how the savings or investment costs accumulate over time.

In this example, Workload Optimization Manager shows monthly realized and missed savings.



In the chart legend, you can click **Realized Savings** or **Missed Savings** to display a filtered view. Click the item again to reset the chart.

Click **Show All** at the bottom of the chart to view and download data in tabular format.

Investments and Savings Charts

IMPORTANT:

We have enhanced the way we track savings and investments to accurately report the impact of actions on your cloud expenses. This enhanced tracking begins in version 3.7.3. For savings and investments before this version, see the **Legacy Cumulative Savings** and **Legacy Cumulative Investments** charts.

Actions for your cloud workloads usually have cost savings or investments attached to them. For example, deleting unattached volumes can lower your costs significantly (savings), while scaling a VM to a different tier to improve performance could incur additional costs (investments). These charts highlight total savings and investments as a result of executing actions. Workload Optimization Manager uses billing data from your cloud provider to calculate savings and investments.

You can add these charts to the default views in the Home Page or to your custom dashboards.



NOTE:

Billing data from your cloud provider generally takes 1 to 2 days to update fully. Savings and investment figures may change until the data is fully updated.

Scale Actions

Scale actions involve moving an entity to a different compute tier or adjusting the entity's allocated capacity. Currently, Workload Optimization Manager calculates savings and investments when scaling the following entities:

- VMs (AWS, Azure, and GCP)
- Volumes (AWS and Azure)
- Databases (Azure SQL vCore or DTU)
- Virtual Machine Specs (Azure App Service plans)

Workload Optimization Manager calculates savings and investment *per entity*. Calculation is based on the *before-action* and *after-action* costs.

- Before-action cost is the cost of an entity before an action was executed. This is based on the cost snapshot on the day of action execution.
- After-action cost is the cost of an entity as reflected in the daily billing report from the cloud provider.

NOTE

When the result of the calculation is a negative amount, Workload Optimization Manager considers savings or investments to be \$0.

Workload Optimization Manager reads the daily billing report from the cloud provider to determine the current daily cost of an entity. Calculation also takes into account workload uptime (for VMs).

Points to consider:

- Calculation can adjust to varying VM uptime and discount coverage over time.
- Calculation stops for terminated entities or entities that Workload Optimization Manager no longer discovers.
- Calculation stops if there is a cost change in the entity that is *not* the result of a Workload Optimization Manager action.

Delete Actions

Delete actions always result in savings. Currently, Workload Optimization Manager calculates savings when deleting the following entities:

- Unattached volumes (AWS, Azure, and GCP)
- Empty Virtual Machine Specs (Azure App Service plans)

Workload Optimization Manager checks the daily cost of an entity on the day the entity was deleted. The daily bill from the cloud provider is not used to calculate savings.

Chart Settings

Click the More options icon (i), and then select **Edit** to modify the following settings:

Scope

By default, the charts are scoped to your global environment. You can change the scope to one or several accounts, billing families, groups, or entities.

- Timeframe
 - Last 7 Days or Last 30 Days Each data point in the chart shows total savings or investments for the given day.
 - Last Year Each data point in the chart shows total savings or investments for the given month.
- Chart Type

You can set the display to:

- Text and Bar Chart
- Text and Area Chart
- Stacked Bar Chart
- Area Chart



- Text
- Type

Switch between the **Savings** and **Investments** views. You can also change the displayed data to **Cumulative Savings** or **Cumulative Investments** to see how the savings or investment costs accumulate over time.

Group By

This setting breaks down data points by the selected group. By default, no group is selected. Each data point only shows the total values for a given day or month, depending on the selected timeframe.

The following groups are supported:

- Account Cloud accounts discovered in your environment
- Action Type Scale and delete actions
- Cloud Service Provider AWS, Azure and GCP
- Entity Type Virtual Machine, Volume, Database (Azure only), Virtual Machine Spec (Azure only)
- Region Regions for the entities
- Resource Group (Azure only) Available resource groups in your environment

For example, if you selected Account:

- The chart represents each account as a distinct color.
- When you hover on a data point, the chart shows a list of accounts, ordered from largest to smallest values.
- The chart legend shows the individual accounts. You can click an account to show/hide values for that account.
- The chart and legend show up to 20 accounts and, if needed, an additional item labeled 'Others' that represents all accounts that are not in the top 20.

Show All

Click Show All at the bottom of the chart to view and download data in tabular format.

Legacy Savings and Investments Charts

IMPORTANT:

These charts show savings and investments before version 3.7.3. We enhanced the tracking of savings and investments in version 3.7.3, and data from this enhanced tracking is available in the **Savings** and **Investments** charts.

Actions for your cloud workloads usually have cost savings or investments attached to them. For example, deleting unattached volumes can lower your costs significantly (savings), while scaling a VM to a different tier to improve performance could incur additional costs (investments).

These charts highlight:

- Total realized savings and investments as a result of executing actions
- Total missed savings and investments when actions are not executed

Information in these charts can help shape your action handling policies. For example, you can start automating actions so you don't miss opportunities to assure performance at the lowest possible cost.

Scope

To display these charts, add them to the default views in the Home Page or to your custom dashboards. By default, these charts are scoped to your global environment. You can change the scope to view granular data.

Another way to view granular data is to set the scope (in the supply chain or by using Search) to one or several accounts, billing families, groups, or workloads.

Scale Actions

For actions to scale workloads (VMs, Database Servers, databases, or volumes), Workload Optimization Manager calculates savings and investment *per workload* based on the hourly cost of the workload price difference, taking into account workload uptime (on page 386).

Calculation can adjust to varying VM uptime and discount coverage over time.



- Calculation stops for terminated entities or entities that Workload Optimization Manager no longer discovers.
- Calculation stops if there is a cost change in the entity that is not the result of a Workload Optimization Manager action.

Volume Delete Actions

For actions to delete volumes, Workload Optimization Manager calculates savings since volume deletion, based on the hourly cost of the deleted volume. It also estimates missed savings based on the hourly cost of the workload price difference and the number of hours that pending actions remain in the system.


Chart Type

You can set the display to:

- Text and Bar Chart
- Text and Area Chart
- Stacked Bar Chart
- Area Chart
- Text

You can edit the chart to switch between the **Savings** and **Investments** views. You can also change the displayed data to **Cumulative Savings** or **Cumulative Investments** to see how the savings or investment costs accumulate over time.

In this example, the chart shows realized and missed savings per month over the last year. It indicates higher rates of realized savings in the last two months as more actions are executed rather than kept pending.



In the chart legend, you can click **Realized Savings** or **Missed Savings** to display a filtered view. Click the item again to reset the chart.

Click Show All at the bottom of the chart to view and download data in tabular format.

Recommended RI Purchases Charts


Workload Optimization Manager can recommend purchasing instance types at a discounted rate to help you increase the percentage of VMs covered by discounted pricing and reduce on-demand costs. This chart shows your pending purchases. Download the list of purchases and then send it your cloud provider or representative to initiate the purchase process.

NOTE:

Purchase actions should be taken along with the related VM scaling actions. To purchase discounts for VMs at their current sizes, run a <u>Buy VM Reservation Plan (on page 577)</u>.

Currently, Workload Optimization Manager can recommend purchase actions for AWS and Azure. Purchase actions for GCP will be introduced in a future release.





Factors Affecting Recommendations

To identify VMs that are good candidates for discounted pricing, Workload Optimization Manager analysis considers the history of a VM (by default, the last 21 days), and it looks for:

- Activity
 - If the VM's VCPU utilization percentile is 20% or higher, then Workload Optimization Manager considers it an active VM.
- Stability
 - If there have been no start, stop, or resize actions for the VM for 16 of the last 21 days, then Workload Optimization Manager considers it stable.

If the current discount inventory cannot support the VM, or if supporting it would exceed your desired coverage, then Workload Optimization Manager can recommend purchasing additional discounts.

Workload Optimization Manager generates purchase actions on a two-week cycle. It also generates a new set of actions if the discount inventory changes or after the platform restarts.

Be aware of the following:

- Different types of discounts have different costs, so the choice between using on-demand or discounted pricing can vary depending on your <u>purchase profile (on page 716)</u>.
- Workload Optimization Manager can only estimate costs because the full data is only available after you complete the purchase. Estimates reflect costs you would see after scaling workloads to the newly purchased instance types. For scaling to already-purchased instance types, the chart reflects the actual costs.
- As Workload Optimization Manager generates purchase actions, it assumes that any other pending actions for the workload will also be executed. For example, assume a workload running on an r4.xlarge template. If Workload Optimization Manager recommends changing that instance type to an m5.medium, it can recommend that you purchase a discounted m5 to cover the workload and reduce costs. This purchase could be on a region that currently doesn't have any m5 workloads. The purchase recommendation assumes you will move the workload to that other region.
- For AWS RIs:
 - For environments that use the *Instance Size Flexible* rules, Workload Optimization Manager can recommend that you buy multiple RIs of smaller instance types to cover the resource requirements of larger instance types. For example, rather than buying one t2.small RI, Workload Optimization Manager can recommend that you buy four t2.nano RIs to offer an equivalent discount.
 - For environments that consolidate billing into Billing Families, Workload Optimization Manager recommends purchases that are within the given billing family. For more information, see <u>AWS Billing Families</u> (on page 248).

Show All

Click Show All to see a table with details for each discount.

The table shows the properties, up-front cost, and break-even period for each discount. The break-even period is the time at which savings will exceed the up-front cost, rounded to the month. The Cost Impact column indicates the monthly savings you would realize when you buy a specific discount.

When you choose one or more check boxes, the total count, up-front cost, and savings appear at the top.







Chart Type

You can set the display to:

- Text
- Ring Chart
- Horizontal Bar

Discount Coverage Chart

This chart shows the estimated percentage of VMs covered by discounts. If you have a high percentage of on-demand VMs, you should be able to reduce your monthly costs by increasing coverage. To increase coverage, you scale VMs to instance types that have existing capacity.





To identify VMs that are good candidates for discounted pricing, Workload Optimization Manager analysis considers the history of a VM (by default, the last 21 days), and it looks for:

Activity

If the VM's VCPU utilization percentile is 20% or higher, then Workload Optimization Manager considers it an active VM.

Stability

If there have been no start, stop, or resize actions for the VM for 16 of the last 21 days, then Workload Optimization Manager considers it stable.

If the current discount inventory cannot support the VM, or if supporting it would exceed your desired coverage, then Workload Optimization Manager can recommend purchasing additional discounts.

Timeframe

The chart shows daily data points and supports the following timeframes:

- Last 7 Days
- Last 30 Days

AWS RIs and Savings Plans

Workload Optimization Manager uses billing data collected from the cloud provider to calculate the values displayed in the chart. In order for Workload Optimization Manager to collect billing data, you must add a billing target in the Target Configuration page.

Workload Optimization Manager supports cost and usage reports created at the management account, but not member accounts.

The chart shows historical data. Data for the current day is not available since the latest data available from the cloud provider is always a few days old.

Hover on a data point in the chart to see the following information:

- The date and time for the data point
- The percentage of coverage. For RIs, coverage is based on normalization factors.

Normalization factor is a measure of RI capacity that you can use to compare or combine the capacity for different instance families.

Workload Optimization Manager measures RI coverage in terms of normalization factors. It compares the number of RIs calculated as normalization factors that cover workload capacity with the total number of normalization factors for a given Workload Optimization Manager scope. Each workload is assigned normalized units depending on its instance type.

Points to consider:

- Scope
 - If you set the scope to a specific AWS account, the chart shows the RI coverage for the workloads for the account and any RIs for the billing family.
 - For AWS GovCloud, you can set the scope to the global environment or the standard account/billing family associated with GovCloud.
- RIs

In AWS, you can turn off RI discount sharing for specific accounts. These accounts will not share any discounts with other accounts. Workload Optimization Manager does not recognize RI coverage or utilization for these accounts. For example, the RI Coverage and RI Utilization charts will show zero values.

Savings Plans

AWS timestamps data in UTC, but the chart presents data in your local time. This difference could result in the appearance of a missing day in the chart, but has no effect on data completeness (the chart always reflects the complete data set).

Azure Reservations

The chart shows data for the current day and any historical data that was polled from your environment. Hover on a data point in the chart to see the following information:

- The date and time for the data point
- The percentage of coverage, based on ratios.



Ratio refers to the number of Azure reservation units that cover workload capacity compared to the total number of reservation units for a given Workload Optimization Manager scope. Each workload is assigned reservation units based on its instance type.

If you set the scope to a specific Azure subscription, this chart shows the reservation coverage for the workloads for the subscription, plus any shared reservations and single-scope reservations owned by this subscription.

GCP Committed Use Discounts

The chart shows the latest data from your environment, but does not show historical data.


Hover on a data point in the chart to see the following information:

- The date and time for the data point
- The percentage of coverage

Discount Inventory Chart

This chart lists the cloud provider discounts discovered in your environment.

- AWS Reserved Instances (RIs) and Savings Plans for non-government and GovCloud workloads
- Azure reservations for non-government and Azure Government workloads
- GCP committed use discounts



Timeframe

The chart shows daily data points and supports the following timeframes:

- Last 7 Days
- Last 30 Days

Scope

You can set the scope to your global cloud environment or to individual AWS accounts, Azure subscriptions, GCP folders, billing families, or regions.


For AWS GovCloud Savings Plans, you can set the scope to the global environment or the standard account/billing family associated with GovCloud.

For AWS GovCloud RIs, you can set the scope to the global environment, or a GovCloud account or billing family.

Show All

Click **Show All** at the bottom of the chart to see detailed information for the discounts in scope. If your scope includes multiple cloud providers, each provider will have its own tab.





Each row in the table corresponds to a discount. Note that there can be several discounts for an Azure subscription or AWS/GCP account, and each discount displays as its own row. Table columns show basic information obtained from the cloud provider, such as the name/ID of the discount, the subscription/account that uses that discount, instance type and location, term, and expiration dates. Click a subscription/account to narrow the scope.

The table supports the following general functionality:

- **Totals**: At the top of the page, you will see the total number of discovered discounts. For AWS RIs and Azure reservations, you will also see total costs and savings. As you select one or more checkboxes, the information changes to reflect the totals for your selections.
- Column Sorting: Click any column heading to sort the list.
- **Download**: Click the Download icon at the upper right section of the page to download the table as a CSV file.

Azure Reservations and AWS RIs

When you add an Azure EA account or an AWS management account as your primary cloud target, Workload Optimization Manager gains full insight into the discounts for your billing families. Even as you selectively add Azure subscriptions or AWS member accounts as secondary targets, Workload Optimization Manager remains aware of all discounts and how they are utilized across the board, and can thus recommend more accurate discount optimization and purchase actions.

Points to consider:

- For AWS, if you added some member accounts as targets, but not a management account, Workload Optimization Manager will not reflect discounts for member accounts that you have not added as targets.
- For Azure:
 - It could take Workload Optimization Manager up to a day to discover newly purchased Azure reservations.
 - There can be delays in billing information updates that Azure makes available to Workload Optimization Manager. If this
 happens, analysis might use partial billing data in its calculations and show incomplete costs for discounts from nonadded Azure subscriptions.

Set the scope to your global environment to view the full inventory. When you click **Show All** at the bottom of the chart, pay attention to the following information shown in the table:

■ For discounts in added accounts (Azure subscriptions or AWS member accounts):



Account column (for AWS) or Subscription column (for Azure)

This column shows the account name for the discount. Click the name to set the scope to that account. Note that there can be several discounts for an account, and each discount displays as its own row.

NOTE:

If there is a failure to re-validate the account for some reason, Workload Optimization Manager shows it as a *non-added* account in the Discount Inventory page.

Est. Current Utilization column



This column shows the percentage of discount capacity currently used by VMs in all accounts. Workload Optimization Manager estimates the percentage if there are VMs in non-added accounts that use the discount (since the exact number of VMs is unknown).

■ For discounts in *non-added* accounts:



Account column (for AWS) or Subscription column (for Azure)

This column shows a grayed-out, non-clickable name to indicate that you have not added the account as a target. Workload Optimization Manager is aware of this account and if the given discount is shared with other accounts because you have added a management or EA account.

Est. Current Utilization column

This column shows the percentage of discount capacity currently used by VMs in all accounts. Workload Optimization Manager estimates the percentage if there are VMs in non-added accounts that use the discount (since the exact number of VMs is unknown).

AWS Savings Plans

If you added targets that are AWS accounts with read-only access to the AWS Savings Plans API, Workload Optimization Manager uses this chart to present the Savings Plans that it discovered in your cloud environment (including GovCloud) and the instance types they use.



GCP Committed Use Discounts

Workload Optimization Manager discovers committed use discounts for your workloads when you add the following as targets:


- A service account with the "Billing Account Viewer" role to the related billing accounts
- Billing accounts



Discount Utilization Chart

This chart shows how well you have utilized your current discount <u>inventory (on page 663)</u>. The desired goal is to maximize the utilization of your inventory and thus take full advantage of the discounted pricing offered by your cloud provider.





Timeframe

The chart shows daily data points and supports the following timeframes:

- Last 7 Days
- Last 30 Days

AWS RIs and Savings Plans

Workload Optimization Manager uses billing data collected from the cloud provider to calculate the values displayed in the chart. In order for Workload Optimization Manager to collect billing data, you must add a billing target in the Target Configuration page.

Workload Optimization Manager supports cost and usage reports created at the management account, but not member accounts.

The chart shows historical data. Data for the current day is not available since the latest data available from the cloud provider is always a few days old.

Hover on a data point in the chart to see the following information:

- The date and time for the data point
- The percentage of utilization

For Savings Plans, utilization is based on the total utilized and committed costs per day.

For RIs, utilization is based on normalization factors.

Normalization factor is a measure of RI capacity that you can use to compare or combine the capacity for different instance families.

Workload Optimization Manager measures RI coverage in terms of normalization factors. It compares the number of RIs calculated as normalization factors that cover workload capacity with the total number of normalization factors for a given Workload Optimization Manager scope. Each workload is assigned normalized units depending on its instance type.

Points to consider:

- Scope
 - You can set the scope to your global cloud environment or to individual accounts, billing families, or regions. Scoping
 to an account shows the RI utilization for the workloads for the entire billing family.
 - For AWS GovCloud RIs, you can set the scope to the global environment, or a GovCloud account or billing family.
 - For AWS GovCloud Savings Plans, you can set the scope to the global environment or the standard account/billing family associated with GovCloud.
- RIs
 - In AWS, you can turn off RI discount sharing for specific accounts. These accounts will not share any discounts with other accounts. Workload Optimization Manager does not recognize RI coverage or utilization for these accounts. For example, the RI Coverage and RI Utilization charts will show zero values.



- Under very rare circumstances, you can have RIs on payment plans that do not resolve to 1-year or 3-year terms. In this case, AWS does not return pricing data for those RIs. Workload Optimization Manager does not include such RIs in its calculations of RI utilization or RI cost.
- Savings Plans

AWS timestamps data in UTC, but the chart presents data in your local time. This difference could result in the appearance of a missing day in the chart, but has no effect on data completeness (the chart always reflects the complete data set).

Azure Reservations

The chart shows data for the current day and any historical data that was polled from your environment. Hover on a data point in the chart to see the following information:

- The date and time for the data point
- The percentage of utilization, based on ratios.

Ratio refers to the number of Azure reservation units that cover workload capacity compared to the total number of reservation units for a given Workload Optimization Manager scope. Each workload is assigned reservation units based on its instance type.

You can set the scope to your global cloud environment or to individual subscriptions, billing families, or regions. Scoping to a subscription shows the reservations utilization for workloads for the entire billing family or for single and shared subscriptions.

GCP Committed Use Discounts

The chart shows the latest data from your environment, but does not show historical data.

Hover on a data point in the chart to see the following information:

- The date and time for the data point
- The percentage of utilization

Cloud Estimated Cost Charts

Cloud Estimated Cost charts show estimated monthly costs and investments for the cloud. Monthly cost amounts are summarized as amounts with and without actions.

Display

The chart shows the information as a Text chart.

Volume Summary Charts

To help you manage your costs on the public cloud, these charts show the distribution and costs of volumes for the given scope. In this way, you can see how volume utilization affects your costs. For these charts, Workload Optimization Manager calculates the costs based on the cost information from the cloud targets.

These charts show the following data:

- Tiers
 - The chart breaks down volumes by tier (disk type) and shows the volume count and monthly cost for each tier.
- Volume State

The chart breaks down volumes by attachment state (attached or unattached) and shows the volume count and monthly cost for each state. For unattached volumes, you can reduce your cloud cost by the given amount if you delete these volumes. Click **Show All** and then click the **Details** button for an unattached volume to execute a delete action.

NOTE:

For an Optimize Cloud plan, the Volume Tier Summary chart shows 'Current' and 'Optimized' results. The 'Current' result includes currently unattached volumes that you can delete to reduce costs, while the 'Optimized' result assumes that unattached volumes have been deleted. To see a list of unattached volumes, click **Show Changes** at the bottom of the chart. For details about Optimize Cloud plans, see Optimize Cloud Plan Results (on page 564).



For a detailed breakdown, click **Show All** at the bottom of the chart. If you have multiple cloud providers, each provider will have its own tab. Click any column heading to sort the list. When you choose one or more check boxes, the total appears at the top.

NOTE:

For Azure environments with VMs in Scale Sets, for any VMs that are powered off, the associated volume shows a utilization of zero GB. This is an accurate presentation of the data that the Azure environment returns for such a powered-off VM. However, it is likely that some of the volume capacity is currently utilized.

Chart Unit

If you are scoped to a particular cloud provider, you can sort tiers and volumes by clicking the Edit option at the top-right corner of the chart, and then choosing one of the following units:

- Count Sort by volume count, from largest to smallest.
- Cost Sort by monthly cost, from highest to lowest.

On-Prem Chart Types

These chart widgets provide information on the status of your on-prem environment.

Density Charts

Density charts show the number of resource consumers (virtual machines or containers) per provider (host or storage). If available, choose the **Show Density** checkbox to see the ratio of consumers to providers.

These charts also show the desired count of virtual machines, assuming you want to fill the headroom completely. Note that the Desired Workloads values are the results of running plans. These plans can calculate workload moves within a cluster to gain more efficiency, but they always respect the cluster boundaries – the plans never move VMs to hosts on different clusters.

To display relevant data, you must set the scope to your global environment or a cluster group. Other scopes are not supported. To display relevant data, you must set the scope to your global environment or a cluster group. Other scopes are not supported.

Chart Type

You can set the display to:

- Stacked Bar Chart
- Line Chart

Ports Charts

Ports charts show the most utilized northbound or southbound ports in your on-prem environment over a given time period. These charts are useful in Fabric environments where you license port channels.

Display

The chart shows the information as Tabular.

Headroom Charts

Headroom charts show how much extra capacity your clusters have to host workloads.

To calculate cluster capacity and headroom, Workload Optimization Manager runs nightly plans that take into account the conditions in your current environment. The plans use the Economic Scheduling Engine to identify the optimal workload distribution for your clusters. This can include moving your current VMs to other hosts within the given cluster, if such moves would result in a more desirable workload distribution. The result of the plan is a calculation of how many more VMs the cluster can support.



To calculate VM headroom, the plan simulates adding VMs to your cluster. The plan assumes a certain capacity for these VMs, based on a specific VM template. For this reason, the count of VMs given for the headroom is an approximation based on that VM template.

You can specify the following types of Headroom charts:

- CPU Headroom
- Memory Headroom
- Storage Headroom

Commodity


You can choose:

- CPU Headroom
- Memory Headroom
- Storage Headroom

Display

The chart shows the information as an Area chart.

Example:



Exhaustion Time Chart

This chart shows the current growth of workloads and projects when workloads will exceed the capacity of your current infrastructure. This is useful for future planning (for example, if you might need to buy more hardware).

You can track CPU, memory, and storage as well as the average monthly Virtual Machine growth and the average VM template. The amount of time is presented as days. For example, storage will be used up in 41 days.

Display

The chart shows the information as a Text chart.

Creating Groups

Groups assemble collections of resources for Workload Optimization Manager to monitor and manage. When setting scope for your Workload Optimization Manager session, you can select groups to focus on those specific resources. For example, if you have a number of VMs devoted to a single customer, you can create a group of just those VMs. When running a planning scenario you can set the scope to work with just that group.



Workload Optimization Manager discovers groups that exist in your environment and allows you to create custom groups. Workload Optimization Manager supports two custom-grouping methods:

Dynamic – You define these groups by specific criteria. You can group services according to naming conventions (all VM names that start with ny), resource characteristics (all hosts with four CPUs), or other criteria such as time zone or number of CPUs.

These groups are dynamic because Workload Optimization Manager updates the group as conditions change.

Static – You create these groups by selecting the specific group members.

NOTE:

Do not use the Workload Optimization Manager user interface to delete discovered groups. If you do, later analysis cycles will discover them again, and add them to your environment. In the meantime, any analysis that relies on those groups can give unexpected results.

You can delete any custom group you have created. Before you do, verify that you do not have any charts, plans, or policies that use the group you want to delete. After you delete the group, such charts, plans, or policies will lose their scope. For example, a policy with no scope has no effect.

To create a group:

1. Navigate to the Settings Page.



Click to navigate to the Settings Page. From there, you can perform a variety of Workload Optimization Manager configuration tasks.

2. Choose Groups.




Groups

Click to navigate to the Group Management Page.

This page lists all the custom groups that you currently have configured for Workload Optimization Manager.

Perform tasks in the Group Management page.



You can perform any of the following tasks:

- Filter groups by type
- Search for groups
- Click a group name to edit it




For a dynamic group, you can edit the set of criteria that select the group members. For a static group, you can add or subtract specific members.

- Expand an entry to see group details
- Select an entry to delete the group
- Create new groups

To work with a long list of groups, you can filter by group type. For example, only show groups of VMs, or groups of host machines. You can also type a string in the **Search** field to filter the list.


4. Expand an entry to see group details.



The details show you information about related entities such as how many hosts provide resources for a group of VMs. If there are any pending actions for the group, the details list those actions as well.

5. Create a new group.

Click **NEW GROUP**, choose a group type, and then specify the group settings.



- Give the group a unique name. To prevent issues, you should never use duplicate names for groups of the same entity type.
- Set whether the group will be static or dynamic.

To create a static group, select the member entities from the list. To filter the list, set group criteria.

To create a dynamic group, set group criteria. The list updates to show the resulting group members.

Specify group criteria.

These criteria are entity attributes that determine group membership. You might create a group of all VMs that have 4 VCPUs. You can choose properties of the member entities, and you can choose properties of entities that are related



to the members. For example, you can make a group of VMs that are hosted by PMs with the substring "Development" in their names.

As you set criteria, the list of entities updates to show the member entities. You also can sort the list by severity (per the most critical entity in group) or group name.

Note that you can use regular expression to express your match strings.

■ When you are finished, save the group.

Save adds this group to the My Groups collection.

Working With Policies

Policies set business rules to control how Workload Optimization Manager analyzes resource allocation, displays resource status, and recommends or executes actions. Workload Optimization Manager includes two fundamental types of policies.

Placement Policy

A placement policy is a set of rules that Workload Optimization Manager must satisfy when generating placement recommendations for on-prem and containerized workloads.

For details, see Placement Policies (on page 673).

Automation Policy

An automation policy is a set of rules that Workload Optimization Manager must satisfy when executing <u>non-parking</u> <u>actions (on page 518)</u> on public cloud or on-prem workloads, or changing settings that affect analysis and action generation.

For details, see Automation Policies (on page 677).

Parking Policy

A parking policy is a set of rules that Workload Optimization Manager must satisfy when enforcing parking actions (start or stop) on public cloud workloads.

For details, see Parking Policies (on page 700).

Policy Management

Use the Policy Management page to view and manage policies. The page shows the following categories of policies:

- All Policies All the currently defined policies
- Placement Policies
 - Imported Placement Policies Placement policies discovered (on page 673) from your targets
 - Workload Optimization Manager Segments Placement policies <u>created (on page 673)</u> from the Policy Management page
- Automation Policies
 - Imported Automation Policies Automation policies discovered (on page 680) from your targets
 - User Defined Automation Policies Automation policies <u>created (on page 680)</u> from the Policy Management page
 - Defaults <u>Default (on page 678)</u> automation policies for the different entity types

NOTE:

To see the placement or automation policies that are applied by a particular entity, set the scope to that entity (from Search or the supply chain), and then click the Policies tab. For more information, see Scope Policies (on page 130).

Parking Policies

NOTE:

All parking policies are manually created from the Policy Management page. There are no default or imported parking policies.

- Global
- Cloud Provider
- Account



Resource Groups

Placement Policies

A placement policy is a set of rules that Workload Optimization Manager must satisfy when generating placement recommendations for on-prem and containerized workloads.

With these policies, Workload Optimization Manager can recommend placement actions that comply with your business rules. For example, a placement policy can constrain VMs to specific hosts. If a VM needs to move to a different host due to resource congestion, Workload Optimization Manager will generate an action to move the VM to one of the hosts defined in the policy.

Workload Optimization Manager discovers placement policies from your targets, and allows you to create your own policies.

NOTE:

You can enable or disable any placement policy to affect placement calculations in the real-time environment or in plans.

When calculating workload placement, Workload Optimization Manager respects cluster boundaries, networks, and provisioned data stores. In addition, the configuration of your environment can specify logical boundaries, and you can create even more boundaries within Workload Optimization Manager. These boundaries impose segments on the market that Workload Optimization Manager uses to model your application infrastructure.

In finance, a market segment divides the market according to the criteria different groups of people use when they buy or sell goods and services. Likewise in the Workload Optimization Manager market, a workload placement segment uses criteria to focus the buying and selling of resources within specific groups of entities. This gives you finer control over how Workload Optimization Manager calculates placements.

Imported Placement Policies

Your on-prem targets can include placement policies of their own. Workload Optimization Manager imports these placement policies, and considers them to be constraints on placement. You cannot disable these imported policies for real-time analysis, but you can disable them for plans.

Workload Optimization Manager imports the following:

- vCenter Server DRS Rules
 - See Other Information Imported from vCenter (on page 221)
- Virtual Machine Manager Availability Sets
 - See Virtual Machine Manager (on page 234)
- Flexera One License Specifications
 - See Flexera (on page 229)

To view imported placement policies, navigate to Settings > Policies, and then click Imported Placement Policies.

Creating Placement Policies

A placement policy is a set of rules that Workload Optimization Manager must satisfy when generating placement recommendations for on-prem and containerized workloads.

With these policies, Workload Optimization Manager can recommend placement actions that comply with your business rules. For example, a placement policy can constrain VMs to specific hosts. If a VM needs to move to a different host due to resource congestion, Workload Optimization Manager will generate an action to move the VM to one of the hosts defined in the policy.

Workload Optimization Manager discovers placement policies from your targets, and allows you to create your own policies.

You can create the following placement policies:

■ Place – Determine which entities use specific providers

For example, the VMs in a consumer group can only run on a host that is in the provider group. You can limit the number of consumers that can run on a single provider – for hosts in the provider group, only 2 instances of VMs in the consumer group can run on the same host. Or no more than the specified number of VMs can use the same storage device.



■ **Don't Place** – Consumers must never run on specific providers

For example, the VMs in a consumer group can never run on a host that is in the provider group. You can use such a segment to reserve specialized hardware for certain workloads.

■ Merge - Merge clusters into a single provider group

For example, you can merge three host clusters in a single provider group. This enables Workload Optimization Manager to move workload from a host in one of the clusters to a host in any of the merged clusters to increase efficiency in your environment.

■ License – Set up hosts to provide licenses for VMs

For VMs that require paid licenses, you can create placement policies that set up certain hosts to be the VMs' preferred license providers. Workload Optimization Manager can then recommend consolidating VMs or reconfiguring hosts in response to changing demand for licenses.

1. Navigate to the Settings Page.



Click to navigate to the Settings Page. From there, you can perform a variety of Workload Optimization Manager configuration tasks.


2. Choose Policies.



Click to navigate to the Policy Management Page.

This page lists all the policies that you currently have configured for Workload Optimization Manager.

3. Create a new Placement policy.



First, select the type of Placement policy to create, then specify the settings:

- Give the policy a name
- Choose the policy type and make the settings
- Save the policy when you're done




Create a Place policy.

POLICY NAME			_
TYPE			
PLACE	DON'T PLACE	MERGE	LICENSE
PLACE			
Choose co	onsumer type	\$ SELECT	GROUP
ON			
Choose p	rovider type	SELECT	GROUP
Limit v	vorkload entities t	o placement	group
Limit t	he maximum num	ber of workl	oad entities per placement entity t

These policies control where workload can be placed. For example, you can specify that a VM will only be placed on a host that is a member of a specific cluster. Or you could specify that any applications in a specific group can only be placed on a datastore that is a member of a specific group.


- Specify the consumer group The group or cluster of entities that will be placed on the identified providers
- Specify the provider group The group or cluster of entities that will provide resources to the consumers
- **Limit workload entities to placement group** Set the policy to only place consumer entities on members of the provider group
- Limit the maximum number of workload entities per placement entity to Limit how many instances of the consumer entities can be placed on a single provider
- 5. Create a **Don't Place** policy.



These policies identify groups or clusters that will never host the consumer entities. For example, you can specify that a VM will never be placed on a host that is a member of a specific cluster. Or you can specify that a set of non-critical applications will never be placed on specialized hardware, as a way to ensure availability for critical applications.

- Specify the consumer group The group or cluster of entities that will be excluded from the identified providers
- Specify the provider group The group or cluster of entities that will not provide resources to the consumers
- 6. Create a Merge policy.





You can create placement policies that merge multiple clusters into a single logical group for the purpose of workload placement.

For example, your environment might divide hosts into clusters according to hardware vendor, or by some other criteria. Workload placement typically does not cross such cluster boundaries. However, there might be no technical reason to apply these boundaries to workload placement. By creating a larger pool of provider resources, Workload Optimization Manager has even more opportunities to increase efficiency in your environment.

For merge policies, keep the following considerations in mind:

- For most policies that merge host and storage clusters, the clusters you place in the Merge segment must be members of the same datacenter.
- For vCenter environments, you can create placement policies that merge data centers to support cross-vCenter moves. In this case, where a data center corresponds to a given vCenter target, the merged clusters can be in different data centers. In this case you must create two merge policies; one to merge the affected data centers, and another to merge the specific clusters.

Also note that the clusters you merge must use the same network names on their respective datacenters.

To create a Merge policy, choose the type of entity to merge, and then select the groups you will merge.

7. Create a License policy.

POLICY NAME			
TYPE			
PLACE	DON'T PLACE	MERGE	LICENSE
LICENSE			
Choose co	nsumer type.	. \$ SELECT	GROUP
ON			
Choose p	ovider type	♦ SELECT	GROUP

Assume you have purchased a number of licenses for a database – you pay for the right to run that database on a certain number of hosts. You can create a license policy to identify the hosts that provide the license, and the VMs that can consume that license.

After you create the policy, Workload Optimization Manager can recommend the following actions in response to changing demand for licenses:

When demand is low, Workload Optimization Manager recommends consolidating VMs on as few license-providing hosts as possible to reduce your license costs. To consolidate, you move VMs to another host and then reconfigure the original hosts to remove their licenses. Note that Workload Optimization Manager will not recommend suspending these hosts. Since they remain active, they can be reconfigured to become providers when demand starts to exceed capacity.

For example, if you have Host_01 providing a license to VM_01 and Host_02 providing a license to VM_02, you will see two recommendations – move VM_02 to Host_01 and then remove the license in Host_01. You will not see a recommendation to suspend Host_01.



When demand exceeds capacity, and there are hosts in the policy that currently do not provide licenses, Workload Optimization Manager recommends reconfiguring those hosts to become providers and then moving VMs to those hosts. If all hosts are currently providing licenses, Workload Optimization Manager recommends adding licenses to the hosts to meet demand.

These actions are more efficient than provisioning new hosts.

To create a License policy:

- Specify the license consumers (VMs).
- Specify the license providers (hosts).

In addition to creating a license policy, you must also create host *automation* policies to allow Workload Optimization Manager to recommend reconfigure actions on hosts. In the automation policies, add the license-providing hosts and then enable the *Reconfigure* action.

8. When you have made all your settings, be sure to save the Policy.

Automation Policies

An automation policy is a set of rules that Workload Optimization Manager must satisfy when executing <u>non-parking actions</u> (on <u>page 518)</u> on public cloud or on-prem workloads, or changing settings that affect analysis and action generation.

Automation policies include the following settings:

- Action Generation
 - This setting specifies whether a specific action will be generated.
- Action Acceptance
 - If a specific action will be generated, this setting specifies the degree of automation for the action. For more information, see Action Acceptance Modes (on page 529).
- Action Orchestration and Workflows
 - These settings specify whether Workload Optimization Manager or a workflow orchestrator will execute the action. For more information, see <u>Action Orchestration</u> (on page 688).
- Constraints and Other Settings
 - These settings affect the Workload Optimization Manager analysis of the state of your environment. These include operational, utilization, and scaling constraints.

The settings you can make are different according to the type of entity this policy will affect. Each setting you add to the policy takes precedence over the default value for that setting.

Default and User-defined Automation Policies

Workload Optimization Manager ships with default automation policies that we believe will give you the best results from our analysis. For certain entities in your environment, you can create automation policies as a way to override the defaults.

For example, **Enforce Non Disruptive Mode** is turned off in the default automation policy for on-prem VMs. In most cases, you might want to turn on the setting, and only turn it off for select VMs. In that case, you would turn it on in the default automation policy for VMs, and then create policies for those groups of VMs for which you want to turn it off.

The default and user-defined automation policies take effect in relation to each other. A default policy has a global effect, while a user-defined policy overrides the default policy for the entities within the indicated scope. You should keep the following points in mind:

- User-defined policies override a subset of settings.
 - A user-defined policy can override a subset of settings for the entity type. For the remainder, Workload Optimization Manager will use the default policy settings on the indicated scope.
- When an entity applies conflicting user-defined policies, Workload Optimization Manager applies the following tie breakers:
 - A scheduled policy always takes precedence over a non-scheduled policy, even if the non-scheduled policy is more
 conservative.
 - Among scheduled policies with identical schedules, the most conservative setting wins.
 - Among non-scheduled policies, the most conservative setting wins.



For example, a VM currently belongs to four groups with different policy settings.


- Group A policy: Resize VM in Manual mode every Saturday.
- Group B policy: Resize VM in Automatic mode every Saturday.
- Group C policy: Resize VM in Manual mode (no schedule).
- Group D policy: Resize VM in Recommend mode (no schedule).

Results:

- On a Saturday, Groups A and B policies take precedence over Groups C and D policies. The VM ultimately applies the Group A setting because it is more conservative.
- On all the other days, only Groups C and D policies are active. The VM applies the Group D setting because it is more conservative.
- User-defined policies always take precedence over default policies.
 - Even if the default policy has a more conservative setting, the setting in the user-defined policy wins for entities in that scope.
- For a global effect, always use default policies.

Default Automation Policies

To view the default automation policies, navigate to Settings > Policies, and then click Defaults.



The page displays a list of all the default policies, by entity type. You can click the entity type to view or change the default settings.

Global Default Policy

Use these settings to modify Workload Optimization Manager analysis globally for any scope of your environment. These defaults affect both default and user-defined automation policies.

ACTION AUTOMATION

Disable All Actions

Attribute	Default Setting
Disable All Actions	OFF

When this is ON, Workload Optimization Manager dos not generate any actions for your environment. For example, assume you have configured a number of polices that automate actions, but you want to stop making changes to the entire environment for a period of time. Turn this ON to stop all execution with a single setting.



OPERATIONAL CONSTRAINTS

VM Growth Observation Period

Attribute	Default Value
VM Growth Observation Period	1 month

Use this setting to specify how much historical data the Workload Optimization Manager analysis will use to calculate time to exhaustion of your cluster resources.

Workload Optimization Manager runs nightly plans to calculate headroom for the clusters in your on-prem environment. To review your cluster headroom in dashboards, set the view scope to a cluster. With that scope, the view includes charts to show headroom for that cluster, as well as time to exhaustion of the cluster resources.

To calculate cluster growth trends, analysis uses historical data for the given clusters. With **VM Growth Observation Period**, you can specify how much historical data the headroom analysis will use to calculate time to exhaustion of your cluster resources. For example, if cluster usage is growing slowly, then you can set the observation to a period that is long enough to capture that rate of growth.

If the historical database does not include at least two entries in the monthly data for the cluster, then analysis uses daily historical data.

Allow Unlimited Host Provisioning

Attribute	Default Setting
Allow Unlimited Host Provisioning	OFF

By default, Workload Optimization Manager allows overprovisioning hosts up to 10 times their memory capacity, and up to 30 times their CPU capacity. When this setting is ON, Workload Optimization Manager removes these overprovisioning limits to allow VM placements on already overprovisioned hosts.

This setting does not stop Workload Optimization Manager from recommending actions to provision new hosts in clusters.

Enable Analysis of On-prem Volumes

Attribute	Default Setting
Enable Analysis of On-prem Volumes	OFF

On-prem volumes (on page 470) represent VM Disks discovered by hypervisor targets. A VM will have one volume for each configured disk and another volume (representing the configuration) that always moves with Disk 1.

OFF (default)

Workload Optimization Manager analyzes volume resources as part of VM analysis. In the real-time market and on-prem plans, any action to move VM storage ensures that volumes stay together on the underlying datastore. A <u>Migrate to Cloud plan (on page 568)</u> will recommend storage per datastore to hold all the VM Disks currently on the datastore.

For example, assume a VM with three disks. Disks 1 and 3 are on Datastore A, while Disk 2 is on Datastore B.

- During a storage migration, VM Disk volumes 1 and 3 will stay on the same datastore.
- A Migrate to Cloud plan will recommend a storage disk for VM Disk volumes 1 and 3, and another storage disk for VM Disk volume 2.

ON

Workload Optimization Manager analyzes resources on each volume independently. In the real-time market and onprem plans, any action to move VM storage migrates volumes to the most optimal datastore. A Migrate to Cloud plan will recommend storage for each volume.

For example, assume a VM with three disks. Disks 1 and 3 are on Datastore A, while Disk 2 is on Datastore B.

- During a storage migration, VM Disk volumes 1, 2, and 3 can migrate to different datastores.
- A Migrate to Cloud plan will recommend three separate storage disks for VM Disk volumes 1, 2, and 3.



IMPORTANT:

When you turn on this setting, your Workload Optimization Manager instance will start to use more memory and storage to perform its analysis. For example an environment with 10,000 VMs and an average of three disks per VM represents a three-fold increase in entities that require analysis. Currently, instances that monitor more than 50,000 VMs will experience a significant drop in performance. For this reason, this setting is turned off by default.

Before turning on this setting, review your <u>VM automation policies (on page 450)</u> and verify that Storage Move actions are in *Recommend* or *Manual* mode. In addition, review your <u>storage placement policies (on page 673)</u> to ensure that individual VM volumes can be placed on the expected storage.

Imported Automation Policies

As Workload Optimization Manager discovers your environment, it can find configurations that set up scopes that need specific policies. For example:

HA Configurations

For vCenter Server environments, Workload Optimization Manager discovers HA cluster settings and translates them into CPU and memory utilization constraints. The discovery creates a group of type *folder* for each HA cluster, and creates a policy that sets the appropriate CPU and memory constraints to that policy.

Availability Sets

In public cloud environments, Workload Optimization Manager discovers groups of VMs that should keep all their VMs on the same template. In the Automation Policies list, these appear with the prefix AvailabilitySet:: on the policy names. You can enable Consistent Resizing for the VMs in each group so Workload Optimization Manager can resize them to the same size.

To view imported automation policies, navigate to Settings > Policies, and then click Imported Automation Policies.

Creating Automation Policies

To override the default automation policies, you can create your own policies. These policies specify the settings you want to change for certain entities in your environment. You can assign a schedule to your policy to set up maintenance windows or other scheduled actions in your environment.


Below are some use cases for creating automation policies.

- Workload Optimization Manager uses a number of settings to guide its analysis of the entities in your environment. The default settings might be fine in most cases, but you might want different analysis for some groups of entities.
- Assume you want to automate scaling and placement actions for the VMs in your environment. It is common to take a cautious approach, and start by automating clusters that are not critical or in production. You can scope the policy to those clusters, and set the action acceptance mode to Automatic for different actions on those VMs (see Action Acceptance Modes (on page 529)).
- If actions require change approval, or integrations into DevOps pipelines to perform tasks before, instead of, or after action execution, you should scope those entities to a group and apply an automation policy.


1. Entry Point

Navigate to the Settings Page and then choose Policies.





This opens the Policy Management Page, which lists all the currently available policies.




Click **NEW AUTOMATION POLICY** and then select the policy type (such as Virtual Machine).

This sets the type of entity that your policy will affect. Note that Workload Optimization Manager supports different actions for different types of entities. For example, you cannot add VMem to a storage device. Setting policy type is the first step you take to focus on which actions you want to map to your workflows.


2. Policy Name

Name the policy.





3. Scope



The scope determines which entities this policy will affect. Choose one or more groups, or create new groups and add them to the policy scope. These groups match the type of entity you have set for the policy.


In Workload Optimization Manager you can find nested groups (groups of groups). For example, the "By PM Cluster" group contains host clusters, and each host cluster is a group. Do not set the policy scope to a parent of nested groups. When setting up policies, be sure you set them to individual groups. If necessary, create a custom group for the settings you want to apply.



NOTE:

A single entity can be a member of multiple groups. This can result in a conflict of settings, where the same entity can have different policy settings. For conflicts among user-defined policy settings, the most conservative setting will take effect. For details, see <u>Default and User-defined Policies</u> (on page 677).

4. Policy Schedule



For use cases and information about how schedules affect policies, see Policy Schedules (on page 687).

The **Select Schedule** fly-out lists all the schedules that are currently defined for your instance of Workload Optimization Manager.

Expand a schedule entry to see its details. The details include a summary of the schedule definition, as well as:

Used in Policies

The number of policies that use this schedule. Click the number to review the policies.

Next Occurrence

When the schedule will next come into effect.

Accepted Actions

How many scheduled actions have been accepted to be executed in the next schedule occurrence. Click the number for a list of these actions.



Awaiting Acceptance

The number of Manual actions affected by this schedule that are in the Pending Actions list, and have not been accepted. Click the number for a list of these actions.

If none of the listed schedules is suitable for your policy (or if none exists), click **New Schedule**. For details, see <u>Managing Calendar Schedules</u> (on page 704).


NOTE:

When you configure a schedule window for a VM resize action, to ensure Workload Optimization Manager will execute the action during the scheduled time, you must turn off the **Enforce Non Disruptive Mode** setting for that scheduled policy. Even if you turn the setting off for the global policy, you still must turn the setting off for your scheduled policy. Otherwise Workload Optimization Manager will not execute the resize action.

5. Automation and Orchestration

You can define automation and orchestration settings for different action types within the same policy. For example, for a group of VMs in a policy, you can automate all *Resize* actions, but require *Suspend* actions to go through an approval process via an Orchestrator (such as ServiceNow).





5.1. Action Type

See a list of actions that are viable for the policy, and then make your selections.

5.2. Action Generation and Acceptance

■ Do not Generate Actions

Workload Optimization Manager never considers your selected actions in its calculations. For example, if you do not want to generate *Resize* actions for VMs in the policy, analysis will still drive toward the desired state, but will do so without considering resizes.

Generate Actions

Workload Optimization Manager generates your selected actions to address or prevent problems. Choose from the following *Action Acceptance* modes to indicate how you would like the actions to execute:

Recommend – Recommend the action so that a user can execute it outside Workload Optimization Manager



- Manual Recommend the action, and provide the option to execute that action through the Workload Optimization Manager user interface
- Automatic Execute the action automatically

For automated resize or move actions on the same entity, Workload Optimization Manager waits five minutes between each action to avoid failures associated with trying to execute all actions at once. Any action awaiting execution stays in queue. For example, if a VM has both vCPU and vMem resize actions, Workload Optimization Manager could resize vCPU first. After this resize completes, it waits five minutes before resizing vMem.

If you have an orchestrator target (such as ServiceNow), and that target includes an installation of the *Workload Optimization Manager Actions* application, you can send the action to the orchestrator. Choose from the following options:

- Generate Action then Send Record to Orchestrator
- Generate Action then Request Approval from Orchestrator

For more information, see Action Orchestration (on page 688).

5.3. Before Execution, Action Execution, and After Execution

By default, generated actions execute without the need for orchestration. Workload Optimization Manager gives you the ability to set up orchestration to affect the execution of actions.

For more information, see Action Orchestration (on page 688).

5.4. Execution Schedule

You can defer the execution of generated actions to a non-critical time window. For example, if a workload experiences memory bottlenecks during the week, you can defer the necessary resize to the weekend. Even if the workload has minimal utilization over the weekend, Workload Optimization Manager can recognize the need to resize, and will execute the action.

For more information, see Action Execution Schedules (on page 688).


6. Constraints and Other Settings

Workload Optimization Manager collects metrics to drive the analysis that it uses when it calculates actions for your environment. It compares current utilization and demand against allocated capacities for resources, so it can recommend actions that keep your environment in optimal running condition.

Automation policies include constraints and other settings that you can make to adjust the analysis that Workload Optimization Manager performs. For example, you can set different levels of overprovisioning for host or VM resources, and Workload Optimization Manager will consider that as a factor when deciding on actions.

The settings you can make are different according to the type of entity this policy will affect. Each setting you add to the policy takes precedence over the default value for that setting.





Policy Schedules

You can set a schedule for an automation policy, which sets a window of time when the policy takes effect. For example, you can modify the operational or scaling Constraints for a given period of time. These settings affect Workload Optimization Manager analysis, and the actions that the platform generates. You can set up scheduled times when you want to change those settings.

Remember that for user-defined automation policies, it is possible that one entity can be in two different scopes. This means that the entity can be under the effect of two different policies. For this reason, user-defined policies keep the rule, *the most conservative setting wins*. However, a more aggressive user-defined policy takes precedence over the corresponding default automation policy.

You must consider these rules when you add schedules to policies. If the more conservative settings are in a default automation policy, then the scheduled change takes effect. However, if the more conservative settings are in another user-defined policy, then the conservative settings win, and the scheduled changes do not take effect.

For details, see Default and User-defined Policies (on page 677).

Policy Schedule and Action Execution Schedule

A scheduled policy can include *actions*. When the policy is in effect, Workload Optimization Manager recommends or automatically executes those actions as they are generated. Some of those actions could be disruptive so you may want to defer their execution to a non-critical time window. In this case, you will need to set an *action execution schedule* within the scheduled policy. For example, you can set a policy that automatically resizes or starts VMs for your customer-facing apps for the entire month of December, in anticipation of an increase in demand. Within this same policy, you can set the resize execution schedule to Monday, from midnight to 7:00 AM, when demand is expected to be minimal.

For more information, see Action Execution Schedules (on page 688).



Action Execution Schedules

You can defer the execution of generated actions to a non-critical time window. For example, if mission-critical VMs experience memory bottlenecks during the week, you can defer the necessary memory resizes to the weekend. Even if the VMs have minimal utilization over the weekend, Workload Optimization Manager can recognize the need to resize, and will execute resize actions. For this particular example, you will need to:

- 1. Create a policy for the VMs.
- 2. Select VMem Resize Up from the list of actions and then set the action mode to either Automatic or Manual.

NOTE

Execution schedules have no effect on recommended actions. It is therefore not necessary to set up an execution schedule if all the actions in your policy will be in *Recommend* mode.

3. Set an Execution Schedule that starts on Saturday at 8:00 AM and lasts 48 hours.

Execution of Scheduled Actions

Workload Optimization Manager posts an action at the time that the conditions warrant it, which means that you might see the action in the Pending Actions list even before the execution schedule takes effect. The action details show what schedule affects the given action, and shows the next occurrence of that schedule.

- Automatic
 - When the schedule takes effect, Workload Optimization Manager executes any pending automated actions.
- Manual

Before the execution schedule, the action details for manually executable actions show the action state as PENDING ACCEPT. If you accept the action (select it and click **Apply Selected**), then Workload Optimization Manager adds it to the queue of actions to be executed during the maintenance window. The action details show the action state as AWAITING EXECUTION. Workload Optimization Manager executes the actions when the schedule takes effect.

Keeping Actions Valid Until the Scheduled Time

If you have scheduled action execution for a later time, then conditions could change enough that the action is no longer valid. If this happens, and the action remains invalid for 24 hours, then Workload Optimization Manager removes it from the list of pending actions. This action will not be executed.

Workload Optimization Manager includes scaling constraints that work to stabilize action decisions for VMs. The resulting actions are more likely to remain valid up until their scheduled window for execution. You can make these settings in the default or user-defined automation policies.

NOTE:

When you configure an execution schedule for a resize action, to ensure Workload Optimization Manager will execute the action during the scheduled time, you must turn off the **Enforce Non Disruptive Mode** setting for the policy. Even if you turn the setting off for the global policy, you still must turn the setting off for your policy. Otherwise Workload Optimization Manager will not execute the resize action. For information about non disruptive mode, see <u>Non-disruptive Mode</u> (on page 451).

Action Orchestration

Action Orchestration specifies whether Workload Optimization Manager will execute an action, or whether Workload Optimization Manager will pass the action request to an orchestrator or an action workflow to effect the change in your environment. In this way, you can integrate supported orchestrators to execute of actions for specific scopes of entities in your environment.

About Orchestrators

Action Orchestration targets assign workflows that execute multiple actions to make changes in your environment. Workload Optimization Manager discovers workflows that you have defined on the orchestrator. You can then set up an automation policy that maps workflows to actions. If the action acceptance mode is *Manual* or *Automatic*, then when Workload Optimization Manager recommends the action, it will direct the orchestrator to use the mapped workflow to execute it.



Workload Optimization Manager supports integration with ServiceNow. You can configure policies that log Workload Optimization Manager actions in your ServiceNow instance, and that submit actions for approval in ServiceNow workflows.

This section shows how to link orchestration workflows to automation policies. It assumes you have already configured an appropriate Orchestration target. It also assumes that you have configured workflows on that target in such a way that Workload Optimization Manager can discover the workflows and map them to automation policies. For information about Orchestration target requirements, see Orchestrator Targets (on page 222).

NOTE:

For some orchestration workflows, it is necessary to schedule an action to execute only during a specific maintenance window. Workload Optimization Manager policies can include schedules to enable this use case. However, you must be sure that you do not set the schedule to the policy that declares the orchestration you want. Instead, you should use two policies for the same scope – one to set up the orchestration, and another to schedule the time window during which the action acceptance mode will be Automatic (to set up the maintenance window). For more information, see Setting Policy Schedules (on page 687).

About Action Workflows

Action workflows can add custom processing to Workload Optimization Manager actions at different entry points. For example, you can create an action workflow that sends an email whenever Workload Optimization Manager recommends moving a VM, or you can create an action workflow that runs as a replacement for the action that Workload Optimization Manager would execute. For example:

Action Script workflow

You can deploy action scripts on a remote machine and configure an Action Script target that communicates with this server. Workload Optimization Manager discovers the exposed scripts and displays them as options you can choose when you specify a workflow in your automation policy. For more information about Action Scripts, see Deploying Action Scripts (on page 692).

■ Webhook workflow


To implement a webhook, you create a workflow that specifies parameters such as the HTTP URL, HTTP method, and payload template. You can then use this workflow in your automation policy to orchestrate how actions execute. For more information about webhooks, see Creating Webhook Workflows (on page 698).

Specifying Action Orchestration

As you create a policy, you specify the entity type and the scope of entities the policy affects. You can also set modes for specific actions. For example, you can set a mode of Manual for the Resize action for a given scope of VMs.

1. Expand Automation and Orchestration and click Add Action. Then select the action type you want to orchestrate.





There is no orchestration for this action by default. The following table describes the supported orchestrations.

	Generate Actions	Generate Action then Send Record to Orchestrator	Generate Action then Request Approval from Orchestrator
Description	Generate actions as usual, but use a workflow to control action execution.	Send a record of the generated actions to the orchestrator (such as ServiceNow).	Defer the generated actions to your orchestration workflow for approval.
			Workload Optimization Manager passes control for this action to your orchestration workflow as a Change Request (CR).
Prerequisites	An Orchestration target	An Orchestration target	An Orchestration target



	Generate Actions	Generate Action then Send Record to Orchestrator	Generate Action then Request Approval from Orchestrator
Action Acceptance	 Recommend – Recommend the action so that a user can execute it outside Workload Optimization Manager Manual – Recommend the action, and provide the option to execute that action through the Workload Optimization Manager 		Action acceptance automatically changes to "External Approval." If the action is approved, the action executes using the default Action Acceptance mode.
Before Execution	The default is Do Nothing. Select Use Workflow to trigger an external orchestration workflow such as a webhook to complete pre- execution tasks. Failure of the workflow indicates an action failure. For example, you can post an email notification to your team that an action has been generated.		
Action Execution	The default is Native. Workload Optimization Manager executes the action with its default action processing. Select Use Workflow to trigger an external orchestration workflow to execute the action. Failure of the workflow indicates an action failure.		
Execution Schedule	There is no execution schedule by default. Workload Optimization Manager executes the action immediately. If the policy includes a schedule, Workload Optimization Manager executes the action at the scheduled time.		There is no execution schedule by default. Workload Optimization Manager executes the action immediately. If the policy includes a schedule Workload Optimization Manager executes the action at the scheduled time. NOTE: Workload Optimization Manager discovers and enforces execution schedules defined in orchestration approval workflows. To avoid potential issues with schedules, set the execution schedule either in the orchestrator (such as ServiceNow) or Workload Optimization Manager.
After Execution	The default is Do Nothing. Select Finalize action workflow to trigger an external orchestration workflow such as a webhook to complete post- execution tasks. Failure of the workflow indicates an action failure.	For example, you can post a platform to let your team known	tion workflow such as a webhook. message to your collaboration w that an action has executed. by the status of the notification



Generate A	ctions	Generate Action then Send Record to Orchestrator	Generate Action then Request Approval from Orchestrator
		Finalize action workflow Trigger an external orchestrato complete post-execution indicates an action failure.	tion workflow such as a webhook tasks. Failure of the workflow

When you have made all your settings, be sure to save the action policy.

Deploying Action Scripts

Action Scripts provide an interface that can add custom processing to Workload Optimization Manager actions.

Action scripts execute on a remote server (a VM or a container) that you have configured as a Workload Optimization Manager target. That server includes a manifest file that identifies the scripts you have deployed, as well the entities and actions they can respond to. Workload Optimization Manager discovers these scripts via the manifest and presents them as orchestration options for actions in automation policies.

For example, assume you have defined a script with:

■ name: MyVmMoveAction

entityType: VIRTUAL MACHINE

actionType: MOVE

Following this example, you can use the API to add orchestration to a policy for move actions on VMs. Because you have defined a script for that action, you can specify Action Script as the orchestration type, and you can choose the MyVmMoveAction script as the orchestration workflow to perform.

To deploy your action scripts, you will:

- Set up the remote Action Script Server (see <u>Setting Up the Action Script Server (on page 692)</u>)
- Create the action script executables on the remote server (see Creating Action Scripts (on page 693))
- Deploy the Action Script Manifest on the remote server (see <u>Deploying the Action Script Manifest (on page 694)</u>)

Setting Up the Action Script Server

Workload Optimization Manager uses remote servers to run action scripts. Managing the processes remotely means that you do not install custom code on the Workload Optimization Manager server, which eliminates associated security risks there. However, you are responsible for maintaining the security of your Action Script Server to ensure the integrity of your custom code. To accomplish this, the configuration of the remote server must meet certain requirements.

Resource Requirements for the Server

The remote server can be a VM or a container. The capacity you configure for the server depends entirely on the processes you intend to run on it. Workload Optimization Manager does not impose any special resource requirements on the server.

Configuring Command Execution

To support execution of your scripts, you must install any software that is necessary to run the scripts, including libraries, language processors, or other processes that your scripts will call.

Workload Optimization Manager calls the scripts as commands on the server. The server must run an SSH service that you configured to support command execution and SFTP operations. Currently, Cisco tested action scripts with the OpenSSH sshd daemon.

The standard port for SSH is 22. You can configure a different port, and provide that for admins who configure the server as an Action Script target.

NOTE:

An action script can invoke any process you deployed on the remote server. You do not have to run scripts; however, you must be able to invoke the processes from the command line. The script manifest gives Workload Optimization Manager the details it needs to build the command line invocation of each script.



Configuring the ActionScript User Account

To run the scripts on your server, Workload Optimization Manager logs on using a user account that is authorized to run the scripts from the command line. You provide the user credentials when you configure the ActionScript target. To support this interaction, the user account must meet the following requirements:

Public Key

The user must have an RSA public key in the .ssh/authorized_keys file. When you configure the ActionScript target, you provide this as the Private Token for the target.

NOTE:

For the ActionScript target to validate, the permissions on the authorized_keys file must be set to 600.

Security for the .ssh Directory

The ActionScript User should be the only user with authorized access. Set file permissions to 700.

Supported Shells

The ActionScript User shell can be either the Bourne shell (usually at /bin/sh) or the Bourne-Again shell (usually at /bin/bash). Workload Optimization Manager passes parameters as it invokes your scripts. At this time it only supports script execution through these shells.

ActionScript Manifest

The ActionScript Manifest is a file that declares an array of Script Objects for each script you want to expose to Workload Optimization Manager. You can create the manifest as either a JSON or a YAML file. You can save the Manifest file to any location on your server, so long as the Scripts User has access to that location, and has read and execute privileges. The location of the manifest is provided as part of the ActionScript target configuration.

After Workload Optimization Manager validates the target, it then discovers these scripts and presents them in the Orchestration Policy user interface.

For details, see Deploying the ActionScript Manifest (on page 694).

Handling ActionScript Timeouts

Workload Optimization Manager limits script execution to 30 minutes. If a script exceeds this limit, Workload Optimization Manager sends a SIGTERM to stop the execution of the process.

Note that Workload Optimization Manager does not make any other attempt to end a process. For example, you might implement the script so it traps the SIGTERM and continues to run. The process should end at the soonest safe opportunity. However, if the process does not end, then you must implement some way to stop it outside of Workload Optimization Manager. A runaway process continues to use its execution thread, which can block other processes (action scripts or primary processes) if there are no more threads in the pool.

Creating Action Scripts

An action script can be any executable that a user can invoke from a command line. You can save these executable files anywhere on the server – The Manifest indicates the path to the file (see <u>Deploying the Action Script Manifest (on page 694)</u>). The Action Script user that you have configured for the script server must have access to your script files, with read and execution privileges.

To execute a script, Workload Optimization Manager builds the appropriate SSH command from the manifest information it has discovered. It grants a timeout limit of 30 minutes by default, or the manifest entry can declare a different limit. If the execution exceeds the limit, Workload Optimization Manager sends a SIGTERM to terminate the process.

Passing Information to the Action Script

Workload Optimization Manager uses two techniques to pass information about an action to the associated action script:

- Pass general information via environment variables
- Pass full action data via stdin

To pass general information into the script, Workload Optimization Manager sets environment variables on the Action Script Server. You can reference these environment variables in your scripts. For example, assume you want to send an email that includes the name of the VM that is an action target. You can get that name via the VMT_TARGET_NAME environment variable.



The following list shows the environment variables that Workload Optimization Manager can set when it executes a script. Note that not all of these variables apply for every action. For example, an action to scale VMEM does not include providers, so the action does not include values for the VMT_CURRENT_INTERNAL, VMT_CURRENT_NAME, VMT_NEW_INTERNAL, or VMT_NEW_NAME variables. If a given variable does not apply, Workload Optimization Manager sets it to an empty string.

■ VMT_ACTION_INTERNAL

The UUID for the proposed action. You can use this to access the action via the REST API. For example, your script could accept or cancel the action according to its own criteria.

■ VMT ACTION NAME

The name of the action.

■ VMT CURRENT INTERNAL

The internal name for the current provider.

■ VMT_CURRENT_NAME

The display name for the current provider.

■ VMT_NEW_INTERNAL

The internal name for the new provider.

■ VMT NEW NAME

The display name for the new provider.

■ VMT TARGET INTERNAL

The internal name of the entity this action will affect. You can use this to access the target entity via the REST API. For example, you can get historical statistics or you can change settings for the entity.

■ VMT_TARGET_NAME

The display name of the entity this action will affect.

■ VMT_TARGET_UUID

The UUID of the entity this action will affect.

For some scripts, you might need a complete description of the associated action. For example, assume you want to analyze the utilization metrics for a given resource. The environment variables for passing general information do not include this information.

When it invokes an action script, Workload Optimization Manager passes the complete data for the associated action via stdin. Your script can load this into a variable to access the specific data it needs. For example, the following loads stdin into myActionData:

```
myActionData=$(cat -)
```

stdin contains a JSON string that represents of the full data associated with this action. For example, the myActionData variable could contain a string similar to:

```
{"actionType":"RIGHT_SIZE","actionItem":[{"actionType":"RIGHT_SIZE","uuid":"143688943343760","targetS
E":{"entityType":"VIRTUAL_MACHINE","id":"4200fcdb-eafe-2a4a-abf5-a7ad2b00555c"...
```

Deploying the ActionScript Manifest

The ActionScript Manifest is a file that declares an array of Script Objects for each script you want to expose to Workload Optimization Manager. The location of the manifest is provided as part of the ActionScript target configuration.

After Workload Optimization Manager validates the target, it then discovers these scripts and presents them in the Orchestration Policy user interface.



Creating the Scripts Manifest File

You can create the manifest as either a JSON or a YAML file. For example, following are two examples of the same manifest: one in YAML and the other in JSON. Notice that in either case, the manifest is an array of two Script objects.

YAML Manifest example

```
scripts:
- name: MyVmMovePrep
description: Execute this script in preperation to a VM Move
scriptPath: vmScripts/movePrep.sh
entityType: VIRTUAL_MACHINE
actionType: MOVE
actionPhase: PRE
- name: MyVmSuspendReplace
description: Execute this instead of a VM Suspend action
scriptPath: vmScripts/suspendReplace.sh
entityType: VIRTUAL_MACHINE
actionType: SUSPEND
actionPhase: REPLACE
```

JSON Manifest example

```
{
    "scripts": [
      "name": "MyVmMovePrep",
      "description": "Execute this script in preperation to a VM Move",
      "scriptPath": "vmScripts/movePrep.sh",
      "entityType": "VIRTUAL_MACHINE",
      "actionType": "MOVE",
      "actionPhase": "PRE"
      "name": "MyVmSuspendReplace",
      "description": "Execute this instead of a VM Suspend action",
      "scriptPath": "vmScripts/suspendReplace.sh",
      "entityType": "VIRTUAL_MACHINE",
      "actionType": "SUSPEND",
      "actionPhase": "REPLACE"
    ]
}
```

You can save the Scripts Manifest file to any location on your server, so long as the Scripts User has access to that location, and has read and execute privileges. You will provide this location as the **Script Path**, which the Workload Optimization Manager administrator will give as part of the ActionScript target configuration.

Note that the filename extension for the manifest must match the file format (either YAML or JSON). For example, you should name the file either MyManifest.json, respectively.



Declaring Script Objects

Each script object in the manifest can contain the following fields:

name

Required - The name for this action script. After Workload Optimization Manager discovers your scripts, it displays this name as a Orchestration Workflow choice in the user interface for creating orchestration policies.

■ description

Optional - A description of the script. The Workload Optimization Manager user interface does not display this description.

■ scriptPath

Required – The path to the executable for this entry. You can give an absolute path, or a path that is relative to the location of the Scripts Manifest. The Action Script User that you set up for the Action Script server must have read and execute privileges for the executable file.

■ entityType

Required - The type of entity this script responds to. Can be one of:

- Switch
- VIRTUAL_DATACENTER
- STORAGE
- DATABASE_SERVER
- WEB SERVER
- VIRTUAL_MACHINE
- DISK_ARRAY
- DATA_CENTER
- PHYSICAL_MACHINE
- CHASSIS
- BUSINESS USER
- STORAGE CONTROLLER
- IO_MODULE
- APPLICATION_SERVER
- APPLICATION
- CONTAINER
- CONTAINER_POD
- LOGICAL_POOL
- STORAGE_VOLUME
- DATABASE
- VIEW_POD
- DESKTOP_POOL

To configure the same script to respond to actions on different entity types, declare separate entries for that script, one for each entity type.

actionType

Required - The type of action this script responds to. Note that different entity types can support different actions. Can be one of:

- START
- MOVE
- SCALE

Resize on cloud - move workload from one cloud template or tier to another.

- SUSPEND
- PROVISION
- RECONFIGURE
- RESIZE
- DELETE



- RIGHT_SIZE
- ACTIVATE
- DEACTIVATE
- BUY_RI

■ actionPhase

Required - Where in the life cycle of an action that you want your script to execute.

Can be one of:

- PRE

For an action that has been accepted, or an AUTOMATED action before it executes, this state is a preparation phase where your script can execute just before the action itself executes.

Run your script to set up conditions just before the action executes.

- REPLACE

For action execution, your script executes instead of the execution that Workload Optimization Manager would perform.

Run your script as a replacement for the Workload Optimization Manager action.

POST

The action has completed execution, either in a SUCCEEDED, FAILING, or FAILED state.

FAILING means that the status was checked after the action execution fails, but before the POST script has finished execution.

Run your script after the action has completed execution.

■ timeLimitSeconds

Optional – How long to run the action before assuming a timeout. When execution exceeds this limit, Workload Optimization Manager sends a SIGTERM to terminate the execution of the process.

If you do not provide a value, Workload Optimization Manager assumes a limit of 30 minutes (1800 seconds).

Webhooks

You can configure automation policies in Workload Optimization Manager to send data via webhooks to external web servers. A webhook is an automated message that Workload Optimization Manager can use to send data to external applications. Things you can do with webhooks include:

- Send notifications to collaboration platforms such as Slack
- Integrate Workload Optimization Manager with workflow management systems
- Override Workload Optimization Manager actions with your own logic

The webhook implementation supports HTTP messaging. In addition, to implement a webhook you create a workflow via the Workload Optimization Manager API.

To set up a webhook, you will:

Identify the application to receive the webhook

Possible applications can include collaboration platforms such as Slack, orchestration platforms such as ServiceNow, cloud provider APIs, or you can create a custom application that responds to HTTP methods.

Create a webhook workflow in your Workload Optimization Manager instance

For this version of Workload Optimization Manager you define webhook workflows via the API.

A webhook definition can include:

- The URL to the application to which you are sending the webhook
- An HTTP method
- A template for the webhook payload
- Authentication credentials to access the application

For information about creating a webhook workflow, see Creating Webhook Workflows (on page 698).

Create an Automation Policy that uses the webhook



Automation Policies include orchestration settings where you can choose to execute a webhook for given actions. Workload Optimization Manager can execute a webhook when it creates an action, before it executes the action, instead of executing the action, and after it executes the action.

For information about creating policies that use webhook workflows for orchestration, see <u>Action Orchestration (on page 688)</u>.

After you set up a webhook, when Workload Optimization Manager generates or executes the action you identified in the policy, it sends a message to the url that you specified in the webhook.

Creating Webhook Workflows

To implement a webhook, you create a workflow that specifies parameters such as the HTTP URL, HTTP method, and payload template. You can then use this workflow in your automation policy to orchestrate how actions execute.

To create a workflow, use the API to POST a Workflow object to Workload Optimization Manager instance. For example, the following curl commands get authorization to access a Workload Optimization Manager server, and then add a simple webhook workflow to that server:

Authenticate on the server

This command requests authentication credentials and stores them in a variable you can set to a cookie in subsequent curl headers, where:

- <T8c_IP_ADDRESS> is the address of the Workload Optimization Manager server
- <ADMIN_ACCOUNT_NAME> is the name of an account with admin privileges
- <ADMIN_PWD> is the admin account password

```
JSESSIONID=$(curl \
    --silent \
    --cookie-jar - \
    --insecure \
    https://<T8c_IP_ADDRESS>/vmturbo/rest/login \
    --data "username=<ADMIN_ACCOUNT_NAME>&password=<ADMIN_PWD>" \
    | awk '/JSESSIONID/{print $7}')
```

Create the workflow

This command creates the workflow on the server, where:

- <T8c_IP_ADDRESS> is the address of the Workload Optimization Manager server
- <WEBHOOK ADDRESS> is the address of the webhook server

```
curl \
    "https://<T8c_IP_ADDRESS>/api/v3/workflows" \
    --insecure \
    --compressed \
    --header 'Accept: application/json' \
    --header 'Content-Type: application/json' \
    --header "cookie: JSESSIONID=$JSESSIONID" \
    --request POST \
    --data '
        "displayName": "My_WebHook",
        "className": "Workflow",
        "description": "First webhook attempt.",
        "discoveredBy":
            "readonly": false
        },
       "type": "WEBHOOK",
```



```
"typeSpecificDetails": {
  "url": "http://<WEBHOOK_ADDRESS>",
        "method": "POST",
        "template": "{ \"text\":\"My Webhook Template -- DATA: Action Details: $action.details\" }",
        "type": "WebhookApiDTO"
  }
}
```

This is a simple webhook that sends its template to the indicated url. For a listing of the parameters you can set in the workflow, see WebhookApiDTO (on page 699) or the API Reference (on page 735).

The template payload is the string My Webhook Template -- DATA: Action Details:, plus the action details that are included in the action's data object. The variable \$action.details is a reference to a field in the ActionApiDTO object that represents the current action. Your template can reference any of the fields in this DTO, starting with action as the object name. For example, \$action.createTime gives you the time the action was created. For a full listing of the ActionApiDTO object, see API Reference (on page 735) or the API Swagger UI.

Sample Webhook Application

A webhook workflow sends a message to an application via HTTP. You express the message as a template that can include values from the action data in its payload. This template can express text, JSON, or any other payload that your application can accept.

You can use webhooks to send messages to a number of existing applications, including Slack, Amazon Web Services, and others.

To deploy a simple example, and to test your webhook templates, you can implement a node.js server that receives the webhook message and prints out the template data. If you install this server on a machine in your network, then you can give its URL in the webhook workflow, and test your response to specific actions.

Following is a listing for a node.js web server that you can use.

```
let port = 9090;
const http = require("http");
console.log(`Starting server on port ${port}`);

http.createServer((request, response) => {
    request.setEncoding('utf8');
    console.log('REQUEST METHOD: ', request.method);

    let datStr = '';
    request.on('data', chunk => {datStr = datStr + chunk});
    request.on('end', () => {console.log('End of DATA: ', datStr)})
}).listen(port);
```

When you run this program, it prints a message to the console to say that it is running, and to identify the port it listens on.

When the server receives a message, it prints out the request method, and then prints out the message payload, as specified in the workflow's template field.

If you have configured an Automation Policy to use this workflow, then this server will log a message for each action that Workload Optimization Manager executes on an entity within the policy's scope.

WebhookApiDTO

The WebhookApiDTO inherits from WorkflowAspect

Required Parameters:



method

- type: string
- description: The http method used to make the request.
- enum: ['GET', 'POST', 'PUT', 'DELETE', 'PATCH']

url

- type: string
- description: The URL that HTTP request is made to.

Optional Parameters:

template

- type: string
- description: The template for the body of request.

authenticationMethod

- type: string
- **description:** The authentication method to use for the request.
- enum: ['NONE', 'BASIC', 'OAUTH']

username

- type: string
- description: The username for the authenticated request.

password

- type: string
- description: The password for the authenticated request.

trustSelfSignedCertificates

- type: boolean
- description: If true, self-signed certificates will be trusted when using HTTPS connections. Defaults to 'false'.

headers

- type: array
- description: The request headers.

oauthData

- type: object
- **description:** Model to define the oAuth data.

Required Parameters:

- clientId: *string* The client id used for oAuth authorization.
- clientSecret: *string* The client secret used for oAuth authorization.
- authorizationServerUrl: string The URL of the authorization server.
- grantType: enum ["CLIENT_CREDENTIALS"]

Optional Parameters:

scope: string The oAuth scope.

Parking Policies

A parking policy is a set of rules that Workload Optimization Manager must satisfy when enforcing parking actions (start or stop) on public cloud workloads.

Parking policies take precedence over:

- Parking actions that were manually executed from the <u>Parking page (on page 599)</u>.
- Parking schedules that were attached to parkable entities from the Parking page.



For example, if a parking policy dictates that a VM must be started everyday from 9:00 AM to 6:00 PM, and a Workload Optimization Manager user manually stopped the VM from the Parking page at 3:00 PM, the VM will be started to comply with the parking policy.

There is no default policy for parkable entities. You must create policies to enforce parking actions. In addition, parking policies do not require you to set the scope to specific entities. Entities are matched to policies based on their membership to predefined groups – Global, Cloud Providers, Accounts, and Resource Groups (Azure only). For example, if a policy applies to a specific account, all parkable entities in that account apply the policy, including new entities added in the future.


Prioritization

When an entity matches multiple policies, any resulting conflicts are resolved using prioritization. Parking policies are prioritized in two ways – by level and within each level.

1. Priority by level

Level represents the first of two tiers of prioritization for policy matching. A policy associated with a lower level (such as Account) has a greater priority than a policy associated with a higher level (such as Global). This mitigates the complexity of prioritizing a large set of policies in a single list.

Level is a required setting when creating parking policies.




Level	Notes
Global (Highest)	Set a policy at the global level if you have multiple cloud providers and all parkable entities discovered from these providers must apply the same policy. This level has the lowest priority.
Cloud Provider AWS Azure GCP	Set a policy at the cloud provider level if all parkable entities discovered from a specific provider must apply the same policy. This level has a higher priority than Global, but a lower priority than Account or Resource Group.
Account AWS accounts Azure subscriptions GCP projects	Set a policy at the account level if all parkable entities discovered from specific accounts must apply the same policy. For AWS and GCP, this level has the highest priority. For Azure, this level has a lower priority than Resource Group.



Level	Notes
Resource Group - Azure only (Lowest)	Set a policy at the Resource Group level if all parkable entities discovered from specific Resource Groups must apply the same policy.
	This level has the highest priority for Azure. If you do not have Azure targets, this level will not display in the user interface, and you can start at the Account level.

2. Priority within each level

If you have created multiple parking policies for a given level, you can control the priority by rearranging policies via the drag-and-drop functionality in the user interface (highlighted in the image below). Priority is given from top to bottom. The current priority for each policy is indicated on the right.



Points to consider:

- A newly created policy appears last in the list. If you want the policy to have a higher priority, move it up the list.
- Changes to the order of policies take effect on the next policy evaluation cycle. Workload Optimization Manager runs policy evaluations every 10 minutes.
- If there are no entities applying the policy at the top of the list, the next policy will be applied to matching entities.

Example

Assume you created three policies, two at the cloud provider level and one at the global level.

Policy	Level	Policy Settings
А	Cloud Provider (first in the list)	Stop parkable entities Saturday, 1:00 PM - 5:00 PM (America_New_York)
В	Cloud Provider (second in the list)	Stop parkable entities Saturday, 2:00 PM - 3:00 PM (America_New_York)
С	Global	Start parkable entities Monday - Friday, 9:00 AM - 6:00 PM (America_New_York)



A parkable entity that matches all three policies will apply policy A instead of policy B, because policy A has a higher priority. The entity will also ignore Policy C in favor of Policy A. This means that the entity will be stopped every Saturday, between 1:00 PM and 5:00 PM. No parking policies are enforced outside this window.

Creating Parking Policies

1. Navigate to **Settings > Policies**.

This opens the Policy Management Page, which lists all the currently available policies.

- 2. Click New Policy > Parking Policy.
- 3. Provide a meaningful name for the policy.
- 4. Attach a schedule to a policy so that it can be enforced automatically according to the specified schedule.

For instructions on creating parking schedules, see Managing Parking Schedules (on page 707).

5. Configure the level.

For details about this setting, see Prioritization (on page 701).

- Global Select Global.
- Cloud Provider Select one or several cloud providers.
- Account Expand one or several cloud providers and then select the accounts that will apply the policy.
- Resource Group (Azure only) Under Azure, expand one or several accounts and then select the Resource Groups
 that will apply the policy.
- Select one or several filters.

Each policy can have filters applied on top of the chosen level. This gives you more fine-grained control over which schedule should apply to each entity. Filters do not the change the priority of a policy.

Filter	Expressions	Input
Name	equals (regex), not equals (regex)	Text
Tag	equals, not equals	Multi-text (tag name and tag value)
Guest OS	equals (regex), not equals (regex)	Text
Instance Type	equals, not equals	Multi-select
Region	equals, not equals	Multi-select

Click Save Policy.

Managing Parking Policies

You can perform any of the following tasks after creating policies.

- Drag and drop policies within the same level, as needed. Remember that priority is given from top to bottom.
- Delete a policy by selecting the policy and then clicking the trash bin icon at the top-right section of the page.

Working With Schedules

Schedules specify a period of time during which certain events can occur. Workload Optimization Manager uses the following types of schedules:

Calendar Schedule

A calendar schedule is a setting that sets up a window of time when an <u>automation policy (on page 680)</u> takes effect. This policy can execute <u>non-parking actions (on page 518)</u> on public cloud or on-prem entities, or change settings that affect analysis and action generation.

Parking Schedule

A parking schedule is a setting that sets up a window of time when parking actions (stop or start) are enforced on VMs and Database Servers (AWS RDS) in your public cloud environment. Click **Park** on the main menu to see a list of parkable VMs and Database Servers.




Managing Calendar Schedules

A calendar schedule is a setting that sets up a window of time when an <u>automation policy (on page 680)</u> takes effect. This policy can execute <u>non-parking actions (on page 518)</u> on public cloud or on-prem entities, or change settings that affect analysis and action generation.

Creating Calendar Schedules

- Navigate to Settings > Schedule.
- 2. Click New Schedule > Calendar Schedule.
- 3. Type a name for the schedule.




4. Set the recurrence for the schedule.

Choose whether the scheduled period occurs just once, or whether it repeats over time. The settings vary according to the recurrence you choose:

■ Does Not Recur

This is a one-time schedule window. A non-recurring window has a start date, and no end date. The window starts on the day and time you specify, and remains open for the given duration.

Daily




Repeat this schedule every given number of days. For example, repeating 30 days is similar to repeating monthly, except it repeats by the count of days, not by the calendar month.



The schedule begins on the **Start Date**, and continues repeating until the **End Date**. If **End Date** is "None", the schedule repeats perpetually.

Weekly



Repeat this schedule every given number of weeks, on the week days you specify. For example, to repeat every weekend, set it to repeat every one week on Saturday and Sunday.

The schedule begins on the **Start Date**, and continues repeating until the **End Date**. If **End Date** is "None", the schedule repeats perpetually.

Monthly



Repeat this schedule every given number of months, to begin on a given day in the month. For example, you can schedule a maintenance window to begin on the first Saturday of each month.

The schedule begins on the **Start Date**, and continues repeating until the **End Date**. If **End Date** is "None", the schedule repeats perpetually.

5. Set the start time and duration.

These settings specify how long the scheduled window remains open. You set the duration in terms of hours and minutes. Using a duration instead of an end time removes ambiguities such as starting before midnight and ending after. However, you should make sure the duration is not longer than the recurrence.

6. Set the time zone.

This gives a reference for the schedule's start time. Workload Optimization Manager uses that reference when it opens and closes the schedule window.


You see the same time zone setting no matter where you are located. Convert the schedule time to your local time to track when the schedule opens in your working day.

Save the schedule.

Viewing Calendar Schedules

To view calender schedules, navigate to **Settings > Schedule**.





The Schedules page lists all the currently defined schedules. From this page you can:

- 1. View list of schedules.
- 2. Click name to edit schedule.
- 3. Select an entry to delete the schedule.
- 4. Expand an entry to see schedule details.

The details include a summary of the schedule definition, as well as:

Used in Policies

The number of policies that use this schedule. Click the number to review the policies.

Next Occurrence

When the schedule will next come into effect.

Accepted Actions

How many scheduled actions have been accepted to be executed in the next schedule occurrence. Click the number for a list of these actions.

Awaiting Acceptance

The number of Manual actions affected by this schedule that are in the Pending Actions list, and have not been accepted. Click the number for a list of these actions.

- 5. Create a schedule.
- Select an entry to defer the next occurrence.

Workload Optimization Manager calculates when the next scheduled window will open. If you want cancel the scheduled occurrence one time, you can select the schedule and defer the upcoming occurrence. This defers the schedule wherever it is applied. If the schedule is applied to more than one policy, this will defer all the policies that use this schedule. Before you defer a schedule, you should expand the details and review all the policies that use this schedule.

Deleting Calendar Schedules

Before you delete a schedule, you should view its details to make sure no policies use it. If you delete a schedule that is in use by any policies, Workload Optimization Manager disables the affected policies until you edit them to either:

- Apply a different schedule to the policy and save the change
- Save the policy with no schedule



Saving with no schedule confirms that you intend for this policy to apply at all times. Because scheduled policies are for special cases, this is usually not what you intend. For example, a scheduled maintenance window can have aggressive action acceptance modes that you do not want to enable during peak hours. If you save the policy with no schedule, then the aggressive settings will take effect at all times.

Workload Optimization Manager posts a confirmation dialog before deleting a schedule that is currently in use.


Managing Parking Schedules

A parking schedule is a setting that sets up a window of time when parking actions (stop or start) are enforced on VMs and Database Servers (AWS RDS) in your public cloud environment. Click **Park** on the main menu to see a list of parkable VMs and Database Servers.

Creating Parking Schedules

- Navigate to Settings > Schedule.
- 2. Click New Schedule > Parking Schedule.

The Create Schedule page displays.



3. Provide a name and description.

When attaching a parking schedule to one or more entities, you will see the *name* of the schedule. It is therefore important to use a name that will help you recognize each schedule and choose the appropriate one.

4. Set the time zone.

This gives a reference for the schedule's start time. Workload Optimization Manager uses that reference when it opens and closes the schedule window.

You see the same time zone setting no matter where you are located. Convert the schedule time to your local time to track when the schedule opens in your working day.

Set the schedule resolution.

By default, each block in the schedule configuration section corresponds to an hour of the day. You can change this to 15-minute increments to give you more flexibility with scheduling. For example, with 15-minute increments, you can enforce parking actions between 8:15 and 20:45. This is not possible with the default schedule resolution.



6. Set a parking schedule.


Parking schedules recur every week, on the days and times that you specify. These schedules include the following states that define the parking policies that you can enforce.

State	Policy
Running (green)	A parkable entity must be running on the selected days and times.
	Workload Optimization Manager will start the entity immediately if:
	The entity is not running at the beginning of the schedule.
	A user stops the entity via the cloud provider.
Stopped (red)	A parkable entity must not be running on the selected days and times.
	Workload Optimization Manager will stop the entity immediately if:
	■ The entity is running at the beginning of the schedule.
	A user starts the entity via the cloud provider.
Do Nothing (gray)	Do not enforce parking actions on the selected days and times. This is the default state for all the blocks.

Basic steps:

- a. Click either the **Running** (green) or **Stopped** (red) button.
- b. Click the blocks for the days and times the action will be enforced. To select multiple contiguous blocks, click and hold, and then drag in any direction.
- c. To undo your selections, click the **Do Nothing** (gray) button and then click the affected blocks.

In the following example, stop actions are enforced every Saturday and Sunday. No parking actions are enforced on all the other days of the week. The selected blocks are shaded red.



Click Create.

The schedule can now be attached to the parkable entities listed in the Parking page. For details about the Parking page, see Park: Stop or Start Cloud Resources (on page 597).


Deleting Parking Schedules

Only unattached parking schedules can be deleted.

- 1. Select one or several unattached schedules to delete.
- 2. Click the delete button at the top-right section of the page.



Templates: Resource Allocations for New Entities



Workload Optimization Manager uses templates to describe new entities that it deploys in your environment or in plans. The templates specify resource allocations for these entities. For example, you can run a plan that adds new VMs to a cluster. If you add ten copies of a template, then the plan places ten new VMs that match the resource allocation you have specified for the template. For your cloud environment, you can see templates to match the instance types in your cloud accounts and subscriptions.

A VM template definition can include one or more images that Workload Optimization Manager uses to deploy the VM in your environment. The image identifies the actual deployment package, including a path to the physical files (for example an OVA).

As you deploy an instance of a VM template, Workload Optimization Manager chooses the best image for that instance.

The Template Catalog shows the templates that are specified or discovered for your installation of Workload Optimization Manager. From this page, you can:

- 1. Filter by type.
- 2. Filter to see only discovered templates.
- Select templates to delete.
- Click to edit the template.
- 5. Expand for details.
- 6. Create a template.

Creating Templates

Templates specify the resources for entities that Workload Optimization Manager can deploy in your environment, or in plans.

A VM template definition can include one or more images that Workload Optimization Manager uses to deploy the VM in your environment. The image identifies the actual deployment package, including a path to the physical files (for example an OVA).

The Template Catalog shows all of the templates that have been specified or discovered for your installation of Workload Optimization Manager. From this page, you an also create new templates and edit existing ones.



Creating and Editing Templates

To create a new template, navigate to the Template Catalog and click **NEW TEMPLATE**. To edit a template, click the template's name. When you create a new template, the first step is to choose the entity type.

1. Navigate to the Settings Page.




Choose Templates.



3. Create or edit a template

To create a new template, navigate to the Template Catalog and click **NEW TEMPLATE**. To edit a template, click the template's name.

4. If you're creating a new template, choose the entity type.



5. Make the settings for your template.

For each type of template, you set allocations for different resources. You can make templates of the following types:

- Virtual Machine
- Host
- Storage
- Container
- Make the settings for your template, and then save your changes.

When the template window opens, it displays the most common resource settings. You can expand the settings to see the full collection for that template type.

7. Save your changes.

After you have made your settings and named the template, click CREATE or SAVE.

VM Template Settings

A VM template describes the resource allocation that you want to provide for a type of VMs. When Workload Optimization Manager deploys the associated VM to your environment or in a plan, it uses these values to determine the size of the VM. Workload Optimization Manager uses the Size settings to calculate the best placement for a VM of this type.

A VM template can optionally include an image description. When Workload Optimization Manager uses the template to deploy a VM to your environment, it uses the image to access the actual bits that install as the VM instance.



NOTE:

Workload Optimization Manager generates a special template called *headroomVM*, which it uses to calculate cluster headroom. The Template Catalog shows the template as editable, but you should not edit it because Workload Optimization Manager will overwrite your changes the next time it generates the template.

VM Size

■ CPU

The virtual CPUs assigned to the VM. Specify the number of **Cores** and the **VCPU** clock speed – Workload Optimization Manager multiplies these values to calculate the host CPU resources it will allocate when placing the VM.

The **Utilization** value sets the percentage of allocated CPU that the placed VM will consume. To ensure the host has left over resources for infrastructure tasks, you should assign less than 100%.

Memory

The amount of memory to allocate for the VM, in MB.

The **Utilization** value sets the percentage of allocated memory that the placed VM will consume. To ensure the host has left over resources for infrastructure tasks, you should assign less than 100%.

Note that you should never allocate less memory than is required for the VM's guest OS.

Storage

The storage resources to allocate for this VM.

- disk/rdm If you choose rdm, then the VM can use VMware Raw Device Mapping for its storage.
- IOPS The capacity for IO operations you give the VM for this datastore.
- Size The amount of storage capacity, in GB.

The **Utilization** value sets the percentage of allocated memory that the placed VM will consume. To ensure the storage has left over resources for infrastructure tasks, you should assign less than 100%.

Note that you can allocate multiple datastores to the VM.

Network

The amount of the host's network throughput to assign to the VM, in Mb/s.

IO

The amount of throughput on the host's IO bus to assign to the VM, in Mb/s

Host Template Settings

Host templates describe models of physical hosts that you can deploy in the on-prem datacenter. As part of capacity planning, you might want to see how to replace your current hosts with different models. To do that, you create templates to represent the hosts you want, and then use those templates when running hardware replacement plans.

The host template is a collection of these settings:

■ CPU

The processor for this host model. Note that CPU size and speed are not the only factors to determine processing power. To address this, you can specify the host CPU in the following ways:

Select from Catalog



When you enable **Select from Catalog**, you can open up a catalog of CPU models that Workload Optimization Manager uses to map the model to an effective capacity for the CPU.

Cores and CPU Speed





When you disable **Select from Catalog**, you can specify the number of **Cores** and the **CPU** clock speed – Workload Optimization Manager multiplies these values to calculate the host CPU resources.

Memory

The amount of memory to allocate for the VM, in MB.

Network

The host's network throughput, in MB/s.

■ IC

The host's IO bus throughput, in MB/s

Price

If you know the price of the host model that you're specifying for the template, you can enter it here. When running a plan, Workload Optimization Manager can use the price to calculate costs or savings when adding or removing host machines in an on-prem datacenter.

Selecting CPUs from the Catalog

CPU processor speed is not necessarily an effective indicator of CPU capacity. For example, processor architecture can make a slower CPU have a greater effective capacity. Newer models of machines can often have fewer cores or less clock speed, but still have a higher effective capacity. This can affect planning in two ways:


- When planning hardware replacement, the plan knows the template's effective capacity. This means the plan knows how to best place workloads on the new hardware.
- For deployed hosts, Workload Optimization Manager discovers the effective capacity and uses that information when calculating workload placement.

To build the catalog of CPU capacity, Workload Optimization Manager uses benchmark data from spec.org. When you set up the CPU for a host template, you can search this catalog for the processor you want, and set it to the template.

NOTE:

Workload Optimization Manager also uses the effective processor capacity when calculating workload placement in real-time. For more information, see Effective CPU Capacity (on page 526).





HCI Host Template Settings

HCI host templates describe models of physical hosts that support participation in a vSAN. Along with the host compute specifications, you also include specifications for storage capacity and redundancy (RAID level and failover). You can use these templates to plan for changes to your vSAN capacity.

NOTE:

For Hyper-V environments, if you run a Hardware Replace plan that replaces hosts with HCl Host templates, the results can be inconsistent or the plan can fail to place all the VMs in the plan scope. This typically occurs when Workload Optimization Manager detects a configuration issue with VMM or Hyper-V. As a result, Workload Optimization Manager treats the VMs as not controllable and will not attempt to place them.

The HCl Host template is a collection of these settings:

■ CPU

The processor for this host model. Note that CPU size and speed are not the only factors to determine processing power. To address this, you can specify the host CPU in the following ways:

Select from Catalog



When you enable **Select from Catalog**, you can open up a catalog of CPU models that Workload Optimization Manager uses to map the model to an effective capacity for the CPU.



Cores and CPU Speed



When you disable **Select from Catalog**, you can specify the number of **Cores** and the **CPU** clock speed – Workload Optimization Manager multiplies these values to calculate the host CPU resources.

Memory

The amount of memory to allocate for the VM, in MB.

Network

The host's network throughput, in MB/s.

IO

The host's IO bus throughput, in MB/s

■ Storage

The capacity for this storage.

- IOPS The effective IOPS capacity.
- Size Raw storage capacity, in GB. A plan that uses this template will compute the effective storage capacity.
- Redundancy

The redundancy method for this storage on the virtualized SAN. This combines the RAID level and the number of host failures to tolerate.

■ Price

If you know the price of the host model that you're specifying for the template, you can enter it here. When running a plan, Workload Optimization Manager can use the price to calculate costs or savings when adding or removing host machines in an on-prem datacenter.

Selecting CPUs from the Catalog

CPU processor speed is not necessarily an effective indicator of CPU capacity. For example, processor architecture can make a slower CPU have a greater effective capacity. Newer models of machines can often have fewer cores or less clock speed, but still have a higher effective capacity. This can affect planning in two ways:


- When planning hardware replacement, the plan knows the template's effective capacity. This means the plan knows how to best place workloads on the new hardware.
- For already deployed hosts, Workload Optimization Manager discovers the effective capacity and uses that information when calculating workload placement.

To build the catalog of CPU capacity, Workload Optimization Manager uses benchmark data from spec.org. When you set up the CPU for a host template, you can search this catalog for the processor you want, and set it to the template.

NOTE:

Workload Optimization Manager also uses the effective processor capacity when calculating workload placement in real-time. For more information, see <u>Effective CPU Capacity (on page 526)</u>.





Storage Template Settings

Storage templates describe models of storage that you can deploy in the on-prem datacenter. As part of capacity planning, you might want to see how to replace your current storage with different models. To do that, you create templates to represent the storage you want, and then use those templates when running hardware replacement plans.

The storage template is a collection of these settings:

Storage

The capacity for this storage.

- IOPS The capacity for IO operations on this storage.
- Size The amount of storage capacity, in GB.
- Price

If you know the price of the storage model that you're specifying for the template, you can enter it here. When running a plan, Workload Optimization Manager can use the price to calculate costs or savings when adding or removing storage in an on-prem datacenter.



Billing and Costs

As you work with Workload Optimization Manager, you can set up costs that Workload Optimization Manager uses in its calculations. This setup includes:

Reserved Instance Settings

To recommend placing workloads on instance types that take advantage of discounted pricing, Workload Optimization Manager uses the real pricing plans that are available to the targets public cloud accounts. Setting up a purchase profile adds even more detail to the pricing structure that Workload Optimization Manager uses in its calculations.


Price Adjustment

Cloud service providers can offer their own price lists, including special costs for services or discounts for workloads. However, Workload Optimization Manager does not discover these adjustments. For example, to reflect any discounted prices in the Workload Optimization Manager display and in Workload Optimization Manager analysis, you must manually configure those discounts. In Workload Optimization Manager, you configure such discounts via **Price Adjustments** for specific billing groups in your cloud environment.

Currency

By default, Workload Optimization Manager uses the dollar symbol (\$) when displaying the costs and savings that it discovers or calculates for your cloud workloads. You can set a different symbol to match your preferred currency. For example, if your cloud provider bills you in euros, change the currency symbol to €.

Reserved Instance Settings



To recommend placing workloads on instance types that take advantage of discounted pricing, Workload Optimization Manager uses the real pricing plans that are available to the targets public cloud accounts. Setting up a purchase profile adds even more detail to the pricing structure that Workload Optimization Manager uses in its calculations.

A purchase profile determines the costs that Workload Optimization Manager will use for all discount purchase decisions in your environment. As it sees opportunities to move workloads to another term, Workload Optimization Manager determines the costs based on the profile, and includes cost information in action descriptions. Workload Optimization Manager also uses this information to calculate projected changes in costs.

Note that the settings you configure apply to your global public cloud environment.

To set up a profile, navigate to **Settings > Billing and Costs**, and display the **RESERVED INSTANCE SETTINGS** tab. Then make the settings for your purchase profile:

Offering Class

For AWS environments, choose the offering class that corresponds to the RI types that you typically use in your environment.



■ Term

For AWS and Azure environments, choose the payment terms you contract for your discounts. TERM can be one of **1 Year** or **3 Year**. Typically, longer term payment plans cost less per year.

Payment

The payment option that you prefer for your AWS RIs:

- All Upfront You make full payment at the start of the RI term.
- Partial Upfront You make a portion of the payment at the start of the term, with the remain cost paid at an hourly rate.
- No Upfront You pay for the RIs at an hourly rate, for the duration of the term.

When you are satisfied with your RI Purchase Profile settings, click **APPLY SETTINGS**. Or to reset the form, click **RESET DEFAULTS**.

Price Adjustments

Cloud service providers can offer their own price lists, including special costs for services or discounts for workloads. However, Workload Optimization Manager does not discover these adjustments. For example, to reflect any discounted prices in the Workload Optimization Manager display and in Workload Optimization Manager analysis, you must manually configure those discounts. In Workload Optimization Manager, you configure such discounts via **Price Adjustments** for specific billing groups in your cloud environment.

Workload Optimization Manager applies these price adjustments to:

- Costs for workload template families, including:
 - Compute
 - Discount Compute
- Costs for services, including:
 - Bandwidth
 - VM Licenses
 - AWS CloudWatch
 - AWS DynamoDB
 - And others

Note that in AWS environments, Workload Optimization Manager does not apply any discounts or other price adjustments to Spot Compute costs.

The general steps to configure a price adjustment are:

- Create the price adjustment:
 - Specify the adjustment scope

To do this, you choose which cloud service provider is giving you the adjustment, and then choose a billing group to set the scope of the adjustment.

Choose the Type

The price adjustment can be a Discount or an Increase. In most cases you will specify discounts for the price adjustment. While this sets the type for the overall adjustment, you can override the type for specific line items.

Specify a Price Adjustment setting

The Price Adjustment is the overall adjustment that your cloud service provider offers for the billing groups in your current scope. For example, AWS might offer you a 10% discount for a given account. For that billing group, you would specify a 10% Discount for the Price Adjustment setting.

Specify Price Overrides (AWS only)

While your service provider might offer a general price adjustment for the billing group you chose, it might also offer further discounts for select services or template families. Or it might offer discounts for some template families, but price increases for some other services. You can configure these differences as Price Overrides.



NOTE:

Workload Optimization Manager uses the adjustments that you configure to display costs in the user interface. However, the values for hourly cost per entity, total hourly cost, total monthly cost, or total yearly cost can show inaccuracies on the order of a fraction of a percent. This is due to rounding when calculating the adjusted cost per entity.

Creating a Price Adjustment

A price adjustment configures adjusted workload pricing that you have negotiated with your Cloud Provider. After you configure an adjustment, Workload Optimization Manager applies it to pricing in the affected cloud scope.

To create a price adjustment in Workload Optimization Manager, you identify the adjustment's scope – the subscriptions or billing families the adjustment applies to – and then set the type and percentage for the price adjustment. This specifies an overall adjustment for the workloads that fall within the billing group. For AWS, you can later drill into the adjustment to specify overrides for specific template families or services.

Notes:

- To use a price adjustment with a given billing group, you must increase the memory allocated to the VM that hosts your Workload Optimization Manager instance. Workload Optimization Manager requires that you provide a minimum amount of memory when you install the product. To use price adjustments, Cisco recommends that you increase the allocated memory as follows:
 - For the first price adjustment assigned to one or more billing groups, increase by 4 GB.
 - For each subsequent price adjustment assigned to one or more billing groups, increase by an additional 1 GB.
- Whenever you add, edit, or remove a Price Adjustment that is in use, you must allow sufficient time for Workload Optimization Manager to fully discover all of the affected environment, and to propagate the changes throughout that environment. In an average environment, this can take up to 30 minutes. As an alternative, you can manually execute rediscovery for the affected cloud subscription or account.

To create a price adjustment:

1. Navigate to the Settings Page.



Click to navigate to the Settings Page. From there, you can perform a variety of configuration tasks.

2. Choose Billing and Costs.



Click to navigate to the Billing and Costs page.

Display the PRICE ADJUSTMENT tab.

Click the **PRICE ADJUSTMENT** tab to see all of the adjustments that have been configured for your environment. In this list you can:

- Click an entry to see details and edit the adjustment
- Select an entry to delete the adjustment
- Create new price adjustments
- Create the price adjustment.

First click **NEW PRICE ADJUSTMENT**, then specify the following settings to configure a price adjustment:

- Give the adjustment a name.
- To set the scope for this adjustment, choose its Billing Groups.

Click in the **BILLING GROUPS** field to display the Billing Groups fly-out.

In the Billing Groups fly-out, choose the cloud service provider you want to work with and then choose the billing group for the scope of this adjustment.



A Billing Group is a set of cloud service provider accounts that are consolidated into a single billing schedule. Billing group details depend on your service provider:

AWS: To consolidate billing, AWS supports billing families of AWS accounts, where there is a master account
and other member accounts. Workload Optimization Manager lists each billing family as a billing group. You can
choose a billing family to set the scope of this adjustment.

After you have chosen your billing group, click SAVE to return to the Add New Price Adjustment fly-out.

- Set the Type for this price adjustment Choose either **Discount** or **Increase**.
- Specify a percentage of adjustment as the Price Adjustment.

Enter the percentage in the PRICE ADJUSTMENT field. The acceptable value depends on the type of adjustment:

- For a discount: 0 99.99%
- For an increase: 0 999.99%

This is the general percentage of adjustment (increase or discount) for the current scope. For any costs within the adjustment scope, Workload Optimization Manager will apply this percentage as it calculates the optimal workload capacity and placement.

NOTE:

If you set an overall adjustment of 0%, then Workload Optimization Manager enforces a Type setting of Discount. The end result is the same, because an increase or a discount of 0% is the same.

5. (AWS only) Specify any price overrides for this price adjustment.


The PRICE ADJUSTMENT percentage you just specified applies as a default in the adjustment scope. However, you might have negotiated different prices for specific services or template families in your cloud environment. To configure these special prices, click **PRICE OVERRIDES** to open the Cloud Cost Adjustment fly-out.

For details, see AWS Price Override (on page 719).

6. Save your work.

After you have configured the price adjustment, click SAVE.

AWS Price Override



To override the PRICE ADJUSTMENT setting for AWS Billing groups, Workload Optimization Manager analysis can use settings for different services that AWS provides to your accounts.

In AWS, you can set up a billing family that includes a *master* account and a given set of *member* accounts. Workload Optimization Manager treats the AWS Billing family as a Billing Group. For more information about billing families and accounts, see <u>AWS Billing Families</u> (on page 248).



Assume you have configured a price adjustment with a discount of 10% for a billing family, to match the overall discount that AWS offers you for that scope. But then assume the account includes extra discounts for some of the services your billing families provide. Then you can create overrides to add the extra discounts to those services.

Workload Optimization Manager uses the adjusted costs in its analysis as it calculates actions. For example, assume a price adjustment of 10% for a billing group, and a discount of 20% for the M4.Large family of templates. As Workload Optimization Manager places a workload, it will consider both the template capacity and the template cost. Even if an M4 template is larger than the workload actually needs, the M4 template could be less expensive because of the added discount. In that case, Workload Optimization Manager will place the workload on the less expensive template.

NOTE:

The Cloud Cost Adjustment table lists the services that are available to you for the AWS Billing family that you have set up as the discount scope. The services this table displays depend on whether the billing family uses the given service, and whether there is any recorded cost at the time that you display the table. For this reason, under some circumstances you might see different services listed in the table.

Under all circumstances, the table lists the services, AWS EC2 Compute, AWS EC2 Reserved Instance, and AWS RDS.

Also, for the Cloud Cost Adjustment table to display CSP Cost and Effective Cost, you must have created a Cost and Usage report in AWS, and you must store it in an S3 bucket.

In the Cloud Cost Adjustment table, you can perform the following:

Override the price adjustment for a service or template family.

To add an override, choose the line item for a service, or expand the row for a template family and:

- Set the Type. Double-click and then choose Discount or Increase. Press Enter to confirm your setting.
- Specify the percentage for this override, and then press Enter to confirm your override. The value you enter here is an absolute value for the discount or increase Workload Optimization Manager will apply for this line item.

When you're done setting these overrides, click Save.

- To remove all overrides and revert back to the PRICE ADJUSTMENT Discount, click CLEAR ALL OVERRIDES.
- To download a report of the discounts for each service, click **DOWNLOAD** and choose CSV or PDF.

The table lists the following information about your discounts:

SERVICES

The different cloud services to which you can set an override discount. To see individual workload templates:

- For Azure, expand Virtual Machines
- For AWS, expand AWS EC2 Compute or EC2 Reserved Instance
- TYPE

Whether this price adjustment will be an increase or a discount. By default, this field shows the setting that you have made for the Price Adjustment. However, you can change it as an override for an individual entry.

■ PRICE ADJUSTMENT %

The percentage that you have specified for the Price Adjustment setting. This is the general adjustment that Workload Optimization Manager applies by default to the given service.

■ OVERRIDE %

If you have entered a value, this is the price adjustment Workload Optimization Manager applies to the given service.

ORIGINAL RATE (LINUX)

The Cloud Service Provider's cost for VM templates, per hour. To see these costs, expand the workload services to show specific templates. The cost assumes no charge for the OS license, as though the VM runs Linux.

■ EFFECTIVE ADJUSTMENT %

The actual adjustment for the given service.

■ ADJUSTED RATE (LINUX)

The discounted cost for VM templates, per hour. To see these costs, expand **Virtual Machines** to show specific templates. The cost assumes no charge for the OS license, as though the VM runs Linux.



AWS Billing Families



As you configure AWS targets, Workload Optimization Manager discovers AWS accounts that are consolidated into *billing families*. A billing family has one *master* account, and zero or more *member* accounts. By recognizing billing families, Workload Optimization Manager more accurately calculates cloud investments and savings, and makes more accurate recommendations for RI coverage.

In the Targets user interface:

- 1. Master accounts appear in bold, with a star next to them.
- 2. You can expand the account entry to see the related member accounts.
- 3. If you expand the entry for a member account, the related accounts includes the family master, indicated by a star.
- 4. Related accounts includes the member accounts

NOTE:

If you expand the entry for a member account, then the related accounts includes the family master, indicated by a star.

5. A gray name indicates a member account that is not configured as a target.

For RI purchases, different accounts in a billing family can share the same RI resources. At the same time, accounts in other billing families cannot use those RIs. This adds flexibility to your RI coverage, while maintaining order over the billing.

In Workload Optimization Manager, if you enable Billing Family Recognition, then you can see the billing family master and member accounts in the Targets user interface, and Workload Optimization Manager can recommend proper RI purchases within the correct billing families.

To enable Billing Family Recognition, ensure the following as you configure your AWS targets:

Use the proper role for each AWS target

To properly discover billing family information for a target, you must give Workload Optimization Manager credentials for an AWS role that includes the permission, organizations: DescribeOrganization. With that permission, Workload Optimization Manager can:

- Discover master accounts and member accounts in different billing families
- Display the account names in the user interface
- Discover billing information for each family and account



- Recommend RI actions that respect billing family boundaries
- Configure targets for the complete billing family

One billing family can consolidate a number of AWS accounts. For Workload Optimization Manager to include these accounts in its analysis, you must configure each one as a separate target. If you do not configure all the accounts in a billing family, then Workload Optimization Manager cannot discover complete billing information for that family, and its analysis will be based on incomplete information.

Workload Optimization Manager displays member accounts that have been configured as targets in regular text. For members that Workload Optimization Manager discovers but have not been configured as targets, Workload Optimization Manager displays their names in grayed text.

If you have enabled Billing Family Recognition, you should keep the following points in mind:

Billing families can grow

Workload Optimization Manager regularly checks the membership of your billing families. If it discovers a new member account, it adds that account to the list of members. If you have already configured the account as a target, then Workload Optimization Manager includes the new member in its analysis of billing families. If the new member is not already a target, then Workload Optimization Manager lists the new member in grayed text.

You can configure discounts per billing family

Workload Optimization Manager includes a feature to set a discount for a billing group, and to override that discount for specific template families within that scope. For more information, see <u>Cloud Discounts (on page 717)</u> and <u>Discount Override: AWS (on page 719)</u>.

You might see master accounts that have no member accounts

AWS treats every account you create as a part of a billing family. Assume you created an account, but you had no reason to consolidate its billing with any other accounts. In that case, the account appears in the Workload Optimization Manager user interface as a master account, but it has no member accounts.

Currency Settings

By default, Workload Optimization Manager uses the dollar symbol (\$) when displaying the costs and savings that it discovers or calculates for your cloud workloads. You can set a different symbol to match your preferred currency. For example, if your cloud provider bills you in euros, change the currency symbol to €.

To change the currency symbol, go to Settings > Billing and Costs and then click the Currency tab.

Workload Optimization Manager saves your preference in the local storage of the browser that you used to access the user interface. It reverts to the default symbol if you use another browser or view the user interface in incognito/private mode.

Currency symbols are for display purposes only. Workload Optimization Manager does not convert monetary amounts when you switch symbols.

Administrative Tasks

To perform Workload Optimization Manager administrative tasks, you will navigate to different pages from **Settings**. The different tasks you can perform for Workload Optimization Manager include:

■ Managing User Accounts (on page 723)

Create and manage user accounts for Workload Optimization Manager.

Maintenance: Logging, and Troubleshooting (on page 731)

Perform general tasks such as setting log levels or sending troubleshooting data to Technical Support.

■ License Configuration (on page 732)

Review the status of your current license, and apply any license upgrades.



Managing User Accounts

As an administrator, you specify accounts that grant users access to Workload Optimization Manager. Credentials for user accounts can either be saved locally on the Workload Optimization Manager server or managed externally through Microsoft Active Directory (AD) or another single sign-on (SSO) provider.

The user account configuration determines the following details:

User Authentication

To configure an account, you set the type of authentication the account uses:

- Local User: Configure the username and password and save those credentials on the Workload Optimization Manager server.
- External User: Single user accounts can authenticate through SSO or through AD.
- External Group: Groups of user accounts can authenticate through SSO or AD.
- User Authorization

You can also specify properties that determine the range of access and features for a user:

- Role: The user role determines access to specific Workload Optimization Manager features.
- Scope: The user scope determines how much of the environment this user can manage.

As you configure user accounts, you can set up access to specific clusters in your environment. You can even set up accounts for tenant customers, and only show them the virtual workloads they own in their specific virtual datacenters.

IMPORTANT:

For self-hosted Workload Optimization Manager instances, you can configure Workload Optimization Manager to use SSO authentication. When SSO is enabled, Workload Optimization Manager permits logins only through the SSO IdP. Whenever you navigate to your Workload Optimization Manager installation, it redirects you to the SSO Identity Provider (IdP) for authentication before it displays the Workload Optimization Manager user interface.

Before you enable SSO for your Workload Optimization Manager installation, you must configure at least one SSO user with Workload Optimization Manager administrator privileges. If you do not, then after you enable SSO, you cannot configure any SSO users in Workload Optimization Manager. To authorize an SSO user as an administrator, use **EXTERNAL AUTHENTICATION** to do one of the following options:

- Configure a single SSO user with administrator authorization.
 - Add an external user. The username must match an account that the IdP manages.
- Configure an SSO user group with administrator authorization.
 - Add an external group. The group name must match a user group on the IdP, and that group must have at least one member.

For information about configuring SSO user groups in SAML, see <u>Configuring a Group for SSO Authentication (on page 729)</u>. For information about configuring SSO authentication for Workload Optimization Manager, see <u>Single Sign-On Authentication (on page 73)</u>.

To work with Workload Optimization Manager accounts:

Navigate to the Settings Page.



Click to navigate to the Settings Page. From there, you can perform a variety of Workload Optimization Manager configuration tasks.

Choose User Management.



User Management

Click to navigate to the User Management Page.






This page lists all the user accounts that you currently have configured for Workload Optimization Manager. You can:


- Click to manage local or external authentication
- Select an entry to delete the account
- Click a name to edit the account
- Create new user or group account
- 3. Filter the list of users.

User Management



To work with a long list of users, you can filter by role (for example, only show administrator or only show observer users). You can also type a string in the **Search** field to filter the list, and you can sort the list by name.

4. Configure Local User accounts.




Workload Optimization Manager stores local accounts and their credentials on the Workload Optimization Manager platform. Local authentication is for individual users, only.

When you choose **LOCAL USERS**, Workload Optimization Manager displays a list of all the local user accounts you have configured for this installation.



Create or edit a local user account.



To add a new local user, click **NEW LOCAL USER**. To edit an existing account, click the account name in the list. To configure a local account, specify:

Authentication

Provide the username and password. Workload Optimization Manager stores these credentials on the local server.

- Authorization User Role
 - Administrator

Users with this role can use all Workload Optimization Manager features and modify settings to configure the Workload Optimization Manager installation. For Workload Optimization Manager instances hosted in the public cloud, this role is limited to the Workload Optimization Manager representative that manages the instances.

Site Administrator

Users with this role can use all Workload Optimization Manager features and modify site-specific settings to configure the Workload Optimization Manager installation. Users can also administer Groups, Policies, Templates, Billing/Costs, and Target Configuration, but not Email, Licenses, Updates, and Maintenance. Users can create other user accounts, except accounts with the Administrator role.

Automator

Users with this role can use all Workload Optimization Manager features (including Plan, Park, and Place), but cannot configure the Workload Optimization Manager installation or create policies.

Deployer

Users with this role can view all Workload Optimization Manager charts and data, use Place to reserve workloads, and create placement policies and templates. However, users cannot run plans or execute any recommended actions.



Advisor

Users with this role can view all Workload Optimization Manager charts and data, and run plans. However, users cannot use Place to reserve workloads, create policies, or execute any recommended actions.

Observer

Users with this role can view the environment, including the Home Page and Dashboards. Users can also use Search to set a scope to the session. For scope, only VM groups and Resource Groups are supported.

Operational Observer

Users with this role can view the environment, including the Home Page, Dashboards, Groups, and Policies. Users can also use Search to set a scope to the session.

Shared Advisor

Users with this role are scoped users. They can view the Home Page and Dashboards, but only see VMs and Applications. Users cannot execute Workload Optimization Manager actions.

Shared Observer

Users with this role are scoped users. They can view the Home Page and custom Dashboards, but only see VMs and Applications. Users cannot see Executive Dashboards or execute Workload Optimization Manager actions. This is the most restricted user.

Report Editor

Users with this role can create, edit, and delete reports. Due to limits to the reporting license, only one user per instance is allowed to have this role (by default, the local **administrator** user). To assign this role to another user, you must first remove it from the current user. Be sure that the new user is *not* a scoped user.

Authorization - Scope (optional)

The scope limits what the user can monitor in your environment. For example, you can scope to a group that contains only the physical machines that support this user's VMs or applications. Click **ADD SCOPE** and choose which groups or clusters this user can see.


NOTE:

Under most circumstances, a scoped user cannot see actions for entities that are outside of the configured scope. However, when zooming in to Host entities, the user can see actions for storage that is outside of the user's scope if the hosts use that storage.

Permission

The user permissions are different for each role.

- When you are done, save the account.
- 6. Configure External Authentication.



For External Authentication, you configure Workload Optimization Manager to use Single Sign-on (SSO) or Active Directory (AD) services to manage the credentials and authentication of users. You can create external accounts to authorize user groups or individual users.

NOTE:

If a user is a member of multiple groups, then Workload Optimization Manager logs the user on via the first SSO or AD that successfully authenticates the user. Also note that Workload Optimization Manager does not support nested AD groups – AD log-ins must be for users in a top-level group.




To enable SSO, you must configure access to the given IdP. For information about configuring SSO, see <u>Single Sign-On Authentication (on page 73)</u>.

To enable AD you must specify either an AD domain, an AD server, or both. Workload Optimization Manager uses this connection for all AD users.

7. Fnable AD authentication.

EDIT AD



To enable AD, click CONNECT TO AD and configure:

Active Directory Domain

To authenticate AD groups, specify a domain so that AD can find a user with the User Principal Name (UPN). If you specify a domain, but not a server, authentication uses any AD server from that domain. If you want to support only AD users and not groups, the domain is optional.

Active Directory Server

To disable AD groups, specify a server but do not specify a domain. If you specify a domain and a server, authentication uses that server and also supports groups.

When you configure an AD server, by default Workload Optimization Manager assumes the AD server port to be 389 or 636. To specify a custom port for the AD server, add the port number to the AD server IP address. For example, 10.10.10.123:444 sets port 444.


■ Secure

Use a secure connection to communicate with AD servers. The AD domain must be configured to use LDAPS, and you must import a certificate into the Workload Optimization Manager server. Workload Optimization Manager can support LDAP channel binding and LDAP signing. To support these Active Directory features, you must configure secure access.

For more information, see Enforcing Secure Access (on page 53).

- When you are done, save your changes.
- 8. Create or edit an SSO or AD account.





This account can be for a user group or for a single user. To add a new account, click **NEW EXTERNAL GROUP** or **NEW EXTERNAL USER**. To edit an existing account, click the account name. To configure an external account, specify:

Authentication

Provide the group or user name for this account. The name you provide must meet certain requirements, depending on the type of account you are creating:

External Group - SSO

Provide a name that matches a group the IdP manages.

External Group - AD

The group name must match a group that is accessible from the domain and servers that you configured in **EDIT AD**.

External User - SSO

Provide a user name that matches a user managed by the IdP.

External User - AD

The username must be a valid User Principal Name (UPN). For example, john@corp.mycompany.com.

Authorization - User Role

Administrator

Users with this role can use all Workload Optimization Manager features and modify settings to configure the Workload Optimization Manager installation. For Workload Optimization Manager instances hosted in the public cloud, this role is limited to the Workload Optimization Manager representative that manages the instances.

Site Administrator

Users with this role can use all Workload Optimization Manager features and modify site-specific settings to configure the Workload Optimization Manager installation. Users can also administer Groups, Policies, Templates, Billing/Costs, and Target Configuration, but not Email, Licenses, Updates, and Maintenance. Users can create other user accounts, except accounts with the Administrator role.

Automator

Users with this role can use all Workload Optimization Manager features (including Plan, Park, and Place), but cannot configure the Workload Optimization Manager installation or create policies.



Deployer

Users with this role can view all Workload Optimization Manager charts and data, use Place to reserve workloads, and create placement policies and templates. However, users cannot run plans or execute any recommended actions.

Advisor

Users with this role can view all Workload Optimization Manager charts and data, and run plans. However, users cannot use Place to reserve workloads, create policies, or execute any recommended actions.

Observer

Users with this role can view the environment, including the Home Page and Dashboards. Users can also use Search to set a scope to the session. For scope, only VM groups and Resource Groups are supported.

Operational Observer

Users with this role can view the environment, including the Home Page, Dashboards, Groups, and Policies. Users can also use Search to set a scope to the session.

Shared Advisor

Users with this role are scoped users. They can view the Home Page and Dashboards, but only see VMs and Applications. Users cannot execute Workload Optimization Manager actions.

Shared Observer

Users with this role are scoped users. They can view the Home Page and custom Dashboards, but only see VMs and Applications. Users cannot see Executive Dashboards or execute Workload Optimization Manager actions. This is the most restricted user.

Report Editor

Users with this role can create, edit, and delete reports. Due to limits to the reporting license, only one user per instance is allowed to have this role (by default, the local **administrator** user). To assign this role to another user, you must first remove it from the current user. Be sure that the new user is *not* a scoped user.

Authorization - Scope (optional)

The scope limits what members of this group can monitor. For example, you can scope for access to only the hosts that support this group's VMs or applications. Click **DEFINE SCOPE** and choose which entities this members of this group can see.

Permission

The user permissions are different for each role.

When you are done, save the account.

Configuring a Group for SSO Authentication

To use SSO authentication in Workload Optimization Manager, you should configure user groups on the IdP. The IdP can authenticate the group members, and then Workload Optimization Manager can assign the user role and scope according to that group's authentication. To manage personnel changes, you only need to manage the membership in the IdP group. For example, if a user leaves your organization, you only need to remove the member from the group on the IdP. Because authorization on Workload Optimization Manager is by group, that user will not have any authorization settings stored on the Workload Optimization Manager server.

IMPORTANT:

Before you enable SSO for your Workload Optimization Manager installation, *you must configure at least one SSO user with Workload Optimization Manager administrator privileges*. If you do not, then once you enable SSO you will not be able to configure any SSO users in Workload Optimization Manager. To authorize an SSO user as an administrator, use **EXTERNAL AUTHENTICATION** to do one of the following:

Configure a single SSO user with administrator authorization.

Add an external user. The username must match an account that is managed by the IdP.

Configure an SSO user group with administrator authorization.

Add an external group. The group name must match a user group on the IdP, and that group must have at least one member.

For more information about configuring SSO authentication, see Single Sign-On Authentication (on page 73).



Specifying a Group in the SAML Response

To support SSO, Workload Optimization Manager recognizes IdP responses that comply with SAML 2.0. To create user groups, for each user response you include an attribute named group, and give the group name as the attribute value. For example, assuming the following users, setting the group attribute for each user assigns that user to the appropriate group.

Users:	Group Attribute:
■ George ■ Paul ■ John ■ Ringo	Attribute Name=group, AttributeValue=Beatles
 Smokey Pete Ronnie Claudette Bobby Marv 	Attribute Name=group, AttributeValue=Miracles

As you specify the user response, to add the user to a group you include a group attribute. For example, to add a user to a group named turbo_admin_group, you would include the following attribute in that user's SAML response:

Setting Group Authorization in Workload Optimization Manager

To set an account role and scope to a user group, you must use the group name that you specify as the value in the given SAML group attribute. In the above example, the group value is turbo_admin_group. To set authorization for that group:

- Open the User Management page to EXTERNAL AUTHENTICATION.
 - Navigate to Settings > User Management, and display the EXTERNAL AUTHENTICATION view.
- 2. Create a new External Group
 - Click **NEW EXTERNAL GROUP**.
- Provide the group name.
 - Be sure to use the name that you specify in the group attribute of the SAML response. For the above example, use the name turbo_admin_group.
- 4. Specify the group's authorization
 - For the above example, since this is turbo_admin_group, you should set the **ADMINISTRATOR** role, and you should not set any scope (grant full access to the environment).
 - After you configure this group in Workload Optimization Manager, then any member of turbo_admin_group that the IdP returns will have full administrator privileges on your Workload Optimization Manager installation.



Maintenance Options

The Maintenance Options Page provides tools to set logging levels and to export data for technical support, and import diagnostic files from Technical Support. Many of these tools are for advanced users. You should contact Cisco technical support before you use them.

To execute these actions, navigate to the Maintenance Options page.

Navigate to the Settings Page.



Click to navigate to the Settings Page.

2. Choose Maintenance Options.




Maintenance Options

Diagnostics



If you are experiencing problems with Workload Optimization Manager, your support engineer might request that you export diagnostic data. You can export the data and then send it to the support engineer as requested.

Logging Levels



You can set the level of logging for different components of the Workload Optimization Manager platform. You should be aware that setting more verbose logging levels increases the disk space required to store the log files. You normally change these settings only while you're working with a Workload Optimization Manager support engineer.


HTTP Proxy



If your environment requires an HTTP proxy for Workload Optimization Manager to access the web, provide the credentials here.




Data Retention



Workload Optimization Manager gathers metrics from your environment to provide historical reports. To optimize data storage, it consolidates the data into three groups - Hourly, Daily, and Monthly. Daily statistics consolidate Hourly data, and Monthly statistics consolidate Daily data. Workload Optimization Manager also saves plans, reports, and audit log entries.

You can always modify the default values to meet your requirements. Remember that the longer the retention period, the more storage is required.

License Configuration



To activate the full range of Workload Optimization Manager features, you must purchase the appropriate license. When you purchase the license, Cisco sends an e-mail message with instructions on how to obtain the license key.

A product license enables specific features as well as a specific number of workloads that you can manage. You can add additional licenses to Workload Optimization Manager as a way to increase the number of workloads your installation can manage. Note that as you add more licenses, they must all support the same feature set.

The License Configuration page shows you:

■ The number of workloads you can manage under this license



- How many workloads are currently in use
- The set of features this license enables
- A list of each license and it status

To navigate to the License Configuration page:

Navigate to the Settings Page.



2. Choose License.



To activate a license or to update your current license:

Obtain your license.

Cisco sends an e-mail message with instructions on how to obtain the license key. Save the license file on your local machine so you can upload it to your Workload Optimization Manager installation.

2. Apply the license to your Workload Optimization Manager installation.

First click **IMPORT LICENSE**. Then browse to the license file that you saved and open it. Or you can drag the file into the **Enter License** fly-out.

After you have uploaded the file, click **SAVE**.

After you have activated your license, you can then add more licenses to increase your workload coverage, or you can license a higher feature set.

NOTE:

This only applies only to legacy Workload Optimization Manager customers. As you apply new licenses to Workload Optimization Manager, you must be sure that they are for the same edition or feature set. If you try to apply an incompatible license file, Workload Optimization Manager displays an *Invalid Feature Set* error. To apply the new license you must either delete your current license so you can install the new feature set, or you must obtain a different license file that matches your current feature set.

After you install a new license, you should clear your browser cache and reload the Workload Optimization Manager user interface.

To increase your licensed workload coverage:

1. Obtain your additional license.

Note that your additional licenses must match the feature set of your current license.

2. Apply the license to your Workload Optimization Manager installation.

To upgrade your license to a higher feature set:

1. Obtain your new license for the new features.

You should obtain a license that supports at least the same number of workloads as your current license.

2. Delete your current license from Workload Optimization Manager.

On the license page, select all the licenses that you currently have installed, then click **DELETE**.

3. Apply the license to your Workload Optimization Manager installation.

Email Settings

Configure email settings to enable email communication from Workload Optimization Manager.

Navigate to the Settings Page.






Click to navigate to the Settings Page. From there, you can perform a variety of Workload Optimization Manager configuration tasks.

2. Navigate to the Email Settings Page.

From here, you can configure:

- SMTP Settings
- General Email Settings

SMTP Settings



The SMTP Settings fields identify the mail relay server you use on your network to enable email communication from Workload Optimization Manager.

If the server requires authentication, provide the username and password here. You can also choose the following encryption options for notifications:

- None
- Ssl
- TIs

General Email Settings



Use this setting to specify the return address (the FROM address) for emails that Workload Optimization Manager generates and sends.



API Reference

This guide will help you to use the Workload Optimization Manager REST API as you script interactions with the Workload Optimization Manager software and develop integrations between Workload Optimization Manager and other software applications.

The REST API exposes Workload Optimization Manager data and processing to remote access via HTTP GET, POST, PUSH, and DELETE methods.

The Workload Optimization Manager user interface is a client to this API, and every feature exposed in the user interface is the product of API calls. To understand the API, you should have a working knowledge of the Workload Optimization Manager user interface, the features it exposes, the data it uses, and the use cases that it supports. In most cases, if you want to script some Workload Optimization Manager behavior, you should be able to execute most of that behavior via the user interface. Stepping through these use cases in that context will help you plan and implement your scripts.

To get the most out of the REST API, you should understand how Workload Optimization Manager organizes its underlying data, and how the various REST resources map to that organization. This introductory section includes discussions of the data that underlies:

- Markets and how they represent your environment (see <u>Markets (on page 743)</u>)
- Plans and an overview of how to work with them (see Plans (on page 745))
- Workload placement policies and how they are represented (see Workload Placement Policies (on page 748))
- Reservations for deployment, and how to set them up (see <u>Reservations (on page 749)</u>)

NOTE:

This guide is not a comprehensive reference to every possible setting and data payload in the REST API. Many endpoint descriptions include samples of API data objects, but they cannot document every possible combination of inputs. For a complete reference to the API, use this guide in conjunction with the Workload Optimization Manager REST Swagger-UI documentation. For more information, see Workload Optimization Manager REST API Swagger Documentation (on page 742).

API Guide Revision History

A revision of the API Guide is available for each major release, if the API undergoes significant change between major releases, or to correct significant errors in the API Guide. Each revision of the API Guide includes the following changes:

- Quarterly (major) release the new revision for the major release, includes fixed issues and improvements to the API
- Bi-weekly (point) release deprecated features are removed from the API or fully implemented as outlined in the API Deprecation History

For a list of upcoming deprecations, see API Deprecation Contract (on page 35).



Version Family	Releases
3.8	3.8.0 (on page 736)
3.7	3.7.1 (on page 33) 3.7.0 (on page 737)
3.6	3.6.1 (on page 33) 3.6.0 (on page 737)
3.5	3.5.1 (on page 34) 3.5.0 (on page 737)
3.4	3.4.1 (on page 34) 3.4.0 (on page 738)

API Guide Revision History

A revision of the API Guide is available for each major release, if the API undergoes significant change between major releases, or to correct significant errors in the API Guide. Each revision of the API Guide includes the following changes:

- Quarterly (major) release the new revision for the major release, includes fixed issues and improvements to the API
- Bi-weekly (point) release deprecated features are removed from the API or fully implemented as outlined in the API Deprecation History

For a list of upcoming deprecations, see API Deprecation Contract (on page 35).

Version Family	Releases
3.8	3.8.0 (on page 736)
3.7	3.7.1 (on page 33) 3.7.0 (on page 737)
3.6	3.6.1 (on page 33) 3.6.0 (on page 737)
3.5	3.5.1 (on page 34) 3.5.0 (on page 737)
3.4	3.4.1 (on page 34) 3.4.0 (on page 738)

API Change History

Each major release of Workload Optimization Manager includes fixes issues and improvements to the API. The following list includes the changes for each major release.

NOTE:

Deprecations are implemented in point releases of Workload Optimization Manager. For example, if API features were deprecated in 8.6.3, those deprecations are linked here in the entry for 8.7.0, along with the list of all other fixes and improvements from the 8.6.x point releases. For the latest deprecation history, see API Deprecation History (on page 33).

3.8.0 API Fixes and Improvements

■ Improvement:

"The Parking APIs are now available."

Workload Optimization Manager supports parking actions for cloud resources. These actions *stop* your cloud resources for a period to help you reduce your cloud expenses, and then *start* these resources later when you need them. Use the Parking endpoint to get a list of parkable entities and execute parking actions on demand.

You can also enforce parking actions according to a schedule. In the Schedules endpoint, use /schedules/timespans/requests to configure parking schedules and attach the schedules to parkable entities. When parking schedules are attached to entities, use the Parking endpoint to pause and resume schedules as needed.

Improvement:



"The API now allows an operator field in the instanceType and newInstanceType action filters."

The API now allows an operator field in the instanceType and newInstanceType action filters. The operator can be EQ (equals) or NEQ (not equal to). If no value is set, the action filter uses EQ.

Improvement:

"The API no longer includes historical price index data in various API methods that return entity statistics."

The API no longer includes historical price index data in various API methods that return entity statistics. Price index is still available for the most recent real-time projected data, and in responses for plan-related requests.

This specifically refers to the StatSnapshotApiDTO structure when epoch is set to CURRENT or HISTORICAL.

3.7.0 API Fixes and Improvements

Improvement:

"API users can now search for entities by their tag as follows: GET /tags/entities? key=<tagKey>."

API users can now search for entities by their tag by calling GET /tags/entities?key=<tagKey>, which includes entities with a slash (/) within a tag string.

NOTE

The existing API call GET /tags/<tagKey>/entites will be permanently deleted in a future release. Until its removal, you can use both of these methods.

Improvement:

"API users can now filter and sort targets."

API users can now filter and sort the list of targets to restrict their view to only their relevant targets.

The following parameters were added to the list of targets request:

- target type (AWS, AWS_BILLING, ACTIONSCRIPT, ACTIONSTREAM_KAFKA, APPDYNAMICS, APPINSIGHTS, AZURE_BILLING, AZURE_EA, AZURE_SERVICE_PRINCIPAL, CISCO_HYPERFLEX, CISCO_UCS_MANAGER, DATADOG, DYNATRACE, EMC_SCALEIO, EMC_VMAX, FLEXERA, GCP_BILLING, GCP_SERVICE_ACCOUNT, HP_ONEVIEW, HPE_3PAR, HYPER_V, INSTANA, JBOSS, JVM, KUBERNETES, MYSQL, NETAPP, NEWRELIC, NUTANIX, ORACLE, PURE, SNMP, SQLSERVER, SERVICENOW, TOMCAT, VMM, VMWARE_HORIZON, WMI, WEBLOGIC, WEBSPHERE, VCENTER)
- validation status (FAILED, IN PROGRESS, SUCCESS)
- health state (CRITICAL, MAJOR, MINOR, NORMAL)

The following parameters for sorting the list of targets were added: target type and health state.

■ Fixed Issue:

"Kubeturbo is using a deprecated API for the APIRequestCount query."

Kubeturbo is using a deprecated API for the APIRequestCount query.

3.6.0 API Fixes and Improvements

Fixed Issue:

"For API developers, when executing requests on the Search endpoint, the API does not paginate the returned result."

For API developers, when executing requests on the Search endpoint, the API does not paginate the returned result.

3.5.0 API Fixes and Improvements

Improvement:



"The API now supports reservations with cluster affinity."

When creating reservations, you can now specify affinity rules for the reserved VMs. You can ensure all the VMs in a reservation deploy to the same cluster. If you do not specify affinity, the VMs deploy to any clusters in the scope. This is the same as earlier behavior for reservations.

For more information, see Affinity Rules (on page 889).

Improvement:

"The /supplychains/leafEntities endpoint is now available."

This release introduces the /supplychains/leafEntities endpoint that you can use to define your own supply chain topology. This endpoint returns a list of 'leaf entities' related to a 'seed entity'.

For more information, see Getting Leaf Entities from a Supply Chain Root (on page 995).

Fixed Issue:

"The maximum entries returned for GET and POST methods is 500."

Starting with Workload Optimization Manager version 3.4.1, GET and POST methods return a maximum of 500 entries when run on ServiceEntities, Groups, or BusinessAccount endpoints. You should always check for pagination in your results.

3.4.0 API Fixes and Improvements

Improvement:

"The API now includes the Plan Destinations endpoint."

A plan destination is an external resource where plan results can be uploaded. Currently, you can upload the results of a 'Migrate to Cloud' plan to the Azure Migrate portal. Use the Plan Destinations endpoint to get plan destinations and run uploads.

Improvement:

"When deleting a reservation, you can now specify whether to permanently delete that reservation."

The API now includes the new reservation_force_delete parameter that you can pass along with a DELETE call to a specific reservation. When reservation_force_delete = true, the system removes the reservation permanently, no matter what state it is in. Before this release, a reservation that you deleted via the API or user interface continued to display for deletion, and was only permanently deleted after 48 hours.

Improvement:

"The API includes a new LABEL commodity type."

The commodityType enum includes a new LABEL commodity type.

Improvement:

"For API developers, when a reservation you create fails, the returned DTO includes more data about the failure."

When you create a reservation, and the reservation fails, the API returns a DTO to explain the cause of the failure. This DTO includes new fields:

- timespan: Indicates whether the reservation calculation was based on realtime or historical resource utilization data.
 Can be one of:
 - Current: The calculations were based on realtime utilization data
 - Historical: The calculations were based on historical utilization
- cluster: The name of the cluster that came the closest to being able to provide the resources that the reservation needed.
- hrefCluster: A link to stats for the closest-seller cluster.
- hrefEntity: A link to stats for the closest-seller entity that is a member of the closest-seller cluster.



For example, the DTO can include data similar to the following for a placement failure:

```
"placements": {
    "failureInfos": [
            "resource": "StorageAmount",
            "timespan": "Historical",
            "closestSeller": {
                "uuid": "74167780552264",
                "displayName": "QSGRID01:DC6DS2",
                "className": "Storage",
                "cluster": "StorageCluster-A",
                "hrefEntity": "/reservations/stats/74167780552264",
                "hrefCluster": "/reservations/stats/74167780552265"
            },
            "maxQuantityAvailable": 248294.59024047852,
            "quantityRequested": 273184.5625,
            "units": "MB"
        }
   ]
}
```

■ Improvement:

"Handling of non-executable actions has been improved."

This release improves the handling of actions that are currently not executable due to prerequisite actions.

For example, in order to suspend Host A, VM_01 in the host must first move to Host B. However, Host B only has capacity for one VM and is currently hosting VM_02. In this case, Host A suspension is blocked by two prerequisite actions – VM_02 moving to another host and VM_01 moving to Host B.

The Action Details page for the main action (Host A suspension in the example) now shows the following information:

"Blocked by actions on target or destination that need to be executed first."

For earlier releases, the Action Details page indicated that the action is blocked by a policy.

For API developers, the ActionApiDTO now shows this state. Workload Optimization Manager sets the BLOCKED_BY key of the relatedActionsCountByType parameter to 0, which indicates that an action is currently not executable due to prerequisite actions.

When all the prerequisite actions have been executed, the main action becomes executable.

■ Improvement:

"When you examine a failed reservation via the API, the data now returns a reason for the failure."

After you create a reservation, you can GET the reservations endpoint for data about the current reservations in your environment. The resulting data includes a status. If the status is PLACEMENT_FAILED, Workload Optimization Manager could not place all the workloads in the reservation for some reason. Starting with version 3.3.4, the placements field in the data includes invalidInfo to give a reason for the placement failure. The reason can be:

- MARKET_CONNECTIVITY_ERROR: The reservation process could not connect to the Market component for some reason.
- MARKET_NOT_READY: The market does not have data from the Headroom plans for the given reservation scope.
- INVALID_CONSTRAINTS: The reservation policies include conflicting or invalid constraints.

For example, the data for a single reservation might include the following data:



Getting Started with the Workload Optimization Manager REST API

The easiest way to see results with the API is to try calls in the Swagger UI. To use the Swagger UI, navigate to:

https://<Your Workload Optimization Manager IP>/swagger/external/index.html

You can use the Swagger UI to navigate to different endpoints and try out their methods. For example, if you navigate to the Users endpoint you can get a listing of all the users that are specified for your Workload Optimization Manager installation. For more information, see <u>Workload Optimization Manager REST API Swagger Documentation (on page 742)</u>.

Ultimately, you will want to implement scripts that use the API to get data, execute actions, or integrate Workload Optimization Manager with other processes. As you work with the API, you need to know about:

- Authentication
- URI Structure
- Response Format
- Time in the Workload Optimization Manager API

Authentication

To use the API, you must have a valid user account on the Workload Optimization Manager instance. Also note that accounts can have different roles. The API will only execute commands that are valid for your user role. For example, to execute Workload Optimization Manager recommended actions, your account must have a role of either administrator, deployer, or automator

To make API calls, you request an authentication token and pass it with each call to the Workload Optimization Manager API. The token request returns a cookie for your authentication. A common way to use this token is to store the cookie locally, and pass it with your API calls.

Example: curl -s -k -c /tmp/cookies -H 'accept: application/json' 'https://localhost/api/ v3/login?hateoas=true' -d 'username=administrator&password=password'

Then, each request must use the -b cookie-filename parameter to use the session cookie delivered by the login request.

Another approach is to get the authentication header and parse out the authentication cookie. Then you can create a header for each API request that includes the cookie. For example, assume you store the value in a variable named token. You could use it like this:

```
headers = {'cookie': token}
r = requests.get('https://10.10.123.456/api/v3/targets/specs', headers=headers, verify=False, stream=True)
```

NOTE: For a more complete explanation, see the <u>Authentication Recipe (on page 1026)</u> in the API Cookbook.



URI Structure

To use the Workload Optimization Manager REST API, your client will make HTTP requests to specific REST resources. The Workload Optimization Manager REST API supports the standard HTTP methods:

■ GET

Get lists of entities or data objects, get individual items.

■ POST

Create new objects in the Workload Optimization Manager environment, or specify filters for certain queries.

■ PUT

Incrementally modify existing entities or objects.

■ DELETE

Delete entities or objects.

The base URI structure for a Workload Optimization Manager REST API resource is:

```
https://<Your_Workload Optimization Manager_IP>/api/<API_version>/<resource_name>
```

For example, to list the users in your installation:

```
https://111.222.33.44/api/v3/users
```

Response Format

The Workload Optimization Manager REST API returns data as JSON objects. Workload Optimization Manager refers to these objects as Data Transfer Objetcs or DTOs. A DTO is an array of key-value pairs that describe the data you have requested, or the data that is the result of executing a POST or PUT. For example, if you GET the users defined for an installation of Workload Optimization Manager, the API returns a DTO similar to this:

In this case, the DTO is an array of one object. In other words, there is only one user accout defined for this installation of Workload Optimization Manager. The user object begins with a links array that gives the URL to this user account. It then follows with properties to describe the given user account.



Note that in most cases to execute a PUT or POST, you will pass the parameters to create the object via a DTO. These DTOs are similar to the associated response DTOs, but they are not identical. For this example of a user account, the response DTO does not include the user account password, but the DTO to create an account must include the password.

You can try out different REST methods in the Swagger UI to see typical response DTOs.

Time in the Workload Optimization Manager API

The Workload Optimization Manager REST API contains requests that require a start time and/or an end time to create or filter information. Time may be entered in three different formats:

■ ISO 8601 Date and Time Format

```
YYYY-MM-DDTHH: MM: SS. For example, 2018-10-07T12:38:17
```

Epoch Time

Epoch Time is represented as the number of seconds that have elapsed since midnight UTC, January 1, 1970. For example, 1514764800 corresponds to January 1, 2018 12:00:00 AM UTC.

Relative time

Relative time is represented as the time relative to when the call is executed. For example, a start time of -1w and an end time of -1d indicates that the results should include entries from a week before the call is executed, to the day before the call is executed. Relative units are case-sensitive. Workload Optimization Manager supports the following relative units:

- m minutes
- h hours
- d days
- w weeks
- M months
- y years

Pagination in the Workload Optimization Manager API

Some API calls return very large datasets. Workload Optimization Manager recommends using the pagination features at all times. This is particularly important for larger environments managed by Workload Optimization Manager. Via scopes and filters for individual requests, data may be preliminarily filtered. Using the limit and x-next-cursor parameters, the data can be returned in manageable chunks.

For example:

https://10.10.10.10/api/v3/markets/214075923753936/entities/stats?limit=5&ascending=true

The request above is to obtain statistics for all entities in a specific market. limit=5 indicates that each page of returned data should have 5 results.

The headers in the returned data will now include x-next-cursor: 5. In order to retrieve the next page of results, use the cursor in the next request:

```
https://10.10.10.10/api/v3/markets/214075923753936/entities/stats?cursor=5&limit=5&ascending=true
```

When the final page is reached, the x-next-cursor will be empty.

If a request features the orderBy, limit, or cursor parameters, using one of those parameters will return paginated results.

Workload Optimization Manager REST API Swagger Documentation

You can try out different REST methods in the Swagger documentation to see typical response DTOs.

To access the Workload Optimization Manager Swagger documentation, navigate to:

https://<Your_Workload Optimization Manager_IP>/swagger/external/index.html



This documentation uses a standard Swagger-Ul application that delivers documentation for all the methods on the different endpoints in the API. This documentation includes a description of the call, a list of parameters to pass, and descriptions of the JSON payloads you POST or PUSH, as well as the payloads you get in the response. If you view the MODEL of a JSON payload, you can navigate the JSON structure to see descriptions of the different object fields.

To access the API, the Swagger-UI requires authentication. If you have already logged into Workload Optimization Manager, your browser session should have a current authentication cookie. The Swagger-UI uses this same cookie for its API authentication.

For each method, the Swagger doc includes a **Try it out** feature where you can set up a call through the Swagger-UI, and then execute it. This generates the following information as a response:

A curl request for your call

The curl commands generated by Swagger may need some modification for use in your environment (for example, escaping quotes or adding the -k modifier in order to use HTTP URLs).

- A standard HTTP request for your call
- The server response code
- The response body The JSON data that the API call returns
- Response headers

NOTE: If you use the SwaggerUI to try out API calls, and the API call returns an error (for example, your call uses incorrect syntax), under some circumstances SwaggerUI does not display the error, and the field for the returned data is empty.

Workload Optimization Manager Markets

Workload Optimization Manager uses market-based analysis to perform workload management. To do this, it constructs a model of your environment, representing each entity as a buyer and seller in a market. You can access this model via a named market resource.

At any time, your Workload Optimization Manager appliance can have a number of markets in memory. To get a list of the current markets in your appliance, execute the following URL:

GET: /rest/markets

This listing returns the main real-time market, plus any plan markets that are in memory at the time of the call. Note that you can pass group UUIDs to set a scope for the call. In that case, the call returns only markets for plans that include the passed groups in their scope.

The Real-Time Market

The real-time market performs analysis and workload management on your environment. You can use the real-time market to access entities and get current or historical data about them.

The real-time market displayName is Market. This market should always be in the RUNNING state. Under no circumstances should you use the API to stop this market.

Workload Optimization Manager performs discovery to populate the topology it manages (the collection of entities in the real-time market). For this reason, you should be careful not to delete entities from or add entities to the real-time market.

For the real-time market, you can safely execute POST, PUT, and DELETE calls to:

- Post a query filter to get filtered lists of actions, notifications, and stats for the real-time market
- Post to create placement policies in the real-time market
- Delete to remove placement policies from the real-time market
- Put to edit placement policies on the real-time market
- Post a scenario to the real-time market to run a plan

When you run a plan scenario against the real-time market, Workload Optimization Manager creates a copy of the real-time market, and modifies the copy according to the plan scenario.



NOTE:

It is possible to execute POST or DELETE methods to modify the topology of the real-time market. However, it is highly unlikely that you would have a reason to do so. You should be aware that changes to the real-time market will affect the analysis Workload Optimization Manager performs. For example, if you remove a VM from the real-time market, Workload Optimization Manager can no longer manage its placement. The VM will still be present in your environment, but it will no longer be managed by Workload Optimization Manager. However, you can't reliably use this technique to make specific entities unavailable to Workload Optimization Manager. For the next discovery pass, Workload Optimization Manager will rediscover the deleted entity, and it will appear in the real-time market again.

Plan Markets

Workload Optimization Manager can have markets other than the real-time market in memory. These other markets represent plans.

A plan market begins as a snapshot of the real-time market. You POST a scenario to the real-time market, and Workload Optimization Manager does two things:

- It makes a copy of the real-time market, to create a plan market. This plan market is just like the real-time market, except for any changes that were declared in the scenario. For example, if the scenario declares a scope for the plan, then the plan market only contains entities that are within that scope.
- It runs economic cycles (buy/sell cycles) against this plan market until there are no more meaningful improvements to be made. At this point the plan run is completed.

Note that once Workload Optimization Manager creates the plan market, that market stays in memory until you delete it. Also note that you can later apply a scenario to the plan market. This is how you run a plan on a plan. The logic flow is the same, and Workload Optimization Manager creates yet another plan market to run the analysis.

Internal-Use Plans

Workload Optimization Manager regularly runs plans to generate data that it displays in the GUI – The Cluster Capacity and Project Cluster Resources dashboards both display data generated by regularly-run plans.

A plan market that is for internal use includes the substring <code>_BasePlan</code> in the displayName. You should not modify these plan markets for any reason.

User-Created Plans

Users can create plans to run what-if scenarios in the environment, and the results are saved as a plan matket. At any time, each user account can have multiple plan markets loaded in the Workload Optimization Manager instance.

You identify planner markets by their names. A plan name is specified as <PlanType><userName> <arbitraryID>.

For example, a valid plan name is CLOUD_MIGRATION_cud_1493140514716. To find out which user owns this plan, you can parse out the user's name and query the API for that user's account information.

When you get a plan market, the response includes information such as:

- uuid: The market's identifier.
- state: Whether the plan succeeded or not. The state can be one of:
 - CREATED
 - READY_TO_START
 - RUNNING
 - COPYING
 - SUCCEEDED
 - STOPPING
 - STOPPED
 - USER_STOPPED
 - DELETING



As long as a plan market is running, Workload Optimization Manager is still calculating the plan results. If the market is stopped, then the plan has been run and you can access data from this market to see the plan results. You can make a PUT call to the market to stop a plan that is running.

For a plan market, you can execute the same POST, PUT, and DELETE methods that you would execute on the real-time market. These include:

- POST a query filter to get filtered lists of actions, notifications, and stats for the plan market
- POST to create placement policies in the plan market
- DELETE to remove placement policies from the plan market
- PUT to edit placement policies on the plan market
- POST a scenario to the plan market to run a plan on plan

You can also safely execute the following methods on a plan market:

- DELETE a plan market
- PUT to save or stop a plan market

NOTE:

It's possible to stop a plan market through the GUI or the API. Also, a plan may have been stopped before it finished its calculations. In this case, the plan results will be incomplete.

Running Plans

A plan is a simulation or what-if scenario that explores the results of possible changes to your environment. To run a plan, Workload Optimization Manager creates a snapshot copy of your real-time market and applies changes to it. It then uses the Economic Scheduling Engine to perform analysis on that plan market.

Before working with plans in the API, you should be familiar with plans via the GUI. You should know what plans can accomplish, and how to specify the plan settings such as:

- Plan scope
- Changes to workland in the environment (adding or removing VMs)
- Changes to supply (adding, removing, or reconfiguring hardware)
- Changes to placement (migrating to the cloud or a different cluster)
- Changes to constraints

To create a plan, you first specify a plan scenario. This is an object that contains all the plan settings. The scenario object contains an array of changes, and each change declares a setting that you want to make.

After you create a scenario, you POST it to a market. In most cases you will post it to the real-time market. When you post the scenario to the market, Workload Optimization Manager does two things:

- It makes a copy of the market, to create a plan market. This plan market is just like the original market, except for any changes that were declared in the scenario. For example, if the scenario declares a scope for the plan, then the plan market only contains entities that are within that scope.
- It runs economic cycles (buy/sell cycles) against this plan market until there are no more meaningful improvements to be made. At this point the plan run is completed.

Saving and Deleting Plan Markets

As you run a plan, Workload Optimization Manager performs analysis and shows the results. It also serializes and saves the plan results so users can load the results into the GUI at a later time.

NOTE:

Updates to Workload Optimization Manager can change the data format for the saved plan results. In that event, then the results will be inconsistent. After each update to Workload Optimization Manager, you should regenerate all the plans you want to save, and save them again.

To delete a plan via the API, just execute a DELETE method on the plan market.



Creating Scenarios

The first step for a plan is to create the scenario. Note that a scenario is entirely separate from the plan. You create a scenario and then POST it to a market to create the plan. But the scenario still exists in memory, and you can apply it to a different market if you wish. For example, you can apply the same scenario to the real-time market at different times.

To create a scenario, use the POST: /rest/scenarios/{name} method. This method takes three parameters:

scope

An array of group UUIDs. For a scope of multiple groups, you must specify groups of the same type.

■ projection days

For a projection scenario, the days to mark each projection period

input

A ScenarioApilnputDTO that can specify all the settings for a scenario.

The input parameter, a ScenarioApilnputDTO, is an object that you can POST to the API to specify scenario settings. The API includes methods to create and delete scenarios. In most cases, you will create a scenario by POSTing or PUTing a ScenarioApilnputDTO with changes to declare the scenario settings you want. Note that the API includes methods you can use to PUT many of these settings into a specific scenario by passing properties directly in the URL. However, you can also make these settings with the ScenarioApilnputDTO. Learning to use this DTO is the most consistent way to create and modify a scenario.

Note that as you create a scenario you can POST all of its settings in the ScenarioApilnputDTO, or you can create an incomplete scenario, and then PUT other changes into the scenario at a different time.

Creating a Projection Scenario

Projection plans calculate infrastructure requirements into the future, so your environment can accommodate changes to workload requirements over time. In a single plan you can specify the scope of the plan, how far into the future to project, and by what increments of time. For example, you can project the requirements of a specific datacenter one year into the future, showing how requirements change at one-month intervals.

When you create a projection scenario via the API, you provide the projection periods as an array of the days from today that you want to project. For example, 0 for today, 30 for 30 days from today, 60 for 60 days from today, and so on.

To create a scenario for a projection plan:

Scope the scenario

A projection plan requires a scope to the scenario.

■ Create a change in the plan of type PROJECTION_PERIODS

This change identifes the plan periods that you want, as an array of days.

```
{
    "changes":[
    {
        "type":"PROJECTION_PERIODS",
        "projectionDays":[0,30,60,90]
    }
]
```

For any plan changes that you want to repeat on specific projection periods, specify a projectionDays array for that change. Note that the items in this array must match the projectionDays that you specified for the PROJECTION PERIODS change.

For example, assume you specified "projectionDays": [0,30,60,90] for the initial projection:

```
- Valid: "projectionDays": [0,30,60,90]
```

- Valid: "projectionDays":[30,90]
- Not valid: "projectionDays": [0,35,70,90]

This listing shows a plan scenario that scopes the plan market, sets up a projection for four periods, and adds one VM to the inventory for two out of four projection periods:



```
"displayName": "My Projection",
  "changes": [
      "type": "SCOPE",
      "scope": [
        {
          "uuid": "5678a46e9716657be88b5e1217df91436e13e4ff",
          "className": "Group",
          "entitiesCount": 2,
           "groupType": "VirtualMachine",
      ]
    },
      "type": "PROJECTION_PERIODS",
      "projectionDays": [
        Ο,
        30,
        60,
        90
      ]
    },
      "type": "ADDED",
      "targets": [
           "uuid": "564d89f4-190b-de1b-cb28-3e2f2126ab48"
      ],
      "value": "1",
      "projectionDays": [
        30
      ]
    }
}
```

Placement Policies in Plans

You can enable or disable placement policies in a plan. This is useful to see how the environment would change if you had a different set of constraints. It's important to note that a placement policy exists in the context of a market. To get a placement policy, query the market that contains it. To create a placement policy for a plan, you will create the poolicy and add it to the plan market.

If you want to enable or disable a placement policy in a plan, you specify that as a change in the scenario. Because the placement policy exists in a market, you have to know which market you will run the plan against, and get the policy from that market.

For example, if you will run the plan against the real-time market, you would:

- Query the real-time market for the policy you want
- Give that policy's UUID in the scenario change object
- In the scenario change object Specify to enable or disable the policy
- When the scenario is complete, POST the scenario to the real-time market



Remember that when you run a plan, Workload Optimization Manager creates a new plan market. This plan market will contain a copy of the placement policy, and will enable or disable it, depending on your setting.

Workload Placement Policies

Workload Placement Policies affect how Workload Optimization Manager calculates placement for the workloads in your environment. Policies can enforce specific business rules to constrain placement, and they can remove boundaries to enable placement calculations across cluster or datacenter boundaries.

A placement policy exists in the context of a market — Either the real-time market or a plan market. Each market has its own set of placement policies. Even if a plan market is an exact copy of the real-time market, the plan market has its own placement policies, each with its own UUID.

Before you work with placement policies via the API, you should understand how they work in the user interface. You should understand the types of placement policies you can create, and the effect of each on market analysis.

The API supports the following types of policies:

- AT_MOST_N: Only the given number of consumers can run on a single member of the providers group. This is set in the capacity property of the policy object.
- BIND_TO_GROUP: The consumers can only run on members of the provider group.
- BIND_TO_COMPLEMENTARY_GROUP: The consumers cannot run on any members of the provider group.
- MUST_RUN_TOGETHER: These consumers must run on the same provider entity.
- AT_MOST_N_BOUND: Only the given number of consumers can run on a single member of the providers group, AND The consumers can only run on members of the provider group.
- MERGE: Remove cluster boundaries for the specified clusters.
- BIND TO GROUP AND LICENSE: Create a license group.

When you get a policy, the returned object describes the policy type, as well as the consumer and provider groups. When you create a policy, you do not have to provide the full data. You provide:

- buyerUuid: The group of consumers for this policy.
- sellerUuid: The provider group for this policy.
- type: The policy type.
- policyName: A display name for this policy.
- enabled: Whether to enable the policy inthe market. Can be true or false.
- capacity: For an AT_MOST_N or AT_MOST_N_BOUND policy, the number of consumers to allow on a provider entity.
- mergeType: For a MERGE policy, the type of clusters to merge. Can be one of Cluster, StorageCluster, DesktopPools, or DataCenter.
- mergeUuids: The groups that you want to merge. The group type must match the "mergeType.

For example, to create a DON'T PLACE policy, post the following inputDto to the market:

```
{
  "buyerUuid": "f82dbbc2b3366052f3bc1ac8a68c9c06b0eb182a",
  "enabled": false,
  "policyName": "PolicyFromApi",
  "sellerUuid": "4a2f5f132ae690af147ccfd6ea9839e79da3db79",
  "type": "BIND_TO_COMPLEMENTARY_GROUP"
}
```

To edit a placement policy, PUT an input Dto to the given policy. Specify the changes you want in the input Dto.



Calculating Reservations and Workload Placement

Workload Optimization Manager includes the capability to reserve resources for VMs you plan to deploy in the future. Workload Optimization Manager calculates optimal placement for these VMs and then reserves the host and storage resources that they need.

To reserve VMs, you will choose a VM template, specify any placement constraints, set how many instances to reserve, and then indicate whether to reserve now or in the future. Because reserved VMs do not yet exist, they do not participate in the real-time market. VM templates specify the resource requirements for each reserved VM, including:

- Compute and storage resources allocated to each VM
- Consumed factor. This is the percentage of allocated CPU, memory, or storage that the reserved VM will utilize.

Note that before using the API to work with reservations, you should understand how reservations work from the user interface.

With the API, you can perform the following:

- Get list of reservations
- See the current placement for the reservation workloads
- Create reservations
- Delete a current reservation

Getting Reservation Information

To get a list of current reservations, execute /rest/reservations. This returns a list of all active reservations. If you know the UUID of the reservation you want, you can pass it to get data for just that reservation.

Each reservation object includes:

- Display name
- Status can be:
 - DEPLOYING Workload Optimization Manager is deploying the workload
 - DEPLOY_SUCCEEDED The workload was successfully deployed
 - IN PROGRESS Placement calculation is in progress
 - PLACEMENT_SUCCEEDED For a new reservation, the environment has sufficient resources to place the workload; if
 you specified a reserve date, this will be an active reservation
 - PLACEMENT_FAILED For a newly created reservation, the environment doesn't have resources to place the workload; if you specified a reserve date, this will be an unfulfilled reservation
 - RETRYING Workload Optimization Manager is trying to place the workload of an unfulfilled reservation
- Time the reservation was created, time to deploy, and time it will expire
- A description of the reserved workload
- The deployment profile that identifies the physical files that will be copied to deploy the workload, as well as optional placement limitations.
- Statistics for the compute and storage resources the reservation sets aside

For example, this listing shows a reservation for one VM:

```
{
  "uuid": "_kWZHIDDmEeePgeXuo0RRbw",
  "displayName": "MyReservation",
  "count": 1,
  "status": "PLACEMENT_SUCCEEDED",
  "reserveDateTime": "Thu May 04 16:27:29 UTC 2017",
  "expireDateTime": "Thu Aug 31 16:27:29 UTC 2017",
  "deployDateTime": "Thu Aug 31 16:27:29 UTC 2017",
  "reserveCount": 1,
```



```
"demandEntities": [
  {
    "uuid": "_kWgb7TDmEeePgeXuo0RRbw",
    "displayName": "MyReservation_C0",
    "className": "VirtualMachine",
    "template": {
      "uuid": "T423f548d-cadc-e525-6df4-1f90724cf696",
      "displayName": "vsphere-dc3.dev.mycorp.com::TMP-SUSE64",
      "className": "VirtualMachineProfile"
   },
    "deploymentProfile": {
      "uuid": "_gHJ0ICXxEeePgeXuo0RRbw",
      "displayName": "DEP-SUSE64",
      "className": "ServiceCatalogItem"
   },
    "placements": {
      "computeResources": [
          "stats": [
            {
              "name": "numOfCpu",
              "value": 1
            },
              "name": "cpuSpeed",
              "value": 2603
            },
              "name": "cpuConsumedFactor",
              "value": 0.5
            },
              "name": "memorySize",
              "value": 2097152
            },
              "name": "memoryConsumedFactor",
              "value": 0.75
            },
              "name": "ioThroughput",
              "value": 0
            },
              "name": "networkThroughput",
              "value": 0
            }
          ],
          "provider": {
            "uuid": "Virtual_ESX_42381da5-12fa-1e82-2f1c-887419380d43",
            "displayName": "hp-esx21.corp.vmturbo.com",
            "className": "PhysicalMachine"
          }
        }
```



```
],
      "storageResources": [
        {
           "stats": [
             {
               "name": "diskSize",
               "value": 18432.363
               "name": "diskIops",
               "value": 0
            }
          ],
           "provider": {
             "uuid": "10545c15-7687ef26",
             "displayName": "QS2:ESXDC3DS1",
             "className": "Storage"
        }
      ]
    }
  }
]
```

Creating a Reservation

To create a reservation, you POST an input DTO that defines the reservation's:

- action: The action type: RESERVATION
- demandName: The display name of the reservation If you do not specify names for the added workloads, this will be the root name for new VMs
- placementParameters:
 - constraintIDs: An array of UUIDs for placement policies that will affect the calculated placement
 - count: The number of workloads to place
 - entityNames: An array of names for the placed VMs The array length should equal count
 - geographicRedundancy: If true place the workloads on unique hosts, otherwise Workload Optimization Manager can place multiple workloads on the same host
 - templateID: The UUID of the template that you will use to place this workload Note that the template must include
 a reference to the deployment profile that you specify in deploymantParameters
- expireDateTime: When to cancel a reservation if Workload Optimization Manager cannot place all the workloads by that date – for a RESERVATION action, Workload Optimization Manager automatically sets the deploy time to equal this time
- reserveDateTime: The time to calculate the workload placement and create the reservation This time cannot be earlier than the time that you POST the reservation to the API

The following listing shows an input DTO that creates a reservation. It will place four workloads, and it gives specific names ot each one.



```
},
    "placementParameters": {
        "geographicRedundancy": false,
        "count": 4,
        "entityNames": [
             "foo", "bar", "baz", "bonk"
        ],
        "templateID": "_UKsnkJkSEeCHcOXEhzJExA"
        }
    }
}

reserveDateTime": "2017-05-04T18:22:12+00:00"
```

Async Placement Calculation

When you POST a reservation, Workload Optimization Manager runs a plan to calculate the optimal placement of the workloads. Depending on the size of the reservation, this can take a significant amount of time. The API calculates the placement asynchronously. If your script relies on the reservation, you should verify that the reservation has completed before moving on.

When you execute a reservation, the response to your POST shows that the calculation is in progress:

```
{
   "uuid": "_0dPrYTDlEeePgeXuo0RRbw",
   "displayName": "MyReservation",
   "count": 4,
   "status": "IN_PROGRESS",
   "reserveDateTime": "Thu May 04 18:22:12 UTC 2017",
   "expireDateTime": "Tue Oct 10 12:38:17 UTC 2017"
}
```

To examine the placement results, GET the reservation using the UUID that the API gives in the response.

Using Templates

To create a reservation you specify a template that contains workload requirements. VM Templates specify the resources that will be available to the VM, including:

- VCPUs
- Virtual Memory
- Storage
- Network Throughput
- IOPS
- IO Throughput

Note that templates can be created by users, and Workload Optimization Manager also discovers templates that are created by the management services in your environment. For example, a hypervisor or a cloud service provider typically manages a number of its own templates — Workload Optimization Manager discovers these. You should never edit a discovered template.

To see whether a template is discovered, GET the template you're interested in and look for the discovered property. This will be true or false.



Workload Optimization Manager REST API Endpoints

The REST API resources give you full access to the Workload Optimization Manager software. This is a complete API that exposes the full set of Workload Optimization Manager capabilities. In fact, the product user interface is implemented as a Workload Optimization Manager client that uses this API.

While the REST API resources are documented in the SwaggerUI, this section provides extra details for the more expressive resources in the API.

To access the Workload Optimization Manager REST SwaggerUI, open a web browser to:

https://<Your_Workload Optimization Manager_IP>/swagger/external/index.html

Utility Requests

Actions Endpoint

Instead of responding to thresholds, Workload Optimization Manager analyzes the operating conditions and constantly recommends actions to keep the entire environment within the desired state. If you execute these actions (or let Workload Optimization Manager execute them for you), the environment will maintain operating conditions that assure performance while also ensuring the lowest possible cost thanks to efficient utilization of your resources.

Using the actions endpoint, you can:

- Get a complete or filtered list of actions in your environment
- Accept or reject actions
- Get statistics related to a specified action
- Get notifications related to a specified action

Actions Utility Requests

Utility requests provide metadata that you can use to make related requests, assemble inputDTOs, or see the potential values of a particular DTO.

Getting the Valid actionMode parameters for a Specified Entity and Action

The actions endpoint contains a utility request that shows the possible values for the actionMode parameter for a specified entity and action type. These can be used to set or understand the possibilities for various action settings.

To specify an entity/action type, this request takes the following parameters:

- action_type
 - START:
 - Start an entity, and add it to the Workload Optimization Manager market.
 - MOVE
 - Move an entity from one provider to another. For example, moving a VM between hosts, or a datastore between disk arrays.
 - SUSPEND:



Suspend the entity to exclude its capacity from your environment. Suspend does not remove the entity from your environment, but the market does not include the entity in its analysis. Based on market conditions, analysis can recommend restarting suspended entities, which includes them in market analysis once again.

- ADD PROVIDER:

This is equivalent to the START action, but for storage entities.

CHANGE:

Move a virtual machine's storage between datastores.

- PROVISION:

Add capacity to your environment.

RECONFIGURE:

Analysis recommends this when a VM is not able to correct a misconfiguration via another type of action. For example, analysis can recommend a RECONFIGURE action when a placement policy requires a VM to move to a host on a particular cluster, but cross-cluster moves are not permitted.

- DELETE:

This is equivalent to the SUSPEND action, but for storage entities.

RESERVE_ON_PM:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular host.

RESERVE ON DS:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular datastore.

- RESIZE_FOR_EFFICIENCY:

A resize that reduces the capacity of a commodity, such as vCPU, or vMEM.

- RESIZE_FOR_PERFORMANCE:

A resize that increases the capacity of a commodity, such as vCPU, or vMEM.

entity_type

- APPLICATION
- APPLICATION_SERVER
- BUSINESS_ACCOUNT
- BUSINESS UNIT
- CHASSIS
- CLOUD_SERVICE
- CONTAINER
- CONTAINER POD
- DATABASE
- DATABASE_SERVER
- DATACENTER
- DISK ARRAY
- DPOD
- IO_MODULE
- LOAD_BALANCER
- LOGICAL_POOL
- NETWORK
- PHYSICAL_MACHINE
- STORAGE
- STORAGE_CONTROLLER
- SWITCH
- VIRTUAL_APPLICATION
- VIRTUAL_DATACENTER
- VIRTUAL_MACHINE



- VPOD

Example: GET https://10.10.10.10/api/v3/actions/availablemodes? action_type=PROVISION&entity_type=PhysicalMachine

Response: An array of strings, where each string is a valid actionMode for the combination provided. In this example, a PROVISION action and the PhysicalMachine entity. An empty response body indicates that the requested entity does not have an action of that type, usually for practical reasons. For example, the Network entity cannot have a MOVE action.

```
[
  "RECOMMEND",
  "DISABLED",
  "MANUAL",
  "AUTOMATIC"]
```

Getting a List of Entry Points for Actions

The actions endpoint contains a utility request that shows the entry points for other action-related requests. These can be used to find the UUID and details relating to a specific action.

Example: GET https://10.10.10.10/api/v3/actions

Response: An array of LinkApiDTO objects, where each object contains a URL to get all actions for a specified market, entity, or group.

```
{
  "links":[
      {
          "rel":"Market actions",
          "href":"https://10.10.10.10/api/v3/markets/{uuid}/actions?ascending=true"
      },
      {
          "rel":"Entity actions",
          "href":"https://10.10.10.10/api/v3/entities/{uuid}/actions?ascending=false"
      },
      {
          "rel":"Group actions",
          "href":"https://10.10.10.10/api/v3/groups/{uuid}/actions?ascending=true"
      }
    ]
}
```

Actions Requests

Action requests handle acceptance, rejection, filtering, and exploration of actions on your Workload Optimization Manager appliance.

If one or more of the entities in the scope of your request no longer exists in the topology, the ActionApiDTO for such entities will contain minimal information about the entities.

Getting a Specified Action

Gets the action details, including the creation time and target entity information, for a specified action UUID.



Example: GET https://10.10.10.10/api/v3/actions/_6QsKkaNWEeiYWYj--U8W5g/details **Response:** The full ActionApiDTO for the requested action:

```
"links":[
    {
      "rel": "self",
      "href": "https://10.10.10.10/api/v3/actions/_6QsKkaNWEeiYWYj--U8W5g"
    },
      "rel": "self",
      "href": "https://10.10.10.10/api/v3/actions/2218532354592"
  ],
  "uuid": "_6QsKkaNWEeiYWYj--U8W5g",
  "createTime":"2018-08-19T07:40:57-04:00",
  "actionType": "MOVE",
  "actionState": "PENDING_ACCEPT",
  "actionMode": "MANUAL",
  "details": "Move VirtualMachine Jboss-EAP-10.203 from dc17-host-01.mycorp.com to dc17-host-02.mycor
p.com",
  "importance":7.4150376,
  "target":{
    "uuid": "421d8db4-3fc6-440b-0575-11383c020c6c",
    "displayName": "Jboss-EAP-10.203",
    "className": "VirtualMachine",
    "aspects":{
      "virtualMachineAspect":{
        "os": "CentOS 4/5/6/7 (64-bit)",
         "connectedNetworks":[
            "uuid": "34f9f5364cd843aa1fe99900621ee3b51a7dc6e5",
            "displayName": "VM Network"
          }
        "numVCPUs":2,
        "ebsOptimized":false
      }
    },
    "environmentType": "ONPREM"
  },
  "currentEntity":{
    "uuid": "34313836-3333-5553-4537-33364e385146",
    "displayName": "dc17-host-01.mycorp.com",
    "className": "PhysicalMachine",
    "environmentType": "ONPREM"
  },
  "newEntity":{
    "uuid": "34313836-3333-5553-4537-33394e43424e",
    "displayName": "dc17-host-02.mycorp.com",
    "className": "PhysicalMachine",
    "environmentType": "ONPREM"
  },
```



```
"risk":{
    "uuid":"_CizZoKN2EeiYWYj--U8W5g",
    "subCategory":"Efficiency Improvement",
    "description":"dc17-host-01.mycorp.com can be suspended for efficiency",
    "severity":"MINOR",
    "importance":0
},
    "actionID":2218532354592
}
```

Getting a Filtered List of Actions

Gets a list of actions, given a scope UUID and filtered by an ActionApilnputDTO using one or more of the following criteria:

- actionModeList
 - DISABLED:

Do not recommend or perform the action. When you disable an action, the user interface will no longer display actions of that type.

RECOMMENDED:

Recommend the action so a user can execute it via the given hypervisor or by other external means

MANUAL:

Recommend the action, and provide the option to execute that action through the Workload Optimization Manager user interface or an /actions API request.

AUTOMATED:

You have directed Workload Optimization Manager to execute the action automatically.

COLLECTION (UNUSED):

Legacy action mode, no longer used.

- actionStateList
 - DISABLED:

An action whose policy has been disabled.

RECOMMEND:

An action that cannot be automated due to policy settings or must be executed outside the system, such as the purchase of hardware.

- PENDING_ACCEPT:

When the action mode is set to manual, a recommended action that has not been accepted or cleared.

ACCEPTED:

An action that has been accepted, but is not yet in progress.

- IN_PROGRESS:

An action that is being executed.

- SUCCEEDED:

An action that was accepted and completed successfully.

- FAILED:

An action that was accepted and did not complete successfully.

- REJECTED:

When the action mode is set to manual, an action that has been rejected by the user.

- CLEARED:

When the action mode is set to manual, an action that is no longer recommended by the market.

- ACCOUNTING:



For cloud entities, an action to resize in order to use a different instance template.

OUEUED:

When more than 10 actions are to be executed for a single target, Workload Optimization Manager will place the 11th and all subsequent actions into a QUEUED state, and they will execute as the previous actions complete.

actionTypeList

- START:

Start an entity, and add it to the Workload Optimization Manager market.

MOVE:

Move an entity from one provider to another. For example, moving a VM between hosts, or a datastore between disk arrays.

- SUSPEND:

Suspend the entity to exclude its capacity from your environment. Suspend does not remove the entity from your environment, but the market does not include the entity in its analysis. Based on market conditions, analysis can recommend restarting suspended entities, which includes them in market analysis once again.

ADD PROVIDER:

This is equivalent to the START action, but for storage entities.

- CHANGE:

Move a virtual machine's storage between datastores.

- PROVISION:

Add capacity to your environment.

- RECONFIGURE:

Analysis recommends this when a VM is not able to correct a misconfiguration via another type of action. For example, analysis can recommend a RECONFIGURE action when a placement policy requires a VM to move to a host on a particular cluster, but cross-cluster moves are not permitted.

- DELETE:

This is equivalent to the SUSPEND action, but for storage entities.

- RESERVE_ON_PM:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular host.

– RESERVE_ON_DS:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular datastore.

RESIZE_FOR_EFFICIENCY:

A resize that reduces the capacity of a commodity, such as vCPU, or vMEM.

- RESIZE FOR PERFORMANCE:

A resize that increases the capacity of a commodity, such as vCPU, or vMEM.

cleared

Default: false.

When true, actions that were removed from the action list before being executed will be returned.

costType

Saving

An action that will decrease cloud spending.

Investment

An action that will increase cloud spending.

cumulative

Default: false.

When true, shows the savings for each action in a scope as a cumulative total, rather than showing the savings for individual actions.



environmentType

ONPREM:

Returns only actions related to entities that are part of your on-premises environment.

CLOUD:

Returns only actions related to entities that are part of your cloud environment.

groupBy

You may group the actions returned by the following criteria: [actionModes, actionStates, actionTypes, risk, riskSeverity, riskSubCategory]

hasReservedInstance

Default: false.

When true, only actions that are related to reserved instances will be returned.

relatedEntityTypes

Returns only actions related to entities of these types within the scope. For example, if your scope is a virtual datacenter and you specify VirtualMachine as a related entity type, the request will include only those actions related to VMs in the specified virtual datacenter.

Choose from the following entity types: [Datacenter, PhysicalMachine, VirtualMachine, Storage, Application, Chassis, DiskArray, IOModule, StorageControl, Switch, VirtualDataCenter, VPod, DPod, Container, Database, DatabaseServerContainer, LogicalPool]

riskSeverityList

Returns only actions of the given severities: [Unknown, Normal, Minor, Major, Critical]

- riskSubCategoryList
- returns only actions of the given subcategories: [Performance Assurance, Efficiency Improvement, Prevention, Compliance]

The following commodities may be returned as the related commodity for an action:

- Access
- ActionPermit
- ActiveSessions
- ApplicationCommodity
- Ballooning
- Biclique
- BufferCommodity
- BurstBalance
- CPU
- CPUAllocation
- CPUProvisioned
- ClusterCommodity
- CollectionTime
- Connection
- Cooling
- Coupon
- CrossCloudMoveSvc
- CrossClusterMoveSvc
- DBCacheHitRate
- DBMem
- DISK_ARRAY_ACCESS
- DSPMAccessCommodity
- DataCenterCommodity
- DatastoreCommodity
- DrsSegmentationCommodity

- Extent
- Flow
- FlowAllocation
- HACommodity
- HOST_LUN_ACCESS
- Heap
- HotStorage
- IOThroughput
- ImageCPU
- ImageMem
- ImageStorage
- InstanceDiskSize
- InstanceDiskType
- LICENSE_ACCESS
- LicenseCommodity
- Mem
- MemAllocation
- MemProvisioned
- Move
- NetThroughput
- NetworkCommodity
- NetworkInterfaceCount
- NetworkPolicy
- NumDisk
- NumberConsumers
- NumberConsumersPM
- NumberConsumersStorage
- PORT_CHANNEL
- PoolCPU
- PoolMem
- PoolStorage
- Power
- ProcessingUnits
- Q1VCPU
- Q2VCPU
- Q3VCPU
- Q4VCPU
- Q5VCPU
- Q6VCPU
- Q7VCPU
- Q8VCPU
- Q16VCPU
- Q32VCPU
- Q64VCPU
- QNVCPU
- ResponseTime
- RightSizeDown
- RightSizeSVC
- RightSizeUp
- SLACommodity



- SameClusterMoveSvc
- SegmentationCommodity
- ServiceLevelCluster
- SoftwareLicenseCommodity
- Space
- Storage
- StorageAccess
- StorageAllocation
- StorageAmount
- StorageClusterCommodity
- StorageLatency
- StorageProvisioned
- Swapping
- TemplateAccess
- TenancyAccess
- Threads
- Transaction
- TransactionLog
- Unknown
- VAppAccess
- VCPU
- VCPULimitQuota
- VCPURequest
- VCPURequestQuota
- VDCCommodity
- VMPMAccessCommodity
- VMem
- VMemLimitQuota
- VMemRequest
- VMemRequestQuota
- VStorage
- Zone

Example: POST https://10.10.10.10/api/v3/actions

Example input: In this example, a list of actions that meet the following criteria will be returned and grouped by the actionMode of the action:

- Is in state PENDING ACCEPT
- Is part of an on-premises environment
- Is an action for a virtual machine
- Is an action generated by the Workload Optimization Manager real-time market

```
"actionInput":{
    "actionStateList":[
        "PENDING_ACCEPT"
],
    "environmentType":"ONPREM",
    "groupBy":[
        "actionModes"
]
},
```



```
"relatedType":"VirtualMachine",
"scopes":[
    "Market"
]
```

Response: A list of ActionApiDTOs that meet the specified criteria.

Accepting or Rejecting a Specified Action

This request accepts or rejects an action with the specified UUID, and takes the following parameters:

action_UUID (Required)

The UUID of the action.

accept (Required)

When true, accepts the action. When false, rejects the action.

Example: POST https://10.10.10.10/api/v3/actions/_QJCzNd3JEeij-LI4LMEROw?accept=false

Response: true, if the action was accepted.

Actions Endpoint Tips

GroupBy Field Criteria

When using the POST requests to query actions and action statistics, there is a groupBy parameter that you may use to group statistics. The valid values for this parameter differ by entity type. Here is the complete list of valid options per entity:

NOTE:

When sending an inputDTO using this field, only the value is needed.

Example: "groupBy": "vmsByPMName"

```
"VirtualMachine":{
  "criteria":[
      "filterType": "vmsByName"
    },
      "filterType": "vmsByPMName"
    },
    {
      "filterType": "vmsByStorage"
    },
      "filterType":"vmsByNetwork"
    },
      "filterType": "vmsByApplication"
    },
      "filterType":"vmsByDatabaseServer"
    },
    {
```



```
"filterType":"vmsByDatabaseServerVersion"
    },
    {
      "filterType":"vmsByDC"
    },
    {
      "filterType":"vmsByVDC"
    },
    {
      "filterType":"vmsByDCnested"
    },
    {
      "filterType":"vmsByNumCPUs"
    },
    {
      "filterType": "vmsByMem"
    },
    {
      "filterType":"vmsByGuestName"
    },
    {
      "filterType": "vmsByAltName"
    },
    {
      "filterType":"vmsByClusterName"
    },
    {
      "filterType":"vmsByDiskArrayName"
    },
    {
      "filterType": "vmsByLogicalPoolName"
    },
      "filterType":"vmsByProfileName"
    },
    {
      "filterType":"vmsByTag"
    },
    {
      "filterType":"vmsByState"
    },
    {
      "filterType": "vmsByBusinessAccountUuid"
    },
      "filterType":"vmsByResourceGroupUuid"
    }
"VirtualDataCenter":{
  "criteria":[
    {
      "filterType":"vdcsByName"
    },
```

] },



```
{
      "filterType": "vdcsByVDCName"
    },
      "filterType":"vdcsByTag"
    },
    {
      "filterType":"vdcsByState"
  ]
},
"PhysicalMachine":{
  "criteria":[
    {
      "filterType": "pmsByName"
    },
      "filterType": "pmsByStorage"
    },
    {
      "filterType": "pmsByNetwork"
    },
    {
      "filterType": "pmsBySwitch"
    },
      "filterType": "pmsByNumVms"
    },
    {
      "filterType": "pmsByDC"
    },
    {
      "filterType": "pmsByMem"
    },
    {
      "filterType": "pmsByNumCPUs"
    },
      "filterType":"pmsByVendorName"
    },
    {
      "filterType": "pmsByCPUModel"
    },
    {
      "filterType":"pmsByModel"
    },
      "filterType": "pmsByTimezone"
    },
      "filterType": "pmsByClusterName"
    },
    {
      "filterType": "pmsByTag"
```



```
},
    {
      "filterType": "pmsByState"
  ]
},
"Storage":{
  "criteria":[
    {
      "filterType":"storageByName"
    },
      "filterType":"storageByTag"
    },
    {
      "filterType": "storageByVMs"
    },
    {
      "filterType": "storageByDC"
    },
    {
      "filterType": "storageByPMCluster"
    },
      "filterType":"storageByState"
    }
  ]
},
"Application":{
  "criteria":[
      "filterType":"appsByName"
    },
      "filterType": "appsByTag"
  ]
},
\verb|"ApplicationComponent": \{ \\
  "criteria":[
      "filterType": "appSrvsByName"
    }
  ]
},
"WebServer":{
  "criteria":[
      "filterType": "wbSrvsByName"
    }
  ]
},
"BusinessApplication":{
  "criteria":[
```



```
{
      "filterType":"busAppsByName"
  ]
},
"Database":{
  "criteria":[
    {
      "filterType": "databaseByName"
    },
      "filterType": "databaseByTag"
    },
    {
      "filterType": "databaseByBusinessAccountUuid"
    },
      "filterType": "databaseByResourceGroupUuid"
    }
  ]
},
"DatabaseServer":{
  "criteria":[
      "filterType": "databaseServerByName"
    },
      "filterType": "databaseServerByTag"
    },
    {
      "filterType": "databaseServerByBusinessAccountUuid"
    },
      "filterType":"databaseServerByEngine"
    },
      "filterType": "databaseServerByEdition"
    },
    {
      "filterType": "databaseServerByVersion"
    }
  ]
},
"VirtualApplication":{
  "criteria":[
    {
      "filterType": "vappsByName"
    }
  ]
},
"Cluster":{
  "criteria":[
    {
      "filterType": "clustersByName"
```



```
},
    {
      "filterType": "clustersByTag"
  ]
},
"DataCenter":{
  "criteria":[
   {
      "filterType":"datacentersByName"
    },
      "filterType":"datacentersByTag"
  ]
},
"Group":{
  "criteria":[
      "filterType": "groupsByName"
   },
      "filterType": "groupsByTargetName"
    }
  ]
},
"StorageCluster":{
  "criteria":[
   {
      "filterType":"storageClustersByName"
  ]
},
"DiskArray":{
  "criteria":[
      "filterType":"diskarrayByName"
  ]
},
"Zone":{
  "criteria":[
      "filterType":"zonsByName"
  ]
},
"Region":{
  "criteria":[
      "filterType":"regsByName"
  ]
},
```



```
"Network":{
  "criteria":[
      "filterType": "netsByName"
    }
  ]
},
"LoadBalancer":{
  "criteria":[
      "filterType":"lbsByName"
    }
  1
},
"Chassis":{
  "criteria":[
      "filterType": "chasByName"
    }
  ]
},
"IOModule":{
  "criteria":[
      "filterType": "ioModuleByName"
    }
  ]
},
"StorageController":{
  "criteria":[
      "filterType": "storagecontrollerByName"
    }
  ]
},
"DPod":{
  "criteria":[
      "filterType":"dpodByName"
    }
  ]
},
"VPod":{
  "criteria":[
      "filterType":"vpodByName"
    }
  ]
},
"LogicalPool":{
  "criteria":[
    {
      "filterType":"logicalPoolByName"
    }
```



```
]
},
"Switch":{
  "criteria":[
      "filterType": "switchByName"
  ]
},
"Container":{
  "criteria":[
      "filterType": "containersByName"
    },
      "filterType": "containersByVMName"
    }
  ]
},
"ContainerPod":{
  "criteria":[
    {
      "filterType": "containerpodsByName"
    },
    {
      "filterType": "containerpodsByVMName"
    }
  ]
},
"ServiceEntity":{
  "criteria":[
    {
      "filterType": "workloadByBusinessAccountUuid"
    },
      "filterType": "workloadByResourceGroupUuid"
  ]
},
"Workload":{
  "criteria":[
    {
      "filterType":"workloadByBusinessAccountUuid"
    },
      "filterType":"workloadByResourceGroupUuid"
    }
  ]
},
"ResourceGroup":{
  "criteria":[
    {
      "filterType": "resourceGroupByName"
    },
```



```
{
      "filterType": "resourceGroupByUuid"
    },
    {
      "filterType": "resourceGroupByBusinessAccountUuid"
    },
    {
      "filterType":"resourceGroupByTag"
  ]
},
"BusinessAccount":{
  "criteria":[
    {
      "filterType": "businessAccountByName"
    },
    {
      "filterType": "businessAccountByUuid"
    },
    {
      "filterType": "subBusinessAccountOfUuid"
    },
    {
      "filterType": "businessAccountValidationStatus"
    },
      "filterType": "businessAccountTargetName"
    },
      "filterType": "businessAccountCloudProvider"
    }
  ]
},
"BillingFamily":{
  "criteria":[
      "filterType": "billingFamilyByName"
  ]
},
"ViewPod":{
  "criteria":[
      "filterType": "viewPodByName"
  ]
"DesktopPool":{
  "criteria":[
      "filterType": "desktopPoolByName"
    },
    {
      "filterType": "desktopPoolByViewPod"
```



```
}

]

},

"BusinessUser":{
    "criteria":[
        {
            "filterType":"businessUserByName"
        },
        {
             "filterType":"businessUserByDesktopPool"
        }
        ]
    }
}
```

Admin Endpoint

The admin endpoint is a collection of requests that enable you to perform various administrative functions. To use the admin endpoint, you must be logged into Workload Optimization Manager as an administrator user.

Using the admin endpoint, you can:

- Export diagnostics locally, and send them to Support
- Get health check results to see if there are issues related to the monitoring and analysis of your environment
- Get or set proxy settings
- Get or set logging levels for various components of your environment
- Get the current product version information and check for updates
- Load existing configuration files for use in your environment

Admin Requests

Exporting Diagnostics

If you are experiencing problems with Workload Optimization Manager, your support representative might request that you export diagnostic data. You can export the data and then send it to the support representative as requested.

```
Example: POST https://10.10.10.10/api/v3/admin/exports
```

Response: true if successful, false if an error occurs while Workload Optimization Manager creates the export. The export file is saved in the /tmp directory on your instance with a file name that begins with bkp-.

Getting Health Check Results

Get health check results regularly to see whether issues exist that are related to the monitoring and analysis of your environment.

Example: GET https://10.10.10.10/api/v3/admin/health

Response: HealthCategoryResponseDTO (on page 1135) with the health check results.

```
{
    "healthCategory": "TARGET",
    "categoryDisplayName": "Targets",
    "categoryHealthState": "CRITICAL",
    "responseItems": [
```



```
"subcategory": "VALIDATION",
      "healthState": "MAJOR",
      "numberOfItems": 2,
      "recommendations": []
    },
      "subcategory": "DISCOVERY",
      "healthState": "CRITICAL",
      "numberOfItems": 6,
      "recommendations": [
          "errorType": "INTERNAL_PROBE_ERROR",
          "description": "{Description}"
      ]
    },
    {
      "subcategory": "DISCOVERY",
      "healthState": "NORMAL",
      "numberOfItems": 23,
      "recommendations": []
  ]
},
  "healthCategory": "ACTION",
  "categoryDisplayName": "Actions",
  "categoryHealthState": "NORMAL",
  "responseItems": [
    {
      "subcategory": "ANALYSIS",
      "healthState": "NORMAL",
      "numberOfItems": 0,
      "recommendations": []
  ]
},
  "healthCategory": "COMPONENT",
  "categoryDisplayName": "Components",
  "categoryHealthState": "NORMAL",
  "responseItems": [
   {
      "subcategory": "CONTAINER PODS",
      "healthState": "NORMAL",
      "numberOfItems": 45,
      "recommendations": [
          "errorType": "INFO",
          "description": "Pods that are in a running state."
        }
      ]
    }
```



```
]
}
1
```

The response includes the following health check categories (healthCategory):

- TARGET see whether issues exist with the targets you added, such as validation or discovery failures.
- ACTION see whether issues exist with analyzing your environment, such as analysis timeouts.
- COMPONENT see whether issues exist with Workload Optimization Manager components, such as container pods that are not running.

Ideally, each healthCategory shows "categoryHealthState": "NORMAL". If you see a different value, review the issues and recommendations in the responseItems key.

Use the following parameters to filter the results:

- category
 - Get results for a specific healthCategory.
- health_state

Get results with a specific categoryHealthState. For example, choose CRITICAL to see issues that require immediate attention.

Getting and Setting a Proxy

Gets the current state of the proxy and proxy details (if enabled).

Example: GET https://10.10.10.10/api/v3/admin/httpproxy

Response: A HttpProxyDTO describing details of the proxy. If no proxy is configured, this request returns "isProxyEnabled": false.

```
{
  "isProxyEnabled":true,
  "proxyHost":"10.10.111.1",
  "userName":"UserName",
  "password":"PW"
}
```

To set the proxy, pass an HttpProxyDTO, making sure to include "isProxyEnabled": true if you want to activate the proxy immediately.

Example: POST https://10.10.10.10/api/v3/admin/httpproxy

Example httpProxyDTO:

```
{
  "isProxyEnabled":true,
  "proxyHost":"10.10.111.1",
  "portNumber":"33128",
  "userName":"ProxyUser",
  "password":"Password"
}
```

Response: true if successful, false if an error occurs while Workload Optimization Manager is setting the proxy.



Getting and Setting Logging Levels by Component

You can set the level of logging for different components of the Workload Optimization Manager platform. The default logging level for all components is INFO. Setting more verbose logging levels can greatly increase the disk space that is required to store the log files. You normally change these settings only while you're working with a Workload Optimization Manager support representative.

The available logging levels are (in order of least to most verbose): INFO, WARN, DEBUG, and TRACE.

Example: GET https://10.10.10.10/api/v3/admin/logginglevels

Response: A LoggingApiDTO with details about your current logging level settings:

```
{
  "componentLoggingLevel":{
    "Extension":"INFO",
    "Analysis":"INFO",
    "Discovery":"INFO",
    "API":"INFO",
    "Presentation":"INFO",
    "Abstraction":"INFO",
    "Monitoring":"INFO"
}
```

To set the logging level for a specific component, pass a partial LoggingApiDTO containing the component and logging level.

Example: POST https://10.10.10.10/api/v3/admin/logginglevels

Example LoggingApiDTO:

```
{
  "componentLoggingLevel":{
    "Extension":"WARN"
  }
}
```

Response: A successful response returns your input in the response body.

Getting the Current Version

Gets the version of each Workload Optimization Manager package that your instance is running. Set the check_for_updates parameter to true to also check for updates that might be available.

This request takes the following parameters:

```
check_for_updates
```

Check for available updates before returning version information. Default: false.

```
Example: GET https://10.10.10.10/api/v3/admin/versions?check_for_updates=true
```

Response: A ProductVersionDTO describing details about the current version and available updates. If you are running the latest version of Workload Optimization Manager, the updates value reads "No Updates Available\n"

```
{
    "versionInfo": "Turbonomic Operations Manager 6.1.7 (Build 20180813223950000)\nvmt-platfor m-6.1.7-20180813223950000.i586
```



```
...,
"updates": "Available Packages\nvmt-bundle.i586 6.2.0-20180817180112000 vmturbo\nvmt-config.x86_64
...,
"marketVersion": 2
}
```

Loading External Configuration Files

To help with diagnosis of some issues, a support representative might want you to load configuration files into your Workload Optimization Manager appliance. Use this request only when you are working with a support representative, who can guide you through the process. The support representative specifies what kind of configuration file you are loading, and the contents of that file, by specifying the required parameters.

Example: POST https://10.10.10.10/api/v3/admin/configfiles?config_type=TOPOLOGY&topology=abc

Response: true if successful, false if an error occurs while you are uploading the configuration.

Businessunits Endpoint

Business units are container objects used for modeling accounts and subscriptions in Public Cloud targets, and for cloud budgets and price adjustements.

Using the businessunits endpoint of the Workload Optimization Manager API, you can:

- For a specified business unit, get a list of:
 - All actions relating to the entities in the business unit
 - Cloud services and pricing models
 - All entities belonging to the business unit
 - Price adjustments
 - Any related (parent, sibling, or child) business units
 - Statistics relating to entities in the business unit
 - Templates available
- Get the supply chain for a specified business unit
- Create a business unit
- Edit a business unit
- Edit a price adjustment
- Delete a business unit

Business units may be one of three types, described below:

■ BUDGET

A business unit that has a budget, and may contain children.

DISCOUNT

A business unit that has a discount, and may contain children.

DISCOVERED

A business unit that has been discovered by the Workload Optimization Manager instance. These business units should not be edited or deleted, except on the discovered target.



Businessunits Requests

Getting Business Units

Gets a list of all business units created on or discovered by your Workload Optimization Manager instance. This request takes the following parameters:

■ type

The type of business unit to return. [BUDGET, DISCOUNT, DISCOVERED]

cloud_type

The cloud provider whose business units to return. [AWS, AZURE, GCP]

has_parent

Whether to return only business units that have parent business units. Default: False. When true, all relevant business units will be returned irrespective of parent business units.

Example: GET https://10.10.10.10/api/v3/businessunits?type=DISCOVERED&cloud_type=AWS

Response: A list of BusinessUnitApiDTOs that meet the selected criteria. In this case, discovered business units that are part of an AWS environment.

```
"uuid": "323871187550",
  "displayName": "Product Trust",
  "className": "BusinessAccount",
  "environmentType": "CLOUD",
  "master": false,
  "hasRelatedTarget": true,
  "budget": {
    "value": 0
  },
  "businessUnitType": "DISCOVERED",
  "cloudType": "AWS",
  "targets": [
      "uuid": "_6glgQEEhEemQ645gSx8RYw",
      "displayName": "PT-AWS",
      "type": "AWS"
  ],
  "costPrice": 0,
  "severity": "Critical",
  "membersCount": 80,
  "memberType": "Workload",
  "related": {
    "rateCard": null,
    "priceAdjustment": null
  },
  "resourceGroupsCount": 0
},
  "uuid": "001844731978",
  "displayName": "Advanced Engineering",
  "className": "BusinessAccount",
  "environmentType": "CLOUD",
```



```
"master": false,
  "hasRelatedTarget": false,
  "budget": {
    "value": 0
  },
  "businessUnitType": "DISCOVERED",
  "cloudType": "AWS",
  "costPrice": 0,
  "severity": "Normal",
  "membersCount": 0,
  "memberType": "Workload",
  "related": {
    "rateCard": null,
    "priceAdjustment": null
  },
  "resourceGroupsCount": 0
},
  "uuid": "192821421245",
  "displayName": "Development",
  "className": "BusinessAccount",
  "environmentType": "CLOUD",
  "master": true,
  "hasRelatedTarget": true,
  "budget": {
    "value": 0
  },
  "businessUnitType": "DISCOVERED",
  "cloudType": "AWS",
  "childrenBusinessUnits": [
   "631949720430",
   "001844731978",
    "323871187550"
  ],
  "targets": [
      "uuid": "_cBVj0MvWEeiFJej-UwMSGg",
      "displayName": "engineering.aws.amazon.com",
      "type": "AWS"
    }
  ],
  "costPrice": 0,
  "severity": "Critical",
  "membersCount": 33,
  "memberType": "Workload",
  "related": {
   "rateCard": null,
    "priceAdjustment": null
  },
  "resourceGroupsCount": 0
},
  "uuid": "631949720430",
  "displayName": "Turbonomic SaaS",
```



```
"className": "BusinessAccount",
    "environmentType": "CLOUD",
    "master": false,
    "hasRelatedTarget": false,
    "budget": {
      "value": 0
   },
    "businessUnitType": "DISCOVERED",
    "cloudType": "AWS",
    "costPrice": 0,
    "severity": "Normal",
    "membersCount": 0,
    "memberType": "Workload",
    "related": {
     "rateCard": null,
     "priceAdjustment": null
    },
    "resourceGroupsCount": 0
]
```

Deleting a Business Unit

To delete a business unit, pass the UUID of the business unit in the request. Note, you cannot delete DISCOVERED business units.

Example: DELETE https://10.10.10.10/api/v3/businessunits/49d50ac3f8adbfe649d53e72c42dd9428d1d3835

Response: A response of 200 indicates successful deletion

Getting Cloud Service and Pricing Model Pairs for a Specified Business Unit

Gets the cloud service name and pricing model for each cloud service.

Example: GET https://10.10.10.10/api/v3/businessunits/192821421245/cloudservices

Response: A list of CloudServicePricingModelApiDTOs representing each cloud service available to the business unit:



```
"uuid": "aws::001844731978::CS::AmazonDynamoDB",
   "displayName": "AWS DynamoDB",
   "pricingModel": "ON_DEMAND"
},
{
   "uuid": "aws::631949720430::CS::AmazonEC2",
   "displayName": "AWS EC2",
   "pricingModel": "ON_DEMAND"
},
{
   "uuid": "aws::001844731978::CS::AmazonEKS",
   "displayName": "AWS EKS",
   "pricingModel": "ON_DEMAND"
},
...
}
```

Getting Price Adjustments Related to a Specified Business Unit

Gets any price adjustments affecting the specified business unit.

Example: GET https://10.10.10.10/api/v3/businessunits/192821421245/priceadjustments **Response:** A list of BusinessUnitPriceAdjustmentApiDTOs showing the corrected prices after adjustment:

```
[
    "servicePriceAdjustments": [
      {
        "uuid": "aws::192821421245::CS::AmazonCloudWatch",
        "displayName": "AWS CloudWatch",
        "pricingModel": "ON_DEMAND"
     },
        "uuid": "aws::192821421245::CS::AWSDeveloperSupport",
        "displayName": "AWS Developer Support",
        "pricingModel": "ON_DEMAND"
     },
      {
        "uuid": "aws::192821421245::CS::AmazonDynamoDB",
        "displayName": "AWS DynamoDB",
        "pricingModel": "ON_DEMAND"
      },
      {
        "uuid": "aws::192821421245::CS::AmazonEC2",
        "displayName": "AWS EC2",
        "pricingModel": "ON_DEMAND",
        "templateDiscounts": [
            "uuid": "aws::VMPROFILE::g3.16xlarge",
            "displayName": "g3.16xlarge",
            "family": "g3",
            "pricesPerDatacenter": [
              {
```



```
"uuid": "aws::ap-southeast-1::DC::ap-southeast-1",
  "displayName": "aws-Asia Pacific (Singapore)",
  "price": 6.68
},
  "uuid": "aws::us-west-2::DC::us-west-2",
  "displayName": "aws-US West (Oregon)",
  "price": 4.56
},
  "uuid": "aws::ca-central-1::DC::ca-central-1",
  "displayName": "aws-Canada (Central)",
  "price": 5.664
},
  "uuid": "aws::eu-west-1::DC::eu-west-1",
  "displayName": "aws-EU (Ireland)",
  "price": 4.84
},
  "uuid": "aws::eu-west-3::DC::eu-west-3",
  "displayName": "aws-EU (Paris)",
  "price": 0
},
  "uuid": "aws::ap-northeast-1::DC::ap-northeast-1",
  "displayName": "aws-Asia Pacific (Tokyo)",
  "price": 6.32
},
  "uuid": "aws::eu-central-1::DC::eu-central-1",
  "displayName": "aws-EU (Frankfurt)",
  "price": 5.7
},
  "uuid": "aws::ap-south-1::DC::ap-south-1",
  "displayName": "aws-Asia Pacific (Mumbai)",
  "price": 0
},
  "uuid": "aws::ap-northeast-2::DC::ap-northeast-2",
  "displayName": "aws-Asia Pacific (Seoul)",
  "price": 0
},
  "uuid": "aws::us-east-1::DC::us-east-1",
  "displayName": "aws-US East (N. Virginia)",
  "price": 4.56
},
  "uuid": "aws::us-west-1::DC::us-west-1",
  "displayName": "aws-US West (N. California)",
  "price": 6.136
},
```



```
"uuid": "aws::sa-east-1::DC::sa-east-1",
      "displayName": "aws-South America (Sao Paulo)",
      "price": 0
    },
      "uuid": "aws::ap-southeast-2::DC::ap-southeast-2",
      "displayName": "aws-Asia Pacific (Sydney)",
      "price": 7.016
    },
      "uuid": "aws::us-east-2::DC::us-east-2",
      "displayName": "aws-US East (Ohio)",
      "price": 4.56
    },
      "uuid": "aws::eu-north-1::DC::eu-north-1",
      "displayName": "aws-EU (Stockholm)",
      "price": 0
    },
      "uuid": "aws::eu-west-2::DC::eu-west-2",
      "displayName": "aws-EU (London)",
      "price": 0
    }
  ]
},
  "uuid": "aws::VMPROFILE::p3.8xlarge",
  "displayName": "p3.8xlarge",
  "family": "p3",
  "pricesPerDatacenter": [
      "uuid": "aws::ap-southeast-1::DC::ap-southeast-1",
      "displayName": "aws-Asia Pacific (Singapore)",
      "price": 16.936
    },
      "uuid": "aws::us-west-2::DC::us-west-2",
      "displayName": "aws-US West (Oregon)",
      "price": 12.24
    },
      "uuid": "aws::ca-central-1::DC::ca-central-1",
      "displayName": "aws-Canada (Central)",
      "price": 13.464
    },
      "uuid": "aws::eu-west-1::DC::eu-west-1",
      "displayName": "aws-EU (Ireland)",
      "price": 13.22
    },
      "uuid": "aws::eu-west-3::DC::eu-west-3",
```



```
"displayName": "aws-EU (Paris)",
                "price": 0
              },
                "uuid": "aws::ap-northeast-1::DC::ap-northeast-1",
                "displayName": "aws-Asia Pacific (Tokyo)",
                "price": 16.776
              },
                "uuid": "aws::eu-central-1::DC::eu-central-1",
                "displayName": "aws-EU (Frankfurt)",
                "price": 15.292
              },
                "uuid": "aws::ap-south-1::DC::ap-south-1",
                "displayName": "aws-Asia Pacific (Mumbai)",
                "price": 0
              },
                "uuid": "aws::ap-northeast-2::DC::ap-northeast-2",
                "displayName": "aws-Asia Pacific (Seoul)",
                "price": 16.936
              },
            ]
          }
       ]
      }
  }
]
```

Editing Price Adjustments of a Specified Business Unit

To edit a price adjustment for the specified business unit, send a BusinessUnitPriceAdjustmentApiDTO with the corrected information (in this case, changing the percent discount from 25 to 50.

Example: PUT https://10.10.10.10/api/v3/businessunits/c0acb428d7b447a5d51f9888d2b6660b5fa5225f

Example Input:

```
{
   "name": "Daltest1",
   "priceAdjustment": {
      "type": "DISCOUNT",
      "value": 50
},
   "childrenBusinessUnits": [
      "192821421245"
],
   "businessUnitType": "DISCOUNT",
   "uuid": "c0acb428d7b447a5d51f9888d2b6660b5fa5225f"
}
```



Response: The full BusinessUnitPriceAdjustmentApiDTO with the corrected values:

```
{
  "uuid": "c0acb428d7b447a5d51f9888d2b6660b5fa5225f",
  "displayName": "Daltest1",
  "className": "BusinessAccount",
  "environmentType": "CLOUD",
  "discount": 50,
  "priceAdjustment": {
    "type": "DISCOUNT",
    "value": 50
 },
  "master": false,
  "hasRelatedTarget": false,
  "budget": {
    "value": 0
 },
  "businessUnitType": "DISCOUNT",
  "cloudType": "AWS",
  "childrenBusinessUnits": [
    "192821421245"
 ],
  "costPrice": 0,
  "severity": "Normal",
  "membersCount": 0,
  "memberType": "Workload",
  "related": {
   "rateCard": null,
    "priceAdjustment": {
      "uuid": "c0acb428d7b447a5d51f9888d2b6660b5fa5225f",
     "displayName": "Daltest1",
      "className": "BusinessAccount"
   }
 },
  "resourceGroupsCount": 0
```

Getting Templates Available to a Business Unit

Referenced Endpoint: Templates (on page 1010)

Gets details about each template available to the specified business unit:

Example: GET https://10.10.10.10/api/v3/businessunits/192821421245/templates

Response: A list of TemplateApiDTOs representing the available templates for the specified business unit:



```
"href": "https://10.10.10.10/api/v3/templates/B4166E9F-589B-357D-AC74-0A534B53CE85"
 }
],
"uuid": "B4166E9F-589B-357D-AC74-0A534B53CE85",
"displayName": "db.x1e.32xlarge",
"className": "DatabaseServerProfile",
"price": 0,
"model": "db.x1e.32xlarge",
"dbEngine": "Oracle",
"dbEdition": "Enterprise",
"computeResources": [
    "stats": [
      {
        "name": "numOfCpu",
       "value": 128
      },
        "name": "cpuSpeed",
        "units": "MHz",
        "value": 384000
     },
        "name": "ioThroughputSize",
        "units": "MB/s",
        "value": 546.875
     },
      {
        "name": "memorySize",
        "units": "MB",
        "value": 3997696
    ]
 }
],
"storageResources": [
 {
    "stats": [
     {
        "name": "diskSize",
        "units": "GB",
        "value": 3840
        "name": "diskIops",
        "value": 35000
   ]
 }
],
"deploymentProfile": {
  "uuid": "5C57DCA5-72AB-34BF-A22D-06719D13182E",
  "displayName": "DEP-RDB-'ap-northeast-1'",
  "className": "ServiceCatalogItem",
```



```
"deployParameters": [
      {
        "targetType": "AWS",
        "providers": [
          {
            "provider": {
              "discoveredBy": {
                "uuid": "_RRn00PMSEeisB7K_chUWVw",
                "displayName": "vmturbodev.aws.amazon.com",
                "type": "AWS"
              }
            }
          }
        ]
      }
    ]
  },
  "discovered": true
},
{
  "links": [
    {
      "rel": "self",
      "href": "https://10.10.10.10/api/v3/templates/aws::VMPROFILE::g3.16xlarge"
    }
  ],
  "uuid": "aws::VMPROFILE::g3.16xlarge",
  "displayName": "g3.16xlarge",
  "className": "VirtualMachineProfile",
  "description": "g3.16xlarge",
  "computeResources": [
      "stats": [
        {
          "name": "ioThroughputSize",
          "units": "MB/s",
          "value": 1750
        },
        {
          "name": "networkThroughputSize",
          "units": "MB/s",
          "value": 2500
        },
        {
          "name": "numOfCpu",
          "value": 64
        },
          "name": "cpuSpeed",
          "units": "MHz",
          "value": 6664.6587
        },
        {
          "name": "cpuConsumedFactor",
```



```
"units": "%",
        "value": 50
      },
        "name": "memorySize",
        "units": "MB",
        "value": 499712
     },
      {
        "name": "memoryConsumedFactor",
        "units": "%",
       "value": 75
     },
        "name": "ioThroughput",
       "units": "MB/s",
        "value": 0
     },
        "name": "networkThroughput",
        "units": "MB/s",
        "value": 0
     }
    ]
 }
],
"storageResources": [
 {
    "stats": [
     {
        "name": "diskSize",
       "units": "GB",
        "value": 976562.5
     },
      {
        "name": "diskIops",
        "value": 20000
      },
        "name": "diskConsumedFactor",
        "units": "%",
        "value": 100
    ]
 }
],
"deploymentProfile": {
 "uuid": "aws::us-east-1::DP::DEP-fake-us-east-1",
 "displayName": "DEP-fake-us-east-1",
  "className": "ServiceCatalogItem",
  "deployParameters": [
      "targetType": "AWS",
      "providers": [
```



Clients Endpoint

A SaaS client, also known as the secure connector for hybrid support, is a lightweight instance of Workload Optimization Manager that you install in your on-prem environment so that a SaaS server can manage on-prem targets (such as VMware vCenter). A SaaS client is not required if your SaaS server manages only cloud, cloud native, or cloud-based APM targets.

Tokens are used to establish the secure connection between the client and server.

Using the clients endpoint, you can:

- Get a list of SaaS client endpoints that need to be accessible to the SaaS server
- Get a list of SaaS clients
- Remove access for all SaaS clients
- Get a list of SaaS client tokens
- Create a token to add a SaaS client
- Delete a SaaS client token

Clients Requests

Getting the SaaS Client Endpoints

Gets a list of SaaS client endpoints that need to be accessible to the SaaS server.

Example: GET https://10.10.10.10/api/v3/clients/networks/configuration

Response:

```
{
   "clientFirewallAllowlist": [
     {
        "name": "claims:0:0",
        "type": "Route",
        "host": "claims-turbonomic.example-host",
        "ip": "9.9.9.9",
        "port": 443
     },
```



```
"name": "skupper:0:0",
      "type": "Route",
      "host": "skupper-turbonomic.example-host",
      "ip": "9.9.9.9",
      "port": 443
    },
      "name": "skupper-edge:0:0",
      "type": "Route",
      "host": "skupper-edge-turbonomic.example-host",
      "ip": "9.9.9.9",
      "port": 443
},
      "name": "skupper-inter-router:0:0",
      "type": "Route",
      "host": "skupper-inter-router-turbonomic.example-host",
      "ip": "9.9.9.9",
      "port": 443
    }
  ]
}
```

Getting a List of SaaS Clients

Gets a list of SaaS clients.

Example: GET https://10.10.10.10.10/api/v3/clients/networks/sites

Response:

Removing Access for All SaaS Clients

Removes access for all SaaS clients.

Example : DELETE https://10.10.10.10.10/api/v3/clients/networks/sites

Response: Status 200

Get a List of SaaS Client Tokens

Gets a list of SaaS client tokens.

Example: GET https://10.10.10.10/api/v3/clients/networks/tokens

Response:

[



```
"id": "ebd939c3-2fa5-11ee-be62-9e7ff38c09f2",
   "created": "1690810016",
  "claimsMade": 0,
  "claimsRemaining": 1,
   "claimExpiration": "1690810916"
},
   "id": "015d769c-2fbd-11ee-a817-d283076531fd",
  "created": "1690819931",
  "claimsMade": 0,
  "claimsRemaining": 1,
   "claimExpiration": "1690820831"
},
   "id": "adb3fccb-2fc0-11ee-a817-d283076531fd",
  "created": "1690821508",
   "claimsMade": 1,
  "claimsRemaining": 0,
   "claimExpiration": "1690822408"
},
{
  "id": "c3c8f093-3048-11ee-a817-d283076531fd",
   "created": "1690879957",
   "claimsMade": 1,
  "claimsRemaining": 0,
   "claimExpiration": "1690880857"
}
```

Creating a Token to Add a SaaS Client

In order to add a new SaaS client, a token must be generated and then applied on the SaaS client. A token can be returned in either base-64 encoded or in raw format depending on the request format.

With a payload in the following format:

```
{ "claimLimit": 1, "expiration": 15 }
```

claimLimit refers to the number of times a token can be applied.

expiration refers to the time in minutes for the token to be claimed, a token that has expired cannot be used to connect client and server.

Example: POST https://10.10.10.10/api/v3/clients/networks/tokens?output=encoded **Response** (encoded in base-64):

```
"id": "c3c8f093-3048-11ee-a817-d283076531fd",
```

"tokenData": "eyJhcGlWZXJzaW9uIjoidjEiLCJkYXRhIjp7ImNhLmNydCl61kxTMHRMUzFDUlVkSlRpQkRSVkpVUlVaSlE wRlVSUzB0TFMwdENrMUpTVVJNVkVORFFXaFhaMEYzUlVKQlowbFNRVXRZTlhaVlFYRXdhMVV6V21NemRESXZRMnBGVDNOMlJGRlp Ta3R2V2tsb2RtTk9RVkZGVEVKUlFYY0tSMnBGVlUxQldVZEJNVlZGUVhoTlVHTXlkREZqU0VKclkya3hlbUZZVW14TVYwNW9UVUkwV0V SVVNYcE5SR042VFZSRmVVNVVhM2RPTVc5WVJGUkpOQXBOUkdONVQxUkZlVTVVYTNkT01XOTNSMnBGV1UxQldVZEJNVlZGUVhoTlVHTXl kREZqU0VKclkya3hlbUZZVW14TVYwNW9UVUkxUWtscVFVNUNaMnR4Q2locmFVYzVkekJDUVZGRlJrRkJUME5CVVRoQlRVbEpRa05uUzBO QlVVVkJjSGhNY0cleE4wcGlSbFZhUmpKTlpDdGphbXN4WTJkUlNsWk9aRWN2SzFRS1dHMDVSMWczWWtoVmJXSnZRWFYyTXk5bk9YbG1j VkJ3VjJ4TVNGSXpkMEkyYkdkUVZrVjFWVkpFZDNaeFNHVmxUWG9yUWpGVlNHeDNWRTVwZG5wRk1nb3pkamw0YWtSTWRHRlVibGhxTlV sWmJWQmpiamRZUTNWaVdXaFNialZNYVRKaVp6SlRaWFJhulVveFZscFFZbk5IUTFwTU5WVndWbFI0VUZWWU5VSnpDazVMZERSQlIwaE5R



MEZtTORGc05YaE9ZM1JOT1RBdk1sSmljMkpLTTNsR1VVcHhObGx1YkVnMmFUVjJRMDkyTW5wR1FtR1NhRm92T1ZkUFpEZE9Sel1LZVhV $\verb|M1NFdHdVRm94VXpnMFFXZEtXSEJZYmpCU01uUm1ZM1F4ZDNaV1ZpdFFRM1poWjBGRVZDczNZV1pwTkhRMFRtcHBUR1ZRUzNaNF1zaEhuR| \\$ WRrVmdvNE5GazBMekZLTm5kWWIyVlBWMDFHWm14S1FWTllkMmhtYVhjeWNtbFRVVkJvVEZBMVlrVllRVlpyYkVSa09GbFNOblJuZDFGSl ${\tt JFR1JRVUp2TWpSM0NtSkVRVT1DWjA1V1NGRTRRa0ZtT0VWQ1FVMURRWEZSZDBoUldVUldVakJzUWtKWmQwWkJXVWxMZDFsQ1FsR1ZTRUY}$ zUlVkRFEzTkhRVkZWUmtKM1RVTUtUVUU0UjBFeFZXUkZkMFZDTDNkUlJrMUJUVUpCWmpoM1NGRlpSRlpTTUU5Q1FsbEZSa05uV1hwc1p ucE50MWQzYkc5VU5WY3ZXbmN3VjJsRVdHUkVaZ3B0UVhOSFFURlZaRVZSVVVWTlFVdERRVVJCVGtKbmEzRm9hMmxIT1hjd1FrRlJjM FpCUVU5RFFWRkZRV2xpZW5vd1RHcHBha2x6VFhGaldXd3hlR1E1Q2tJeVNrbHFlV2h6ZEdWWWRrVn1kR1EzUzNSTWR6VnJSbk13Tnp kNkszbzNSVkZOWmxGWFRqQk1SSFpsWVdWc016RkNOWFJwYkhkelFub3dkMj10VEc4S1FqWnVablJXV25SbWRISjVMM3ByYWtWUmNXb EpRMDlUU1ZaVU5GWlhheXRCVVRSU1YzWlZiVU54UkRSQ2NsSkZkMWxsVWpWaVUyUlFUMUZxYWpoeWNBbzFjRz10WjA1aFNYZzJjWEZYT WtkbVNVeHlOSFJrT1haNVlWbGFiSE5VV2k5aGEyTXZRM1I2THpOVlpXMXdZa2hUYWpNNVlVVXlUelJVT1dWRFJtWlhDamRwY1ZOTlFrU kRjVVpJVkdZeE9T0UZRMFZGT1RFdlowaExkSEV5TTJ4VVZEaFNSRWh2U21jdlEyODRUakUzYUVKa2NFRk1NVU5wYVdwcFVtWm9Zbk1L UlZWalpYVnFRV1JtWjB4dmMxcGtXRUkxVlZKUlF6QnRSak5LTkVwa2VtUjRPV2t4YnpjeU5sZDJXRT1GVFRWTGVGTnhibGRvVDBjcl NWWm5RVE4xU1FwUmR6MDlDaTB0TFMwdFJVNUVJRU5GVWxSSlJrbERRVlJGTFMwdExTMEsiLCJwYXNzd29yZCI6Ik5FWk1XR3g2ZGxGQ 1ZreHBOREExTTJ0dk5URjBlR1ZXU0dnNVZURm9RbmRNY0ZGTGFFW1RhbWRNVUhWV1ZFMWxaMnN3UVhVNFZUZ3dTa1YwY1RVME9FUXhX RTFHWld3M1JHWXpiWE5MTnpoSk1HulNiVlJGYUdRd1VGUnRNbFoyV1VaTWFUT1FTbU5pVVZKbVozWmplR05PWkdsc2JqSmpiRWM1Wmp WS01raz0ifSwia2luZCI6IlNlY3JldCIsIm1ldGFkYXRhIjp7ImFubm90YXRpb25zIjp7InNrdXBwZXIuaW8vZ2VuZXJhdGVkLWJ5Ijo iNWU5MjJmM2EtOWU2Ni00YmQzLTg1YTAtMmE5M2M5YzUxMzRlIiwic2t1cHBlci5pby9zaXRlLXZlcnNpb24i0iIxLjIuNyIsInNrdXBw ZXIuaW8vdXJsIjoiaHR0cHM6Ly85LjQ2LjgwLjE0MjozMDM3My9jM2M4ZjA5My0zMDQ4LTExZWUtYTgxNy1kMjgzMDc2NTMxZmQifSwib GFiZWxzIjp7InNrdXBwZXIuaW8vdHlwZSI6InRva2VuLWNsYWltIn0sIm5hbWUiOiJjM2M4ZjA5My0zMDQ4LTExZWUtYTgxNy1kMjgzMD c2NTMxZmQifX0="

Example: POST https://10.10.10.10/api/v3/clients/networks/tokens?output=raw **Response** (in raw format):

```
"apiVersion": "v1",
"kind": "Secret",
"metadata": {
    "name": "2f2cb866-304c-11ee-a817-d283076531fd",
    "annotations": {
        "skupper.io/generated-by": "5e922f3a-9e66-4bd3-85a0-2a93c9c5134e",
        "skupper.io/site-version": "1.2.7",
        "skupper.io/url": "https://9.46.80.142:30373/2f2cb866-304c-11ee-a817-d283076531fd"
    },
    "labels": {
        "skupper.io/type": "token-claim"
    }
},
"data": {
```

"ca.crt": "LS0tLS1CRUdJTiBDRVJUSUZJQ0FURS0tLS0tCk1JSURMVENDQWhXZ0F3SUJBZ01SQUtYOXZVQXEwa1UzWmMzdDI
vQ2pFT3N3RFFZSktvWklodmNOQVFFTEJRQXcKR2pFWU1CWUdBMVVFQXhNUGMydDFjSEJsY2kxemFYUmxMV05oTUIOWERUSXpNRGN6TVR
FeU5Ua3doMw9YRFRJNApNRGN5T1RFeU5Ua3doMw93R2pFWU1CWUdBMVVFQXhNUGMydDFjSEJsY2kxemFYUmxMV05oTUIJQklqQU5CZ2t
xCmhraUc5dzBCQVFFRkFBT0NBUThBTUIJQkNns0NBUUVBcHhMcG5xN0pmRlVaRjJOZCtjamsxY2dSS1ZOZEcvK1QKWG05R1g3YkhVbWJ
vQXV2My9nOXlmcVBwV2xMSFIzd012bGdQVkV1VVJEd3ZxSGV1TXorQjFWSGx3VE5pdnpFMgozdj14akRMdGFUblhqOU1ZbVBjbjdYQ3V
iWWhSbjVMaTJiZzJTZXRARUoxVlpQYnNHQ1pMNVVwVlR4UFVYNUJzCk5LdDRCR0hNQ0FmODFsNXhOY3RNNTAvMlJic2JKM31FUUpxN
1lubEg2aTV2Q092MnpFQmFSaFovOVdPZDdoRzYKeXU3SEtwUFoxUzg0QWdKWHBYbjBSMnRiY3Qxd3ZVVitQQ3ZhZ0FEVCs3YVZpNHQ0T
mppTFVQS3Z4R3hHTEdkVgo4NFk0LzFKNndYb2VPV01GZmxKQVNYd2hmaXcycmlTUVBoTFAlYkVYQVZrbERkOFlSNnRnd1FJREFRQUJ
vMjR3CmJEQU9CZ05WSFE4QkFmoEVCQU1DQXFRd0hRWURWUjBsQkJZd0ZBWU1Ld11CQ1FVSEF3RUdDQ3NHQVFVRkJ3TUMKTUE4R0ExVWR
Fd0VCL3dRRk1BTUJBZjh3SFFZRFZSME9CQ11FRkNnWXpsZnpNN1d3bG9UNVcvWncwV21EWGREZgpNQXNHQTFVZEVRUUVNQUtDQURBTkJ
na3Foa21HOXcwQkFRc0ZBQU9DQVFFQWlienowTGppaklzTXFjWWwxeGQ5CkIySklqeWhzdGVYdkVydFQ3S3RMdzVrRnMwNzd6K3o3RVF
NZ1FXTjBMRHZ1YWVSMzFCNXRpbHdzQnowd29tTG8KQjzuZnRWWnRmdHJ5L3prakVRcWlJQ09TSVZUNFZXaytBUTRRV3ZVbUNxRDRCclJ
Fd11lujviu2RQT1FqajhycAo1cG9tZ05hSXg2cXFXMkdmSUxyNHRkOXZ5YVlabHNUWi9ha2MvQ3R6LzNVZWlwYkhTajM5YUUyTZRUOWV
DRmZXCjdpcVNNQkRDcUZIVGYxOS9FQ0VFNTEvZ0hLdHEyM2xUVDhSREhvSmcvQ284TjE3aEJkcEFIMUNpaWppUmZoYnMKRVVjZXVQQWR



 $\verb|mZ0xvc1pkWEI1VVJRQzBtRjNKNEpkemR4OWkxbzcyNld2WE9FTTVLeFNxbldoT0crSVZnQTN1SQpRdz09Ci0tLS0tRU5EIENFUlRJRklD|\\ OVRFLS0tLS0K",$

"password": "Nk9tQmM4OTRPMnBTeUd6OGp6M1paa2ZNNDJ1QW9NaX1RRExvYVFqWGg0VWZBeFpucEg0MmFnZTI4anFKY3VsTmJ
XUFZLSzNqT3p1Z1EyeTk2WGQ5M3FBcGRqVHNudHJKeDR4ZEhaMHpVMXZURW9IMU45Q3RFaFB0ZHVyZk9YZXo="
 }
}

Removing a SaaS Client Token

SaaS client tokens can be removed based on their unique token ID.

Example: DELETE https://10.10.10.10/api/v3/clients/networks/tokens?tokenId=<TOKEN_ID>

Response: Status 200

Entities Endpoint

Entities are the objects in your topology that Workload Optimization Manager manages. For example, VMs, hosts, datastores, and applications are all entities. Workload Optimization Manager discovers entities via targets, it monitors and analyzes their utilization of resources, and it recommends actions to change the placement, configuration, or state of entities.

Each market manages a set of entities. Using a market's UUID, you can get a list of entities managed by that market. For each entity you can get a full range of data, including the resources it buys and sells, the providers it buys resources from, actions for the entity, and other associated information.

Remember that more than one market can be resident in memory at a given time — Workload Optimization Manager maintains a real-time market, and there can also be plan markets in memory. As you access market entities, you should keep the following in mind:

- Entities in the real-time market reflect the current state in your physical environment
- You should never add or remove entities in the real-time market
- Entities in a plan market reflect a snapshot of the environment from when the market was created
- Plan markets can be scoped to a subset of your physical environment
- You can add or remove entities in a plan market

An interesting point about entities and markets – A plan market can contain entities that are also managed by the real-time market. These entities have the same stats in both markets. Workload Optimization Manager independently performs analysis on these entities in both markets.

Using the entities endpoint of the Workload Optimization Manager API, you can get a list of entities (from the market or group that contains the entities). For an individual entity you can get:

- Actions and related data for an entity
- Constraints assigned to the entity
- Through the entity constraints, get the available providers and consumers for the entity
- Groups the entity belongs to
- Notifications and notification data
- Workload placement policies that affect this entity
- Automation policies that affect this entity
- Stats for the entity
- The supply chain of entities that stitch directly with this entity
- Any tags that are defined for the entity

This endpoint contains references to start and end times for certain operations. For more information, including valid time formats, see <u>Time in the Workload Optimization Manager API (on page 742)</u>



Entities Utility Requests

Utility requests provide metadata that you can use to make related requests, assemble inputDTOs, or see the potential values of a particular DTO.

Getting a List of Entry Points for Entities

The entities endpoint contains a utility request that shows the entry points you can use to get lists of entities. These can be used to find the UUID and details relating to specific entities.

Example: GET https://10.10.10.10/api/v3/entities

Response: An array of Link objects, where each object contains a URL to get all entities for a specified market or group.

```
{
  "links":[
     {
        "rel":"Market actions",
        "href":"https://10.10.10.10/api/v3/markets/{uuid}/entities"
     },
     {
        "rel":"Group actions",
        "href":"https://10.10.10.10/api/v3/groups/{uuid}/entities"
     }
     ]
}
```

Getting a List of Entry Points for a Single Entity

If you pass an entity UUID to the entities endpoint, then you get a description of the entity, plus a list of entry points for entity data such as stats, constraints, actions, etc.

Example: GET https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073

Response: An array of Link objects, where each object contains a URL to get information about the entity.



```
},
{
    "rel": "To Constraints",
    "href": "https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/policies"
},
{
    "rel": "To Settings",
    "href": "https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/settings?include_settingspolicies=false"
},
{
    "rel": "To Entity List",
    "href": "https://10.10.10.10/api/v3/entities"
}
],
...
}
```

Entities Requests

Getting Entities

Referenced Endpoint: Groups (on page 819)

To get a list of entities, start with the object that contains those entities. This is usually a market or a group. You work with individual entities via their UUIDs – A list of entities gives you a list of UUIDs that you can work with.

NOTE:

When working with groups, you should remember that a list of entities in the group is not the same as a list of group members. Assume a group of host clusters. In that case, the list of entities would be all the hosts in those clusters, while the group members would be a list of clusters, plus all the hosts in each cluster. For more information, see Groups Endpoint (on page 819).

Example: GET https://10.10.10.10/api/v3/groups/_BZbFsWXUEemoItN1K8jw3Q/entities **Response:** A list of EntityApiDTOs.



```
"remoteId": "azure::VM::2ffc038a-7af3-4d23-86a9-211da2e4d433",
  "providers": [
      "uuid": "azure::ST::eastus2-managed_premium",
      "displayName": "azure-eastus2-Managed Premium",
      "className": "Storage"
     },
      "uuid": "azure::eastus2::PM::eastus2",
      "displayName": "azure-eastus2",
      "className": "PhysicalMachine"
     }
 ],
 "consumers": [
   {
    "uuid": "azure::APP::2ffc038a-7af3-4d23-86a9-211da2e4d433",
    "displayName": "GuestLoad [e47f9c97-b44d-4461-be02-0304b97e201e]",
    "className": "Application"
   }
 ],
 "template": {
   "uuid": "azure::VMPROFILE::Standard_DS13_v2",
   "displayName": "Standard_DS13_v2",
   "discovered": false,
   "enableMatch": false
 },
 "environmentType": "CLOUD",
 "tags": {
   "instance_group": [
     "diego_cell"
 }
},
{
```

Getting Actions Related to an Entity

Referenced Endpoint: Actions (on page 753)

If you provide the entity UUID but do not provide an action UUID, this returns a list of ActionApiDTOs for all the actions that are current for the entity. If you provide both the entity UUID and the action UUID, it returns the ActionApiDTO for the specified action.

This request takes the following parameters:

entity_Uuid

The UUID of the entity whose actions will be returned.

action_Uuid

The UUID of the action you want to get - Required to get a single action.

cursor

When making subsequent calls to retrieve additional results, this is the cursor returned by the last call to this method.

■ limit



The maximum number of items to return. Must be a positive integer. If not set, the server will provide a default (20).

order_by

The field to order the results by. [creation_date, name, risk_category, savings, severity].

ascending

Default: true. When false, results will be in descending order.

Examples:

- Get a list of actions for the passed entity: GET https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/actions?order_by=severity&ascending=true
- Get a single action for the entity: GET https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/actions/9223304219064809841

Response: A list of ActionApiDTOs representing the actions that are current for the given entity, or a single ActionApiDTO for the specified action. The following listing shows the list of ActionApiDTOs wrapped in an array.

```
[
    "links": [
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/actions/9223304219106592017"
      },
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/actions/2560158594896"
     }
    ],
    "uuid": "9223304219106592017",
    "createTime": "2019-04-23T10:41:37-04:00",
    "actionType": "RIGHT_SIZE",
    "actionState": "PENDING_ACCEPT",
    "actionMode": "MANUAL",
    "details": "Scale down VMem for VirtualMachine vEOS-4 from 2 GB to 623 MB",
    "importance": 0,
    "target": {
      "uuid": "420bleeb-6190-a9d2-6436-4327ad3ac073",
     "displayName": "vEOS-4",
      "className": "VirtualMachine",
      "discoveredBy": {
        "uuid": "_FJwg0EzHEemaXZFqO1sC0g",
        "displayName": "vsphere-dc11.dev.mycorp.com",
        "type": "vCenter"
      },
      "aspects": {
        "virtualMachineAspect": {
          "os": "Other 2.6.x Linux (32-bit)",
          "connectedNetworks": [
              "uuid": "d2da5316adfff0bf779652bbe7eb76c3307c2ab5",
              "displayName": "Infrastructure"
            },
              "uuid": "bbef68e6ee0e76ba2c82960012b4ba563b78fdbb",
              "displayName": "vmnet4"
```



```
},
        {
          "uuid": "d59c5e7e738ad9d2e2cb45aac5fe0073d36b49fb",
          "displayName": "vmnet6"
        },
          "uuid": "96a42a4d438d1336e8d2c6962c976d889792af8a",
          "displayName": "vmnet8"
        },
          "uuid": "067bc9d882e9681c55d964295e43134711520145",
          "displayName": "vmnet57"
        },
          "uuid": "05b0ce5abc5cecc4104b26514b11618d77818c6d",
          "displayName": "vmnet59"
      ],
      "numVCPUs": 1,
      "type": "VMEntityAspectApiDTO"
   }
 },
 "environmentType": "ONPREM"
},
"currentEntity": {
  "uuid": "_3vIfwmXVEemoItN1K8jw3Q",
 "className": "VMem"
},
"newEntity": {
  "uuid": "_5fnl82XVEemoItN1K8jw3Q",
 "className": "VMem",
  "aspects": {
    "virtualMachineAspect": {
     "os": "Linux (Free)",
      "type": "VMEntityAspectApiDTO"
 }
},
"currentValue": "2097152.0",
"newValue": "637952.0",
"resizeToValue": "637952.0",
"risk": {
 "uuid": "_5fr3YWXVEemoItN1K8jw3Q",
  "subCategory": "Efficiency Improvement",
 "description": "Underutilized VMem in Virtual Machine 'vEOS-4'",
  "severity": "MINOR",
  "importance": 0,
 "reasonCommodity": "VMem"
},
"stats": [
 {
    "name": "costPrice",
    "filters": [
      {
```



```
"type": "savingsType",
            "value": "savings"
          }
        ],
        "units": "$",
        "value": 69.58008
      }
    ],
    "currentLocation": {
      "uuid": "98e12595449d993db8861c1f94c8f86ba277f17b",
      "displayName": "Cloud",
     "className": "DataCenter"
   },
    "newLocation": {
      "uuid": "98e12595449d993db8861c1f94c8f86ba277f17b",
     "displayName": "Cloud",
      "className": "DataCenter"
   },
    "actionID": 2560158594896
 },
]
```

Getting a Filtered List of Actions Related to an Entity

Referenced Endpoint: Actions (on page 753)

Gets a list of actions, given a market UUID and filtered by an ActionApilnputDTO using one or more of the following criteria:

- actionModeList
 - DISABLED:

Do not recommend or perform the action. When you disable an action, the user interface will no longer display actions of that type.

- RECOMMENDED:

Recommend the action so a user can execute it via the given hypervisor or by other external means

- MANUAL:

Recommend the action, and provide the option to execute that action through the Workload Optimization Manager user interface or an /actions API request.

AUTOMATED:

You have directed Workload Optimization Manager to execute the action automatically.

– COLLECTION (UNUSED):

Legacy action mode, no longer used.

- actionStateList
 - DISABLED:

An action whose policy has been disabled.

_ PECOMMEND.

An action that cannot be automated due to policy settings or must be executed outside the system, such as the purchase of hardware.

– PENDING_ACCEPT:

When the action mode is set to manual, a recommended action that has not been accepted or cleared.

ACCEPTED:



An action that has been accepted, but is not yet in progress.

- IN_PROGRESS:

An action that is being executed.

SUCCEEDED:

An action that was accepted and completed successfully.

– FAILED:

An action that was accepted and did not complete successfully.

REJECTED:

When the action mode is set to manual, an action that has been rejected by the user.

CLEARED:

When the action mode is set to manual, an action that is no longer recommended by the market.

- ACCOUNTING:

For cloud entities, an action to resize in order to use a different instance template.

- OUEUED:

When more than 10 actions are to be executed for a single target, Workload Optimization Manager will place the 11th and all subsequent actions into a QUEUED state, and they will execute as the previous actions complete.

actionTypeList

- START:

Start an entity, and add it to the Workload Optimization Manager market.

MOVE:

Move an entity from one provider to another. For example, moving a VM between hosts, or a datastore between disk arrays.

- SUSPEND:

Suspend the entity to exclude its capacity from your environment. Suspend does not remove the entity from your environment, but the market does not include the entity in its analysis. Based on market conditions, analysis can recommend restarting suspended entities, which includes them in market analysis once again.

- ADD PROVIDER:

This is equivalent to the START action, but for storage entities.

CHANGE:

Move a virtual machine's storage between datastores.

- PROVISION:

Add capacity to your environment.

- RECONFIGURE:

Analysis recommends this when a VM is not able to correct a misconfiguration via another type of action. For example, analysis can recommend a RECONFIGURE action when a placement policy requires a VM to move to a host on a particular cluster, but cross-cluster moves are not permitted.

- DELETE:

This is equivalent to the SUSPEND action, but for storage entities.

RESERVE_ON_PM:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular host.

– RESERVE_ON_DS:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular datastore.

- RESIZE_FOR_EFFICIENCY:

A resize that reduces the capacity of a commodity, such as vCPU, or vMEM.

- RESIZE_FOR_PERFORMANCE:

A resize that increases the capacity of a commodity, such as vCPU, or vMEM.

cleared



Default: false.

When true, actions that were removed from the action list before being executed will be returned.

■ costType

Saving

An action that will decrease cloud spending.

- Investment

An action that will increase cloud spending.

cumulative

Default: false.

When true, shows the savings for each action in a scope as a cumulative total, rather than showing the savings for individual actions.

environmentType

ONPREM:

Returns only actions related to entities that are part of your on-premises environment.

- CLOUD:

Returns only actions related to entities that are part of your cloud environment.

groupBy

You may group the actions returned by the following criteria: [actionModes, actionStates, actionTypes, risk, riskSeverity, riskSubCategory]

hasReservedInstance

Default: false.

When true, only actions that are related to reserved instances will be returned.

relatedEntityTypes

Returns only actions related to entities of these types within the scope. For example, if your scope is a virtual datacenter and you specify VirtualMachine as a related entity type, the request will include only those actions related to VMs in the specified virtual datacenter.

Choose from the following entity types: [Datacenter, PhysicalMachine, VirtualMachine, Storage, Application, Chassis, DiskArray, IOModule, StorageControl, Switch, VirtualDataCenter, VPod, DPod, Container, Database, DatabaseServerContainer, LogicalPool]

riskSeverityList

Returns only actions of the given severities: [Unknown, Normal, Minor, Major, Critical]

- riskSubCategoryList
- returns only actions of the given subcategories: [Performance Assurance, Efficiency Improvement, Prevention, Compliance]

This request takes the following parameters:

entity_Uuid

The UUID of the market whose actions will be returned.

cursor

When making subsequent calls to retrieve additional results, this is the cursor returned by the last call to this method.

■ limit

The maximum number of items to return. Must be a positive integer. If not set, the server will provide a default (20).

order_by

The field to order the results by: [creation_date, name, risk_category, savings, severity].

ascending

Default: true. When false, results will be in descending order.

Example: POST https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/actions?order_by=severity&ascending=true



Example input: In this example, a list of actions that meet the following criteria will be returned and grouped by the actionMode of the action, in order of severity:

- Is in state PENDING ACCEPT
- Is part of an on-premises environment
- Is an action for a virtual machine

```
{
  "actionInput":{
     "actionStateList":[
         "PENDING_ACCEPT"
  ],
     "environmentType":"ONPREM",
     "groupBy":[
         "actionModes"
  ]
  },
  "relatedType":"VirtualMachine",
  "scopes":[
        "Market"
  ]
}
```

Response: A list of ActionApiDTOs that meet the specified criteria.

Getting Statistics for a Filtered List of Actions Of an Entity

Referenced Endpoint: <u>Actions (on page 753)</u> Referenced Endpoint: <u>Stats (on page 973)</u>

Gets a list of statistics for a filtered list of actions that are current for the passed entity. Statistics returned include the number of actions, total savings/investment, and the number of entities affected by the actions. In addition to the Entity UUID, provide an ActionApilnputDTO using one or more of the following criteria:

- actionModeList
 - DISABLED:

Do not recommend or perform the action. When you disable an action, the user interface will no longer display actions of that type.

RECOMMENDED:

Recommend the action so a user can execute it via the given hypervisor or by other external means

_ ΜΔΝΙΙΔΤ.

Recommend the action, and provide the option to execute that action through the Workload Optimization Manager user interface or an /actions API request.

- AUTOMATED:

You have directed Workload Optimization Manager to execute the action automatically.

– COLLECTION (UNUSED):

Legacy action mode, no longer used.

- actionStateList
 - DISABLED:

An action whose policy has been disabled.

- RECOMMEND:

An action that cannot be automated due to policy settings or must be executed outside the system, such as the purchase of hardware.



- PENDING_ACCEPT:

When the action mode is set to manual, a recommended action that has not been accepted or cleared.

ACCEPTED:

An action that has been accepted, but is not yet in progress.

- IN PROGRESS:

An action that is being executed.

SUCCEEDED:

An action that was accepted and completed successfully.

- FAILED:

An action that was accepted and did not complete successfully.

- REJECTED:

When the action mode is set to manual, an action that has been rejected by the user.

CLEARED:

When the action mode is set to manual, an action that is no longer recommended by the market.

ACCOUNTING:

For cloud entities, an action to resize in order to use a different instance template.

OUEUED:

When more than 10 actions are to be executed for a single target, Workload Optimization Manager will place the 11th and all subsequent actions into a QUEUED state, and they will execute as the previous actions complete.

actionTypeList

- START:

Start an entity, and add it to the Workload Optimization Manager market.

MOVE

Move an entity from one provider to another. For example, moving a VM between hosts, or a datastore between disk arrays.

- SUSPEND:

Suspend the entity to exclude its capacity from your environment. Suspend does not remove the entity from your environment, but the market does not include the entity in its analysis. Based on market conditions, analysis can recommend restarting suspended entities, which includes them in market analysis once again.

– ADD PROVIDER:

This is equivalent to the START action, but for storage entities.

CHANGE:

Move a virtual machine's storage between datastores.

- PROVISION:

Add capacity to your environment.

RECONFIGURE:

Analysis recommends this when a VM is not able to correct a misconfiguration via another type of action. For example, analysis can recommend a RECONFIGURE action when a placement policy requires a VM to move to a host on a particular cluster, but cross-cluster moves are not permitted.

- DELETE:

This is equivalent to the ${\tt SUSPEND}$ action, but for storage entities.

– RESERVE_ON_PM:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular host.

- RESERVE_ON_DS:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular datastore.

- RESIZE_FOR_EFFICIENCY:

A resize that reduces the capacity of a commodity, such as vCPU, or vMEM.



- RESIZE FOR PERFORMANCE:

A resize that increases the capacity of a commodity, such as vCPU, or vMEM.

cleared

Default: false.

When true, actions that were removed from the action list before being executed will be returned.

■ costType

- Saving

An action that will decrease cloud spending.

- Investment

An action that will increase cloud spending.

cumulative

Default: false.

When true, shows the savings for each action in a scope as a cumulative total, rather than showing the savings for individual actions.

environmentType

ONPREM:

Returns only actions related to entities that are part of your on-premises environment.

- CLOUD:

Returns only actions related to entities that are part of your cloud environment.

groupBy

You may group the actions returned by the following criteria: [actionModes, actionStates, actionTypes, risk, riskSeverity, riskSubCategory]

hasReservedInstance

Default: false.

When true, only actions that are related to reserved instances will be returned.

relatedEntityTypes

Returns only actions related to entities of these types within the scope. For example, if your scope is a virtual datacenter and you specify VirtualMachine as a related entity type, the request will include only those actions related to VMs in the specified virtual datacenter.

Choose from the following entity types: [Datacenter, PhysicalMachine, VirtualMachine, Storage, Application, Chassis, DiskArray, IOModule, StorageControl, Switch, VirtualDataCenter, VPod, DPod, Container, Database, DatabaseServerContainer, LogicalPool]

riskSeverityList

Returns only actions of the given severities: [Unknown, Normal, Minor, Major, Critical]

- riskSubCategoryList
- returns only actions of the given subcategories: [Performance Assurance, Efficiency Improvement, Prevention, Compliance]

Example: POST https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/actions/stats

Example input: Get a list of stats for actions that meet the following criteria, grouped by the actionMode of the action, in order of severity:

- Is in state PENDING_ACCEPT
- Is part of an on-premises environment
- Is an action for a virtual machine
- Is an action generated by the Workload Optimization Manager real-time market

```
{
    "actionInput":{
```



```
"actionStateList":[
    "PENDING_ACCEPT"
],
    "environmentType":"ONPREM",
    "groupBy":[
        "actionModes"
]
},
"relatedType":"VirtualMachine"
```

Response: A list of StatSnapshotApiDTOs that aggregate statistics about the filtered actions.

```
[
  {
    "date": "2019-04-24T03:56:34-04:00",
    "statistics": [
     {
        "name": "numActions",
        "values": {
          "max": 1,
          "min": 1,
          "avg": 1,
          "total": 1
        },
        "value": 1
      },
      {
        "name": "costPrice",
        "filters": [
          {
            "type": "property",
            "value": "savings"
          }
        ],
        "units": "$",
        "values": {
          "max": 69.77539,
          "min": 69.77539,
          "avg": 69.77539,
          "total": 69.77539
        },
        "value": 69.77539
      },
      {
        "name": "numEntities",
        "values": {
          "max": 1,
          "min": 1,
          "avg": 1,
          "total": 1
        },
        "value": 1
      }
```



```
}
```

Getting the Constraints for placement of an entity

When it calculates where to place an entity, Workload Optimization Manager respects whatever placement constraints there might be in your environment. For example, unless you have a Merge Cluster policy in effect, VM placement is constrained to hosts in the same cluster.

This call gets a ConstraintApiDTO object, which describes these constraints for the specified entity. The data in this object is equivalent to the Placement Constraints view that you can see in the user interface. To see this view, you drill down to the policy view for a single entity. In this view you can see the entity's related providers and consumers. You can also open a view for each related entity to show the constraints that limit potential placement for the entity. Also in this view, you can test out different placement options. (For information about testing different placement options, see <u>Inspecting placement options</u> within constraints for an element (on page 791).)

In the same way, the ConstraintApiDTO contains data objects to describe the current placement relationships, as well as potential changes you could make. The DTO delivers an array of objects for each consumer or provider. Within each object:

- relation indicates whether the entity is a provider (bought) or consumer (sold)
- relatedEntities describes the current consumer or provider
- placementOptions show other placement you could exploit for this relationship, if you were to remove the current constraints (via merge policies or other means)

 $\textbf{Example:} \ \texttt{GET https://10.10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/constraints}$

Response: This listing shows a subset of the related entities and placement options:

```
"relation": "bought",
    "entityType": "PhysicalMachine",
    "relatedEntities": [
      {
        "links": [
            "rel": "self",
            "href": "https://10.10.10.10/api/v3/entities/30333436-3638-5355-4532-313159335631?include_asp
ects=false"
        ],
        "uuid": "30333436-3638-5355-4532-313159335631",
        "displayName": "hp-dl571.dev.mycorp.com",
        "className": "PhysicalMachine",
        "priceIndex": 6.577457,
        "state": "ACTIVE",
        "severity": "Normal",
        "discoveredBy": {
          "uuid": "_FJwg0EzHEemaXZFq01sC0g",
          "displayName": "vsphere-dc11.dev.mycorp.com",
          "type": "vCenter"
        },
        "remoteId": "host-30",
        "environmentType": "ONPREM"
      }
    ],
```



```
"numPotentialEntities": 1,
"placementOptions": [
    "constraintType": "ClusterCommodity",
    "scope": {
      "uuid": "17fe23bc346750d62dce8ba4274fa99b4739975f",
      "displayName": "Cloud\\Physical"
   },
    "target": {
      "uuid": "_FJwg0EzHEemaXZFqO1sC0g",
      "displayName": "vCenter:vsphere-dc11.dev.mycorp.com",
      "type": "vCenter"
   },
    "numPotentialEntities": 3,
    "key": "Cluster::17fe23bc346750d62dce8ba4274fa99b4739975f"
 },
  {
    "constraintType": "NetworkCommodity",
    "scope": {
      "displayName": "NetworkCommodity/vEOS-4"
    },
    "numPotentialEntities": 2,
    "key": "DistributedVirtualPortgroup::vmnet4"
 },
  {
    "constraintType": "DatastoreCommodity",
    "scope": {
      "uuid": "5a822e24-584bce98-ecb2-441ea15e2534",
      "displayName": "SCIO:ESXDC11DS2"
   },
    "target": {
      "uuid": "_FJwg0EzHEemaXZFqO1sC0g",
      "displayName": "vCenter:vsphere-dc11.dev.mycorp.com",
      "type": "vCenter"
   },
    "numPotentialEntities": 2,
    "key": "Storage::5a822e24-584bce98-ecb2-441ea15e2534"
  },
  {
    "constraintType": "DataCenterCommodity",
    "scope": {
      "uuid": "98e12595449d993db8861c1f94c8f86ba277f17b",
      "displayName": "Cloud"
    },
    "target": {
      "uuid": "_FJwg0EzHEemaXZFqO1sC0g",
      "displayName": "vCenter:vsphere-dc11.dev.mycorp.com",
      "type": "vCenter"
    },
    "numPotentialEntities": 7,
    "key": "DataCenter::98e12595449d993db8861c1f94c8f86ba277f17b"
  }
]
```

},



Inspecting Placement Options Within Constraints for an Element

Within the given constraints that limit placement of an entity, there are usually a number of options for placement. The current placement is just one of many.

For information about getting entity constraints, see Getting the Constraints for Placement of an Entity (on page 791).

When you get the constraints for an entity, the ConstraintApiDTO includes other placement options for that entity on its providers, and options to place other consumers on the entity. The call in this section passes these placement options and returns the respective providers or consumers that satisfy the resulting constraint changes.

Making this call is equivalent to clicking **Find More Placement Options** in the user interface. To see this in the user interface, set the scope to a single entity, display the POLICIES tab, and scroll down to the Placement Constraints section. Then click **Constraints** next to the provider you want to explore, and click **Find More Placement Options**.

Example: POST https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/constraints/entities

Example input: In this example, we pass two placement options, that we copied from a ConstraintApiDTO for the entity we're inspecting. Note that each placement option in the ConstraintApiDTO includes a constraintType and a key. To pass a placement option, these are the only fields we need. For this example we pass a ClusterCommodity constraint and a DatastoreCommodity constraint.

```
{
   "relation": "bought",
   "placementOptions": [
     {
        "constraintType": "ClusterCommodity",
        "key": "Cluster::17fe23bc346750d62dce8ba4274fa99b4739975f"
      },
      {
        "constraintType": "DatastoreCommodity",
        "key": "Storage::5a822e24-584bce98-ecb2-441ea15e2534"
      }
    ]
}
```

Response: In the data we posted (above), the cluster commodity has three potential entities, and the datastore commodity has two potential entities. The response brings back the intersection of these three potential provider entities – Two hosts.



```
"uuid": "30343835-3638-584d-5131-323530394e39",
    "displayName": "hp-dl569.dev.mycorp.com",
    "className": "PhysicalMachine",
    "priceIndex": 1.031998,
    "state": "ACTIVE",
    "severity": "Normal",
    "discoveredBy": {
      "uuid": "_FJwg0EzHEemaXZFqO1sC0g",
      "displayName": "vsphere-dcl1.dev.mycorp.com",
      "type": "vCenter"
    },
    "remoteId": "host-3323",
    "environmentType": "ONPREM"
  },
    "links": [
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/entities/30333436-3638-5355-4532-313159335631?include_aspec
ts=false"
      }
    ],
    "uuid": "30333436-3638-5355-4532-313159335631",
    "displayName": "hp-dl571.dev.mycorp.com",
    "className": "PhysicalMachine",
    "priceIndex": 6.916899,
    "state": "ACTIVE",
    "severity": "Normal",
    "discoveredBy": {
      "uuid": "_FJwg0EzHEemaXZFqO1sC0g",
      "displayName": "vsphere-dcl1.dev.mycorp.com",
      "type": "vCenter"
    },
    "remoteId": "host-30",
    "environmentType": "ONPREM"
]
```

Getting Group Membership of an Entity

Referenced Endpoint: Groups (on page 819)

The Groups endpoint tells you which entities are in a given group. The /entities/{entity_Uuid}/groups call tells you which groups a given entity belongs to. You can make this call in two modes:

Include relationship paths

In this mode the results include only those groups that are in a buy or sell relationship with the entity. For example, a VM entity might have relationships with a datacenter and a host cluster. The call would return entries for the datacenter, the host cluster, and the VM itself.

Do not include relationship paths

In this mode the call returns every group that includes the passed entity as a member entity. This can be a large number of groups, including all the discovered groups as well as any custom groups you created. The results do not show buy/sell relationships.



This request takes the following parameters:

entity_Uuid

The UUID of the entity whose actions will be returned.

path

Default: false. When true, results include only related groups, and they show the providers and consumers for each group when applicable.

Examples:

- All groups (path = false): GET https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/groups?path=false
- Buy/Sell related groups, only (path = true): GET https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/groups?path=true

Response: A list of related groups. For the default (path = false), this returns an array of group objects.

```
[
    "links": [
     {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/groups/_lSlr0GddEemDFcIzuV5wcQ?include_aspects=false"
     }
    ],
    "uuid": "_lSlr0GddEemDFcIzuV5wcQ",
    "displayName": "CUD_Vm_Group_vEOS",
    "className": "Group",
    "environmentType": "ONPREM",
    "entitiesCount": 5,
    "membersCount": 5,
    "groupType": "VirtualMachine",
    "severity": "Normal",
    "isStatic": true,
    "logicalOperator": "OR",
    "activeEntitiesCount": 3
 },
 ]
```

Getting Settings Policies Affecting an Entity

Referenced Endpoint: <u>Settings Policies (on page 967)</u>

This call returns an array of SettingsPolicyApiDTOs for all the Automation Policies that are effective for the given entity. Note that one entity can be in multiple groups, and so it can have policies that set different values for the same setting. In that case, the most conservative setting takes effect. The data returned by this call does not reflect which setting takes precedence in this case. The call merely reflects what you would see in the user interface.

 $\textbf{Example:} \ \texttt{GET https://10.10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/settingspolicies} \\$

Response: An array of SettingsPolicyApiDTOs that are effective for the entity.

```
[
    {
     "uuid": "_i-QuUGXUEemoItN1K8jw3Q",
```



```
"displayName": "CUD_VM_AUTOMATION_POLICY",
"entityType": "VirtualMachine",
"scopes": [
 {
    "uuid": "_BZbFsWXUEemoItN1K8jw3Q",
    "displayName": "CUD_VM_Group",
    "groupType": "VirtualMachine",
    "isStatic": true,
    "logicalOperator": "AND"
 }
],
"settingsManagers": [
    "uuid": "automationmanager",
    "displayName": "Action Mode Settings",
    "category": "Automation",
    "settings": [
        "uuid": "startVM",
        "displayName": "Start",
        "value": "MANUAL",
        "defaultValue": "RECOMMEND",
        "valueType": "STRING",
        "options": [
            "label": "Disabled",
            "value": "DISABLED"
          },
            "label": "Recommend",
            "value": "RECOMMEND"
          },
            "label": "Manual",
            "value": "MANUAL"
          },
            "label": "Automated",
            "value": "AUTOMATIC"
          }
        ],
        "entityType": "VirtualMachine",
        "sourceGroupName": "Global"
      }
    ]
 }
"disabled": false,
"readOnly": false,
"default": false
```

]



Getting Statistics of an Entity

Referenced Endpoint: Stats (on page 973)

Gets all statistics for the specified entity. This request takes the following parameters:

entity_uuid

The entity whose statistics will be returned.

– C

Used internally by Workload Optimization Manager.

Example: GET https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/stats **Response:** A list of StatSnapshotApiDTOs representing the current values of the statistics.

```
"displayName": "AdityaReplica",
"date": "2019-04-24T20:09:46-04:00",
"statistics": [
 {
    "name": "priceIndex",
    "relatedEntityType": "VirtualMachine",
    "values": {
     "max": 1.01,
     "min": 1.01,
      "avg": 1.01,
     "total": 1.01
   },
    "value": 1.01
 },
  {
    "displayName": "CPUProvisioned/AdityaReplica",
    "name": "CPUProvisioned",
    "capacity": {
      "max": 3120000,
      "min": 3120000,
      "avg": 3120000,
      "total": 3120000
    },
    "relatedEntityType": "VirtualMachine",
    "filters": [
     {
        "type": "relation",
        "value": "bought"
     }
    ],
    "units": "MHz",
    "values": {
      "max": 5200,
     "min": 5200,
     "avg": 5200,
      "total": 5200
   },
    "value": 5200
  },
```



```
{
  "displayName": "Swapping/AdityaReplica",
  "name": "Swapping",
  "capacity": {
    "max": 40000000,
    "min": 40000000,
    "avg": 40000000,
    "total": 40000000
  },
  "relatedEntityType": "VirtualMachine",
  "filters": [
    {
      "type": "relation",
      "value": "bought"
    }
  ],
  "units": "bit/sec",
  "values": {
    "max": 0,
    "min": 0,
    "avg": 0,
    "total": 0
  },
  "value": 0
},
{
  "displayName": "NumDisk/AdityaReplica",
  "name": "NumDisk",
  "capacity": {
    "max": 2147483650,
    "min": 2147483650,
    "avg": 2147483650,
    "total": 2147483650
  "relatedEntityType": "VirtualMachine",
  "filters": [
    {
      "type": "relation",
      "value": "bought"
    }
  ],
  "values": {
    "max": 1,
    "min": 1,
    "avg": 1,
    "total": 1
  },
  "value": 1
},
```

}



Getting a Filtered List of Statistics for an Entity

Referenced Endpoint: Stats (on page 973)

Gets a list of statistics filtered by a user-created StatPeriodApilnputDTO. For more information about the criteria that make up the input for this request, see the Swagger documentation for this request, located at https://cyour_Workload Optimization Manager_IP>/swagger/external/index.html.

Example: POST https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/stats

Example Input: This input will return the values for the VMem, VCPU, and VStorage statistics of the specified entity, ordered first by key, then relatedEntity, then virtualDisk.

```
"statistics": [
      "name": "VMem",
      "groupBy": [
        "key",
        "relatedEntity",
         "virtualDisk"
      ]
    },
      "name": "VCPU",
      "groupBy": [
        "key",
        "relatedEntity",
         "virtualDisk"
      ]
    },
      "name": "VStorage",
      "groupBy": [
        "key",
        "relatedEntity",
        "virtualDisk"
      ]
}
```

Response: An array of StatSnapshotApiDTOs representing the filtered statistics for the entity:



```
"min": 2663,
    "avg": 2663,
    "total": 2663
  },
  "relatedEntityType": "VirtualMachine",
  "filters": [
    {
      "type": "virtualDisk",
     "value": ""
    },
      "type": "key",
      "value": null
    },
      "type": "relation",
      "value": "sold"
    }
  ],
  "relatedEntity": {
    "uuid": "c0849b50a2cce61f57ea0e49e2199503e82f3f54",
    "displayName": "GuestLoad[vEOS-4]",
    "className": "Application"
  },
  "units": "MHz",
  "values": {
    "max": 143,
    "min": 91.47,
    "avg": 91.47,
    "total": 91.47
  },
  "value": 91.47
},
{
  "displayName": "vEOS-4",
  "name": "VMem",
  "capacity": {
   "max": 2097152,
    "min": 2097152,
    "avg": 2097152,
    "total": 2097152
  },
  "relatedEntityType": "VirtualMachine",
  "filters": [
    {
      "type": "virtualDisk",
      "value": ""
    },
    {
      "type": "key",
      "value": null
    },
    {
      "type": "relation",
```



```
"value": "sold"
          }
        ],
        "relatedEntity": {
          "uuid": "c0849b50a2cce61f57ea0e49e2199503e82f3f54",
          "displayName": "GuestLoad[vEOS-4]",
          "className": "Application"
        },
        "units": "KB",
        "values": {
          "max": 188740,
          "min": 130022,
          "avg": 130022,
          "total": 130022
        },
        "value": 130022
      }
  }
1
```

Getting the Supply Chain of an Entity

Referenced Endpoint: Supply Chains (on page 993)

Workload Optimization Manager models your environment as a market of buyers and sellers. It maps the entities it discovers to a supply chain that represents the buy/sell relationships between these entities.

In the user interface, the default view on the Home Page shows the global supply chain. You can change scope to drill down to a supply chain for the relationships to a single entity. This is the same as the result when you get a supply chain for an entity via the API. The returned data is a SupplyChainApiDTO that expresses the scope for the passed entity.

The supply chain shows tiers of entity types, where depth indicates where in the supply chain levels a specific tier is. When you get a supply chain for an entity, the entity is at depth = 0. The depths for tiers above the entity are negative. For example, if a VM is at depth = 0, then the application that consumes from the VM would be at depth = -1. Likewise, providers to the VM would have positive depths. For example, storage that provides resources to the VM would have depth = 1, and a disk array that hosts the storage would have depth = 2.

The supply chain request takes the following parameters:

entity uuid

The entity that sets the scope of the supply chain.

types

An array of strings for the entity types you want to include in the supply chain. If you leave this blank, the call returns the complete supply chain for this entity. If you specify any types, the returned supply chain contains only those types. Note that this rule also applies to the entity that sets the scope (entity_uuid) - If you do not include that entity's type, then the supply chain will not include that entity, even though it sets the scope of the request.

entity_states

An array of strings. Limit the supply chain to include only entities in the given state. Entity states are:

- ACTIVE: The entity is actively consuming resources
- EVACUATED: All consumers have been moved off of the entity, and it can be suspended or terminated
- FAILOVER: The entity is reserved for failover and will not participate in the market
- IDLE: The entity is powered off and not actively consuming market resources
- LAUNCH: The entity is starting up
- MAINTENANCE: The entity is in Maintenance mode
- NOT_MONITORED: Workload Optimization Manager does not currently monitor the entity



- QUEUED: More than ten actions are to be executed for a single target, and this entity has pending actions in the queue
- RESOURCE_ALLOCATION: For internal use
- RESOURCE_RELEASE: For internal use
- SUSPEND: The entity has been placed in Suspend mode
- SUSPEND_PENDING: The entity is making preparations to suspend, or is the next entity of its type to suspend
- TERMINATE_PENDING: The entity is making preparations to terminate, or is the next entity of its type to terminate
- UNKNOWN: Workload Optimization Manager is unable to obtain the current state of the entity
- environment_type

Limit the supply chain to a specific environment type. If you do not specify environment type, the supply chain includes all environments, which is the same as HYBRID. The environment types are:

- HYBRID
- CLOUD
- ONPREM
- detail_type

The level of detail you want in your supply chain. Can be one of:

- compact: Minimal detail about the supply chain items
- entity: The supply chain items include full entity descriptions
- aspects: The supply chain items also include aspects (mata data stored with the entity)
- health

Whether to include a health summary with the entities in the supply chain. false by default.

Example: GET https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073/supplychains?

types=VirtualMachine&types=Storage&types=DiskArray&detail_type=compact&health=true

This example gets a supply chain for a VM entity, with the following settings: including the VM, storage, and disk arrays:

- Only include the VM, its storage, and the disk arrays
- Give compact details
- Show the entity health

Response: The SupplyChainApiDTO for the filtered request:

```
"seMap": {
  "VirtualMachine": {
    "depth": 0,
    "entitiesCount": 1,
    "healthSummary": {
      "Normal": 1
   },
    "stateSummary": {
      "ACTIVE": 1
   },
    "connectedProviderTypes": [
      "PhysicalMachine",
      "Storage",
      "VirtualDataCenter"
    1.
    "connectedConsumerTypes": [
      "Application"
    ],
    "instances": {
      "420b1eeb-6190-a9d2-6436-4327ad3ac073": {
        "links": [
```



```
"rel": "self",
              "href": "https://10.10.10.10/api/v3/entities/420bleeb-6190-a9d2-6436-4327ad3ac073?include_a
spects=false"
          ],
          "uuid": "420b1eeb-6190-a9d2-6436-4327ad3ac073",
          "displayName": "vEOS-4",
          "className": "VirtualMachine",
          "priceIndex": 1.1463195,
          "state": "ACTIVE",
          "severity": "Normal",
          "discoveredBy": {
            "uuid": "_FJwg0EzHEemaXZFqO1sC0g",
            "displayName": "vsphere-dc11.dev.mycorp.com",
           "type": "vCenter"
          "remoteId": "vm-100",
          "environmentType": "ONPREM"
      }
    },
    "Storage": {
      "depth": 1,
      "entitiesCount": 2,
      "healthSummary": {
        "Normal": 2
      },
      "stateSummary": {
        "ACTIVE": 2
      },
      "connectedProviderTypes": [
        "DiskArray"
      "connectedConsumerTypes": [
        "PhysicalMachine",
        "VirtualMachine"
      ],
      "instances": {
        "5a822e24-584bce98-ecb2-441ea15e2534": {
          "links": [
            {
              "rel": "self",
              "href": "https://10.10.10.10/api/v3/entities/5a822e24-584bce98-ecb2-441ea15e2534?include_a
spects=false"
          "uuid": "5a822e24-584bce98-ecb2-441ea15e2534",
          "displayName": "SCIO:ESXDC11DS2",
          "className": "Storage",
          "priceIndex": 1.2797012,
          "state": "ACTIVE",
          "severity": "Normal",
          "discoveredBy": {
```



```
"uuid": "_FJwg0EzHEemaXZFq01sC0g",
       "displayName": "vsphere-dc11.dev.mycorp.com",
       "type": "vCenter"
     },
     "remoteId": "datastore-2357",
      "environmentType": "ONPREM",
      "tags": {
       "Datastore_DC11": [
         "True"
       ]
     }
   },
    "9bd4ee88-99c64661": {
     "links": [
          "rel": "self",
          "href": "https://10.10.10.10.10/api/v3/entities/9bd4ee88-99c64661?include_aspects=false"
     ],
     "uuid": "9bd4ee88-99c64661",
      "displayName": "QS1:NFSShare",
     "className": "Storage",
     "priceIndex": 20000,
     "state": "ACTIVE",
      "severity": "Normal",
     "discoveredBy": {
       "uuid": "_gOQEYEaREemB8r4uTzazvA",
       "displayName": "vsphere-dc5.dev.mycorp.com",
        "type": "vCenter"
     },
      "remoteId": "datastore-1411",
      "environmentType": "ONPREM",
     "tags": {
       "DimStor": [
         "DimStorTag"
       "Datastore_DC11": [
         "True"
       ],
       "Test_Tag": [
          "MyStorageTag"
       ]
   }
 }
"DiskArray": {
 "depth": 2,
 "entitiesCount": 2,
  "healthSummary": {
    "Normal": 2
 },
  "stateSummary": {
    "ACTIVE": 2
```

},



```
},
      "connectedConsumerTypes": [
        "Storage"
      ],
      "instances": {
        "DiskArray-9bd4ee88-99c64661": {
          "links": [
              "rel": "self",
              "href": "https://10.10.10.10/api/v3/entities/DiskArray-9bd4ee88-99c64661?include_aspects=f
alse"
            }
          ],
          "uuid": "DiskArray-9bd4ee88-99c64661",
          "displayName": "DiskArray-QS1:NFSShare",
          "className": "DiskArray",
          "priceIndex": 0,
          "state": "ACTIVE",
          "severity": "Normal",
          "discoveredBy": {
            "uuid": "_oQ2aIEG1EemgjaEqcE-BJw",
            "displayName": "vsphere-dc13.dev.mycorp.com",
            "type": "vCenter"
          },
          "remoteId": "datastore-982",
          "environmentType": "ONPREM"
        "DiskArray-5a822e24-584bce98-ecb2-441ea15e2534": {
          "links": [
            {
              "rel": "self",
              "href": "https://10.10.10.10/api/v3/entities/DiskArray-5a822e24-584bce98-ecb2-441ea15e2534?
include_aspects=false"
          ],
          "uuid": "DiskArray-5a822e24-584bce98-ecb2-441ea15e2534",
          "displayName": "DiskArray-SCIO:ESXDC11DS2",
          "className": "DiskArray",
          "priceIndex": 0,
          "state": "ACTIVE",
          "severity": "Normal",
          "discoveredBy": {
            "uuid": "_FJwg0EzHEemaXZFqO1sC0g",
            "displayName": "vsphere-dcl1.dev.mycorp.com",
            "type": "vCenter"
          },
          "remoteId": "datastore-2357",
          "environmentType": "ONPREM"
     }
    }
 }
```



Getting the Tags on an Entity

Referenced Endpoint: Tags (on page 996)

Workload Optimization Manager discovers tags and tag values that are assigned to different entities in your environment. This call returns the tag and value sets for the entity you pass.

Example: GET https://10.10.10.10/api/v3/entities/9bd4ee88-99c64661/tags

Response: A TagApiDTO for the passed entity. This gives an array of key/value pairs, where the value is an array of strings.

```
{
    "key": "Datastore_DC11",
    "values": [
        "True"
    ]
},
{
    "key": "Test_Tag",
    "values": [
        "MyStorageTag"
    ]
},
{
    "key": "DimStor",
    "values": [
        "DimStorTag"
    ]
}
```

Groups Endpoint

A group is a collection of entities (such as physical machines, containers, clusters, or even other groups) that Workload Optimization Manager can work with as a unit. The most common use of groups is to set scope for display in charts or for processing in plans, and to retrieve statistics for a subset of your environment.

This endpoint contains references to start and end times for certain operations. For more information, including valid time formats, see <u>Time in the Workload Optimization Manager API (on page 742)</u>

Using the groups endpoint of the Workload Optimization Manager API, you can:

- Get a list of all groups on your Workload Optimization Manager appliance
- Create a group
- Edit a group
- Delete a group
- Get a list of actions for a specified groups
- Get a list of entities in a specified group
- Get parent groups of a specified group
- Get a list of members of a specified group
- Get a list of notifications for a specified group
- Get a list of settings for a specified group
- Get a list of policies for a specified group
- Get statistics for a specified group



- Get the supply chain related to a specified group
- Get the tags belonging to a specified group

Group Types and Class Names

Workload Optimization Manager subdivides the entities on your appliance by the following group class name, to aid in both searching and understanding the purpose of a group:

■ Folder

These appear in the user interface as folders, and are for visual organization. Discovered folders represent the folder structure in the target – for example, the vCenter folder structure. In addition, Workload Optimization Manager discovers vCenter Server resource pools, and groups them into folders.

■ Group

Workload Optimization Manager places discovered entities into standard groups, and users can create groups of their own with static or dynamic membership.

RefGroup

A RefGroup can be a group of groups- for example, a group of PM cluster groups that make up a hypervisor targetor a group defined by a relationship. For example, the built-in group PMsByDatacenter is a RefGroup reflecting the relationship between the datacenters and hosts.

Cluster / StorageCluster

Groups that correspond to discovered clusters.

DiscoveredGroup

Groups that are defined by a target service. For example, Workload Optimization Manager can discover DRS domains that were defined in vCenter Server.

MarketGroup

A group that is based on the infrastructure cost of that entity type. These groups are based on the Infrastructure Cost settings in the Workload Optimization Manager policies.

StaticMetaGroup / RefMetaGroup / MetaGroup

Groups used internally by Workload Optimization Manager. These should not be modified in any way.

In addition, each group has a groupType that identifies the type of members that group contains. Remember that when you create a group in the user interface or via the API, you cannot add more than one type of member. The different group types include:

Cluster

A group of clusters. For example, you could create a group of all PM clusters that include the name "Development".

ServiceEntity

An internal group type reserved for groups that Workload Optimization Manager discovers or creates. Note that the group will still contain members of only one type.

Entity Type

- APPLICATION
- APPLICATION SERVER
- BUSINESS ACCOUNT
- BUSINESS_UNIT
- CHASSIS
- CLOUD_SERVICE
- CONTAINER
- CONTAINER_POD
- DATABASE
- DATABASE SERVER
- DATACENTER
- DISK_ARRAY
- DPOD



- IO_MODULE
- LOAD_BALANCER
- LOGICAL_POOL
- NETWORK
- PHYSICAL_MACHINE
- STORAGE
- STORAGE_CONTROLLER
- SWITCH
- VIRTUAL APPLICATION
- VIRTUAL_DATACENTER
- VIRTUAL MACHINE
- VPOD

Understanding the different group types helps you find the group you want. If you know the name of a specific group, then you can filter the returned list for a group of that name. Or if you want to step through all the clusters Workload Optimization Manager has discovered, you can filter all the entries with a className of Cluster or StorageCluster.

Group Filter Types

Workload Optimization Manager utilizes regex and a filterType to build a group. The filterType is the criterion to which the regex will match. For example, a filterType of pmsByName will apply the regex to the display names of physical machines.

The available options for this parameter depend on the entity making up your group:

- VirtualMachine
 - vmsByName
 - vmsByPMName
 - vmsByStorage
 - vmsByNetwork
 - vmsByApplication
 - vmsByDatabaseServer
 - vmsByDatabaseServerVersion
 - vmsByDC
 - vmsByVDC
 - vmsByDCnested
 - vmsByNumCPUs
 - vmsByMem
 - vmsByGuestName
 - vmsByAltName
 - vmsByClusterName
 - vmsByDiskArrayName
 - vmsByLogicalPoolName
 - vmsByTag
 - vmsByState
 - vmsByBusinessAccountUuid
 - vmsByResourceGroupUuid
- VirtualDataCenter
 - vdcsByName
 - vdcsByVDCName
 - vdcsByTag
 - vdcsByState

PhysicalMachine

- pmsByName
- pmsByStorage
- pmsByNetwork
- pmsBySwitch
- pmsByNumVms
- pmsByDC
- pmsByMem
- pmsByNumCPUs
- pmsByVendorName
- pmsByCPUModel
- pmsByModel
- pmsByTimezone
- pmsByClusterName
- pmsByTag
- pmsByState

Storage

- storageByName
- storageByTag
- storageByVMs
- storageByDC
- storageByPMCluster
- storageByState
- volumeByDeletable

Application Component

- appSrvsByName
- appsByName
- WebServer
 - wbSrvsByName
- BusinessApplication
 - busAppsByName
- Database
 - databaseByName
 - databaseByTag
 - databaseByBusinessAccountUuid
 - databaseByResourceGroupUuid
- DatabaseServer
 - databaseServerByName
 - databaseServerByTag
 - databaseServerByBusinessAccountUuid
 - databaseServerByEngine
 - databaseServerByEdition
 - databaseServerByVersion
- VirtualApplication
 - vappsByName
- Cluster
 - clustersByName
 - clustersByTag



- DataCenter
 - datacentersByName
 - datacentersByTag
- Group
 - groupsByName
- StorageCluster
 - storageClustersByName
- DiskArray
 - diskarrayByName
- Zone
 - zonsByName
- Region
 - regsByName
- Network
 - netsByName
- LoadBalancer
 - IbsByName
- Chassis
 - chasByName
- StorageController
 - storagecontrollerByName
- DPod
 - dpodByName
- VPod
 - vpodByName
- LogicalPool
 - logicalPoolByName
- Switch
 - switchByName
- Container
 - containersByName
 - containersByPodName
 - containersByVMName
 - containersByNamespace
 - containerSpecsByName
- ContainerPod
 - containerPodsByName
 - containerPodsByNamespace
 - containerPodsByVMName
- ServiceEntity

NOTE: Groups of type ServiceEntity are the only groups that have multiple entity types, and are used exclusively for cloud targets.

- workloadByBusinessAccountUuid
- workloadByResourceGroupUuid
- Workload
 - workloadByBusinessAccountUuid



- workloadByResourceGroupUuid
- workloadControllersByName
- workloadControllersByNamespace
- workloadControllersByKind
- ResourceGroup
- resourceGroupByName
- resourceGroupByUuid
- resourceGroupByBusinessAccountUuid
- BusinessAccount
 - businessAccountByName
 - businessAccoutByUuid
 - subBusinessAccountOfUuid
 - businessAccountValidationStatus
 - businessAccountTargetName
 - businessAccountCloudProvider
- BillingFamily
 - billingFamilyByName
- ViewPod
 - viewPodByName
- DesktopPool
 - desktopPoolByName
 - desktopPoolByViewPod
- BusinessUser
 - businessUserByDesktopPool
 - businessUserByName
 - businessUserByViewPod
- Cloud-Specific Filters
 - computeTiersByName
 - computeTiersByMem
 - databaseTiersByName
 - databaseTiersBvDBMem
 - databaseServerTiersByName
 - databaseServerTiersByVMem

Note that in the case of a discovered resource group, group members can be discovered by multiple targets. In that case, the Workload Optimization Manager API returns a single target for the group.

Groups Requests

Pagination for Group Requests

When you request group data, the API uses pagination to return subsets of the data. You should always use pagination when available to make sure you get your data in manageable chunks. To paginate returned data, the limit, orderBy, and cursor parameters control how the APIs paginate their data. If you do not specify a limit for the following requests, the API will paginate the data to a default limit of records:

- GET /groups
- GET /groups/<groupId>/members
- GET /groups/<groupId>/entities

If your scripts make these requests without setting a limit, you should be sure they check for a pagination cursor in the returned data.



For general information about pagination, see Pagination in the Workload Optimization Manager API (on page 742).

Getting a List of Groups

Gets a list of all groups on your Workload Optimization Manager appliance. This will include Workload Optimization Manager internal and default groups, as well as any groups discovered from your targets, in addition to your custom groups.

Example: GET https://10.10.10.10/api/v3/groups

Response: A list of GroupApiDTOs representing the groups on your appliance.

```
[
    "links": [
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/groups/_S4k98SFQEd-S4dn3K4_SSA?include_aspects=false"
    ],
    "uuid": "_S4k98SFQEd-S4dn3K4_SSA",
    "displayName": "Datacenters",
    "className": "Group",
    "environmentType": "ONPREM",
    "entitiesCount": 12,
    "membersCount": 12,
    "groupType": "DataCenter",
    "severity": "Critical",
    "isStatic": false,
    "logicalOperator": "AND",
    "activeEntitiesCount": 44
 },
    "links": [
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/groups/_S4k94SFQEd-S4dn3K4_SSA?include_aspects=false"
      }
    ],
    "uuid": "_S4k94SFQEd-S4dn3K4_SSA",
    "displayName": "Chassis",
    "className": "Group",
    "environmentType": "ONPREM",
    "entitiesCount": 2,
    "membersCount": 1,
    "groupType": "Chassis",
    "severity": "Normal",
    "isStatic": false,
    "logicalOperator": "AND",
    "activeEntitiesCount": 2
 },
]
```

Creating a Group

In order to create a group in Workload Optimization Manager, provide a GroupApiDTO with a groupType and isStatic.

For a dynamic group (isStatis = false), you also include the criteriaListinformation:

caseSensitive

If true, the regex will be evaluated as case-sensitive.

- expType
- For strings, the allowable values are EQ and NEQ (Equals, Does Not Equal). For integers, you may additionally use GT, LT, GTE, LTE (Greater than, less than, greater than or equal to, and less than or equal to, respectively).
- expVal

The value of the regular expression.

filterType

See Group Filter Types for a full list of available options

For a static group:

- Provide UUIDs for each entity that is a member of the group in the memberJuidList
- DO NOT provide any criteriaList parameters

Example: POST https://10.10.10.10/api/v3/groups/

Example input, showing the creation of a dynamic group of VMs whose names start with "AJ":

Response:



Example input, showing the creation of a static group of Hosts:

```
"isStatic": true,

"displayName": "Dallas-Static",

"memberUuidList": [

"4C4C4544-0042-5A10-804A-B1C04F384331",

"4C4C4544-004A-3610-8057-C8C04F464331",

"Virtual_ESX_42381e13-4256-64bb-f554-d17798ddb2ba"
],

"criteriaList": [],

"groupType": "PhysicalMachine"
```

Response:

Editing a Group

In order to edit a user-created group, send the complete GroupApiDTO with your changes as the input to this request.

Example: PUT https://10.10.10.10/api/v3/groups/_Y6BL4FDQEemD69d9a0uLJQ

Example Input:A modified GroupApiDTO. In this case, the expVal parameter has been modified.

```
{
  "isStatic": false,
  "displayName": "Dallas-Host",
```



Response: The full GroupApiDTO reflecting your changes:

```
"links": [
  {
    "rel": "self",
    "href": "https://10.10.10.10/api/v3/groups/_Y6BL4FDQEemD69d9a0uLJQ?include_aspects=false"
  }
],
"uuid": "_Y6BL4FDQEemD69d9a0uLJQ",
"displayName": "Dallas-Host",
"className": "Group",
"environmentType": "ONPREM",
"entitiesCount": 0,
"membersCount": 0,
"groupType": "PhysicalMachine",
"severity": "Normal",
"isStatic": false,
"logicalOperator": "AND",
"criteriaList": [
    "expVal": "hp*change",
    "expType": "EQ",
    "filterType": "pmsByName",
    "caseSensitive": false
  }
],
"activeEntitiesCount": 0
```

Deleting a Group

To delete a user-created group, pass the UUID of the group in the URL of the request.

Example: DELETE https://10.10.10.10/api/v3/groups/_vn_u0FJ0EemD69d9a0uLJQ

Response: A response of 200 indicates successful deletion.

Getting Actions Related to a Group

Referenced Endpoint: Actions (on page 753)



Gets a list of actions relating to the entities in the specified group. To get a single action, include the UUID of the action in the request. This request takes the following parameters:

group_Uuid

The UUID of the group whose actions will be returned.

cursor

When making subsequent calls to retrieve additional results, this is the cursor returned by the last call to this method.

limit

The maximum number of items to return. Must be a positive integer. If not set, the server will provide a default (20).

order_by

The field to order the results by. [creation_date, name, risk_category, savings, severity].

ascending

Default: true. When false, results will be in descending order.

Examples:

All actions: GET https://10.10.10.10/api/v3/groups/421dd4ce-a4c1-231a-71e7-64fbf598bc65/actions?limit=50&order_by=creation_date&ascending=true

Single action: GET https://10.10.10.10.10/api/v3/groups/421dd4ce-a4c1-231a-71e7-64fbf598bc65/actions/_pJg98EQaEemD69d9a0uLJQ

Response: A list of ActionApiDTOs related to the specified group:

```
[
  {
    "links": [
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/actions/_pJg98EQaEemD69d9a0uLJQ"
     },
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/actions/2500817580000"
      }
    ],
    "uuid": "_pJg98EQaEemD69d9a0uLJQ",
    "createTime": "2019-03-11T12:28:03-04:00",
    "actionType": "RIGHT_SIZE",
    "actionState": "PENDING_ACCEPT",
    "actionMode": "MANUAL",
    "details": "Scale down Memory reservation for Virtual Machine 'AJ_Test' from 2 GB to 1 GB",
    "importance": 0,
    "target": {
      "uuid": "421dd4ce-a4c1-231a-71e7-64fbf598bc65",
      "displayName": "AJ_Test",
      "className": "VirtualMachine",
      "aspects": {
        "virtualMachineAspect": {
          "os": "CentOS 4/5/6/7 (64-bit)",
          "ip": [
            "10.10.10.107"
          "connectedNetworks": [
              "uuid": "34f9f5364cd843aa1fe99900621ee3b51a7dc6e5",
              "displayName": "VM Network"
```



```
}
        ],
        "numVCPUs": 1,
        "ebsOptimized": false
    },
    "environmentType": "ONPREM"
  },
  "currentEntity": {
    "uuid": "_pJlPYUQaEemD69d9a0uLJQ",
    "className": "Mem"
  },
  "newEntity": {
    "uuid": "_pLCA40QaEemD69d9a0uLJQ",
    "className": "Mem",
    "aspects": {
      "virtualMachineAspect": {
       "os": "Linux (Free)",
        "ebsOptimized": false
      }
    }
  },
  "currentValue": "2097152.0",
  "newValue": "1048576.0",
  "resizeToValue": "1048576.0",
  "risk": {
   "uuid": "_pL_qMEQaEemD69d9a0uLJQ",
    "subCategory": "Efficiency Improvement",
    "description": "Underutilized Memory reservation",
    "severity": "MINOR",
    "importance": 0
  },
  "currentLocation": {
   "uuid": "cdcd967d1e08d20936c3aa9a0879c635214c79ee",
    "displayName": "ACM",
    "className": "DataCenter"
  },
  "newLocation": {
    "uuid": "cdcd967d1e08d20936c3aa9a0879c635214c79ee",
    "displayName": "ACM",
    "className": "DataCenter"
  },
  "actionID": 2500817580000
},
  "links": [
      "rel": "self",
      "href": "https://10.10.10.10/api/v3/actions/_XdP4EEQ8EemD69d9a0uLJQ"
    },
    {
      "rel": "self",
      "href": "https://10.10.10.10/api/v3/actions/2501049335840"
    }
```



```
],
"uuid": "_XdP4EEQ8EemD69d9a0uLJQ",
"createTime": "2019-03-11T16:29:28-04:00",
"actionType": "RIGHT_SIZE",
"actionState": "PENDING_ACCEPT",
"actionMode": "MANUAL",
"details": "Remove VMem limit for VirtualMachine AJ_Test to maximize efficiency",
"importance": 0,
"target": {
  "uuid": "421dd4ce-a4c1-231a-71e7-64fbf598bc65",
  "displayName": "AJ_Test",
  "className": "VirtualMachine",
  "aspects": {
    "virtualMachineAspect": {
      "os": "CentOS 4/5/6/7 (64-bit)",
      "ip": [
       "10.10.10.107"
      ],
      "connectedNetworks": [
          "uuid": "34f9f5364cd843aa1fe99900621ee3b51a7dc6e5",
          "displayName": "VM Network"
        }
      ],
      "numVCPUs": 1,
      "ebsOptimized": false
  },
  "environmentType": "ONPREM"
},
"currentEntity": {
  "uuid": "_XdP4EkQ8EemD69d9a0uLJQ",
  "className": "VMem"
},
"newEntity": {
  "uuid": "_Xnq_YUQ8EemD69d9a0uLJQ",
  "className": "VMem",
  "aspects": {
    "virtualMachineAspect": {
      "os": "Linux (Free)",
      "ebsOptimized": false
    }
  }
},
"currentValue": "2097152.0",
"newValue": "0.0",
"resizeToValue": "0.0",
"risk": {
  "uuid": "_XnuCsUQ8EemD69d9a0uLJQ",
  "subCategory": "Efficiency Improvement",
  "description": "VMem congestion in Virtual Machine 'AJ_Test'",
  "severity": "MAJOR",
  "reasonCommodity": "VMem",
  "importance": 0
```



```
},
    "currentLocation": {
        "uuid": "cdcd967dle08d20936c3aa9a0879c635214c79ee",
        "displayName": "ACM",
        "className": "DataCenter"
},
    "newLocation": {
        "uuid": "cdcd967dle08d20936c3aa9a0879c635214c79ee",
        "displayName": "ACM",
        "className": "DataCenter"
},
        "actionID": 2501049335840
}
```

Getting the Entities in a Group

Referenced Endpoint: Entities (on page 791)

Gets all entities contained within a group.

NOTE: This request will not return the contents of nested groups. In order to see groups of groups, use the groups/members request.

Example: GET https://10.10.10.10/api/v3/groups/_4L0PcE9SEemD69d9a0uLJQ/entities **Response:** A list of EntityApiDTOs representing the entities in the specified group.

```
[
    "links": [
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/actions/_pJg98EQaEemD69d9a0uLJQ"
     },
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/actions/2500817580000"
     }
    ],
    "uuid": "_pJg98EQaEemD69d9a0uLJQ",
    "createTime": "2019-03-11T12:28:03-04:00",
    "actionType": "RIGHT_SIZE",
    "actionState": "PENDING_ACCEPT",
    "actionMode": "MANUAL",
    "details": "Scale down Memory reservation for Virtual Machine 'AJ_Test' from 2 GB to 1 GB",
    "importance": 0,
    "target": {
      "uuid": "421dd4ce-a4c1-231a-71e7-64fbf598bc65",
     "displayName": "AJ_Test",
     "className": "VirtualMachine",
      "aspects": {
        "virtualMachineAspect": {
          "os": "CentOS 4/5/6/7 (64-bit)",
          "ip": [
           "10.10.10.107"
```



```
],
      "connectedNetworks": [
          "uuid": "34f9f5364cd843aa1fe99900621ee3b51a7dc6e5",
          "displayName": "VM Network"
      ],
      "numVCPUs": 1,
      "ebsOptimized": false
    }
 },
  "environmentType": "ONPREM"
},
"currentEntity": {
  "uuid": "_pJlPYUQaEemD69d9a0uLJQ",
  "className": "Mem"
},
"newEntity": {
  "uuid": "_pLCA40QaEemD69d9a0uLJQ",
  "className": "Mem",
  "aspects": {
    "virtualMachineAspect": {
      "os": "Linux (Free)",
      "ebsOptimized": false
    }
  }
},
"currentValue": "2097152.0",
"newValue": "1048576.0",
"resizeToValue": "1048576.0",
"risk": {
  "uuid": "_pL_qMEQaEemD69d9a0uLJQ",
  "subCategory": "Efficiency Improvement",
  "description": "Underutilized Memory reservation",
  "severity": "MINOR",
  "importance": 0
},
"currentLocation": {
  "uuid": "cdcd967d1e08d20936c3aa9a0879c635214c79ee",
  "displayName": "ACM",
  "className": "DataCenter"
},
"newLocation": {
  "uuid": "cdcd967d1e08d20936c3aa9a0879c635214c79ee",
  "displayName": "ACM",
  "className": "DataCenter"
"actionID": 2500817580000
```

]



Getting the Parent Groups of a Group

For a specified group, gets any group that the specified group belongs to.

NOTE: Workload Optimization Manager contains a default parent group for user-created groups called "My Groups". This group should not be modified or deleted.

This request takes the following parameters:

- group_Uuid
 - The UUID of the group whose actions will be returned.
- path

Default: false. When true, this request returns the parent group, along with any groups traversed to obtain the parent group. For groups that are not nested, this returns the group whose ID you entered and its parent group.

Example: GET https://10.10.10.10/api/v3/groups/_4L0PcE9SEemD69d9a0uLJQ/groups?path=true **Response:** A list of GroupApiDTOs representing the group and parent group.

```
"links": [
    {
      "rel": "self",
      "href": "https://10.10.10.10/api/v3/groups/_S4k68yFvEd-S4dn3T4_SSA?include_aspects=false"
    }
  ],
  "uuid": "_S4k68yFvEd-S4dn3T4_SSA",
  "displayName": "My Groups",
  "className": "Group",
  "environmentType": "ONPREM",
  "entitiesCount": 1,
  "membersCount": 3,
  "groupType": "ServiceEntity",
  "severity": "Major",
  "isStatic": false,
  "logicalOperator": "AND",
  "activeEntitiesCount": 1
},
  "links": [
    {
      "rel": "self",
      "href": "https://10.10.10.10/api/v3/groups/_4L0PcE9SEemD69d9a0uLJQ?include_aspects=false"
    }
  ],
  "uuid": "_4L0PcE9SEemD69d9a0uLJQ",
  "displayName": "Dallas-Dynamic",
  "className": "Group",
  "environmentType": "ONPREM",
  "entitiesCount": 1,
  "membersCount": 1,
  "groupType": "VirtualMachine",
  "severity": "Major",
  "isStatic": false,
  "logicalOperator": "AND",
  "criteriaList": [
```



```
{
    "expVal": "AJ.*",
    "expType": "EQ",
    "filterType": "vmsByName",
    "caseSensitive": false
    }
    ],
    "activeEntitiesCount": 1
}
```

Getting the Members of a Group

Referenced Endpoint: Entities (on page 791)

Gets all members of a group.

NOTE: This request returns nested groups and the member entities of each. To get only the *entities* in the specified group, use the groups/entities request.

Example: GET https://10.10.10.10/api/v3/groups/_4L0PcE9SEemD69d9aOuLJQ/members

Response: A list of serviceEntityApiDTOs representing the members of the group:

```
"links": [
     {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/entities/183b37c68211668aecd36eadcdce9110ebc58f85?include_asp
ects=false"
     }
    ],
    "uuid": "183b37c68211668aecd36eadcdce9110ebc58f85",
   "displayName": "Olga",
   "className": "VirtualDataCenter",
   "priceIndex": 1,
    "state": "ACTIVE",
   "severity": "Normal",
    "discoveredBy": {
     "uuid": "_h3Km4Bs3EemMFrqlXNi1yQ",
      "displayName": "vsphere-dc23.corp.vmturbo.com",
     "type": "vCenter"
   },
    "remoteId": "resgroup-96",
    "environmentType": "ONPREM"
 },
    "links": [
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/entities/2332ba0f9dc14c07f11adb38e12df43c4bc8ca56?include_asp
ects=false"
     }
    ],
    "uuid": "2332ba0f9dc14c07f11adb38e12df43c4bc8ca56",
```



```
"displayName": "olga_do_not_touch_1",
    "className": "VirtualDataCenter",
    "priceIndex": 1,
    "state": "ACTIVE",
    "severity": "Normal",
    "discoveredBy": {
      "uuid": "_5kMqwNLnEeiJs9KWCzOdUQ",
      "displayName": "vsphere-dc1.dev.mycorp.com",
      "type": "vCenter"
    },
    "remoteId": "resgroup-1088",
    "environmentType": "ONPREM"
  },
    "links": [
     {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/entities/6668eb0940bf970d24eb13279b31a52f3c44a91f?include_asp
ects=false"
     }
    ],
    "uuid": "6668eb0940bf970d24eb13279b31a52f3c44a91f",
    "displayName": "Gilad",
    "className": "VirtualDataCenter",
    "priceIndex": 1,
    "state": "ACTIVE",
    "severity": "Normal",
    "discoveredBy": {
      "uuid": "_lj_tkH39EeiKy53b3GBglA",
      "displayName": "vsphere-dc5.dev.mycorp.com",
      "type": "vCenter"
    },
    "remoteId": "resgroup-1953",
    "environmentType": "ONPREM"
  },
    "links": [
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/entities/20b9e0acf4c6f7d5b00f744d1dc954616095f1f2?include_asp
ects=false"
     }
    ],
    "uuid": "20b9e0acf4c6f7d5b00f744d1dc954616095f1f2",
    "displayName": "ACM",
    "className": "VirtualDataCenter",
    "priceIndex": 1,
    "state": "ACTIVE",
    "severity": "Normal",
    "discoveredBy": {
      "uuid": "_lj_tkH39EeiKy53b3GBglA",
     "displayName": "vsphere-dc5.dev.mycorp.com",
     "type": "vCenter"
    },
```



```
"remoteId": "resgroup-v1946",
    "environmentType": "ONPREM"
 },
    "links": [
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/entities/56e6cfd2bc88ef5675df9dc3e06796ceb8b6e301?include_asp
ects=false"
     }
    ],
    "uuid": "56e6cfd2bc88ef5675df9dc3e06796ceb8b6e301",
    "displayName": "olga_do_not_touch_7",
    "className": "VirtualDataCenter",
    "priceIndex": 1,
   "state": "ACTIVE",
    "severity": "Normal",
    "discoveredBy": {
     "uuid": "_GRNtoNu0Eeilt9UDtI29QA",
     "displayName": "vsphere-dc7.dev.mycorp.com",
      "type": "vCenter"
   },
    "remoteId": "resgroup-1066",
    "environmentType": "ONPREM"
 }
]
```

Getting Settings of a Group

Referenced Endpoint: Settings (on page 963)

Gets both global and user-modified settings for the specified group. To get a single setting, pass the setting UUID as part of the request URL. This request takes the following parameters:

■ group_Uuid

The Uuid of the group whose settings will be returned

include_settingspolices

Default: false. When true, returns the settings policies affecting the specified group, in addition to the settings.

Example: GET https://10.10.10.10/api/v3/groups/_WvaGkOBjEeierZ9b1bxmgg/settings?include settingspolicies=false

Response: A list of SettingsManagerApiDTOs representing the settings, or settings and settings policies for the specified group:



```
"valueType": "STRING",
      "entityType": "VirtualMachine",
      "sourceGroupName": "Global"
    },
    {
      "uuid": "Password",
      "displayName": "Password",
      "value": "",
      "defaultValue": "",
      "valueType": "STRING",
      "entityType": "VirtualMachine",
      "sourceGroupName": "Global"
    },
    . . .
  },
  {
  "uuid": "controlmanager",
  "displayName": "Action Workflow",
  "category": "Automation",
  "settings": [
    {
      "uuid": "moveVMWorkflow",
      "displayName": "Move Workflow",
      "value": "",
      "defaultValue": "",
      "valueType": "STRING",
      "entityType": "VirtualMachine",
      "sourceGroupName": "Global"
    }
  ]
}
```

Editing a Specified Setting of a Group

Referenced Endpoint: Settings (on page 963)

Edits a specified setting for the specified group. This request takes the following parameters:

- group_Uuid
 - The Uuid of the group whose setting will be edited
- settingsManager_Uuid
 - The Uuid of the settings manager whose setting will be edited
- setting_Uuid

The Uuid of the setting to change

Example: PUT https://10.10.10.10/api/v3/groups/_WvaGkOBjEeierZ9b1bxmgg/settings/appsettingsmanager/Retry_Interval

Example Input:

The new value for the setting:

```
{
    "value": "61"
```



}

Response: A ServiceEntityApiDTO representing the specified setting, with your changed value(s):

```
"uuid": "Retry_Interval",
  "displayName": "Retry Interval [mins]",
  "value": "61",
  "defaultValue": "60.0",
  "valueType": "NUMERIC",
  "min": 0,
  "max": 50000,
  "entityType": "VirtualMachine",
  "sourceGroupName": "A_Few_ACM_VMs"
```

Getting Settings Policies of a Group

Referenced Endpoint: Settings Policies (on page 967)

Gets the settings policies of the specified group.

Example:

Response:

Getting Statistics of a Group

Referenced Endpoint: Stats (on page 973)

Gets all statistics for the specified group:

NOTE:

When you retrieve statistics for a cluster, using the /groups endpoint will return the aggregated statistics for all applicable cluster entities. For individual stats per entity, use the /stats endpoint.

Some statistics are only valid for certain scopes. When you request given statistics for a scope that doesn't include them, the API does not return any data. For example, the numVMs statistic is valid in only the Market and Cluster scopes – the API omits numVMs data from the response when you query other scopes.

Example: https://10.10.10.10/api/v3/groups/_WvaGkOBjEeierZ9b1bxmgg/stats

Response: A list of StatSnapshotApiDTOs representing the statistics for the specified group:



```
},
{
  "displayName": "(multiple)",
  "name": "Q1VCPU",
  "capacity": {
    "max": 20000,
    "min": 20000,
    "avg": 20000,
    "total": 60000
  "reserved": {
    "max": 10000,
    "min": 10000,
    "avg": 10000,
    "total": 30000
  },
  "filters": [
    {
      "type": "relation",
      "value": "bought"
  ],
}
]
```

Getting a Filtered List of Statistics of a Group

Referenced Endpoint: Stats (on page 973)

Gets a filtered list of statistics for the specified group. For more information about creating a filtered list of statistics, including example POSTs and responses, see *Filtered Statistics* in the <u>Statistics Endpoint (on page 973)</u>

Example: POST https://10.10.10.10/api/v3/groups/_WvaGkOBjEeierZ9b1bxmgg/stats

Example input:

}

Response: A list of StatSnapshotApiDTOs representing the statistics for the specified group:



```
"displayName": "A_Few_ACM_VMs",
"date": "2019-03-24T00:00:00-04:00",
"statistics": [
 {
    "name": "Mem",
    "capacity": {
     "max": 134214448,
      "min": 134214448,
      "avg": 134214448,
     "total": 1073715580
   },
    "filters": [
       "type": "relation",
       "value": "bought"
     }
    ],
    "units": "KB",
    "values": {
     "max": 2073084,
     "min": 679782.1,
     "avg": 1124840.4,
     "total": 4499361.5
   },
    "value": 1124840.4
 },
  {
    "name": "MemAllocation",
    "capacity": {
     "max": 504346624,
      "min": 504346624,
     "avg": 504346624,
     "total": 4034772990
   },
    "filters": [
     {
        "type": "relation",
       "value": "bought"
     }
    ],
    "units": "KB",
    "values": {
     "max": 2073084,
      "min": 679782.1,
      "avg": 1124840.4,
     "total": 4499361.5
   },
    "value": 1124840.4
 },
  {
    "name": "Q1VCPU",
    "capacity": {
```



```
"max": 20000,
      "min": 20000,
      "avg": 20000,
      "total": 120000
    },
    "filters": [
      {
        "type": "relation",
        "value": "bought"
      }
    ],
    "values": {
      "max": 90,
      "min": 14,
      "avg": 41.08,
      "total": 123.23
   },
    "value": 41.08
 }
]
```

Getting the Supply Chain of a Group

Referenced Endpoint: Supply Chains (on page 993)

Using one or more of the following parameters, you can filter the supply chain that is returned by this request:

market_Uuid

The UUID of the market whose supply chain will be returned

■ types

The entity types whose supply chain will be returned. Choose from:

- APPLICATION
- APPLICATION_SERVER
- BUSINESS_ACCOUNT
- BUSINESS_UNIT
- CHASSIS
- CLOUD_SERVICE
- CONTAINER
- CONTAINER_POD
- DATABASE
- DATABASE_SERVER
- DATACENTER
- DISK_ARRAY
- DPOD
- IO_MODULE
- LOAD_BALANCER
- LOGICAL_POOL
- NETWORK
- PHYSICAL_MACHINE



- STORAGE
- STORAGE_CONTROLLER
- SWITCH
- VIRTUAL_APPLICATION
- VIRTUAL_DATACENTER
- VIRTUAL_MACHINE
- VPOD
- entity_states

Only return entities in the specified states. Choose from:

- ACTIVE:

Entity is actively consuming resources.

EVACUATED:

Entity is ready to suspend and will not participate in the market, but will not generate a SUSPEND action.

NOTE: This state replaces the SUSPEND state, and requires additional configuration to enable. Workload Optimization Manager does not recommend enabling this state.

– FAILOVER:

This entity is reserved for failover and will not participate in the market.

TDI.E.

Entity is powered off and not actively consuming market resources.

- LAUNCH:

Entity is starting.

– MAINTENANCE:

Entity is in maintenance mode.

NOT MONITORED:

Entity is not currently monitored by Workload Optimization Manager.

OUEUED:

Entity is in the process of changing from one state to another.

NOTE: This state is internal to Workload Optimization Manager and will not appear in the UI, but may appear in an API response if the call is executed at the precise moment the entity is changing state.

RESOURCE_ALLOCATION:

Cloud entity is being created.

– RESOURCE_RELEASE:

Cloud Entity is being deleted.

- SUSPEND:

Entity is suspended or the guest OS is in sleep, standby, or suspended state. The entity is not removed from the environment, but will not be used in market decisions. Based on market conditions, suspended entities can be started, re-adding them to the market.

- SUSPEND PENDING:

Entity is making preparations to suspend, or is the next entity of its type to suspend.

- TERMINATE PENDING:

Entity is in the process of being deleted.

UNKNOWN:

Workload Optimization Manager is unable to obtain the current state of the entity.

This occurs when the entity is reported to the hypervisor as having a state of <code>DISCONNECTED</code>, <code>ORPHANED</code>, or <code>INVALID</code>.

- environment_type
- Only return actions that affect entities in the specified environment type. [CLOUD, HYBRID, ONPREM].



detail_type

The level of detail returned for each item in the returned supply chain. [compact, entity, aspects].

health

Return a small summary of the health of the returned supply chain.

Example: GET https://10.10.10.10/api/v3/groups/_WvaGkOBjEeierZ9b1bxmgg/supplychains? types=PhysicalMachine&entity_states=ACTIVE&entity_states=SUSPEND&entity_states=MAINTENANCE&envir

Response: A SupplychainApiDTO representing the supply chain of the specified group:

```
"seMap": {
    "PhysicalMachine": {
      "depth": 1,
      "entitiesCount": 3,
      "healthSummary": {
        "Minor": 1,
        "Normal": 2
      },
      "stateSummary": {
        "ACTIVE": 3
      },
      "connectedProviderTypes": [
        "DataCenter",
        "Storage"
      1,
      "instances": {
        "34313836-3333-5553-4537-33364e385146": {
          "links": [
              "rel": "self",
              "href": "https://10.10.10.10/api/v3/entities/34313836-3333-5553-4537-33364e385146?include_a
spects=false"
          ],
          "uuid": "34313836-3333-5553-4537-33364e385146",
          "displayName": "dc17-host-01.dev.mycorp.com",
          "className": "PhysicalMachine",
          "priceIndex": 3.2925103,
          "state": "ACTIVE",
          "severity": "Normal",
          "discoveredBy": {
            "uuid": "_yXCEIF6hEeiNCKdg4ZVvVQ",
            "displayName": "vsphere-dc17.dev.mycorp.com",
            "type": "vCenter"
          },
          "remoteId": "host-621",
          "environmentType": "ONPREM"
        },
      }
```



Groups Endpoint Tips

GroupBy Field Criteria

When using the POST requests to query actions and action statistics, you can use the <code>groupBy</code> parameter to organize the results. The valid values for this parameter differ by entity type:

NOTE:

When sending an inputDTO using this field, only the value is needed.

Example: "groupBy": "vmsByPMName"

```
"VirtualMachine":{
  "criteria":[
    {
      "filterType":"vmsByName"
    },
      "filterType": "vmsByPMName"
    },
    {
      "filterType": "vmsByStorage"
    },
    {
      "filterType":"vmsByNetwork"
    },
    {
      "filterType": "vmsByApplication"
    },
      "filterType":"vmsByDatabaseServer"
    },
    {
      "filterType": "vmsByDatabaseServerVersion"
    },
    {
      "filterType":"vmsByDC"
    },
    {
      "filterType":"vmsByVDC"
    },
      "filterType": "vmsByDCnested"
    },
      "filterType": "vmsByNumCPUs"
    },
    {
      "filterType":"vmsByMem"
    },
      "filterType":"vmsByGuestName"
    },
```



```
{
      "filterType": "vmsByAltName"
    },
    {
      "filterType": "vmsByClusterName"
    },
    {
      "filterType":"vmsByDiskArrayName"
    },
      "filterType": "vmsByLogicalPoolName"
    },
    {
      "filterType":"vmsByProfileName"
    },
    {
      "filterType":"vmsByTag"
    },
      "filterType":"vmsByState"
    },
      "filterType":"vmsByBusinessAccountUuid"
    },
      "filterType":"vmsByResourceGroupUuid"
    }
  ]
},
\verb|"VirtualDataCenter":{|} \\
  "criteria":[
      "filterType":"vdcsByName"
    },
      "filterType": "vdcsByVDCName"
    },
      "filterType":"vdcsByTag"
    },
      "filterType": "vdcsByState"
    }
  ]
},
"PhysicalMachine":{
  "criteria":[
      "filterType": "pmsByName"
    },
      "filterType":"pmsByStorage"
    },
    {
```



```
"filterType": "pmsByNetwork"
    },
    {
      "filterType": "pmsBySwitch"
    },
    {
      "filterType": "pmsByNumVms"
    },
    {
      "filterType":"pmsByDC"
    },
    {
      "filterType": "pmsByMem"
    },
    {
      "filterType": "pmsByNumCPUs"
    },
    {
      "filterType": "pmsByVendorName"
    },
    {
      "filterType": "pmsByCPUModel"
    },
    {
      "filterType":"pmsByModel"
    },
    {
      "filterType": "pmsByTimezone"
    },
    {
      "filterType": "pmsByClusterName"
    },
      "filterType": "pmsByTag"
    },
      "filterType": "pmsByState"
  ]
},
"Storage":{
  "criteria":[
      "filterType": "storageByName"
    },
    {
      "filterType":"storageByTag"
    },
    {
      "filterType":"storageByVMs"
    },
      "filterType": "storageByDC"
    },
```



```
{
      "filterType": "storageByPMCluster"
    },
    {
      "filterType": "storageByState"
    }
  ]
},
"Application":{
  "criteria":[
    {
      "filterType": "appsByName"
    },
      "filterType": "appsByTag"
  ]
},
\verb|"ApplicationComponent":{\{}
  "criteria":[
    {
      "filterType": "appSrvsByName"
  ]
},
"WebServer":{
  "criteria":[
    {
      "filterType": "wbSrvsByName"
},
"BusinessApplication":{
  "criteria":[
    {
      "filterType": "busAppsByName"
  ]
},
"Database":{
  "criteria":[
    {
      "filterType":"databaseByName"
    },
      "filterType":"databaseByTag"
    },
      "filterType": "databaseByBusinessAccountUuid"
    },
    {
      "filterType": "databaseByResourceGroupUuid"
    }
  ]
```



```
},
"DatabaseServer":{
  "criteria":[
    {
      "filterType": "databaseServerByName"
    },
    {
      "filterType": "databaseServerByTag"
    },
      "filterType": "databaseServerByBusinessAccountUuid"
    },
    {
      "filterType": "databaseServerByEngine"
    },
    {
      "filterType": "databaseServerByEdition"
    },
      "filterType": "databaseServerByVersion"
    }
},
"VirtualApplication":{
  "criteria":[
      "filterType": "vappsByName"
    }
},
"Cluster":{
  "criteria":[
      "filterType": "clustersByName"
    },
      "filterType": "clustersByTag"
  ]
},
"DataCenter":{
  "criteria":[
      "filterType": "datacentersByName"
    },
    {
      "filterType": "datacentersByTag"
    }
  ]
},
"Group":{
  "criteria":[
    {
      "filterType": "groupsByName"
```



```
},
    {
      "filterType": "groupsByTargetName"
  ]
},
"StorageCluster":{
  "criteria":[
   {
      "filterType":"storageClustersByName"
  ]
},
"DiskArray":{
  "criteria":[
      "filterType":"diskarrayByName"
  ]
},
"Zone":{
  "criteria":[
      "filterType":"zonsByName"
  ]
},
"Region":{
  "criteria":[
   {
      "filterType": "regsByName"
  ]
},
"Network":{
  "criteria":[
   {
      "filterType": "netsByName"
},
"LoadBalancer":{
  "criteria":[
   {
      "filterType":"lbsByName"
  ]
},
"Chassis":{
  "criteria":[
   {
      "filterType":"chasByName"
    }
  ]
```



```
},
"IOModule":{
  "criteria":[
      "filterType": "ioModuleByName"
  ]
},
"StorageController":{
  "criteria":[
      "filterType": "storagecontrollerByName"
    }
  ]
},
"DPod":{
  "criteria":[
      "filterType":"dpodByName"
  ]
},
"VPod":{
  "criteria":[
      "filterType":"vpodByName"
  1
},
"LogicalPool":{
  "criteria":[
      "filterType":"logicalPoolByName"
  1
},
"Switch":{
  "criteria":[
      "filterType": "switchByName"
    }
  ]
},
"Container":{
  "criteria":[
    {
      "filterType": "containersByName"
    },
      "filterType": "containersByVMName"
  ]
},
"ContainerPod":{
```



```
"criteria":[
    {
      "filterType": "containerpodsByName"
    },
      "filterType": "containerpodsByVMName"
},
"ServiceEntity":{
  "criteria":[
      "filterType":"workloadByBusinessAccountUuid"
    },
      "filterType": "workloadByResourceGroupUuid"
    }
  ]
},
"Workload":{
  "criteria":[
    {
      "filterType": "workloadByBusinessAccountUuid"
    },
      "filterType": "workloadByResourceGroupUuid"
    }
  ]
},
"ResourceGroup":{
  "criteria":[
      "filterType": "resourceGroupByName"
    },
      "filterType": "resourceGroupByUuid"
    },
      "filterType": "resourceGroupByBusinessAccountUuid"
    },
      "filterType": "resourceGroupByTag"
    }
  ]
},
"BusinessAccount":{
  "criteria":[
      "filterType": "businessAccountByName"
    },
      "filterType":"businessAccountByUuid"
    },
    {
```



```
"filterType": "subBusinessAccountOfUuid"
    },
    {
      "filterType": "businessAccountValidationStatus"
    },
    {
      "filterType": "businessAccountTargetName"
    },
    {
      "filterType": "businessAccountCloudProvider"
    }
  ]
},
"BillingFamily":{
  "criteria":[
    {
      "filterType": "billingFamilyByName"
  ]
},
"ViewPod":{
  "criteria":[
    {
      "filterType": "viewPodByName"
  ]
},
"DesktopPool":{
  "criteria":[
    {
      "filterType": "desktopPoolByName"
    },
      "filterType": "desktopPoolByViewPod"
    }
},
"BusinessUser":{
  "criteria":[
      "filterType":"businessUserByName"
    },
      "filterType": "businessUserByDesktopPool"
    }
  1
```



Licenses Endpoint

A product license determines the product features you can use, and the number of workloads that you can manage with Workload Optimization Manager. To increase the number of workloads you can manage, you can add additional licenses to your Workload Optimization Manager installation. Note that if you use multiple licenses, they must all support the same feature set.

In all circumstances, you should contact your sales representative to make sure that you get the correct license, and that you know how to install it properly.

Using the licenses endpoint, you can:

- Get a license summary
- Get a list of licenses currently added to your Workload Optimization Manager appliance
- Add a license
- Delete a license

Licenses Requests

Getting Licenses

Gets a list of licenses. For instances with multiple licenses, the licenses/summary request will return a summed total of licensed workload. For example, if you have two licenses for 10,000 workloads each, the /licenses request will return both LicenseApiDTOs in a list. The /licenses/summary call will return a single summed LicenseApiDTO, which will state that you have capacity for 20,0000 workloads.

Examples:

- List of Licenses: GET https://10.10.10.10/api/v3/licenses
- License Summary: GET https://10.10.10.10/api/v3/licenses/summary

Adding a License

Adds a license to your Workload Optimization Manager installation. You may optionally specify the dryRun parameter which, when set to true, will validate the license file but not apply it to the appliance.

NOTE:

This request requires a multipart file as input. Due to this requirement, this request cannot be executed directly from the Swagger.

Example: POST https://10.10.10.10/api/v3/licenses?file=%5Bobject%20File%5D&dryRun=true

Deleting a License

Removes the specified license from your Workload Optimization Manager installation. Deleting a license may reduce your licensed workload capacity below your current usage. In this case, you will be unable to add more targets until more workload capacity is available.

Example: DELETE https://10.10.10.10/api/v3/licenses/_I_WVcJtWEeiGEs_doVlDOw

Logs Requests

The logs endpoint is not implemented at this time.



Markets Endpoint

Workload Optimization Manager uses market-based analysis to perform workload management. To do this, it constructs a model of your environment, representing each entity as a buyer and seller in a market. You can access this model via a named market resource. There are two types of markets:

Real-Time Market

The real-time market performs analysis and workload management on your environment. You can use the real-time market to access entities and get current or historical data about them.

The displayName of the real-time market is Market. This market should always be in the RUNNING state. You should not attempt to use the API to stop this market.

Workload Optimization Manager performs discovery to populate the topology it manages (the collection of entities in the real-time market). For this reason, you should never use the API add or delete entities in the real-time market.

■ Plan Market

A plan market begins as a snapshot of the real-time market. You POST a scenario to the real-time market, and Workload Optimization Manager makes a copy of the real-time market to create a plan market. This plan market is just like the real-time market, except for any changes that were declared in the scenario. For example, if the scenario declares a scope for the plan, then the plan market only contains entities that are within that scope.

Workload Optimization Manager runs economic cycles (buy/sell cycles) against this plan market until there are no more meaningful improvements to be made. At this point the plan run is completed.

Note that once Workload Optimization Manager creates the plan market, that market stays in memory until you delete it. Also note that you can later apply a scenario to the plan market. This is how you run a plan on a plan. The logic flow is the same, and Workload Optimization Manager creates yet another plan market to run the analysis.

This endpoint contains references to start and end times for certain operations. For more information, including valid time formats, see <u>Time in the Workload Optimization Manager API (on page 742)</u>

Using the markets endpoint of the Workload Optimization Manager API, you can:

- Get a list of markets
- Save or Stop a plan market
- Delete a plan market
- See unplaced entities in a plan market
- Get filtered and unfiltered lists of actions, entities, notifications, policies, reservations, and statistics for a particular market
- Get, edit, and delete placement policies in the real-time market

Determining the Status of the Main Market

After restarting the Workload Optimization Manager instance, the UI and API may be available before the real-time market has finished initializing and loading the topology of your environment. To check market status, execute the GET /markets/market uuid request with a market UUID of Market.

If information about the market is returned, it has initialized. If the real-time market is not initialized, the following response will be returned:

```
"type":400,
  "exception":"com.vmturbo.api.exceptions.OperationFailedException: Infrastructure is not controlled yet.
Could not get market.",
  "message":"Infrastructure is not controlled yet. Could not get market."
}
```



Markets Requests

Getting a List of Markets

Returns all the Markets currently stored on your Workload Optimization Manager appliance. To get the details of a single market, include the UUID of the market in the request.

NOTE

One market will have the displayName of *Market*. This market is the real-time market. You should not add nor delete entities directly to this market using the API, nor should you attempt to execute a STOP action on this market.

Examples:

- All Markets: GET https://10.10.10.10/api/v3/markets
- Single Market: GET https://10.10.10.10/api/v3/markets/_0x30YUglEd-gHc4L513yOA

Response: A list of MarketApiDTOs representing the markets on your appliance.

Stopping or Saving Plan Markets

For troubleshooting, you may need to stop or save a plan market that is taking a long time to run, or does not seem to complete. These operations should never be used on the real-time market. Note that a manually-stopped plan market may have incomplete data.

This request takes the following parameters:

market_Uuid

The UUID of the market that will be stopped or saved.

operation

The operation to perform on the market. [stop, save]

Example: POST https://10.10.10.10/api/v3/markets/_NO8_sCi_EemDHtuQzfdzxw?operation=stop

Response: The MarketApiDTO of the specified market, showing its state as STOPPING.

```
{
   "links": [
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/markets/_N08_sCi_EemDHtuQzfdzxw"
```



```
},
    "rel": "Market notifications",
    "href": "https://10.10.10.10/api/v3/markets/_NO8_sCi_EemDHtuQzfdzxw/notifications"
  },
    "rel": "Market actions",
    "href": "https://10.10.10.10/api/v3/markets/_NO8_sCi_EemDHtuQzfdzxw/actions?ascending=true"
  },
    "rel": "To Entities",
    "href": "https://10.10.10.10/api/v3/markets/_NO8_sCi_EemDHtuQzfdzxw/entities"
  },
    "rel": "To Constraints",
    "href": "https://10.10.10.10/api/v3/markets/_NO8_sCi_EemDHtuQzfdzxw/policies"
  },
    "rel": "To Reservations",
    "href": "https://10.10.10.10/api/v3/markets/_NO8_sCi_EemDHtuQzfdzxw/reservations"
  },
    "rel": "To Statistics",
    "href": "https://10.10.10.10/api/v3/markets/_NO8_sCi_EemDHtuQzfdzxw/stats"
  },
    "rel": "To Unplaced Entities",
    "href": "https://10.10.10.10/api/v3/markets/_NO8_sCi_EemDHtuQzfdzxw/unplacedentities"
  },
    "rel": "To Market List",
    "href": "https://10.10.10.10/api/v3/markets"
  }
],
"uuid": "_NO8_sCi_EemDHtuQzfdzxw",
"displayName": "ADD_WORKLOAD_administrator_1549313730114",
"className": "Market",
"state": "STOPPING",
"scenario": {
  "uuid": "2452690315520",
  "displayName": "Add Workload 1",
  "owners": [],
  "type": "ADD_WORKLOAD"
},
"unplacedEntities": false,
"runDate": "2019-02-04T15:55:30-05:00",
"environmentType": "ONPREM"
```

Deleting a Plan Market

}

Deleting a plan market removes the market entity along with all the topological links, such as actions, notifications, entities, policies and reservations. This operation is permanent. To delete a plan market, pass the UUID of the market in the request.



This request takes the following parameters:

market Uuid

The UUID of the market that will be deleted.

Example: DELETE https://10.10.10.10/api/v3/markets/_NO8_sCi_EemDHtuQzfdzxw

Response: The MarketApiDTO of the specified market, showing its state as DELETING.

```
"links":[
  {
    "rel": "self",
    "href": "https://10.10.10.10/api/v3/markets/2452692215536"
  }
],
"uuid": "2452692215536",
"displayName": "ADD_WORKLOAD_administrator_1549313730114",
"className": "Market",
"state": "DELETING",
"scenario":{
  "uuid":"2452692204928",
  "displayName": "Add Workload 1",
  "owners":[
      "links":[
        {
          "rel": "self",
          "href": "https://10.10.10.10/api/v3/users/_4T_7kwY-Ed-WUKbEYSVIDw"
        }
      ],
      "uuid": "_4T_7kwY-Ed-WUKbEYSVIDw",
      "displayName": "Administrator User",
      "username": "administrator",
      "roleUuid":"_4UAioQY-Ed-WUKbEYSVIDw",
      "roleName": "administrator",
      "loginProvider": "Local",
      "type": "DedicatedCustomer",
      "showSharedUserSC":false
    }
  ],
  "type": "ADD_WORKLOAD"
},
"saved":true,
"unplacedEntities":false,
"runDate": "2019-02-04T15:55:30-05:00",
"runCompleteDate": "2019-02-04T15:57:26-05:00",
"environmentType": "ONPREM"
```

Getting a Filtered List of Actions for a Market

Referenced Endpoint: Actions (on page 753)



Gets a list of actions, given a market UUID and filtered by an ActionApilnputDTO using one or more of the following criteria:

actionModeList

- DISABLED:

Do not recommend or perform the action. When you disable an action, the user interface will no longer display actions of that type.

RECOMMENDED:

Recommend the action so a user can execute it via the given hypervisor or by other external means

– MANUAL:

Recommend the action, and provide the option to execute that action through the Workload Optimization Manager user interface or an /actions API request.

AUTOMATED:

You have directed Workload Optimization Manager to execute the action automatically.

– COLLECTION (UNUSED):

Legacy action mode, no longer used.

actionStateList

- DISABLED:

An action whose policy has been disabled.

RECOMMEND:

An action that cannot be automated due to policy settings or must be executed outside the system, such as the purchase of hardware.

PENDING ACCEPT:

When the action mode is set to manual, a recommended action that has not been accepted or cleared.

ACCEPTED:

An action that has been accepted, but is not yet in progress.

IN_PROGRESS:

An action that is being executed.

SUCCEEDED:

An action that was accepted and completed successfully.

- FAILED:

An action that was accepted and did not complete successfully.

- REJECTED:

When the action mode is set to manual, an action that has been rejected by the user.

CLEARED:

When the action mode is set to manual, an action that is no longer recommended by the market.

- ACCOUNTING:

For cloud entities, an action to resize in order to use a different instance template.

QUEUED:

When more than 10 actions are to be executed for a single target, Workload Optimization Manager will place the 11th and all subsequent actions into a QUEUED state, and they will execute as the previous actions complete.

actionTypeList

- START:

Start an entity, and add it to the Workload Optimization Manager market.

– MOVE:

Move an entity from one provider to another. For example, moving a VM between hosts, or a datastore between disk arrays.

- SUSPEND:



Suspend the entity to exclude its capacity from your environment. Suspend does not remove the entity from your environment, but the market does not include the entity in its analysis. Based on market conditions, analysis can recommend restarting suspended entities, which includes them in market analysis once again.

- ADD PROVIDER:

This is equivalent to the START action, but for storage entities.

CHANGE:

Move a virtual machine's storage between datastores.

- PROVISION:

Add capacity to your environment.

RECONFIGURE:

Analysis recommends this when a VM is not able to correct a misconfiguration via another type of action. For example, analysis can recommend a RECONFIGURE action when a placement policy requires a VM to move to a host on a particular cluster, but cross-cluster moves are not permitted.

- DELETE:

This is equivalent to the SUSPEND action, but for storage entities.

RESERVE_ON_PM:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular host.

RESERVE ON DS:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular datastore.

- RESIZE_FOR_EFFICIENCY:

A resize that reduces the capacity of a commodity, such as vCPU, or vMEM.

- RESIZE_FOR_PERFORMANCE:

A resize that increases the capacity of a commodity, such as vCPU, or vMEM.

cleared

Default: false.

When true, actions that were removed from the action list before being executed will be returned.

costType

Saving

An action that will decrease cloud spending.

Investment

An action that will increase cloud spending.

cumulative

Default: false.

When true, shows the savings for each action in a scope as a cumulative total, rather than showing the savings for individual actions.

environmentType

ONPREM:

Returns only actions related to entities that are part of your on-premises environment.

- CLOUD:

Returns only actions related to entities that are part of your cloud environment.

groupBy

You may group the actions returned by the following criteria: [actionModes, actionStates, actionTypes, risk, riskSeverity, riskSubCategory]

hasReservedInstance

Default: false.

When true, only actions that are related to reserved instances will be returned.

relatedEntityTypes



Returns only actions related to entities of these types within the scope. For example, if your scope is a virtual datacenter and you specify VirtualMachine as a related entity type, the request will include only those actions related to VMs in the specified virtual datacenter.

Choose from the following entity types: [Datacenter, PhysicalMachine, VirtualMachine, Storage, Application, Chassis, DiskArray, IOModule, StorageControl, Switch, VirtualDataCenter, VPod, DPod, Container, Database, DatabaseServerContainer, LogicalPool]

riskSeverityList

Returns only actions of the given severities: [Unknown, Normal, Minor, Major, Critical]

- riskSubCategoryList
- returns only actions of the given subcategories: [Performance Assurance, Efficiency Improvement, Prevention, Compliance]

This request takes the following parameters:

market_Uuid

The UUID of the market whose actions will be returned.

cursor

When making subsequent calls to retrieve additional results, this is the cursor returned by the last call to this method.

limit

The maximum number of items to return. Must be a positive integer. If not set, the server will provide a default (20).

order_by

The field to order the results by. [creation_date, name, risk_category, savings, severity].

ascending

Default: true. When false, results will be in descending order.

```
Example: POST https://10.10.10.10/api/v3/markets/Market/actions? order_by=severity&ascending=true
```

Example input: In this example, a list of actions that meet the following criteria will be returned and grouped by the actionMode of the action, in order of severity:

- Is in state PENDING_ACCEPT
- Is part of an on-premises environment
- Is an action for a virtual machine
- Is an action generated by the Workload Optimization Manager real-time market

```
"actionInput":{
    "actionStateList":[
        "PENDING_ACCEPT"
],
    "environmentType":"ONPREM",
    "groupBy":[
        "actionModes"
]
},
"relatedType":"VirtualMachine",
"scopes":[
    "Market"
]
```

Response: ActionApiDTOs meeting the specified criteria.

{



```
"uuid": "_qFuM8CiOEemDHtuQzfdzxw",
    "createTime": "2019-02-04T10:07:58-05:00",
    "actionType": "RIGHT_SIZE",
    "actionState": "PENDING_ACCEPT",
    "actionMode": "MANUAL",
    "details": "Scale VirtualMachine 8f0e3136-b259-43e5-41f8-0d2c64c62acc from Standard_B2ms to Standard_E2s_v3",
    "importance": 0,
    ...
}
```

Getting Statistics for a Filtered List of Actions for a Market

Referenced Endpoint: <u>Actions (on page 753)</u> Referenced Endpoint: <u>Stats (on page 973)</u>

Gets a list of statistics for a filtered list of actions. Statistics returned include the number of actions, total savings/investment, and the number of entities affected by the actions. In addition to the Market UUID, provide an ActionApilnputDTO using one or more of the following criteria:

actionModeList

- DISABLED:

Do not recommend or perform the action. When you disable an action, the user interface will no longer display actions of that type.

RECOMMENDED:

Recommend the action so a user can execute it via the given hypervisor or by other external means

– MANUAL:

Recommend the action, and provide the option to execute that action through the Workload Optimization Manager user interface or an /actions API request.

- AUTOMATED:

You have directed Workload Optimization Manager to execute the action automatically.

- COLLECTION (UNUSED):

Legacy action mode, no longer used.

actionStateList

- DISABLED:

An action whose policy has been disabled.

RECOMMEND:

An action that cannot be automated due to policy settings or must be executed outside the system, such as the purchase of hardware.

– PENDING_ACCEPT:

When the action mode is set to manual, a recommended action that has not been accepted or cleared.

- ACCEPTED:

An action that has been accepted, but is not yet in progress.

- IN PROGRESS:

An action that is being executed.

SUCCEEDED:

An action that was accepted and completed successfully.

- FAILED:

An action that was accepted and did not complete successfully.



- REJECTED:

When the action mode is set to manual, an action that has been rejected by the user.

- CLEARED:

When the action mode is set to manual, an action that is no longer recommended by the market.

- ACCOUNTING:

For cloud entities, an action to resize in order to use a different instance template.

OUEUED:

When more than 10 actions are to be executed for a single target, Workload Optimization Manager will place the 11th and all subsequent actions into a QUEUED state, and they will execute as the previous actions complete.

actionTypeList

- START:

Start an entity, and add it to the Workload Optimization Manager market.

MOVE

Move an entity from one provider to another. For example, moving a VM between hosts, or a datastore between disk arrays.

- SUSPEND:

Suspend the entity to exclude its capacity from your environment. Suspend does not remove the entity from your environment, but the market does not include the entity in its analysis. Based on market conditions, analysis can recommend restarting suspended entities, which includes them in market analysis once again.

- ADD PROVIDER:

This is equivalent to the START action, but for storage entities.

- CHANGE:

Move a virtual machine's storage between datastores.

- PROVISION:

Add capacity to your environment.

RECONFIGURE:

Analysis recommends this when a VM is not able to correct a misconfiguration via another type of action. For example, analysis can recommend a RECONFIGURE action when a placement policy requires a VM to move to a host on a particular cluster, but cross-cluster moves are not permitted.

- DELETE:

This is equivalent to the SUSPEND action, but for storage entities.

RESERVE_ON_PM:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular host.

– RESERVE_ON_DS:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular datastore.

- RESIZE FOR EFFICIENCY:

A resize that reduces the capacity of a commodity, such as vCPU, or vMEM.

- RESIZE FOR PERFORMANCE:

A resize that increases the capacity of a commodity, such as vCPU, or vMEM.

cleared

Default: false.

When true, actions that were removed from the action list before being executed will be returned.

costType

Saving

An action that will decrease cloud spending.

Investment

An action that will increase cloud spending.



cumulative

Default: false.

When true, shows the savings for each action in a scope as a cumulative total, rather than showing the savings for individual actions.

- environmentType
 - ONPREM:

Returns only actions related to entities that are part of your on-premises environment.

- CLOUD:

Returns only actions related to entities that are part of your cloud environment.

■ groupBy

You may group the actions returned by the following criteria: [actionModes, actionStates, actionTypes, risk, riskSeverity, riskSubCategory]

hasReservedInstance

Default: false.

When true, only actions that are related to reserved instances will be returned.

relatedEntityTypes

Returns only actions related to entities of these types within the scope. For example, if your scope is a virtual datacenter and you specify VirtualMachine as a related entity type, the request will include only those actions related to VMs in the specified virtual datacenter.

Choose from the following entity types: [Datacenter, PhysicalMachine, VirtualMachine, Storage, Application, Chassis, DiskArray, IOModule, StorageControl, Switch, VirtualDataCenter, VPod, DPod, Container, Database, DatabaseServerContainer, LogicalPool]

riskSeverityList

Returns only actions of the given severities: [Unknown, Normal, Minor, Major, Critical]

- riskSubCategoryList
- returns only actions of the given subcategories: [Performance Assurance, Efficiency Improvement, Prevention, Compliance]

Example: POST https://10.10.10.10/api/v3/markets/Market/actions/stats

Example input: In this example, a list of actions that meet the following criteria will be returned and grouped by the actionMode of the action, in order of severity:

- Is in state PENDING ACCEPT
- Is part of an on-premises environment
- Is an action for a virtual machine
- Is an action generated by the Workload Optimization Manager real-time market

```
"actionInput":{
    "actionStateList":[
        "PENDING_ACCEPT"
],
    "environmentType":"ONPREM",
    "groupBy":[
        "actionModes"
]
},
"relatedType":"VirtualMachine",
"scopes":[
    "Market"
]
```



Response: A list of StatSnapshotApiDTO containing statistics about the filtered actions.

```
"date": "2019-02-05T14:40:08-05:00",
    "statistics":[
      {
        "name": "numActions",
        "values":{
          "max":268,
          "min":268,
          "avg":268,
          "total":268
        },
         "value":268
      },
      {
         "name": "costPrice",
        "filters":[
            "type": "property",
             "value": "savings"
        ],
        "units": "$",
         "values":{
          "max":24100,
          "min":24100,
          "avg":24100,
           "total":24100
        },
        "value":24100
      },
    ]
  }
]
```

Getting All Entities Within a Market

Referenced Endpoint: Entities (on page 791)

Gets a list of all entities in the specified market. This request may be used to retrieve a list of entities used in a plan market.

Example: GET https://10.10.10.10/api/v3/markets/2452692215536/entities

Response: A list of ServiceEntityApiDTOs, representing the entities in the market. In this case, note that there is an attribute entitled realtimeMarketRefrence because these are entities from a plan market.



```
"href":"https://10.10.10.10/api/v3/entities/_QQVtEyi_EemDHtuQzfdzxw?include_aspects=false"
}
],
"uuid":"_QQVtEyi_EemDHtuQzfdzxw",
"displayName":"osp-master-2",
"className":"VirtualMachine",
"priceIndex":3.6063216,
"state":"ACTIVE",
"severity":"Normal",
"realtimeMarketReference":{
    "uuid":"42000c5d-9ae5-44f0-252c-daabbb423a86"
},
"environmentType":"ONPREM"
},
```

Getting Statistics of Entities Within a Market

Referenced Endpoint: <u>Stats (on page 973)</u> Referenced Endpoint: <u>Entities (on page 791)</u>

Gets statistics related to entities in a specified market. For example, this request may be used to see the final calculated statistics for entities in a plan market. For more information about creating a filtered list of statistics, including example POSTs and responses, see *Filtered Statistics* in the <u>Statistics Endpoint (on page 973)</u>.

Getting Statistics of a Specified Group of Entities Within a Market

Referenced Endpoint: Stats (on page 973)
Referenced Endpoint: Groups (on page 819)
Referenced Endpoint: Entities (on page 791)

Gets statistics related to a specific group of entities in a specified market. For example, this request may be used to see the final calculated statistics for a group of hosts in a plan market. For more information about creating a filtered list of statistics, including example POSTs and responses, see *Filtered Statistics* in the Statistics Endpoint (on page 973).

Getting Policies for a Market

Referenced Endpoint: Policies (on page 881)

Returns a list of all current policies affecting a specified market. For a plan market, this is a list of policies that you created, enabled, disabled, or changed in the plan configuration. For the real-time market, this is a list of policies currently available on your appliance. To get a single policy, include the UUID of the policy in the request.

Examples:

- All policies: GET https://10.10.10.10/api/v3/markets/2481646239616/policies
- One policy:

GET https://10.10.10.10/api/v3/markets/2481646239616/policies/_z3LKSTk0EemeycL7hWgJNw

Response: A list of PolicyApiDTOs representing the policies requested.



```
],
   "uuid":"_z3LxVzk0EemeycL7hWgJNw",
   "displayName": "DalTestPolMerge",
   "type": "MERGE",
   "name": "DalTestPolMerge",
   "enabled":true,
   "commodityType": "ClusterCommodity",
   "mergeType": "Cluster",
   "mergeGroups":[
      {
         "uuid": "91ff08749fd278925d73b61b0f0f69d79c99fc3a",
         "displayName":"PMs_Beta DC6\\Cluster-1",
         "className": "Group",
         "groupType": "PhysicalMachine",
         "isStatic":true,
         "logicalOperator": "AND"
      },
         "uuid": "8c17d8e79c3db85ed5d3868de622cb89187849ce",
         "displayName": "PMs_Beta DC6\\Cluster-2",
         "className": "Group",
         "groupType": "PhysicalMachine",
         "isStatic":true,
         "logicalOperator": "AND"
      }
   ]
},
   "links":[
      {
         "rel": "self",
         "href": "https://10.10.10.10/api/v3/policies/_z3LKSTk0EemeycL7hWgJNw"
   ],
   "uuid": "_z3LKSTk0EemeycL7hWgJNw",
   "displayName": "CommSegmentation/SegmentManager__4T_7kwY-Ed-WUKbEYSVIDw_1551123454966",
   "type": "MUST_RUN_TOGETHER",
   "name": "CommSegmentation/SegmentManager__4T_7kwY-Ed-WUKbEYSVIDw_1551123454966",
   "enabled":false,
   "capacity":1000000000,
   "commodityType": "DrsSegmentationCommodity",
   "consumerGroup":{
      "uuid": "_z2M57Dk0EemeycL7hWgJNw",
      "displayName": "Buyers-Group-GROUP-DRS-KTG-rule/DC13-Cluster/vsphere-dc13.dev.mycorp.com",
      "className": "DiscoveredGroup",
      "groupType": "VirtualMachine",
      "isStatic":true,
      "logicalOperator": "AND"
   },
   "providerGroup":{
      "uuid": "_z2M57zk0EemeycL7hWgJNw",
      "displayName": "Sellers-Group-GROUP-DRS-KTG-rule/DC13-Cluster/vsphere-dc13.dev.mycorp.com",
      "className": "DiscoveredGroup",
      "groupType": "PhysicalMachine",
```



Deleting a Placement Policy for a Market

Referenced Endpoint: Policies (on page 881)

Deletes the specified policy, given the UUID of the policy and the market. Note that if you delete an imported policy, it will reappear after the next discovery cycle of the target it was imported from. To delete imported policies, delete them on the target directly.

Example: DELETE https://10.10.10.10/api/v3/markets/2481646239616/policies/ _z3LxVzk0EemeycL7hWgJNw

Response: A successful deletion request returns a Response Code of 200.

Getting Reservations for a Market

Referenced Endpoint: Reservations (on page 884)

Returns a list of all current reservations for a specified market. For the real-time market, this is a list of reservations currently active on your appliance.

Example: GET https://10.10.10.10/api/v3/markets/Market/reservations

Response: A list of DemandReservationApiDTOs representing any current reservations.

```
{
   "uuid": "_I6z38Tk8EemeycL7hWgJNw",
   "displayName": "DalRes2",
   "count":1,
   "status": "RESERVED",
   "reserveDateTime": "Mon Feb 25 15:30:07 EST 2019",
   "expireDateTime": "Mon Mar 25 08:29:54 EDT 2019",
   "deployDateTime": "Tue Mar 26 08:29:54 EDT 2019",
   "reserveCount":1,
   "deployCount":0,
   "demandEntities":[
         "uuid": "_JEZRwTk8EemeycL7hWgJNw",
         "displayName": "DalRes2_C0",
         "className": "VirtualMachine",
         "template":{
            "uuid": "T-ef47f3dbdde39f888052332cbe7d0cf2",
            "displayName": "AVG:PMs_ACM\\ACM Cluster for last 10 days",
            "className": "VirtualMachineProfile"
         },
         "placements":{
            "computeResources":[
                   "stats":[
                         "name": "numOfCpu",
                         "value":2
```



```
},
            "name": "cpuSpeed",
            "units": "MHz",
            "value":5320
         },
            "name": "cpuConsumedFactor",
            "units":"%",
            "value":4.2516437
         },
         {
            "name": "memorySize",
            "units": "MB",
            "value":6631
         },
            "name": "memoryConsumedFactor",
            "units":"%",
            "value":46.328953
         },
            "name": "ioThroughput",
            "units": "MB/s",
            "value":0.05301181
         },
            "name": "networkThroughput",
            "units": "MB/s",
            "value":0.103116125
         }
      ],
      "provider":{
         "uuid": "30333436-3638-5355-4532-313159335631",
         "displayName": "hp-dl571.dev.mycorp.com",
         "className": "PhysicalMachine"
],
"storageResources":[
      "stats":[
            "name": "diskSize",
            "units":"GB",
            "value":92.468285
         },
            "name": "diskIops",
             "value":1.6827557
      ],
      "provider":{
         "uuid": "5a822e24-584bce98-ecb2-441ea15e2534",
```



Running a Scenario on a Market

Referenced Endpoint: Scenarios (on page 895)

When you run a scenario on the real-time market, it creates a plan market showing the results of the scenario. If you run a second scenario a plan market, that is called running a "plan over plan". This runs a plan new configuration on a market that is already the result of a plan run.

Example: POST https://10.10.10.10/api/v3/markets/Market/scenarios/2452690315520? ignore constraints=false

Response: A MarketApiDTO showing the new state of the market- if successful, COPYING.

```
"links":[
   {
      "rel": "self",
      "href": "https://10.10.10.10/api/v3/markets/_ps_iUDlBEemeycL7hWgJNw"
   },
   {
      "rel": "Market notifications",
      "href": "https://10.10.10.10/api/v3/markets/_ps_iUDlBEemeycL7hWgJNw/notifications"
  },
   {
      "rel": "Market actions",
      "href": "https://10.10.10.10/api/v3/markets/_ps_iUDlBEemeycL7hWgJNw/actions?ascending=true"
  },
   {
      "rel": "To Entities",
      "href": https://10.10.10.10/api/v3/markets/_ps_iUDlBEemeycL7hWgJNw/entities"
  },
      "rel": "To Constraints",
      "href": https://10.10.10.10/api/v3/markets/_ps_iUDlBEemeycL7hWgJNw/policies"
  },
   {
      "rel": "To Reservations",
      "href": "https://10.10.10.10/api/v3/markets/_ps_iUDlBEemeycL7hWgJNw/reservations"
  },
   {
      "rel": "To Statistics",
      "href": "https://10.10.10.10/api/v3/markets/_ps_iUDlBEemeycL7hWgJNw/stats"
  },
   {
      "rel": "To Unplaced Entities",
```



```
"href": "https://10.10.10.10/api/v3/markets/_ps_iUDlBEemeycL7hWgJNw/unplacedentities"
   },
   {
      "rel": "To Market List",
      "href": "https://10.10.10.10/api/v3/markets"
],
"uuid": "_ps_iUDlBEemeycL7hWgJNw",
"displayName": "API_Plan_Market",
"className": "Market",
"state": "COPYING",
"scenario":{
   "uuid":"2452690315520",
   "displayName": "Add Workload 1",
   "owners":[
   "type": "ADD_WORKLOAD"
},
"unplacedEntities":false,
"runDate": "2019-02-25T16:09:34-05:00",
"environmentType": "ONPREM"
```

Getting Statistics for a Market

Referenced Endpoint: Stats (on page 973)

Gets statistics about the specified market. This call can be used to see statistics from the real-time market, or to see the resultant statistics in a plan market after the scenario has been applied.

Example: GET https://10.10.10.10/api/v3/markets/Market/stats

Response: A list of StatSnapshotApiDTOs representing the statistics of the real-time market.

```
{
   "displayName": "PMs",
   "date": "2019-02-23T00:00:00-05:00",
   "statistics":[
         "name": "CPUHeadroom",
         "capacity":{
            "max":8610,
            "min":0,
            "avg":1602.22,
            "total":14420
         },
         "units":"VM",
         "values":{
            "max":8595,
            "min":0,
            "avg":1571.44,
            "total":14143
         },
         "value":1571.44
```



```
},
{
    "name":"CPUExhaustion",
    "units":"Day",
    "values":{
        "max":2147483650,
        "min":0,
        "avg":2147483650,
        "total":2147483650
    },
        "value":2147483650
},
    ...
...
]
```

Getting a Filtered List of Statistics for a Market

Referenced Endpoint: Stats (on page 973)

Gets a list of statistics about the specified market, filtered by the criteria in the StatPeriodApilnputDTO you must pass as an inputDTO to this request. For more information about creating a filtered list of statistics, including example POSTs and responses, see *Filtered Statistics* in the <u>Statistics Endpoint (on page 973)</u>.

Example:

Example Input:

Response: An array of StatSnapshotApiDTOs representing the filtered statistics for the market.

Getting the Supply Chain for a Market

Referenced Endpoint: Supply Chains (on page 993)

Using one or more of the following parameters, you can filter the supply chain that is returned by this request:

market_Uuid

The UUID of the market whose supply chain will be returned

types

The entity types whose supply chain will be returned. Choose from:

- APPLICATION
- APPLICATION_SERVER
- BUSINESS_ACCOUNT
- BUSINESS UNIT
- CHASSIS
- CLOUD_SERVICE
- CONTAINER
- CONTAINER_POD
- DATABASE
- DATABASE_SERVER
- DATACENTER
- DISK_ARRAY



- DPOD
- IO_MODULE
- LOAD BALANCER
- LOGICAL_POOL
- NETWORK
- PHYSICAL_MACHINE
- STORAGE
- STORAGE_CONTROLLER
- SWITCH
- VIRTUAL_APPLICATION
- VIRTUAL DATACENTER
- VIRTUAL MACHINE
- VPOD

entity_states

Only return entities in the specified states. Choose from:

- ACTIVE:

Entity is actively consuming resources.

EVACUATED:

Entity is ready to suspend and will not participate in the market, but will not generate a SUSPEND action.

NOTE: This state replaces the SUSPEND state, and requires additional configuration to enable. Workload Optimization Manager does not recommend enabling this state.

- FAILOVER:

This entity is reserved for failover and will not participate in the market.

- IDLE:

Entity is powered off and not actively consuming market resources.

- LAUNCH:

Entity is starting.

MAINTENANCE:

Entity is in maintenance mode.

– NOT_MONITORED:

Entity is not currently monitored by Workload Optimization Manager.

QUEUED:

Entity is in the process of changing from one state to another.

NOTE: This state is internal to Workload Optimization Manager and will not appear in the UI, but may appear in an API response if the call is executed at the precise moment the entity is changing state.

- RESOURCE_ALLOCATION:

Cloud entity is being created.

- RESOURCE_RELEASE:

Cloud Entity is being deleted.

SUSPEND:

Entity is suspended or the guest OS is in sleep, standby, or suspended state. The entity is not removed from the environment, but will not be used in market decisions. Based on market conditions, suspended entities can be started, re-adding them to the market.

- SUSPEND PENDING:

Entity is making preparations to suspend, or is the next entity of its type to suspend.

- TERMINATE_PENDING:

Entity is in the process of being deleted.



UNKNOWN:

Workload Optimization Manager is unable to obtain the current state of the entity.

This occurs when the entity is reported to the hypervisor as having a state of <code>DISCONNECTED</code>, <code>ORPHANED</code>, or <code>INVALID</code>.

- environment_type
- Only return actions that affect entities in the specified environment type. [CLOUD, HYBRID, ONPREM].
- detail type

The level of detail returned for each item in the returned supply chain. [compact, entity, aspects].

health

Return a small summary of the health of the returned supply chain.

Example: GET https://10.10.10.10/api/v3/markets/Market/supplychains?types=VirtualMachine& entity_states=RESOURCE_ALLOCATION&entity_states=ACTIVE&environment_type=ONPREM&detail_type=aspective.

Response: A SupplychainApiDTO representing the entities meeting your criteria. In the above example, a supply chain including Virtual Machines in the ACTIVE or RESOURCE_ALLOCATION states, in an ONPREM environment, and a healthcheck will be included at the end of the request.

```
"seMap":{
      "VirtualMachine":{
         "depth":-1,
         "entitiesCount":335,
         "healthSummary":{
            "Major":6,
            "Minor":148,
            "Normal":181
         },
         "stateSummary":{
            "ACTIVE":335
         },
         "connectedProviderTypes":[
            "PhysicalMachine",
            "Storage",
            "VirtualDataCenter"
         ],
         "connectedConsumerTypes":[
            "Application"
         ],
         "instances":{
            "421edc7a-761d-9a79-9378-7140caecd50f":{
               "links":[
                      "rel": "self",
                      "href": "https://10.10.10.10/api/v3/entities/421edc7a-761d-9a79-9378-7140caecd50f?inc
lude_aspects=false"
               ],
               "uuid": "421edc7a-761d-9a79-9378-7140caecd50f",
               "displayName": "vm-max-test-netapp",
               "className": "VirtualMachine",
               "priceIndex":1.0070138,
               "state": "ACTIVE",
               "severity": "Normal",
               "discoveredBy":{
```



```
"uuid": "_8c98wBwnEem2J-ksdl1CgA",
           "displayName": "vsphere-dc7.dev.mycorp.com",
           "type": "vCenter"
        },
        "remoteId": "vm-281",
        "aspects":{
           "virtualMachineAspect":{
               "os": "SUSE Linux Enterprise 11 (64-bit)",
               "connectedNetworks":[
                     "uuid": "7d6d67a50cfe1979797de159220841a37a55a50c",
                     "displayName": "VM network"
                  }
              ],
               "numVCPUs":1,
              "ebsOptimized":false
        },
        "environmentType": "ONPREM"
                   . . .
 ]
. . .
```

Markets Endpoint Tips

Unplaced Entities

When running a plan in Workload Optimization Manager, you can add workload or remove infrastructure – if the remaining resources are insufficient for the workload, entities may be "unplaced". Workload Optimization Manager provides an array of the unplaced workloads.

NOTE: An example will be forthcoming.

Finding a Previously Run Plan Market

While the Workload Optimization Manager UI makes a plan look like one item, it is not. A plan comprises two parts:

- A scenario, which represents the configuration options for the plan For more information about plan configuration, see Scenarios (on page 895).
- The plan market that is created when a scenario is run this contains the actions, notifications, etc. that make up the state of the market after the plan.

The simplest way to discover a plan market is to execute the GET https://10.10.10.10.10/api/v3/markets and disregard the main market. The main market DTO entry will be similar to the following:

```
{
  "uuid":"777777",
  "displayName":"Market",
  "className":"Market",
  "state":"RUNNING",
  "stateProgress":100,
  "unplacedEntities":false,
```



```
"environmentType":"HYBRID"
}
```

The other markets that the request returns are plan markets. Plan market DTOs are similar to:

```
{
  "uuid":"214172431889696",
  "displayName":"Add Workload 2",
  "className":"Market",
  "state":"SUCCEEDED",
  "stateProgress":100,
  "scenario":{
      "uuid":"214172431885856",
      "displayName":"Add Workload 2",
      "owners":[
      {
            "uuid":"2993567556912",
            "showSharedUserSC":false
      }
    ]
    ...
}
```

The outer-most unid and displayName parameters are the UUID and display name of plan market. The state field shows the results of the plan run, where SUCCEEDED means the plan finished successfully, and FAILED means the plan did not finish running- usually because it was cancelled by the user.

Within the plan itself, the scenario parameter includes information about the scenario used on the market. Note the inner uuid and displayName are the UUID and display name of the scenario, which you can use to see all markets created using this scenario.

Finally, iterating over the return of the /markets call above, and looking at each market and comparing the UUID of the scenario (in this case, 214172431889696), you can see how many times the scenario was run, and also each market containing the results of that run.

Notifications Endpoint

Notifications are system and market messages from your Workload Optimization Manager instance.

This endpoint contains references to start and end times for certain operations. For more information, including valid time formats, see <u>Time in the Workload Optimization Manager API (on page 742)</u>

Using the notifications endpoint, you can:

- Get all notifications
- Get a filtered list of notifications
- Get related actions for a specified notification

Notification Categories

Each notification from your Workload Optimization Manager instance belongs to a particular category of the following:

- Discovery
- Monitoring
- Control
- Mediation



- Healthcheck
- InterAppliance
- MarketAction
- MarketProblem
- Presentation
- Deploy
- Security

Notifications Requests

Getting Notifications

Gets a list of system and market level notifications. For a list of notifications, the API returns an array of LogEntryApiDTOs. Each LogEntryApiDTO will contain details about the notification, including the time, state, severity, and importance of the notification. To get a single notification, include the UUID of the notification in the request.

This request takes the following parameters:

start_time

The start time for a historic range of notifications.

end_time

The end time for a historic range of notifications.

category

The category of notifications to return. [Discovery, Monitoring, Control, Mediation, Healthcheck, InterAppliance, MarketAction, MarketProblem, Presentation, Deploy, Security]

cursor

When making subsequent calls to retrieve additional results, this is the cursor returned by the last call to this method.

limit

The maximum number of items to return. Must be a positive integer. If not set, the server will provide a default (20).

order_by

The field to order the results by. This value can be any field found in the response.

ascending

Default: true. When false, results will be in descending order.

Examples:

- All Notifications (no parameters): GET https://10.10.10.10/api/v3/notifications
- All Notifications (parameters): GET https://10.10.10.10/api/v3/notifications? start_time=1237056032&end_time=1238056032&limit=100&order_by=name&ascending=true
- Single Notification: GET https://10.10.10.10/api/v3/notifications/_5wcf4J5WEeinZ-6Uu4soUw

Response:



```
"subCategory": "Validation",
    "description": "Validation of target hp-cluster.corp.mycorp.com failed",
    "shortDescription": "Validation Failed",
    "state": "NOTIFY",
    "severity": "MAJOR",
    "importance":0
 },
    "links":[
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/notifications/_sQ7xUJ5XEeinZ-6Uu4soUw"
      }
    ],
    "uuid":"_sQ7xUJ5XEeinZ-6Uu4soUw",
    "logActionTime":1534096010470,
    "targetSE": "Hyper-V:hp-cluster.corp.mycorp.com",
    "category": "Discovery",
    "subCategory": "Discovery",
    "description": "Could not get domain for the 'hp-cluster.corp.mycorp.com' target",
    "shortDescription": "Discovery failed",
    "state": "NOTIFY",
    "severity": "MAJOR",
    "importance":0
 },
]
```

Parking Endpoint

Workload Optimization Manager supports 'parking' actions for cloud resources. These actions *stop* your cloud resources for a given period of time to help you reduce your cloud expenses, and then *start* these resources later when you need them. You can enforce parking actions on demand, or automatically via parking schedules and policies.

Using the Parking endpoint of the Workload Optimization Manager API, you can:

- Get a list of parkable entities
- Enforce parking actions on demand

To enforce parking actions according to a schedule, use /schedules/timespans/ requests in the Schedules endpoint. With these requests, you can configure parking schedules and then attach the schedules to parkable entities. For details, see Parking Schedules Requests (on page 947).

When parking schedules have been attached to entities, you can use the Parking endpoint to pause and resume schedules as needed.

Parking Requests

Pagination for Parking Requests

When you request parking entities, the API uses pagination to return subsets of the data. You should always use pagination when available to make sure you get your data in manageable chunks. To paginate returned data, the limit and cursor parameters control how the APIs paginate their data.



Example: POST https://10.10.10.10/api/v3/parking/entities? cursor=10&limit=5&order_by=DISPLAY_NAME

This example returns the 11th through 16th entities ordered by display name.

For general information about pagination, see Pagination in the Workload Optimization Manager API (on page 742).

Getting Parkable Entities

Provides a list of entities that can be stopped or started.

Example: POST https://10.10.10.10/api/v3/parking/entities

Results may be sorted by one of the following: DISPLAY_NAME, TYPE, STATE, ACCOUNT_NAME, PROVIDER, REGION_NAME, INSTANCE_TYPE or COST. The default sort order is ascending but it may be reversed by including ascending=false in the query string.

Example: POST https://10.10.10.10/api/v3/parking/entities? order_by=DISPLAY_NAME&ascending=true

Getting a Filtered List of Parkable Entities

The simplest form of filtering is to provide one of the following top-level keys:

Field	Possible Values	Example
providers	AWS, AZURE, GCP	{"providers": ["AWS", "GCP"]}
status	STOPPED, RUNNING, STARTING, STOPPING	{"status": ["RUNNING", "STARTING"]}
entityTypes	VirtualMachine, DatabaseServer NOTE: DatabaseServer only applies to AWS RDS instances.	{"entityTypes": ["VirtualMachine"]}

Example: POST https://10.10.10.10/api/v3/parking/entities

Example input that fetches all running VMs in all of your AWS targets:

```
{"entityTypes": ["VirtualMachine"], "status":["RUNNING"], "providers": ["AWS"]}
```

Example: POST https://10.10.10.10/api/v3/parking/entities

Example input, showing the same query with the addition of the field logicalOperator. The logicalOperator value can either be AND or OR, and will control whether the supplied filters are all required or are optional. For example, this request now fetches all entities that are a virtual machine, or are running, or are provided by an AWS target:

```
{"entityTypes": ["VirtualMachine"], "status": "RUNNING"], "providers": ["AWS"], "logicalOperator": "OR"}
```

Advanced Filtering

More powerful filtering is available by using criteriaList. This object supports additional fields and provides more control over your filter expressions, including regular expression filtering. Each element in a criteriaList contains the following keys: expVal, expType, and filterType.

filterType	ехрТуре	Constraints
displayName	EQ, NEQ, RXEQ, RXNEQ	
accountName	EQ, NEQ, RXEQ, RXNEQ	
regionName	EQ, NEQ, RXEQ, RXNEQ	
instanceType	EQ, NEQ, RXEQ, RXNEQ	



filterType	expType	Constraints
scheduleName	EQ, NEQ, RXEQ, RXNEQ	
tags	EQ, NEQ, RXEQ, RXNEQ	Discovered tags containing pipes may produce unexpected results when using an expType of RXEQ or RXNEQ
cost	EQ, NEQ, GT, LT, GTE, LTE	

Example: POST https://10.10.10.10/api/v3/parking/entities

Example input that fetches all entities within the "Engineering" account:

```
{
  "criteriaList": [
    {
      "expVal": "Engineering",
      "expType": "EQ",
      "filterType": "accountName"
    }
]
```

Advanced filtering may also take advantage of logicalOperator, if desired.

Example: POST https://10.10.10.10/api/v3/parking/entities

Example input that returns all entities in either the "Engineering" or "Test" accounts:

Executing Parking Actions

You may start or stop parkable entities on demand by submitting a manual action request. Manual actions are executed immediately.

NOTE

Manual actions will not be accepted if the entities are controlled by a schedule. For these entities, you must first pause schedule enforcement.

Example: POST https://10.10.10.10/api/v3/parking/bulkActionRequest

Example input that generates actions to start the provided entities:

```
{"action": "START", "entityUuids": ["74913973295604"]}
```



Constraints: action can either be START or STOP.

Response:

This API responds with one element for each entityUuid provided and indicates the resulting state.

```
[{"state":"STARTING","entityUUID":"74913973295604"}]
```

If an action could not be generated for a particular entityUuid, the response will contain an error message:

```
[{"error": "unable to toggle the entity", "entityUUID": "74913973295605"}]
```

If an action is requested for multiple entities, a response may contain a partial success. Check the response body to understand whether the action succeeded for a particular entity.

```
[{"state":"STARTING","entityUUID":"74913973295604"}, {"error":"unable to toggle the entity","entityUUID":"74913973295605"}]
```

Pausing and Resuming Parking Schedules

Parking schedules must first be configured and attached to entities using /schedules/timespans requests. For details, see Parking Schedules Requests (on page 947).

After attaching schedules to entities, you can pause or resume schedules using the Parking endpoint.

Pausing Parking Schedules

There are times when pausing schedule enforcement is useful. The most common use is when you need to pause an environment during non-typical work hours or when an unanticipated maintenance window requires automation outside Workload Optimization Manager to start and stop workloads. Like <u>attaching and detaching schedules (on page 954)</u>, you may pause or resume 1-N entities from schedule enforcement.

Example: POST https://10.10.10.10/api/v3/parking/enforcementPauses

Example input that pauses schedule enforcement for 1-N entities using a duration in minutes (only supported unit):

```
{"entityUuids":["74913973295604"],"durationMinutes":15}
```

Example input that pauses schedule enforcement for 1-N entities until 12:26 PM Central (UTC-5) in ISO 8601 date and time format:

```
{"entityUuids":["74913973295604"],"until":"2023-05-16T14:26:00-05:00"}
```

Resuming Parking Schedules

Example: DELETE https://10.10.10.10/api/v3/parking/enforcementPauses

Example input that resumes schedule enforcement for 1-N entities:

```
{"entityUuids":["74913973295604"]}
```

Policies Endpoint

Policies set business rules to control how Workload Optimization Manager analyzes resource allocation, how it displays resource status, and how it recommends or executes actions. There are two kinds of policies:

Placement Policies

To modify workload placement decisions, Workload Optimization Manager divides its market into segments that constrain the valid placement of workloads. Workload Optimization Manager discovers placement rules that are defined by the targets in your environment, and you can create your own segments.



Automation Policies

Workload Optimization Manager uses Automation Policies to guide its analysis and resulting actions. These policies can specify Action Automation, Orchestration, and Constraints (operational, utilization, and scaling constraints).

Workload Optimization Manager ships with default settings that we believe will give you the best results from our analysis and control. For some scopes of your environment, you might want to change these settings. For example, you might want to change action automation for that scope, or change the utilization constraints.

The hypervisors that you set as targets can include placement policies of their own. Workload Optimization Manager imports these placement policies, and you can choose to enable or disable them as you wish. By default, Workload Optimization Manager enables imported placement policies.

Using the policies endpoint, you can:

- Get API entry points for policies
- See details about a specific policy

Policies Utility Requests

Utility requests provide metadata that you can use to make related requests, assemble inputDTOs, or see the potential values of a particular DTO.

The policies endpoint contains a utility request that shows the entry points for policy-related requests. These can be used to find the UUID and details relating to a specific policy.

Example: GET https://10.10.10.10/api/v3/policies

Response: An array of Link objects, where each object contains a URL to get all policies for a specified market, entity, or group.

```
"links":[
    {
        "rel":"Market policies",
        "href":"https://10.10.10.10/api/v3/markets/{uuid}/policies"
    },
    {
        "rel":"Entity policies",
        "href":"https://10.10.10.10/api/v3/entities/{uuid}/policies"
    },
    {
        "rel":"Group policies",
        "href":"https://10.10.10.10/api/v3/groups/{uuid}/policies"
    }
],
    "enabled":false
```

Policies Requests

Getting the Details of a Specified Policy

The single policy request gets the details of a specified policy, given that policy's UUID. You may use this after getting policies that affect a certain scope, to view details of those policies.

```
Example: GET https://10.10.10.10/api/v3/policies/104:domain-c7:10.10.111.111
```

Response: A PolicyApiDTO describing details about the policy, including the group information for the provider of the policy.

{



```
"links":[
    "rel": "self",
    "href": "https://10.10.10.10/api/v3/policies/104:domain-c7:10.10.111.111"
  }
],
"uuid": "104:domain-c7:10.10.111.111",
"displayName": "GROUP-DRS-LN-rule/Cluster1/10.10.111.111",
"type": "BIND_TO_GROUP",
"name": "GROUP-DRS-LN-rule/Cluster1/10.10.111.111",
"enabled":true,
"capacity":1000000000,
"commodityType": "DrsSegmentationCommodity",
"consumerGroup":{
  "uuid": "7843e134bab4fb841b9cb7dd98ef04acf1f36f7b",
  "displayName": "Buyers-Group-GROUP-DRS-vmGroup1/Cluster1/10.10.111.111",
  "className": "DiscoveredGroup",
  "groupType": "VirtualMachine",
  "isStatic":true,
  "logicalOperator": "AND"
},
"providerGroup":{
  "uuid": "597a35089bfe405291911f3191cf24234d4713d1",
  "displayName": "Sellers-Group-GROUP-DRS-hostGrp1/Cluster1/10.10.111.111",
  "className": "DiscoveredGroup",
  "groupType": "PhysicalMachine",
  "isStatic":true,
  "logicalOperator": "AND"
```

Creating a Policy

Policies are created for a specific market- either a plan market, or the real-time market. For more information about policy creation, see the <u>Markets (on page 855)</u> endpoint.

Price Lists Utility Requests

Utility requests provide metadata that you can use to make related requests, assemble inputDTOs, or see the potential values of a particular DTO.

The price list endpoint contains a sample rate card file and RateCardApiDTO. To access this sample:

- Execute the GET https://10.10.10.10/api/v3/pricelists request, and locate the price list whose displayName begins with Sample Azure Rate Card.
- 2. Record the UUID of this rate card.
- 3. Execute the https://10.10.10.10/api/v3/pricelists/{uuid_from_step_2}/export request, and download the file that makes up the response body.

Price Lists Requests

The price lists endpoint is not implemented at this time.



Reservations Endpoint

Workload Optimization Manager uses reservations to save the resources you will need if you want to deploy workloads at a future date. Workload Optimization Manager calculates optimal placement for these workloads, and then it reserves whatever resources the different hosts and storage entities will need to support those workloads. For example, you can instruct Workload Optimization Manager on 01 January to reserve the resources required for 100 workloads on 07 January.

Using the reservations endpoint of the Workload Optimization Manager API, you can:

- Get a list of reservations
- Create a reservation
- Get information about a specific reservation
- Delete a reservation

Reservation States

Reservations will be in one of the following states:

FUTURE

The reservation is set to occur after the current date.

■ TNTTTAT

The reservation is being created; occurs at the start time of the reservation.

■ INPROGRESS

The reservation request has been sent to the market provider(s), and is awaiting results.

■ INVALID

This error state occurs when a reservation is placed on an unready market (for example, when the market component is restarting) or one of the constraints or templates used in the reservation has been deleted between the creation of the reservation, and the start date.

■ PLACEMENT FAILED

The reservation has completed, but there were insufficient resources to place all entites.

■ RESERVED

The reservation has completed and was able to obtain all needed resources.

■ UNFULFILLED

The reservation has been added to the database, but has not yet been sent to the market.

Reservations in the Product

From the Workload Placement Page, you can set up reservations to save the resources you will need to deploy workloads at a future date. Workload Optimization Manager uses its intelligent workload management to calculate optimal placement for these workloads, and then it reserves whatever resources the different hosts and storage entities will need to support those workloads.

When creating a reservation in the product, you will select the VM template, any constraints (scope, policy, network), then give your reservation a name, virtual machine count, and start and end dates.

Reservations Requests

Getting Reservations

For a list of reservations, the API returns a list of DemandReservationApiDTOs. Each DemandReservationApiDTO will contain the entity information for the reserved instances, the count to be deployed, and current status. To get the DTO of a particular reservation, include the UUID in the request.

This request takes the following parameters:

Status



Returns only reservations in the specified status. [PLACEMENT_SUCCEEDED, PLACEMENT_FAILED, UNFULFILLED, RESERVED, DEPLOY_FAILED, DEPLOY_SUCCEEDED, FUTURE]

Examples:

■ All reservations with a status of PLACEMENT_SUCCEEDED:

```
GET https://10.10.10.10/api/v3/reservations?status=PLACEMENT_SUCCEEDED
```

A single reservation:

GET https://10.10.10.10/api/v3/reservations/_TszrkcwHEei7A9DOcc4f1g

Response:

```
[
    "uuid": "215446856141616",
    "displayName": "MyReservation",
    "count": 1,
    "status": "RESERVED",
    "reserveDateTime": "2022-11-01T13:28:00Z",
    "expireDateTime": "2022-12-01T14:28:00Z",
    "constraintInfos": [
        "uuid": "74635127126226",
        "constraintType": "DATA_CENTER"
     }
   ],
    "reservationDeployed": false,
    "mode": "NO_GROUPING",
    "grouping": "NONE",
    "demandEntities": [
        "template": {
          "uuid": "215364307544240",
          "displayName": "headroomVM",
          "className": "VirtualMachineProfile"
        "placements": {
          "computeResources": [
              "stats": [ ...
              Stats for CPU, CPUProvisioned, Mem, MemProvisioned, IOThroughput, NetThroughput
              ...],
              "provider": {
                "uuid": "74635127126242",
                "displayName": "hp-dl3111.eng.vmturbo.com",
                "className": "PhysicalMachine"
              },
              "linkedResources": [
                  "uuid": "285741371272387",
                  "displayName": "DC13/Physical Hosts_Cluster2 - Intel"
              ]
          ],
```



```
"storageResources": [
          {
            "stats": [ ...
             Stats for StorageProvisioned, StorageAmount, StorageAccess
            ...],
            "provider": {
              "uuid": "74635124839222",
              "displayName": "QSGRID01:DC1314Shared",
              "className": "Storage"
            }
          }
        ]
      }
    }
  1
}
```

Creating a Placement Reservation

To create a placement reservation, POST a completed DemandReservationApilnputDTO as input to this request. The DTO specifies reservation type, the template to use, the UUIDs of constraints such as placement or network policies, and other attributes of the reservation.

Example: POST https://10.10.10.10/api/v3/reservations

Example inputDTO, to execute a reservation for two instances of a template:

```
"demandName": "MyReservation1",
"action": "RESERVATION",
"mode": "NO_GROUPING",
"grouping": "NONE",
"reserveDateTime": "2022-11-01T21:03:22Z",
"expireDateTime": "2022-12-01T21:03:22Z",
"parameters": [
    "placementParameters": {
      "count": 2,
      "templateID": "215364307544240",
      "entityNames": [
        "MyRes1_VM1",
        "MyRes1_VM2"
      ],
      "constraintIDs": [
        "285815619396128"
    }
  }
1
```

Response: A DemandReservationApiDTO that will include the status of the placement attempt. Note that the status of this reservation is FUTURE. When Workload Optimization Manager executes the reservation, if it succeeds in placing the reserved VMs then the placements field will contain descriptions of the host and storage providers for the two VMs.



```
"uuid": "215447101807136",
"displayName": "MyReservation1",
"count": 2,
"status": "FUTURE",
"reserveDateTime": "2022-11-01T21:03:22Z",
"expireDateTime": "2022-12-01T21:03:22Z",
"constraintInfos": [
    "uuid": "285815619396128",
    "constraintType": "POLICY"
],
"reservationDeployed": false,
"mode": "NO_GROUPING",
"grouping": "NONE",
"demandEntities": [
    "template": {
      "uuid": "215364307544240",
      "displayName": "headroomVM",
      "className": "VirtualMachineProfile"
    },
    "placements": {}
  },
    "template": {
      "uuid": "215364307544240",
      "displayName": "headroomVM",
      "className": "VirtualMachineProfile"
    },
    "placements": {}
]
```

Deleting a Reservation

Deletes the specified reservation and removes all reserved resources associated with that reservation. This will also remove any pending deployment related to the deleted reservation.

Example: DELETE https://10.10.10.10/api/v3/reservations/_i-FLwdLiEeiuY7KDiLoLWg

Response: A successful deletion request returns a Response Code of 200.

Reservations Endpoint Tips

Customizing a Reservation

When creating a reservation, you should be familiar with <u>placement policies (on page 881)</u>, <u>templates (on page 1010)</u>, scope constraints, and network constraints.



NOTE:

Use network constraint to limit workload placement to the networks that Workload Optimization Manager discovered in your environment.

This request takes the following parameters of the DemandReservationApiInputDTO:

demandName

The display name of the reservation – If you do not specify names for the reserved workloads, they will all get this as the root name, with a numeric suffix. For example, MyReservation1, MyReservation2, etc.

action

The action type: This is always RESERVATION.

reserveDateTime

The time to calculate the workload placement and create the reservation – This time cannot be earlier than the time that you POST the reservation to the API.

expireDateTime

When to cancel the reservation. At this time, Workload Optimization Manager will delete the reservation. To take advantage of the reserved resources, you should deploy the actual VMs to their reserved locations before this time.

parameters

A DemandReservationParametersDTO, which is itself composed of a PlacementParametersDTO and DeploymentParametersDTO.

In order to pass a completed DemandReservationParametersDTO, you will create a PlacementParametersDTO with the following parameters:

count

The number of workloads in this reservation

templateID

The UUID of the template used for creating the workload required for the placement

entityNames

Name of the placed workload, which will be affixed with a numeric suffix for reservations of more than one workload

constraintIDs

The UUIDs of the scope, group and any policies or network constraints that the reservation will adhere to

For example, the following POST creates a reservation of 10 VMs, scoped to a specific virtual data center with a UUID of 73365042986774 and network with a UUID of 73365048169751. Because it does not specify entityNames (an array of names for the VMs), Workload Optimization Manager will generate the VM names.



```
}
```

Affinity Rules

When creating reservations, you can specify affinity rules for the reserved VMs, to ensure all the VMs in a reservation deploy to the same cluster. If you do not specify affinity, the VMs deploy to any clusters in the reservation's scope. These settings are optional, but if you choose to specify affinity, you must specify compatible values for both settings.

These setting respect other constraints you might have set for the reservation. For example, if you scope the reservation to a group of clusters, with a cluster affinity rule Workload Optimization Manager will choose one cluster from that scope and try to place all the VMs on it.

To specify affinity for a reservation, you declare:

■ mode (optional):

Can be one of:

- AFFINITY Group reserved VMs in the same cluster. The grouping parameter must be set to CLUSTER. If there is
 no cluster that can host the requested VMs, the reservation will be UNFULLFILLED.
- NO_GROUPING Do not group reserved VMs in the same cluster. The grouping parameter must be set to NONE.
- grouping (optional):

Can be one of:

- CLUSTER Group reserved VMs. The mode parameter must be set to CLUSTER.
- NONE Do not group reserved VMs. The mode parameter must be set to NO_GROUPING.

```
{
  "demandName": "MyReservation1",
  "action": "RESERVATION",
  "mode": "AFFINITY",
  "grouping": "CLUSTER",
  ...
}
```

Getting Reservation Information

To get a list of current reservations, execute the GET https://10.10.10.10/api/v3/reservations request. This returns a list of all active reservations. If you know the UUID of the reservation you want to retrieve, you can pass it to get data for just that reservation.

Each reservation object describes:

- Display name
- Status can be:
 - IN PROGRESS Placement calculation is in progress
 - PLACEMENT_SUCCEEDED For a new reservation, the environment has sufficient resources to place the workload; if you specified a reserve date, this will be an active reservation
 - PLACEMENT_FAILED For a newly created reservation, the environment doesn't have resources to place the workload; if you specified a reserve date, this will be an unfulfilled reservation
 - RETRYING Workload Optimization Manager is trying to place the workload of an unfulfilled reservation
- Time the reservation was created, and time it will expire
- A description of the reserved workload
- Statistics for the compute and storage resources the reservation sets aside

For example, this listing shows a successful reservation for one VM:

{



```
"uuid": "_kWZHIDDmEeePgeXuo0RRbw",
"displayName": "MyReservation",
"count":1,
"status": "PLACEMENT_SUCCEEDED",
"reserveDateTime": "Thu May 04 16:27:29 UTC 2017",
"expireDateTime": "Thu Aug 31 16:27:29 UTC 2017",
"deployDateTime": "Thu Aug 31 16:27:29 UTC 2017",
"reserveCount":1,
"demandEntities":[
    "uuid": "_kWgb7TDmEeePgeXuo0RRbw",
    "displayName": "MyReservation_C0",
    "className": "VirtualMachine",
    "template":{
      "uuid": "T423f548d-cadc-e525-6df4-1f90724cf696",
      "displayName": "vsphere-dc3.dev.mycorp.com::TMP-SUSE64",
      "className": "VirtualMachineProfile"
    },
    "placements":{
      "computeResources":[
        {
          "stats":[
            {
              "name": "numOfCpu",
              "value":1
            },
              "name": "cpuSpeed",
              "value":2603
            },
              "name": "cpuConsumedFactor",
              "value":0.5
            },
              "name": "memorySize",
              "value":2097152
            },
              "name": "memoryConsumedFactor",
              "value":0.75
            },
              "name": "ioThroughput",
              "value":0
            },
              "name": "networkThroughput",
              "value":0
            }
          ],
          "provider":{
            "uuid": "Virtual_ESX_42381da5-12fa-1e82-2f1c-887419380d43",
            "displayName": "hp-esx21.corp.vmturbo.com",
```



```
"className": "PhysicalMachine"
          }
        }
      ],
      "storageResources":[
           "stats":[
             {
               "name": "diskSize",
               "value":18432.363
             },
               "name": "diskIops",
               "value":0
             }
          ],
           "provider":{
             "uuid": "10545c15-7687ef26",
             "displayName": "QS2:ESXDC3DS1",
             "className": "Storage"
        }
      ]
    }
1
```

Creating a Reservation

To create a reservation, you POST an input DTO that defines the reservation's:

- action: The action type: RESERVATION
- demandName: The display name of the reservation If you do not specify names for the added workloads, this will be the
 root name for new VMs
- placementParameters:
 - constraintIDs: An array of UUIDs for placement policies that will affect the calculated placement
 - count: The number of workloads to place
 - entityNames: An array of names for the placed VMs The array length should equal count
 - geographicRedundancy: If true place the workloads on unique hosts, otherwise Workload Optimization Manager can place multiple workloads on the same host
 - templateID: The UUID of the template that you will use to place this workload Note that the template must include
 a reference to the deployment profile that you specify in deploymantParameters
- expireDateTime: When to cancel a reservation if Workload Optimization Manager cannot place all the workloads by that date – for a RESERVATION action, Workload Optimization Manager automatically sets the deploy time to equal this time
- reserveDateTime: The time to calculate the workload placement and create the reservation This time cannot be earlier than the time that you POST the reservation to the API

The following listing shows an input DTO that creates a reservation. It will place four workloads, and it gives specific names ot each one.

```
{
  "action": "RESERVATION",
  "demandName": "MyReservation",
  "expireDateTime": "2017-10-10T12:38:17+00:00",
  "parameters": [
```



```
{
    "deploymentParameters": {
        "deploymentProfileID": "_c9CJMDDAEeePgeXuo0RRbw"
},
    "placementParameters": {
        "geographicRedundancy": false,
        "count": 4,
        "entityNames": [
            "foo","bar","baz","bonk"
        ],
        "templateID": "_UKsnkJkSEeCHcOXEhzJExA"
        }
    }
}

// "reserveDateTime": "2017-05-04T18:22:12+00:00"
```

Reserved Instances Endpoint

Workload Optimization Manager analysis takes advantage of AWS Reserved Instances and Azure Reserved VM Instances to calculate optimal workload placement and to arrive at the best possible costs for your deployments on the cloud.

Using the reserved instances endpoint of the Workload Optimization Manager API, you can:

- Get a single reserved instance or list of reserved instances present in your environment
- Get statistics related to the reserved instances

Reserved Instances Requests

Getting Reserved Instances

For a list of reserved instances, the API returns an array of ReservedInstanceApiDTOs. Each ReservedInstanceApiDTO will contain the validation status, target type and category, and input field names and values. To get a single reserved instance, include the UUID of the reserved instance in the request.

This request takes the following parameters:

scope

Returns only reserved instances in the specified scope. This can be the scope of a group of entities or target. For example, to see reserved instances for a single AWS target, use that target's UUID here.

Examples:

- All Reserved instances: GET https://10.10.10.10/api/v3/reservedinstances
- Reserved Instances for a Specified Scope: GET https://10.10.10.10//api/v3/reservedinstances? scope=_zeCtIMAVEei2-fP3xzx1Fw

Response:



```
"discovered": false,
  "family": "i3"
"platform": "LINUX",
"type": "STANDARD",
"location": {
  "uuid": "aws::eu-west-1::DC::eu-west-1",
  "displayName": "aws-EU (Ireland)"
},
"accountId": "19265476245",
"targetId": "_zeCtIMAVEei2-fP3xzx1Fw",
"masterAccountId": "194356375",
"term": {
  "units": "Year",
  "values": {
    "max": 1,
    "min": 1,
    "avg": 1,
    "total": 1
 },
  "value": 1
},
"payment": "PARTIAL_UPFRONT",
"onDemandPrice": {
 "units": "$/h",
  "values": {
    "max": 0.172,
    "min": 0.172,
    "avg": 0.172,
    "total": 0.172
 },
  "value": 0.172
},
"costPrice": {
  "units": "$/h",
  "values": {
    "max": 0.11193608,
    "min": 0.11193608,
    "avg": 0.11193608,
    "total": 0.11193608
 },
  "value": 0.11193608
},
"coupons": {
  "capacity": {
    "max": 16,
    "min": 16,
    "avg": 16
  },
  "units": "RICoupon",
  "values": {
    max: 0,
    "min": 0,
    "avg": 0,
```



```
"total": 0
},
    "value": 0
},
    "totalCoupons": 0,
    "expDate": "Sat Apr 06 19:11:19 EDT 2019",
    "instanceCount": 1,
    "tenancy": "DEFAULT",
    "upFrontCost": 490,
    "actualHourlyCost": 0.0560000017285347,
    "effectiveHourlyCost": 0.11193607478789543
},
...
```

Getting Entities Covered by Reserved Instances

Given the UUID of a reserved instance, the API returns a list of entities covered by the reserved instance.

This request takes the following parameters:

reservedInstance_Uuid

The UUID of the reserved instance.

Example: GET https://10.10.10.10/api/v3/reservedinstances/1234/coveredEntities

Response: An array of BaseApiDTOs describing the entities covered by the specified RI.

```
{
    "uuid":"73943736161360",
    "displayName":"pyaus",
    "className":"VirtualMachine"
},
{
    "uuid":"73812178348464",
    "displayName":"ptaub807disabled",
    "className":"VirtualMachine"
},
{
    "uuid":"73746051159552",
    "displayName":"pymm",
    "className":"VirtualMachine"
}
```

Roles Requests

The roles endpoint is not implemented at this time.



Scenarios Endpoint

To run a plan scenario, Workload Optimization Manager creates a snapshot copy of your real-time market and modifies that snapshot according to the scenario. It then uses the Economic Scheduling Engine to perform analysis on that plan market. A scenario can modify the snapshot market by changing the workload, adding or removing hardware resources, or changing or eliminating constraints such as cluster boundaries or placement policies.

As it runs a plan, Workload Optimization Manager continuously analyzes the plan market until it arrives at the optimal conditions that market can achieve. When it reaches that point, the Economic Scheduling Engine cannot find better prices for any of the resources demanded by the workload – the plan stops running, and it displays the results as the plan's desired state.

The display includes the resulting workload distribution across hosts and datastores, as well as a list of actions the plan executed to achieve the desired result.

For example, assume a scenario that adds virtual machines to a cluster. To run the plan, Workload Optimization Manager takes a snapshot of the current market, and adds the VMs to the specified cluster. Workload Optimization Manager then runs analysis on the plan market, where each entity in the supply chain shops for the resources it needs, always looking for a better price – looking for those resources from less-utilized suppliers. This analysis continues until all the resources are provided at the best possible price.

The results might show that you can add more workload to your environment, even if you reduce compute resources by suspending physical machines. The recommended actions would then indicate which hosts you can take offline, and how to distribute your virtual machines among the remaining hosts.

The settings you make in a scenario correspond to the plan settings you can make in the user interface. These include:

- Plan scope
- Changes to workload (adding, removing, or replacing VMs or containers)
- Changes to supply (adding, removing, replacing PMs or storage)
- Enable/disable placement policies and other constraints
- Changes to action modes
- Enable/disable provisioning of supply
- Enable/disable resizing of workloads

Using the scenarios endpoint of the Workload Optimization Manager API, you can:

- Get a list of scenarios on your instance
- Create a scenario
- Get a list of markets that are connected to a particular scenario

Scenarios Requests

Getting Scenarios

The API returns a ScenarioApiDTO including the following fields when you execute a GET /scenarios request:

- uuic
 - The unique identifier for this scenario.
- displayName

By default, Workload Optimization Manager creates a display name that matches the scenario type. You may rename the scenario after creation using a PUT request.

- owners
 - An array of user accounts that can use the scenario. Currently, this is always the user that created the scenario.
- type

The type of scenario. When a user creates a scenario in the GUI, this matches the given type that user chooses from the Plan Wizard.

- scope
 - An array of scope objects to specify the scope of the plan.
- projectionDays



An array of days to specify how far into the future to project the plan. For example, a value of [30, 60, 120] would return projections after one, two, and four months, respectively.

■ topologyChanges

An array of additions or deletions to the set of entities in the plan scope.

loadChanges

An array of changes to the utilization percentage for different groups of entities within the plan scope.

configChanges

An array of configuration changes for different groups of entities within the plan scope.

■ changes - DEPRECATED

An array of scenario settings that make changes to the market before running the plan.

Example: GET https://10.10.10.10/api/v3/scenarios?show_all=false

Response:

```
"uuid": "214704587455872",
"displayName": "Migrate to Public Cloud 1_CLOUD_MIGRATION__CONSUMPTION",
"type": "CLOUD_MIGRATION",
"scope": [
    "uuid": "73935388327649",
    "displayName": "aws-EU (Frankfurt)",
    "className": "Region"
 }
],
"projectionDays": [
 0
],
"topologyChanges": {
  "migrateList": [
    {
      "projectionDay": 0,
      "source": {
        "uuid": "285041726554576",
        "displayName": "Unknown"
      },
      "destination": {
        "uuid": "73935388327649",
        "displayName": "aws-EU (Frankfurt)",
        "className": "Region",
        "state": "ACTIVE",
        "severity": "Minor",
        "discoveredBy": {
          "uuid": "73935444966640",
          "displayName": "testmachine",
          "category": "Public Cloud",
          "type": "AWS",
          "readonly": false
        "severityBreakdown": {
          "MINOR": 1
        },
        "numRelatedVMs": 2,
```



```
"environmentType": "CLOUD",
        "vendorIds": {
          "vmturboamp": "aws::eu-central-1::DC::eu-central-1"
      },
      "sources": [
        {
          "uuid": "285041726554576",
          "displayName": "Unknown"
      ],
      "destinations": [
          "uuid": "73935388327649",
          "displayName": "aws-EU (Frankfurt)",
          "className": "Region",
          "state": "ACTIVE",
          "severity": "Minor",
          "discoveredBy": {
            "uuid": "73935444966640",
            "displayName": "testmachine",
            "category": "Public Cloud",
            "type": "AWS",
            "readonly": false
          "severityBreakdown": {
            "MINOR": 1
          },
          "numRelatedVMs": 2,
          "environmentType": "CLOUD",
          "vendorIds": {
            "vmturboamp": "aws::eu-central-1::DC::eu-central-1"
          }
        }
      ],
      "destinationEntityType": "VirtualMachine",
      "removeNonMigratingWorkloads": true
  ]
},
"loadChanges": {
  "utilizationList": [],
  "maxUtilizationList": []
},
"configChanges": {
  "addPolicyList": [],
  "removePolicyList": [],
  "automationSettingList": [],
  "removeConstraintList": [],
  "riSettingList": [
      "uuid": "ri.aws.preferredOfferingClass",
      "displayName": "Type",
      "value": "STANDARD",
```



```
"valueObjectType": "String"
 },
   "uuid": "ri.aws.preferredPaymentOption",
   "displayName": "Payment",
   "value": "ALL_UPFRONT",
    "valueObjectType": "String"
    "uuid": "ri.aws.preferredTerm",
   "displayName": "Term",
   "value": "YEARS_1",
   "valueObjectType": "String"
],
"osMigrationSettingList": [
    "uuid": "linuxTargetOs",
   "displayName": "linuxTargetOs",
   "value": "LINUX",
    "valueObjectType": "String"
 },
    "uuid": "linuxByol",
   "displayName": "linuxByol",
   "value": "false",
   "valueObjectType": "String"
 },
   "uuid": "rhelTargetOs",
   "displayName": "rhelTargetOs",
   "value": "RHEL",
    "valueObjectType": "String"
 },
    "uuid": "rhelByol",
   "displayName": "rhelByol",
   "value": "false",
    "valueObjectType": "String"
 },
   "uuid": "slesTargetOs",
    "displayName": "slesTargetOs",
    "value": "SLES",
   "valueObjectType": "String"
   "uuid": "slesByol",
   "displayName": "slesByol",
   "value": "false",
    "valueObjectType": "String"
   "uuid": "windowsTargetOs",
```



```
"displayName": "windowsTargetOs",
        "value": "WINDOWS",
        "valueObjectType": "String"
      },
        "uuid": "windowsByol",
        "displayName": "windowsByol",
        "value": "false",
        "valueObjectType": "String"
        "uuid": "selectedMigrationProfileOption",
        "displayName": "selectedMigrationProfileOption",
        "value": "MATCH_SOURCE_TO_TARGET_OS",
        "valueObjectType": "String"
      },
        "uuid": "matchToSource",
        "displayName": "matchToSource",
        "value": "true",
        "valueObjectType": "String"
    ],
    "includedCoupons": {
      "includedCouponOidsList": [],
      "iswhiteList": true
    },
    "subscription": {
      "uuid": "73935382668544",
      "displayName": "EngineeringSample",
      "className": "BusinessAccount",
      "accountId": "323871187550",
      "master": false,
      "cloudType": "AWS",
      "riSupported": false,
      "hasRelatedTarget": false
    }
  }
}
```

Creating a Scenario

In order to create a scenario, see the <u>Scenario DTO Breakdown (on page 900)</u>. For examples of complete ScenarioApiDTOs, see <u>Scenario Configuration Examples (on page 912)</u>.

Deleting a Scenario

Deletes the specified scenario. Note that this does not delete plan markets you create using that scenario.

Example: DELETE https://10.10.10.10/api/v3/scenarios/__xwWYAE3EeiNKPbzHdETIA

Response: A successful deletion request returns a Response Code of 200.



Scenario DTO Breakdown

Scenario DTO Overview

A scenario DTO assembles configuration settings that you use to set up and run a plan. To run a plan, you will POST the scenario to a market. For most plans, this will be the real-time market. In the case of a plan-over-plan, this will be the market created from the first scenario.

Workload Optimization Manager will then run a plan based on the combination of the scenario and the market state.

These configuration settings fall into one of several groups:

Configuration Changes (ConfigChangesApiDTO)

Adding and removing placement policies, removing constraints, and providing automation settings, OS migration settings, reserved instance settings, and associated business units.

■ Load Changes (LoadChangesApiDTO)

Modifications to the current and max utilization values, and peak baseline values.

Time-Based Topology Changes (TimeBasedTopologyChangesApiDTO)

Settings to include reserved VMs and periodically add historical workload to the environment.

Topology Changes (TopologyChangesApiDTO)

Settings to add, remove, replace, and migrate workload, or to specify the clusters for an Alleviate Pressure plan.

DTO Configuration Changes

The scenario configuration changes, located in the configChanges parameter of the ScenarioApiDTO, enable you to perform the following tasks:

addPolicyList

Add a placement policy to the market generated for this plan.

automationSettingList

Change one of the available automation plan settings: VM Resize, Host Provision/Suspend, and Storage Provision/Suspend.

osMigrationSettingList

For a Migrate to Cloud plan, this parameter will contain the source and destination OS platforms, and their BYOL (Bring Your Own License) status.

removeConstraintList

Remove a constraint from the market generated for this plan.

removePolicyList

Remove a placement policy from the market generated for this plan.

riSettingList

Add information about your reserved cloud instances.

subscription

Associate a business unit to the plan.

Adding and Removing Placement Policies

Referenced Endpoint: Policies (on page 881)

When running plans, you might want to see what your environment would look like with or without certain policies enabled, or with a new policy present. You can see the effects of these changes by passing the UUIDs of current policies, or a PolicyApiDTO for a new policy.

Example input (Current Policies):



```
"uuid": "52672058-a93b-d0a9-bbd9-5acd33f27882" }
```

Example input (New Policy):

```
"addPolicyList": [
     {
        "capacity": null,
        "consumerGroup": {
          "uuid": "8c17d8e79c3db85ed5d3868de622cb89187849ce",
          "displayName": "PMs_Beta DC6\\Cluster-2",
          "className": "Group",
          "groupType": "PhysicalMachine",
          "isStatic": true,
          "logicalOperator": "AND"
        },
        "enabled": true,
        "mergeGroups": null,
        "mergeType": null,
        "name": "DalTestPolMerge",
        "displayName": "DalTestPolMerge",
        "providerGroup": {
          "uuid": "91ff08749fd278925d73b61b0f0f69d79c99fc3a",
          "displayName": "PMs_Beta DC6\\Cluster-1",
          "className": "Group",
          "groupType": "PhysicalMachine",
          "isStatic": true,
          "logicalOperator": "AND"
        },
        "type": "MERGE",
        "uuid": ""
      }
    ]
```

Setting Plan Automation Settings

Use the plan automation settings to see the effect of your scenario if VM resizes, Host Provisioning / Suspension, and Storage Provisioning / Suspension are enabled or disabled.



```
"uuid": "suspendPM",
    "displayName": "Suspend for PHYSICALMACHINES disabled",
    "value": "false",
    "entityType": "PhysicalMachine"
  },
    "uuid": "provisionDS",
    "displayName": "Provision for STS disabled",
    "value": "false",
    "entityType":"Storage"
  },
    "uuid": "suspendDS",
    "displayName": "Suspend for STS enabled",
    "value": "true",
    "entityType": "Storage"
  }
]
```

Additionally, you can use these settings to adjust operational constraints, such as provisioned values for CPU and MEM:

Example Input:

Providing Cloud Reserved Instance Information

Workload Optimization Manager enables you to upload RI pricing information specific to the scenario.



```
"displayName": "Payment",
    "value": "PARTIAL_UPFRONT",
    "entityType": "PARTIAL_UPFRONT"
 },
  {
    "uuid": "preferredOfferingClass",
    "displayName": "Type",
    "value": "STANDARD",
    "entityType": "STANDARD"
 },
  {
    "uuid": "preferredCoverage",
    "displayName": "Coverage",
    "value": "80",
    "entityType": "80"
 },
  {
    "uuid": "riCoverageOverride",
    "displayName": "RI Coverage Override",
    "value": "false",
    "entityType": "false"
  }
]
```

Removing Constraints

Referenced Endpoint: Entities (on page 791)

When running plans, you might want to see what your environment would look like with or without certain constraints. For example, if a group of virtual machines was allowed to move to any cluster of your environment.

In order to remove a constraint, you must know its UUID. To get a list of constraints for this entity, execute the /entities/ENTITY_UUID/constraints request for the entity whose constraint you wish to remove.

Setting OS Migration Settings for a Migrate to Cloud Plan

When performing a Migrate to Cloud plan, you might want to use custom OS migration settings. You can specify both the OS mapping, and the BYOL (bring your own license) status of each OS in the mapping.

```
"osMigrationSettingList":[
    {
      "uuid":"linuxTargetOs",
      "displayName":"linuxTargetOs",
```



```
"value": "LINUX"
},
  "uuid":"linuxByol",
  "displayName": "linuxByol",
  "value":"true"
},
  "uuid": "rhelTargetOs",
  "displayName": "rhelTargetOs",
  "value": "RHEL"
},
  "uuid": "rhelByol",
  "displayName": "rhelByol",
  "value": "false"
},
  "uuid":"slesTargetOs",
  "displayName": "slesTargetOs",
  "value": "WINDOWS"
},
  "uuid":"slesByol",
  "displayName": "slesByol",
  "value":"true"
},
  "uuid": "windowsTargetOs",
  "displayName": "windowsTargetOs",
  "value": "WINDOWS"
},
  "uuid": "windowsByol",
  "displayName": "windowsByol",
  "value":"true"
},
  "uuid": "showMatchSourceToTargetOsOption",
  "displayName": "showMatchSourceToTargetOsOption",
  "value":"true"
},
  "uuid": "showByolOption",
  "displayName": "showByolOption",
  "value": "false"
},
  "uuid": "showCustomOsOption",
  "displayName": "showCustomOsOption",
  "value":"true"
},
  "uuid": "matchToSource",
```



```
"displayName":"matchToSource",
    "value":"false"
},
{
    "uuid":"selectedMigrationProfileOption",
    "displayName":"selectedMigrationProfileOption",
    "value":"CUSTOM_OS"
}
```

Scenario DTO Load Changes

The scenario load changes, located in the <code>loadChanges</code> parameter of the ScenarioApiDTO, make workload utilization changes that enable you to change the following values:

baselineDate

If your plan should be run using historical data, the date of the data to be used.

maxUtilizationList

Changes the max utilization values for a group of entities in your plan.

peakBaselineList

Changes the peak baseline values for a group of entities in your plan.

utilizationList

Changes the utilization values for a group of entities in your plan.

Changing the Baseline Date

Example input:

```
"baselineDate": 1552622400000
```

Changing the Utilization For a Group of Entities

Example input:

```
"utilizationList": [
    {
        "percentage": -12,
        "projectionDay": 0,
        "target": {
            "displayName": "Global Environment",
            "uuid": "Market"
        }
    }
}
```

Changing the Maximum Utilization For a Group of Entities

```
"maxUtilizationList": [
    {
      "maxPercentage": 82,
      "projectionDay": 0,
      "target": {
      "displayName": "All On-prem Hosts",
```



```
"className": "Group",
        "uuid": "_PE0v-YEUEee_hYfzgV9uYg"
      }
    },
    {
      "maxPercentage": 85,
      "projectionDay": 0,
      "target": {
        "displayName": "ACM_datastore",
        "className": "Group",
        "uuid": "c31a6f99f4409700115fc61fca71e5449ad68700"
      }
    },
    {
      "maxPercentage": 77,
      "projectionDay": 0,
      "target": {
        "displayName": "Beta DC6_datastore",
        "className": "Group",
        "uuid": "5544c35ed3d7fc0d33879d3457c219d7e40fc176"
    }
  ]
}
```

Scenario DTO Time-Based Topology Changes

The scenario time-based topology changes, located in the timebasedTopologyChanges parameter of the ScenarioApiDTO, make time-dependent topology changes to your scenario, such as:

addHistoryVMs

If true, Workload Optimization Manager will add additional workload to your scenario each month equal to the workload added to the real-time market in the previous month.

includeReservation

If true, Workload Optimization Manager will take current reservations and reflect their resource utilization when the scenario runs.

Adding Historical VM Usage and/or Including VM Reservations

Example input:

Scenario DTO Topology Changes

The scenario topology changes, located in the topologyChanges parameter of the ScenarioApiDTO, make topology changes to your scenario, such as:

addList

A list of entities to add to your environment as part of plan configuration.



migrateList

A list of entities to move from one set of providers to another as part of plan configuration.

relievePressureList

In a Relieve Pressure plan, the source and target clusters.

removeList

A list of entities to be removed from your environment as part of plan configuration.

replaceList

A list of entities and the templates to replace them in your environment as part of plan configuration.

Adding Workload

Adding workload to a scenario simulates the effect of increased VM or container density in your environment. You can add multiple copies of VM groups or individual VMs.

```
"addList": [
  {
    "count": 3,
    "projectionDays": [
     0
   ],
    "target": {
      "uuid": "421dd4ce-a4c1-231a-71e7-64fbf598bc65",
      "displayName": "AJ_Test",
      "className": "VirtualMachine"
   }
 },
  {
    "count": 10,
    "projectionDays": [
     0
    ],
    "target": {
      "uuid": "421e503d-d0c0-75f9-8cce-79421924a90d",
      "displayName": "olg_test",
      "className": "VirtualMachine"
  },
  {
    "count": 5,
    "projectionDays": [
     0
    "target": {
      "uuid": "420f1840-297f-5a39-9543-b72046b9126f",
      "displayName": "opensuse_with_stress_template",
      "className": "VirtualMachine"
   }
  },
    "count": 1,
    "projectionDays": [
     0
    ],
```



```
"target": {
    "uuid": "53523c9a4c5d67962a96f90f59456b0c3e72aca0",
    "displayName": "Development67_vm",
    "className": "VirtualMachine"
    }
}
```

Migrating Workload to the Cloud

Workload Optimization Manager includes a special plan to simulate migration of on-premise workload to the cloud, or migration of workloads from one cloud to another. This plan focuses on optimizing your costs on the cloud by choosing the best templates (most adequate compute resources) and regions to host your workloads. If analysis discovers on-premise workloads that are good candidates for Reserved Instances (RIs), then it recommends migrating to those templates, and can even recommend purchasing more RI capacity. For each group of virtual machines to be migrated (source), you must provide a destination.

```
"migrateList": [
  {
    "projectionDay": 0,
    "source": {
     "uuid": "4656c0ba6b976d05d1a9470ee673672022e8e926",
      "displayName": "ACM_vm",
      "className": "VirtualMachine",
     "severity": "Major"
   },
    "destination": {
      "uuid": "GROUP-PMsByTargetType_Azure",
     "displayName": "PMs_Azure",
     "className": "PhysicalMachine"
  },
    "projectionDay": 0,
    "source": {
     "uuid": "fe23c8642efc5ad2ed4fa1cc502dfb179b8dc9d2",
     "displayName": "Development DC1_vm",
     "className": "VirtualMachine",
      "severity": "Major"
   },
    "destination": {
     "uuid": "GROUP-PMsByTargetType_Azure",
     "displayName": "PMs_Azure",
     "className": "PhysicalMachine"
   }
  },
    "projectionDay": 0,
    "source": {
     "uuid": "f0e26cb417d8143173270b7f01c7213e027cd9e5",
     "displayName": "Development DC7_vm",
     "className": "VirtualMachine",
      "severity": "Major"
   },
```



```
"destination": {
    "uuid": "GROUP-PMsByTargetType_Azure",
    "displayName": "PMs_Azure",
    "className": "PhysicalMachine"
    }
}
```

Relieve Pressure

Including this parameter creates an Alleviate Pressure plan to find out how to migrate workloads from a stressed or hot cluster over to a cluster with more headroom.

Example input:

```
"relievePressureList": [
  {
    "projectionDay": 0,
    "sources": [
        "uuid": "11c63ebd77647e7b9c9fb85dd2d4c77464cbeac2",
        "displayName": "DC13\\DC13-Cluster",
        "className": "Cluster"
     }
    ],
    "destinations": [
        "uuid": "57a4026a69ba4b46ebc430cb62d5c55eeea00695",
        "displayName": "DC13\\Physical Hosts_Cluster2 - Intel",
        "className": "Cluster"
    ]
  }
1
```

Removing Workload

Removing workload in a scenario configuration simulates the effect of decreased VM or container density in your environment. You can remove VM groups or individual VMs.



```
"className": "VirtualMachine"
   }
 },
  {
    "projectionDay": 0,
    "target": {
      "uuid": "421e048b-f66b-539c-f743-7dcc7b40943b",
      "displayName": "Gilad_XL_Storage_Testing - Pure-1",
      "className": "VirtualMachine"
   }
 },
  {
    "projectionDay": 0,
    "target": {
      "uuid": "421e9199-7159-04f2-29fc-6a501f44d1be",
      "displayName": "Gilad_XL_Storage_Testing - Pure-2",
      "className": "VirtualMachine"
   }
 },
  {
    "projectionDay": 0,
    "target": {
      "uuid": "421d9ec6-ab97-84d0-4b12-2db88ae43e2a",
      "displayName": "MS-SQLServer-3",
      "className": "VirtualMachine"
   }
  }
]
```

Replacing Workload

When you replace workload, you select one or more VMs or containers that you want to change (target), and then you select a template to use in their place.

```
"replaceList": [
 {
    "projectionDay": 0,
    "target": {
     "uuid": "421ef003-e152-5a25-6e03-19698340cd01",
     "displayName": "centos_imp_7",
     "className": "VirtualMachine",
      "severity": "Minor"
   },
    "template": {
     "uuid": "_wIBz8Jj4EeC6nYMiQT1jqA",
     "displayName": "Microsoft_SQL2008-small",
     "className": "VirtualMachineProfile"
   }
 },
  {
    "projectionDay": 0,
    "target": {
     "uuid": "42001807-bc8f-b144-8ff6-eb0d0d32cc7a",
```



```
"displayName": "cheuk-OpsMgr-172.113",
    "className": "VirtualMachine",
    "severity": "Minor"
  },
  "template": {
    "uuid": "_wIBz8Jj4EeC6nYMiQT1jqA",
    "displayName": "Microsoft_SQL2008-small",
    "className": "VirtualMachineProfile"
  }
},
{
  "projectionDay": 0,
  "target": {
    "uuid": "4211806a-65f2-8be1-1015-a4abe1a2ab6f",
    "displayName": "dim-dc13amd-6.2.7_01",
    "className": "VirtualMachine",
    "severity": "Minor"
  },
  "template": {
    "uuid": "_wIBz8Jj4EeC6nYMiQT1jqA",
    "displayName": "Microsoft_SQL2008-small",
    "className": "VirtualMachineProfile"
  }
},
{
  "projectionDay": 0,
  "target": {
    "uuid": "42008beb-264e-b0f6-2295-f3443e4ce7d6",
    "displayName": "enOpenShiftInfra1",
    "className": "VirtualMachine",
    "severity": "Minor"
  },
  "template": {
    "uuid": "_wIBz8Jj4EeC6nYMiQT1jqA",
    "displayName": "Microsoft_SQL2008-small",
    "className": "VirtualMachineProfile"
},
{
  "projectionDay": 0,
  "target": {
    "uuid": "420036f6-27c3-0252-439d-e23bcff63d02",
    "displayName": "enOpenShiftInfra2",
    "className": "VirtualMachine",
    "severity": "Minor"
  },
  "template": {
    "uuid": "_wIBz8Jj4EeC6nYMiQT1jqA",
    "displayName": "Microsoft_SQL2008-small",
    "className": "VirtualMachineProfile"
},
{
  "projectionDay": 0,
```



```
"target": {
    "uuid": "4200ba09-71eb-3084-026e-1770c23abaa4",
    "displayName": "enOpenshiftDNS",
    "className": "VirtualMachine",
    "severity": "Minor"
},
    "template": {
    "uuid": "_wIBz8Jj4EeC6nYMiQT1jqA",
    "displayName": "Microsoft_SQL2008-small",
    "className": "VirtualMachineProfile"
}
}
```

Scenario Configuration Examples

Basic Scenario POSTs and Responses

Most scenarios consist of multiple configuration changes. However, the UI provides several starting points for custom configuration based on plan type.

Workload Optimization Manager provides the same starting point in the API via the /scenarios endpoint and the following list of POST calls and server responses:

The following examples are simplified in order to accomplish a single goal. There are many other options you might choose in conjunction with those in the following examples.

Add Workload

```
"configChanges": {
  "addPolicyList": [],
  "automationSettingList": [],
  "removeConstraintList": [],
  "removePolicyList": [],
  "riSettingList": [],
  "osMigrationSettingList": [],
  "subscription": {}
},
"displayName": "Add Workload- Basic",
"loadChanges": {
  "utilizationList": [],
  "maxUtilizationList": []
"projectionDays": [
 0
],
"scope": [
    "uuid": "Market",
    "displayName": "Global Environment",
    "className": "Market"
  }
```



```
],
  "topologyChanges": {
    "addList": [
      {
        "count": 50,
        "projectionDays": [
          0
        ],
        "target": {
          "uuid": "421dd4ce-a4c1-231a-71e7-64fbf598bc65",
          "displayName": "AJ_Test",
          "className": "VirtualMachine"
      }
    ],
    "migrateList": [],
    "removeList": [],
    "replaceList": [],
    "relievePressureList": []
  },
  "type": "ADD_WORKLOAD"
Response:
  "uuid": "2502057162928",
  "displayName": "Add Workload- Basic",
  "owners": [
      "uuid": "_4T_7kwY-Ed-WUKbEYSVIDw",
      "username": "administrator",
      "showSharedUserSC": false
    }
  "type": "ADD_WORKLOAD",
  "scope": [
    {
      "uuid": "_0x30YUglEd-gHc4L513yOA",
      "displayName": "Market",
      "className": "Market"
    }
  ],
  "projectionDays": [
    0
  "topologyChanges": {
    "addList": [
        "projectionDays": [
          0
        ],
        "target": {
          "uuid": "421dd4ce-a4c1-231a-71e7-64fbf598bc65",
```



```
"displayName": "AJ_Test",
        "className": "VirtualMachine"
      "count": 50
    }
  ]
},
"loadChanges": \{\},
"configChanges": {},
"changes": [
 {
    "index": 1,
    "type": "SCOPE",
    "scope": [
        "uuid": "_0x30YUglEd-gHc4L513yOA",
        "displayName": "Market",
        "className": "Market"
      }
    ]
  },
    "index": 2,
    "type": "PROJECTION_PERIODS",
    "projectionDays": [
      0
    ]
  },
    "index": 3,
    "type": "ADDED",
    "description": "50 AJ_Test",
    "targets": [
        "uuid": "421dd4ce-a4c1-231a-71e7-64fbf598bc65",
        "displayName": "AJ_Test",
        "className": "VirtualMachine",
        "severity": "Major"
      }
    ],
    "value": "50",
    "projectionDays": [
     0
    ]
  }
],
"timebasedTopologyChanges": {}
```

Decommission Hosts

POST:

{



```
"configChanges": {
  "addPolicyList": [],
  "automationSettingList": [
      "uuid": "provisionPM",
      "displayName": "PROVISION for PHYSICALMACHINES disabled",
      "value": "false",
      "entityType": "PhysicalMachine"
    }
  ],
  "removeConstraintList": [],
  "removePolicyList": [],
  "riSettingList": [],
  "osMigrationSettingList": [],
  "subscription": {}
},
"displayName": "Decommission Hosts- Basic",
"loadChanges": {
  "utilizationList": [],
  "maxUtilizationList": []
},
"projectionDays": [
 0
],
"scope": [
  {
    "uuid": "Market",
    "displayName": "Global Environment",
    "className": "Market"
  }
],
"topologyChanges": {
  "addList": [],
  "migrateList": [],
  "removeList": [
      "projectionDay": 0,
      "target": {
        "uuid": "4C4C4544-0042-5A10-804A-B1C04F384331",
        "displayName": "dell-pe1944.corp.vmturbo.com",
        "className": "PhysicalMachine"
      }
    },
    {
      "projectionDay": 0,
      "target": {
        "uuid": "4C4C4544-004A-3610-8057-C8C04F464331",
        "displayName": "dell-pe1953.corp.vmturbo.com",
        "className": "PhysicalMachine"
      }
    },
    {
      "projectionDay": 0,
      "target": {
```



```
"uuid": "4C4C4544-0059-4D10-8030-B3C04F464331",
          "displayName": "dell-pe1954.corp.vmturbo.com",
          "className": "PhysicalMachine"
        }
      }
    ],
    "replaceList": [],
    "relievePressureList": []
  },
  "type": "DECOMMISSION_HOST"
Response:
  "uuid": "2502061312640",
  "displayName": "Decommission Hosts- Basic",
  "owners": [
    {
      "uuid": "_4T_7kwY-Ed-WUKbEYSVIDw",
      "username": "administrator",
      "showSharedUserSC": false
    }
  ],
  "type": "DECOMMISSION_HOST",
  "scope": [
      "uuid": "_0x30YUglEd-gHc4L513yOA",
      "displayName": "Market",
      "className": "Market"
    }
  ],
  "projectionDays": [
    0
  ],
  "topologyChanges": {
    "removeList": [
      {
        "projectionDay": 0,
        "target": {
          "uuid": "4C4C4544-0042-5A10-804A-B1C04F384331",
          "displayName": "dell-pe1944.corp.vmturbo.com",
          "className": "PhysicalMachine"
        }
      },
      {
        "projectionDay": 0,
        "target": {
          "uuid": "4C4C4544-004A-3610-8057-C8C04F464331",
          "displayName": "dell-pe1953.corp.vmturbo.com",
          "className": "PhysicalMachine"
        }
      },
```



```
"projectionDay": 0,
      "target": {
        "uuid": "4C4C4544-0059-4D10-8030-B3C04F464331",
        "displayName": "dell-pe1954.corp.vmturbo.com",
        "className": "PhysicalMachine"
    }
  ]
},
"loadChanges": \{\},
"configChanges": {
  "automationSettingList": [
      "uuid": "provisionPM",
      "displayName": "Provision",
      "value": "false",
      "defaultValue": "RECOMMEND",
      "valueType": "STRING",
      "options": [
        {
          "label": "Disabled",
          "value": "DISABLED"
        },
          "label": "Recommend",
          "value": "RECOMMEND"
        },
        {
          "label": "Manual",
          "value": "MANUAL"
        },
        {
          "label": "Automated",
          "value": "AUTOMATIC"
        }
      "entityType": "PhysicalMachine",
      "sourceGroupName": "Global"
    }
  ]
},
"changes": [
    "index": 1,
    "type": "SCOPE",
    "scope": [
        "uuid": "_0x30YUglEd-gHc4L513yOA",
        "displayName": "Market",
        "className": "Market"
    ]
  },
```



```
"index": 2,
  "type": "PROJECTION_PERIODS",
  "projectionDays": [
  ]
},
  "index": 3,
  "type": "REMOVED",
  "description": "dell-pe1944.corp.vmturbo.com",
  "targets": [
      "uuid": "4C4C4544-0042-5A10-804A-B1C04F384331",
      "displayName": "dell-pe1944.corp.vmturbo.com",
      "className": "PhysicalMachine",
      "severity": "Critical"
    }
  ],
  "value": "1",
  "projectionDays": [
   0
},
  "index": 4,
  "type": "REMOVED",
  "description": "dell-pe1953.corp.vmturbo.com",
  "targets": [
      "uuid": "4C4C4544-004A-3610-8057-C8C04F464331",
      "displayName": "dell-pe1953.corp.vmturbo.com",
      "className": "PhysicalMachine",
      "severity": "Critical"
    }
  ],
  "value": "1",
  "projectionDays": [
    0
  ]
},
  "index": 5,
  "type": "REMOVED",
  "description": "dell-pe1954.corp.vmturbo.com",
  "targets": [
    {
      "uuid": "4C4C4544-0059-4D10-8030-B3C04F464331",
      "displayName": "dell-pe1954.corp.vmturbo.com",
      "className": "PhysicalMachine",
      "severity": "Critical"
    }
  ],
  "value": "1",
  "projectionDays": [
```



```
0
    ]
  },
    "index": 6,
    "type": "SET_ACTION_SETTING",
    "description": "Provision for PhysicalMachine disabled",
    "targets": [
      {
        "uuid": "PhysicalMachine"
    ],
    "value": "PhysicalMachine",
    "enable": false,
    "name": "provision",
    "projectionDays": [
      0
  }
],
"timebasedTopologyChanges": {}
```

Migrate to Cloud

```
"configChanges": {
  "addPolicyList": [],
  "automationSettingList": [],
  "removeConstraintList": [],
  "removePolicyList": [],
  "riSettingList": [],
  "osMigrationSettingList": [],
  "subscription": {}
},
"displayName": "Migrate to Public Cloud- Basic",
"loadChanges": {
  "utilizationList": [],
  "maxUtilizationList": []
},
"projectionDays": [
 0
],
"scope": [
    "uuid": "4656c0ba6b976d05d1a9470ee673672022e8e926",
    "displayName": "ACM_vm",
    "groupType": "VirtualMachine",
    "className": "Group"
  },
    "uuid": "_lRrTYB--EeewItqBJctLGw",
```



```
"displayName": "All Cloud Zones",
      "groupType": "PhysicalMachine",
      "className": "Group"
    }
  ],
  "topologyChanges": {
    "addList": [],
    "migrateList": [
      {
        "projectionDay": 0,
        "source": {
          "uuid": "4656c0ba6b976d05d1a9470ee673672022e8e926",
          "displayName": "ACM_vm",
          "className": "VirtualMachine"
        },
        "destination": {
          "uuid": "_lRrTYB--EeewItqBJctLGw",
          "displayName": "All Cloud Zones",
          "className": "PhysicalMachine"
        }
      }
    ],
    "removeList": [
      {
        "projectionDay": 0,
        "target": {
          "uuid": "_nuoxwETSEemi-4wSMHOOWA",
          "displayName": "All VMs In All Cloud Zones",
          "className": "VirtualMachine"
        }
      }
    ],
    "replaceList": [],
    "relievePressureList": []
  },
  "type": "CLOUD_MIGRATION"
Response:
  "uuid": "2502081867536",
  "displayName": "Migrate to Public Cloud- Basic",
  "owners": [
    {
      "uuid": "_4T_7kwY-Ed-WUKbEYSVIDw",
      "username": "administrator",
      "showSharedUserSC": false
    }
  "type": "CLOUD_MIGRATION",
  "scope": [
      "uuid": "4656c0ba6b976d05d1a9470ee673672022e8e926",
```



```
"displayName": "ACM_vm",
    "className": "Group",
    "groupType": "VirtualMachine",
    "isStatic": true,
    "logicalOperator": "AND"
  },
    "uuid": "_lRrTYB--EeewItqBJctLGw",
    "displayName": "All Cloud Zones",
    "className": "Group",
    "groupType": "PhysicalMachine",
    "isStatic": true,
    "logicalOperator": "AND"
],
"projectionDays": [
 0
],
"topologyChanges": {
  "removeList": [
   {
      "projectionDay": 0,
      "target": {
        "uuid": "_nuoxwETSEemi-4wSMHOOWA",
        "displayName": "All VMs In All Cloud Zones",
        "className": "Group"
    }
  ],
  "migrateList": [
   {
      "projectionDay": 0,
      "source": {
        "uuid": "4656c0ba6b976d05d1a9470ee673672022e8e926",
        "displayName": "ACM_vm",
        "className": "Group"
      },
      "destination": {
        "uuid": "_lRrTYB--EeewItqBJctLGw",
        "displayName": "All Cloud Zones",
        "className": "Group"
    }
  ]
},
"loadChanges": {},
"configChanges": {
  "osMigrationSettingList": [
    {
      "uuid": "matchToSource",
      "value": "true"
    }
  ]
},
```



```
"changes": [
 {
    "index": 1,
    "type": "SCOPE",
    "scope": [
        "uuid": "4656c0ba6b976d05d1a9470ee673672022e8e926",
        "displayName": "ACM_vm",
        "className": "Group",
        "entitiesCount": 83,
        "groupType": "VirtualMachine",
        "severity": "Major",
        "logicalOperator": "AND"
     },
        "uuid": "_lRrTYB--EeewItqBJctLGw",
        "displayName": "All Cloud Zones",
        "className": "Group",
        "entitiesCount": 78,
        "groupType": "PhysicalMachine",
        "severity": "Normal",
        "logicalOperator": "AND"
    ]
 },
   "index": 2,
    "type": "PROJECTION_PERIODS",
    "projectionDays": [
     0
   ]
 },
   "index": 3,
    "type": "REMOVED",
    "description": "All VMs In All Cloud Zones",
    "targets": [
        "uuid": "_nuoxwETSEemi-4wSMHOOWA",
        "displayName": "All VMs In All Cloud Zones",
        "className": "Group",
        "entitiesCount": 154,
        "groupType": "VirtualMachine",
        "severity": "Major",
        "logicalOperator": "AND"
     }
    "value": "1",
    "projectionDays": [
     0
  },
    "index": 4,
```



```
"type": "MIGRATION",
    "description": "Migrate [ACM_vm] to All Cloud Zones",
    "targets": [
        "uuid": "4656c0ba6b976d05d1a9470ee673672022e8e926",
        "displayName": "ACM_vm",
        "className": "Group",
        "entitiesCount": 83,
        "groupType": "VirtualMachine",
        "severity": "Major",
        "logicalOperator": "AND"
      },
        "uuid": "_lRrTYB--EeewItqBJctLGw",
        "displayName": "All Cloud Zones",
        "className": "Group",
        "entitiesCount": 78,
        "groupType": "PhysicalMachine",
        "severity": "Normal",
        "logicalOperator": "AND"
      }
    ],
    "projectionDays": [
      0
    ]
  },
    "index": 5,
    "type": "SET_TARGET_OS",
    "targets": [
        "uuid": "4656c0ba6b976d05d1a9470ee673672022e8e926",
        "displayName": "ACM_vm",
        "className": "Group",
        "entitiesCount": 83,
        "groupType": "VirtualMachine",
        "severity": "Major",
        "logicalOperator": "AND"
      }
    ],
    "projectionDays": [
    ]
  }
],
"timebasedTopologyChanges": \{\}
```

Optimize Cloud

```
{
    "configChanges": {
```



```
"addPolicyList": [],
  "automationSettingList": [
      "uuid": "resize",
      "displayName": "resize for VMS enabled",
      "value": "true",
      "entityType": "VirtualMachine"
    }
  ],
  "removeConstraintList": [],
  "removePolicyList": [],
  "riSettingList": [
      "uuid": "preferredOfferingClass",
      "displayName": "Type",
      "value": "STANDARD",
      "entityType": "STANDARD"
    },
    {
      "uuid": "preferredTerm",
      "displayName": "Term",
      "value": "YEARS_3",
      "entityType": "YEARS_3"
    },
    {
      "uuid": "preferredPaymentOption",
      "displayName": "Payment",
      "value": "ALL_UPFRONT",
      "entityType": "ALL_UPFRONT"
    },
    {
      "uuid": "preferredCoverage",
      "displayName": "Coverage",
      "value": "80",
      "entityType": "80"
    },
    {
      "uuid": "riCoverageOverride",
      "displayName": "RI Coverage Override",
      "value": "false",
      "entityType": "false"
    }
  "osMigrationSettingList": [],
  "subscription": {}
},
"displayName": "Optimize Cloud- Basic",
"loadChanges": {
  "utilizationList": [],
  "maxUtilizationList": []
},
"projectionDays": [
 0
],
```



```
"scope": [
    {
      "uuid": "GROUP-PMsByTargetType_AWS",
      "displayName": "PMs_AWS",
      "groupType": "PhysicalMachine",
      "className": "Group"
    }
  ],
  "topologyChanges": {
    "addList": [],
    "migrateList": [],
    "removeList": [],
    "replaceList": [],
    "relievePressureList": []
  },
  "type": "OPTIMIZE_CLOUD"
Response:
  "uuid": "2502117573632",
  "displayName": "Optimize Cloud- Basic",
  "owners": [
    {
      "uuid": "_4T_7kwY-Ed-WUKbEYSVIDw",
      "username": "administrator",
      "showSharedUserSC": false
    }
  ],
  "type": "OPTIMIZE_CLOUD",
  "scope": [
    {
      "uuid": "be95c99fc2a2195ac896204766a52d0e141818a6",
      "displayName": "PMs_AWS",
      "className": "Group",
      "groupType": "PhysicalMachine",
      "isStatic": true,
      "logicalOperator": "AND"
    }
  ],
  "projectionDays": [
    0
  ],
  "topologyChanges": \{\},
  "loadChanges": {},
  "configChanges": {
    "automationSettingList": [
        "uuid": "resize",
        "displayName": "resize",
        "value": "true"
      }
    ],
```



```
"riSettingList": [
 {
    "uuid": "preferredPaymentOption",
    "displayName": "Payment",
    "value": "ALL_UPFRONT",
    "defaultValue": "ALL_UPFRONT",
    "valueType": "STRING",
    "options": [
     {
        "label": "ALL_UPFRONT",
        "value": "ALL_UPFRONT"
     },
      {
        "label": "PARTIAL_UPFRONT",
        "value": "PARTIAL_UPFRONT"
      },
        "label": "NO_UPFRONT",
        "value": "NO_UPFRONT"
    ],
    "sourceGroupName": "Global"
  },
  {
    "uuid": "preferredTerm",
    "displayName": "Term",
    "value": "YEARS_3",
    "defaultValue": "YEARS_1",
    "valueType": "STRING",
    "options": [
      {
        "label": "YEARS_1",
        "value": "YEARS_1"
     },
      {
        "label": "YEARS_3",
        "value": "YEARS_3"
     }
    ],
    "sourceGroupName": "Global"
 },
  {
    "uuid": "preferredCoverage",
    "displayName": "Coverage",
    "value": "80",
    "defaultValue": "80",
    "valueType": "NUMERIC",
    "min": 0,
    "max": 100,
    "sourceGroupName": "Global"
 },
  {
    "uuid": "riCoverageOverride",
    "displayName": "RI Coverage Override",
```



```
"value": "false",
      "defaultValue": "false",
      "valueType": "BOOLEAN",
      "sourceGroupName": "Global"
    },
    {
      "uuid": "preferredOfferingClass",
      "displayName": "Type",
      "value": "STANDARD",
      "defaultValue": "STANDARD",
      "valueType": "STRING",
      "options": [
          "label": "STANDARD",
          "value": "STANDARD"
        },
          "label": "CONVERTIBLE",
          "value": "CONVERTIBLE"
        }
      ],
      "sourceGroupName": "Global"
  1
},
"changes": [
    "index": 1,
    "type": "SCOPE",
    "scope": [
        "uuid": "be95c99fc2a2195ac896204766a52d0e141818a6",
        "displayName": "PMs_AWS",
        "className": "Group",
        "entitiesCount": 50,
        "groupType": "PhysicalMachine",
        "severity": "Normal",
        "logicalOperator": "AND"
    ]
  },
    "index": 2,
    "type": "PROJECTION_PERIODS",
    "projectionDays": [
      0
    ]
  },
    "index": 3,
    "type": "ENABLED",
    "description": "Resize enabled",
    "targets": [],
    "enable": true,
```



```
"projectionDays": [
      0
    ]
  },
    "index": 4,
    "type": "RI_SETTINGS",
    "targets": [
      {
        "uuid": "preferredPaymentOption | ALL_UPFRONT"
      },
        "uuid": "preferredTerm|YEARS_3"
      },
        "uuid": "preferredCoverage | 80"
      },
        "uuid": "riCoverageOverride|false"
      },
        "uuid": "preferredOfferingClass|STANDARD"
      }
    ],
    "projectionDays": [
      0
    ]
  }
],
"timebasedTopologyChanges": \{\}
```

On-Prem Workload Migration (Cluster to Cluster)

```
"configChanges": {
  "addPolicyList": [],
  "automationSettingList": [],
  "removeConstraintList": [],
  "removePolicyList": [],
  "riSettingList": [],
  "osMigrationSettingList": [],
  "subscription": {}
},
"displayName": "On-Prem Workload Migration 1",
"loadChanges": {
  "utilizationList": [],
  "maxUtilizationList": []
},
"projectionDays": [
 0
],
```



```
"scope": [
    {
      "uuid": "3e47ff3351f3247367c00c08fdc5bb974695c443",
      "displayName": "DC23-Datacenter\\DC23-cluster1",
      "groupType": "PhysicalMachine",
      "className": "Cluster"
    }
  ],
  "topologyChanges": {
    "addList": [
      {
        "count": 1,
        "projectionDays": [
          0
        ],
        "target": {
          "uuid": "67d24a6f265151876e87f39475fb4ee4b4170098",
          "displayName": "AvailabilitySet::ARSEN-AVS-NCUS",
          "className": "VirtualMachine"
        }
      }
    ],
    "migrateList": [],
    "removeList": [],
    "replaceList": [],
    "relievePressureList": []
  },
  "type": "WORKLOAD_MIGRATION"
Response:
  "uuid": "2502063893936",
  "displayName": "On-Prem Workload Migration- Basic",
  "owners": [
      "uuid": "_4T_7kwY-Ed-WUKbEYSVIDw",
      "username": "administrator",
      "showSharedUserSC": false
    }
  ],
  "type": "WORKLOAD_MIGRATION",
  "scope": [
    {
      "uuid": "_0x30YUglEd-gHc4L513yOA",
      "displayName": "Market",
      "className": "Market"
    }
  ],
  "projectionDays": [
    0
  ],
  "topologyChanges": {
```



```
"addList": [
    {
      "projectionDays": [
      ],
      "target": {
        "uuid": "a6d365f4fbf03fb9a2e8cdb29e38045e31cee41b",
        "displayName": "Beta DC6_vm",
        "className": "Group"
      },
      "count": 1
    }
  ]
"loadChanges": {},
"configChanges": {},
"changes": [
  {
    "index": 1,
    "type": "SCOPE",
    "scope": [
        "uuid": "_0x30YUglEd-gHc4L513yOA",
        "displayName": "Market",
        "className": "Market"
    ]
  },
    "index": 2,
    "type": "PROJECTION_PERIODS",
    "projectionDays": [
    ]
  },
    "index": 3,
    "type": "ADDED",
    "description": "1 Beta DC6_vm",
    "targets": [
        "uuid": "a6d365f4fbf03fb9a2e8cdb29e38045e31cee41b",
        "displayName": "Beta DC6_vm",
        "className": "Group",
        "entitiesCount": 56,
        "groupType": "VirtualMachine",
        "severity": "Major",
        "logicalOperator": "AND"
      }
    ],
    "value": "1",
    "projectionDays": [
      0
    ]
```



```
}
],
"timebasedTopologyChanges": {}
}
```

Hardware Refresh

```
"configChanges": {
  "addPolicyList": [],
  "automationSettingList": [],
  "removeConstraintList": [],
  "removePolicyList": [],
  "riSettingList": [],
  "osMigrationSettingList": [],
  "subscription": {}
"displayName": "Hardware Refresh- Basic",
"loadChanges": {
  "utilizationList": [],
  "maxUtilizationList": []
},
"projectionDays": [
 0
],
"scope": [
    "uuid": "Market",
    "displayName": "Global Environment",
    "className": "Market"
  }
],
"topologyChanges": {
  "addList": [],
  "migrateList": [],
  "removeList": [],
  "replaceList": [
    {
      "projectionDay": 0,
      "target": {
        "uuid": "4C4C4544-0042-5A10-804A-B1C04F384331",
        "displayName": "dell-pe1944.corp.vmturbo.com",
        "className": "PhysicalMachine",
        "severity": "Critical"
      },
      "template": {
        "uuid": "_juCtwJkfEeCX4rLBy_KD2g",
        "displayName": "HP_DL580 G7",
        "className": "PhysicalMachineProfile"
    },
```



```
"projectionDay": 0,
        "target": {
          "uuid": "4C4C4544-004A-3610-8057-C8C04F464331",
          "displayName": "dell-pe1953.corp.vmturbo.com",
          "className": "PhysicalMachine",
          "severity": "Critical"
        },
        "template": {
          "uuid": "_juCtwJkfEeCX4rLBy_KD2g",
          "displayName": "HP_DL580 G7",
          "className": "PhysicalMachineProfile"
        }
      },
      {
        "projectionDay": 0,
        "target": {
          "uuid": "4C4C4544-0059-4D10-8030-B3C04F464331",
          "displayName": "dell-pe1954.corp.vmturbo.com",
          "className": "PhysicalMachine",
          "severity": "Critical"
        },
        "template": {
          "uuid": "_juCtwJkfEeCX4rLBy_KD2g",
          "displayName": "HP_DL580 G7",
          "className": "PhysicalMachineProfile"
        }
      },
      {
        "projectionDay": 0,
        "target": {
          "uuid": "Virtual_ESX_4238e933-3923-8334-37fe-3aec8fbd046f",
          "displayName": "hp-esx22.dev.mycorp.com",
          "className": "PhysicalMachine",
          "severity": "Critical"
        },
        "template": {
          "uuid": "_juCtwJkfEeCX4rLBy_KD2g",
          "displayName": "HP_DL580 G7",
          "className": "PhysicalMachineProfile"
        }
      }
    ],
    "relievePressureList": []
  },
  "type": "RECONFIGURE_HARDWARE"
Response:
  "uuid": "2502070918448",
  "displayName": "Hardware Refresh- Basic",
  "owners": [
    {
```



```
"uuid": "_4T_7kwY-Ed-WUKbEYSVIDw",
    "username": "administrator",
    "showSharedUserSC": false
  }
],
"type": "RECONFIGURE_HARDWARE",
"scope": [
  {
    "uuid": "_0x30YUglEd-gHc4L513yOA",
    "displayName": "Market",
    "className": "Market"
  }
],
"projectionDays": [
 0
],
"topologyChanges": {
  "replaceList": [
    {
      "projectionDay": 0,
      "target": {
        "uuid": "4C4C4544-0042-5A10-804A-B1C04F384331",
        "displayName": "dell-pe1944.corp.vmturbo.com",
        "className": "PhysicalMachine"
      },
      "template": {
        "uuid": "_juCtwJkfEeCX4rLBy_KD2g",
        "displayName": "HP_DL580 G7",
        "className": "PhysicalMachineProfile"
      }
    },
    {
      "projectionDay": 0,
      "target": {
        "uuid": "4C4C4544-004A-3610-8057-C8C04F464331",
        "displayName": "dell-pe1953.corp.vmturbo.com",
        "className": "PhysicalMachine"
      },
      "template": {
        "uuid": "_juCtwJkfEeCX4rLBy_KD2g",
        "displayName": "HP_DL580 G7",
        "className": "PhysicalMachineProfile"
      }
    },
      "projectionDay": 0,
      "target": {
        "uuid": "4C4C4544-0059-4D10-8030-B3C04F464331",
        "displayName": "dell-pe1954.corp.vmturbo.com",
        "className": "PhysicalMachine"
      },
      "template": {
        "uuid": "_juCtwJkfEeCX4rLBy_KD2g",
        "displayName": "HP_DL580 G7",
```



```
"className": "PhysicalMachineProfile"
        }
      },
      {
        "projectionDay": 0,
        "target": {
          "uuid": "Virtual_ESX_4238e933-3923-8334-37fe-3aec8fbd046f",
          "displayName": "hp-esx22.dev.mycorp.com",
          "className": "PhysicalMachine"
        },
        "template": {
          "uuid": "_juCtwJkfEeCX4rLBy_KD2g",
          "displayName": "HP_DL580 G7",
          "className": "PhysicalMachineProfile"
      }
    ]
  },
  "loadChanges": {},
  "configChanges": {},
  "changes": [
    {
      "index": 1,
      "type": "SCOPE",
      "scope": [
          "uuid": "_0x30YUglEd-gHc4L513yOA",
          "displayName": "Market",
          "className": "Market"
      ]
    },
      "index": 2,
      "type": "PROJECTION_PERIODS",
      "projectionDays": [
        0
      ]
    },
      "index": 3,
      "type": "REPLACED",
      "description": "Replace [dell-pe1944.corp.vmturbo.com, dell-pe1953.corp.vmturbo.com, dell-pe1954.c
orp.vmturbo.com, hp-esx... with HP_DL580 G7",
      "targets": [
        {
          "uuid": "4C4C4544-0042-5A10-804A-B1C04F384331",
          "displayName": "dell-pe1944.corp.vmturbo.com",
          "className": "PhysicalMachine",
          "severity": "Critical"
        },
          "uuid": "4C4C4544-004A-3610-8057-C8C04F464331",
          "displayName": "dell-pe1953.corp.vmturbo.com",
```



```
"className": "PhysicalMachine",
        "severity": "Critical"
      },
        "uuid": "4C4C4544-0059-4D10-8030-B3C04F464331",
        "displayName": "dell-pe1954.corp.vmturbo.com",
        "className": "PhysicalMachine",
        "severity": "Critical"
      },
        "uuid": "Virtual_ESX_4238e933-3923-8334-37fe-3aec8fbd046f",
        "displayName": "hp-esx22.dev.mycorp.com",
        "className": "PhysicalMachine",
        "severity": "Critical"
      },
        "uuid": "_juCtwJkfEeCX4rLBy_KD2g",
        "displayName": "HP_DL580 G7",
        "className": "PhysicalMachineProfile"
      }
    ],
    "value": "0",
    "projectionDays": [
      0
  }
],
"timebasedTopologyChanges": {}
```

Alleviate Pressure

```
"configChanges": {
  "addPolicyList": [],
  "automationSettingList": [],
  "removeConstraintList": [],
  "removePolicyList": [],
  "riSettingList": [],
  "osMigrationSettingList": [],
  "subscription": {}
},
"displayName": "Alleviate Pressure- Basic",
"loadChanges": {
  "utilizationList": [],
  "maxUtilizationList": []
},
"projectionDays": [
 0
"scope": [
  {
```



```
"uuid": "11c63ebd77647e7b9c9fb85dd2d4c77464cbeac2",
      "displayName": "DC13\\DC13-Cluster",
      "className": "Cluster"
    },
      "uuid": "57a4026a69ba4b46ebc430cb62d5c55eeea00695",
      "displayName": "DC13\\Physical Hosts_Cluster2 - Intel",
      "className": "Cluster"
    }
  ],
  "topologyChanges": {
    "addList": [],
    "migrateList": [],
    "removeList": [],
    "replaceList": [],
    "relievePressureList": [
        "projectionDay": 0,
        "sources": [
          {
            "uuid": "11c63ebd77647e7b9c9fb85dd2d4c77464cbeac2",
            "displayName": "DC13\\DC13-Cluster",
            "className": "Cluster"
          }
        ],
        "destinations": [
            "uuid": "57a4026a69ba4b46ebc430cb62d5c55eeea00695",
            "displayName": "DC13\\Physical Hosts_Cluster2 - Intel",
            "className": "Cluster"
          }
        ]
      }
    ]
  },
  "type": "ALLEVIATE_PRESSURE"
Response:
  "uuid": "2531404249984",
  "displayName": "On-Prem Workload Migration 1",
  "owners": [
    {
      "uuid": "_4T_7kwY-Ed-WUKbEYSVIDw",
      "username": "administrator",
      "showSharedUserSC": false
    }
  "type": "WORKLOAD_MIGRATION",
  "scope": [
      "uuid": "3e47ff3351f3247367c00c08fdc5bb974695c443",
```



```
"displayName": "DC23-Datacenter\\DC23-cluster1",
    "className": "Cluster",
    "groupType": "PhysicalMachine",
    "isStatic": true,
    "logicalOperator": "AND"
  }
],
"projectionDays": [
 0
],
"topologyChanges": {
  "addList": [
    {
      "projectionDays": [
       0
      ],
      "target": {
        "uuid": "67d24a6f265151876e87f39475fb4ee4b4170098",
        "displayName": "AvailabilitySet::ARSEN-AVS-NCUS",
        "className": "DiscoveredGroup"
      },
      "count": 1
    }
  1
},
"loadChanges": {},
"configChanges": {},
"changes": [
    "index": 1,
    "type": "SCOPE",
    "scope": [
        "uuid": "3e47ff3351f3247367c00c08fdc5bb974695c443",
        "displayName": "DC23-Datacenter\\DC23-cluster1",
        "className": "Cluster",
        "entitiesCount": 3,
        "groupType": "PhysicalMachine",
        "severity": "Critical",
        "logicalOperator": "AND"
      }
    ]
  },
    "index": 2,
    "type": "PROJECTION_PERIODS",
    "projectionDays": [
      0
    ]
  },
    "index": 3,
    "type": "ADDED",
    "description": "1 AvailabilitySet::ARSEN-AVS-NCUS",
```



```
"targets": [
      {
        "uuid": "67d24a6f265151876e87f39475fb4ee4b4170098",
        "displayName": "AvailabilitySet::ARSEN-AVS-NCUS",
        "className": "DiscoveredGroup",
        "entitiesCount": 3,
        "groupType": "VirtualMachine",
        "severity": "Critical",
        "logicalOperator": "AND"
      }
    ],
    "value": "1",
    "projectionDays": [
     0
    ]
  }
],
"timebasedTopologyChanges": {}
```

Optimize Current Environment

The result of a plan run with no custom configuration is an optimization of your current environment, respecting all current policies and constraints.

POST:

```
"configChanges": {
  "addPolicyList": [],
  "automationSettingList": [],
  "removeConstraintList": [],
  "removePolicyList": [],
  "riSettingList": [],
  "osMigrationSettingList": [],
  "subscription": {}
"displayName": "Custom- No Config",
"loadChanges": {
  "utilizationList": [],
  "maxUtilizationList": []
},
"projectionDays": [],
"scope": [
  {
    "uuid": "Market",
    "displayName": "Global Environment",
    "className": "Market"
  }
],
"topologyChanges": {
  "addList": [],
  "migrateList": [],
  "removeList": [],
  "replaceList": [],
```



```
"relievePressureList": []
  },
  "type": "CUSTOM"
Response:
  "uuid": "2502119526800",
  "displayName": "Custom- No Config",
  "owners": [
    {
      "uuid": "_4T_7kwY-Ed-WUKbEYSVIDw",
      "username": "administrator",
      "showSharedUserSC": false
  ],
  "type": "CUSTOM",
  "scope": [
      "uuid": "_0x30YUglEd-gHc4L513yOA",
      "displayName": "Market",
      "className": "Market"
  ],
  "changes": [
      "index": 1,
      "type": "SCOPE",
      "scope": [
        {
           "uuid": "_0x30YUglEd-gHc4L513yOA",
          "displayName": "Market",
          "className": "Market"
      ]
    }
  ]
```

Scenario Future Load Configuration Example

Future Load Plans

Future load plans are a type of plan in which commodities from active VMs are taken and applied to passive or low-workload VMs, simulating the effect on the environment if these passive VMs became active. For example, you may want to investigate the effect on your environment if your disaster recovery VMs were forced to run at historical peak values. In this case, the production VMs whose commodities will be used are the active VMs, and the currently idle disaster recovery VMs are the passive VMs.

Currently, there are two future load plan types:

■ PEAKOFPEAKS



The peak-of-peaks future load plan replicates in the passive VMs every commodity of the active VMs reaching its historical peak utilization simultaneously, and the plan result will reflect the effect on your environment.

CUSTOM

The custom future load plan replicates in the passive VMs every commodity of the active VMs reaching its current utilization simultaneously, and the plan result will reflect the effect on your environment.

The setup and configuration for both future load plans differ only in the content of the type parameter- all other steps will be identical.

The settings you make in a scenario correspond to the plan settings you can make in the user interface. These include:

- Plan scope
- Changes to workload (adding, removing, or replacing VMs or containers)
- Changes to supply (adding, removing, replacing PMs or storage)
- Enable/disable placement policies and other constraints
- Changes to action modes
- Enable/disable provisioning of supply
- Enable/disable resizing of workloads

Future Load Prerequisites

In order to run a future load plan, you must retrieve statistics for the entities to be included in the plan. Typically, this is done utilizing the POST /markets/market_uuid/entities/stats request, with startDate and scopes parameters.

Example input for statistic retrieval:

```
{
   "period": {
      "startDate": 1237056032
},
   "scopes": [
      "4223ae0c-c99b-f6ca-c1ef-3f367bdf5528",
      "4223bb37-0090-f332-0140-cc3cce7b3735",
      "4223dc55-78f2-2cd7-9abf-b09b1be835b4",
      "42231932-83af-10d9-f0cd-26c8a08a9e18",
      "422374a3-2c64-b613-a9a7-1f900a2314b4"
]
```

Once the call is completed, copy the response in its entirety- or if using Swagger, click the Download button next to the response and copy the contents of the file.

Running the Future Load Plan

After creating the ScenarioApiDTO, the response will include the uuid of the created scenario. Use this uuid along with the uuid of the market to run the plan against (typically the real-time market) in the POST /markets/market_uuid/scenarios/scenario_uuid request.

Viewing the Peak of Peak Plan

After running the plan, the response will include the uuid of the created plan market, which you should note. Results can be viewed using the GET /markets/market_uuid request.



Schedules Endpoint

Schedules specify a period of time during which certain events can occur. Workload Optimization Manager uses the following types of schedules:

Calendar Schedule

A calendar schedule is a setting that sets up a window of time when an *automation policy* takes effect. This policy can execute *non-parking* actions on public cloud or on-prem entities, or change settings that affect analysis and action generation.

To configure calendar schedules, you must use /schedules requests. With these requests, you can:

- Get calendar schedules
- Create calendar schedules
- Edit or delete calendar schedules
- View all policies using a specific calendar schedule

NOTE: When you configure a schedule window for a resize action, to ensure Workload Optimization Manager will execute the action during the scheduled time, you must turn off the Enforce Non Disruptive Mode setting for that scheduled policy. Even if you turn the setting off for the global policy, you still must turn the setting off for your scheduled policy. Otherwise Workload Optimization Manager will not execute the resize action.

Parking Schedule

A parking schedule is a setting that sets up a window of time when *parking* actions (stop or start) are enforced on entities in your public cloud environment.

To configure parking schedules, you must use /schedules/timespans/ requests. With these requests, you can:

- Get parking schedules
- Create parking schedules
- Attach parking schedules to parkable entities
- Detach parking schedules from parkable entities
- Edit or delete parking schedules

Calendar Schedules Requests

The requests listed in this topic only apply to calendar schedules used in automation policies. For details about parking schedules that can be attached to parkable entities, see Parking Schedules Requests (on page 947).

Getting Calendar Schedules

Gets a list of schedules. For a list of schedules, the API returns an array of ScheduleApiDTOs. Each ScheduleApiDTO will contain details about the schedule, including the start and end time and date and recurrence. To get a single schedule, include the UUID of the notification in the request.

Examples:

- All Schedules: GET https://10.10.10.10/api/v3/schedules
- Single Schedule: GET https://10.10.10.10/api/v3/schedules/284466929277824

Response:



```
"Mon",
        "Fri"
      "interval": 1
    },
    "timeZone": "America/Denver",
    "nextOccurrence": "2020-03-02T16:30:00",
    "nextOccurrenceTimestamp": 1583191800000
 },
    "uuid": "284466929277824",
    "displayName": "DalSched2",
    "startTime": "2020-02-29T16:30",
    "endTime": "2020-02-29T17:45",
    "recurrence": {
     "type": "MONTHLY",
      "daysOfMonth": [
     ],
      "interval": 3
    },
    "timeZone": "America/Denver",
    "nextOccurrence": "2020-05-05T16:30:00",
    "nextOccurrenceTimestamp": 1588717800000
 }
]
```

Adding a Calendar Schedule

In order to create a schedule in Workload Optimization Manager, you must provide a valid ScheduleApiDTO.

Example: POST https://10.10.10.10/api/v3/schedules

Example input, showing a schedule to be run weekly on Friday between the hours of 0000 and 0400 that starts on 2019-12-20 and has no end date:

```
{
  "displayName":"DallasSched",
  "endTime":"2019-12-20T04:00",
  "startTime":"2019-12-20T00:00",
  "timeZone":"America/Denver",
  "recurrence":{
      "type":"WEEKLY",
      "interval":1,
      "daysOfWeek":[
      "Fri"
      ]
  }
}
```

Getting Policies Using a Calendar Schedule

Given a schedule ID, retrieve any policies associated with that schedule.



Example: GET https://10.10.10.10/api/v3/schedules/284466929277824/settingsPolicy **Response:** An array of SettingspolicyApiDTOs that represent the policies using the specified schedule.

```
[
    "uuid": "284466929430656",
    "displayName": "DalStorage",
    "entityType": "Storage",
    "scopes": [
        "uuid": "284460958528132",
        "displayName": "HawthorneHC_datastore",
        "isStatic": true,
        "logicalOperator": "AND"
     }
    ],
    "settingsManagers": [
      {
        "uuid": "automationmanager",
        "displayName": "Action Mode Settings",
        "category": "Automation",
        "settings": [
          {
            "uuid": "suspend",
            "displayName": "Suspend",
            "value": "MANUAL",
            "defaultValue": "MANUAL",
            "valueType": "STRING",
            "valueObjectType": "String",
            "options": [
                "label": "Disabled",
                "value": "DISABLED"
              },
                "label": "Recommend",
                "value": "RECOMMEND"
              },
                "label": "Manual",
                "value": "MANUAL"
              },
                "label": "Automatic",
                "value": "AUTOMATIC"
              }
            ],
            "entityType": "Storage"
        ]
      }
    ],
    "schedule": {
```



```
"uuid": "284466929277824",
      "displayName": "DalSched2",
      "startTime": "2020-02-29T16:30",
      "endTime": "2020-02-29T17:45",
      "recurrence": {
        "type": "MONTHLY",
        "daysOfMonth": [
          5
        ],
        "interval": 3
      },
      "timeZone": "America/Denver",
      "nextOccurrence": "2020-05-05T16:30:00",
      "nextOccurrenceTimestamp": 1588717800000
    },
    "disabled": false,
    "readOnly": false,
    "default": false
]
```

Calendar Schedules Tips

When creating schedules, you can set multiple timing criteria. Below are schedules with examples of advanced timing. For basic schedules, see the Schedules Endpoint (on page 941).

Bi-Weekly Calendar Schedule with Specific Days

This schedule is set to run biweekly, indicated by the "type": "WEEKLY" and "interval": 2 fields. As indicated by the daysOfWeek array, this schedule is active on Monday, Wednesday, and Friday.

InputDTO:

```
{
  "displayName":"Schedule1",
  "endDate":"2020-07-10",
  "endTime":"2020-05-06T19:30",
  "startTime":"2020-05-06T15:30",
  "timeZone":"America/Denver",
  "recurrence":{
    "type":"WEEKLY",
    "interval":2,
    "daysOfWeek":[
        "Mon",
        "Fri"
    ]
}
```

The API response for this schedule:



```
"uuid": "284559431391120",
"displayName": "DallasTest",
"endDate": "2020-07-10",
"startTime": "2020-05-06T15:30",
"endTime": "2020-05-06T19:30",
"recurrence":{
  "type": "WEEKLY",
  "daysOfWeek":[
    "Mon",
    "Wed",
    "Fri"
  ],
  "interval":2
},
"timeZone": "America/Denver",
"nextOccurrence": "2020-05-06T15:30:00",
"nextOccurrenceTimestamp":1588800600000
```

Six-Month Calendar Schedule with Specific Week of the Month

This schedule is set to run every six months, indicated by the "type": "MONTHLY" and "interval": 6 fields. As indicated by the daysOfWeek array this schedule is active on Wednesday, and the "weekOfTheMonth": 2 indicates that this schedule will only run on the second week of the month.

This schedule was created on May 5th, 2020. Converting the timestamp in the API Response to a human-readable date, we see that the next run is on Wednesday, May 13, 2020 3:30:00 PM, the second Wednesday in May.

Input DTO:

```
"displayName":"DallasTest2",
"endDate":"2020-10-19",
"endTime":"2020-05-06T19:15",
"startTime":"2020-05-06T15:30",
"timeZone":"America/Denver",
"recurrence":{
    "type":"MONTHLY",
    "interval":6,
    "daysOfWeek":[
        "Wed"
    ],
    "weekOfTheMonth":[
        2
    ]
}
```

The API response for this schedule:

```
{
"uuid":"284559434037456",
```



```
"displayName":"DallasTest2",
"endDate":"2020-10-19",
"startTime":"2020-05-06T15:30",
"endTime":"2020-05-06T19:15",
"recurrence":{
    "type":"MONTHLY",
    "daysOfWeek":[
        "Wed"
    ],
    "weekOfTheMonth":[
        2
    ],
    "interval":6
},
"timeZone":"America/Denver",
"nextOccurrence":"2020-05-13T15:30:00",
"nextOccurrenceTimestamp":1589405400000
```

Getting Policies Attached to a Specific Calendar Schedule

In order to see what policies are using a schedule, use the $https://10.10.10.10/api/v3/schedules/{schedule_UUID}/settingsPolicy request.$

Response: An array of SettingspolicyApiDTOs that represent the policies using the specified schedule, whose details are also included.

```
[
    "uuid": "284466929430656",
    "displayName": "DalStorage",
    "entityType": "Storage",
    "scopes": [
      {
        "uuid": "284460958528132",
        "displayName": "HawthorneHC_datastore",
        "isStatic": true,
        "logicalOperator": "AND"
     }
    ],
    "settingsManagers": [
        "uuid": "automationmanager",
        "displayName": "Action Mode Settings",
        "category": "Automation",
        "settings": [
            "uuid": "suspend",
            "displayName": "Suspend",
            "value": "MANUAL",
            "defaultValue": "MANUAL",
            "valueType": "STRING",
            "valueObjectType": "String",
```



```
"options": [
          {
            "label": "Disabled",
            "value": "DISABLED"
          },
            "label": "Recommend",
            "value": "RECOMMEND"
          },
            "label": "Manual",
            "value": "MANUAL"
          },
          {
            "label": "Automatic",
            "value": "AUTOMATIC"
          }
        ],
        "entityType": "Storage"
      }
    ]
  }
],
"schedule": {
 "uuid": "284466929277824",
  "displayName": "DalSched2",
  "startTime": "2020-02-29T16:30",
  "endTime": "2020-02-29T17:45",
  "recurrence": {
    "type": "MONTHLY",
    "daysOfMonth": [
    1.
    "interval": 3
 },
  "timeZone": "America/Denver",
  "nextOccurrence": "2020-05-05T16:30:00",
  "nextOccurrenceTimestamp": 1588717800000
},
"disabled": false,
"readOnly": false,
"default": false
```

Parking Schedules Requests

The requests listed in this topic currently only apply to parking schedules and parkable entities. For details about calendar schedules used in automation policies, see <u>Calendar Schedules Requests</u> (on page 941).

Getting Parking Schedules

]

Gets a list of parking schedules. For a list of schedules, the API returns an array of parking schedule metadata. To get a single parking schedule, include the parking schedule UUID in the URL.



Examples:

- All Schedules: GET https://10.10.10.10/api/v3/schedules/timespans
- Single Schedule: GET https://10.10.10.10/api/v3/schedules/timespans/778668020368144

All Schedules Response:

```
[
    "uuid": "778601653004480",
    "displayName": "testing",
    "timeZone": "America/New_York"
 },
    "uuid": "778603154693344",
    "displayName": "everyday of the week",
    "timeZone": "America/New_York"
 },
    "uuid": "778668020368144",
    "displayName": "Sample Schedule",
    "description": "This is a sample schedule where entities are active during normal business hours but
may undergo maintenance in the early hours of Sunday.",
    "timeZone": "America/Chicago"
 }
]
```

Single Schedule Response:

```
"uuid": "778668020368144",
 "displayName": "Sample Schedule",
 "description": "This is a sample schedule where entities are active during normal business hours but may
undergo maintenance in the early hours of Sunday.",
 "timeZone": "America/Chicago",
 "timeSpans": {
   "type": "WeekDayTimeSpansApiDTO",
   "sunday": [
     {
       "begins": "00:00",
       "ends": "01:59",
       "policy": {
         "type": "ParkingItemApiDTO",
         "state": "OFF"
     },
     {
       "begins": "02:00",
       "ends": "03:59",
       "policy": {
         "type": "ParkingItemApiDTO",
         "state": "IGNORE"
       }
     },
     {
```



```
"begins": "04:00",
    "ends": "23:59",
    "policy": {
     "type": "ParkingItemApiDTO",
     "state": "OFF"
  }
],
"monday": [
 {
    "begins": "00:00",
    "ends": "06:59",
    "policy": {
     "type": "ParkingItemApiDTO",
     "state": "OFF"
   }
 },
  {
    "begins": "07:00",
    "ends": "16:59",
    "policy": {
     "type": "ParkingItemApiDTO",
     "state": "ON"
   }
 },
  {
    "begins": "17:00",
    "ends": "23:59",
    "policy": {
     "type": "ParkingItemApiDTO",
     "state": "OFF"
   }
 }
],
"tuesday": [
 {
    "begins": "00:00",
    "ends": "06:59",
    "policy": {
     "type": "ParkingItemApiDTO",
     "state": "OFF"
   }
 },
  {
    "begins": "07:00",
    "ends": "16:59",
    "policy": {
     "type": "ParkingItemApiDTO",
     "state": "ON"
   }
 },
    "begins": "17:00",
    "ends": "23:59",
```



```
"policy": {
      "type": "ParkingItemApiDTO",
      "state": "OFF"
 }
],
"wednesday": [
 {
    "begins": "00:00",
    "ends": "06:59",
    "policy": {
     "type": "ParkingItemApiDTO",
      "state": "OFF"
 },
    "begins": "07:00",
    "ends": "16:59",
    "policy": {
     "type": "ParkingItemApiDTO",
      "state": "ON"
 },
    "begins": "17:00",
    "ends": "23:59",
    "policy": {
     "type": "ParkingItemApiDTO",
      "state": "OFF"
 }
],
"thursday": [
    "begins": "00:00",
    "ends": "06:59",
    "policy": {
     "type": "ParkingItemApiDTO",
      "state": "OFF"
    }
 },
    "begins": "07:00",
    "ends": "16:59",
    "policy": {
     "type": "ParkingItemApiDTO",
     "state": "ON"
   }
 },
    "begins": "17:00",
    "ends": "23:59",
    "policy": {
     "type": "ParkingItemApiDTO",
```



```
"state": "OFF"
        }
      }
    ],
    "friday": [
      {
        "begins": "00:00",
        "ends": "06:59",
        "policy": {
          "type": "ParkingItemApiDTO",
          "state": "OFF"
        }
      },
      {
        "begins": "07:00",
        "ends": "16:59",
        "policy": {
          "type": "ParkingItemApiDTO",
          "state": "ON"
        }
      },
      {
        "begins": "17:00",
        "ends": "23:59",
        "policy": {
          "type": "ParkingItemApiDTO",
          "state": "OFF"
        }
    ],
    "saturday": [
      {
        "begins": "00:00",
        "ends": "23:59",
        "policy": {
          "type": "ParkingItemApiDTO",
          "state": "OFF"
      }
    ]
  }
}
```

Adding a Parking Schedule

To create a parking schedule, you must provide a valid ParkingItemApiDTO.

Example: POST https://10.10.10.10/api/v3/schedules/timespans

Example input, showing a schedule that causes entities to stay powered on Monday through Friday from 7:00 AM to 5:00 PM. Entities are off all other times except for a two-hour window on Sunday morning between 2:00 AM and 4:00 AM where the schedule does not enforce a powered state:

```
{
  "displayName": "Sample Schedule",
  "timeZone": "America/Chicago",
```



```
"description": "This is a sample schedule where entities are active during normal business hours but may
undergo maintenance in the early hours of Sunday.",
 "timeSpans": {
   "type": "WeekDayTimeSpansApiDTO",
   "monday": [
       "policy": {"type": "ParkingItemApiDTO", "state": "OFF"},
       "begins": "00:00",
       "ends": "06:59"
     },
       "policy": {"type": "ParkingItemApiDTO", "state": "ON"},
       "begins": "07:00",
       "ends": "16:59"
     },
     {
       "policy": {"type": "ParkingItemApiDTO", "state": "OFF"},
       "begins": "17:00",
       "ends": "23:59"
    }
   ],
   "tuesday": [
     {
       "policy": {"type": "ParkingItemApiDTO", "state": "OFF"},
       "begins": "00:00",
       "ends": "06:59"
     },
     {
       "policy": {"type": "ParkingItemApiDTO", "state": "ON"},
       "begins": "07:00",
       "ends": "16:59"
     },
       "policy": {"type": "ParkingItemApiDTO", "state": "OFF"},
       "begins": "17:00",
       "ends": "23:59"
     }
   ],
   "wednesday": [
     {
       "policy": {"type": "ParkingItemApiDTO", "state": "OFF"},
       "begins": "00:00",
       "ends": "06:59"
     },
       "policy": {"type": "ParkingItemApiDTO", "state": "ON"},
       "begins": "07:00",
       "ends": "16:59"
     },
       "policy": {"type": "ParkingItemApiDTO", "state": "OFF"},
       "begins": "17:00",
       "ends": "23:59"
     }
```



```
],
"thursday": [
    "policy": {"type": "ParkingItemApiDTO", "state": "OFF"},
    "begins": "00:00",
    "ends": "06:59"
 },
  {
    "policy": {"type": "ParkingItemApiDTO", "state": "ON"},
    "begins": "07:00",
    "ends": "16:59"
 },
  {
    "policy": {"type": "ParkingItemApiDTO", "state": "OFF"},
    "begins": "17:00",
    "ends": "23:59"
 }
],
"friday": [
 {
    "policy": {"type": "ParkingItemApiDTO", "state": "OFF"},
    "begins": "00:00",
    "ends": "06:59"
 },
  {
    "policy": {"type": "ParkingItemApiDTO", "state": "ON"},
    "begins": "07:00",
    "ends": "16:59"
 },
  {
    "policy": {"type": "ParkingItemApiDTO", "state": "OFF"},
    "begins": "17:00",
    "ends": "23:59"
 }
],
"saturday": [
 {
    "policy": {"type": "ParkingItemApiDTO", "state": "OFF"},
    "begins": "00:00",
    "ends": "23:59"
 }
],
"sunday": [
 {
    "policy": {"type": "ParkingItemApiDTO", "state": "OFF"},
    "begins": "00:00",
    "ends": "01:59"
 },
    "policy": {"type": "ParkingItemApiDTO", "state": "IGNORE"},
    "begins": "02:00",
    "ends": "03:59"
 },
  {
```



Constraints:

- displayName value must be unique.
- timeZone value must be consistent with the IANA Timezone Database (for example, UTC or America/New_York).
- begins and ends values are HH:MM representations of a 24-hour clock and are considered inclusive.
- If time spans (or days of the week) are omitted, the system behaves the same as if a corresponding time span with a policy state of IGNORE exists.
- Time spans cannot overlap.

Attaching Parking Schedules to Entities

Once a parking schedule is created and your parkable entities are discovered, you can attach a schedule to one or more entities.

Example: POST https://10.10.10.10/api/v3/schedules/timespans/778668074428784/entities

Constraints:

- Parking schedule only.
- Entity must be a VirtualMachine discovered from cloud targets (AWS, Azure, or GCP), or a DatabaseServer (AWS RDS instance).

Example input that attaches an existing parking schedule to 1-N entities:

```
{"entityUuids":["74913973295604","74913973295605","74913973295606"]}
```

Detaching Parking Schedules

You can detach a parking schedule from one or more entities.

Example: DELETE https://10.10.10.10/api/v3/schedules/timespans/778668074428784/entities Example input that detaches an existing parking schedule from a 1-N entity.

```
{"entityUuids":["74913973295604","74913973295606"]}
```

Constraints: Parking schedule only.

Updating a Parking Schedule

Update an existing parking schedule. Below is an example request to update a schedule to enforce a powered off state from midnight Monday to midnight Tuesday. The schedule does not enforce a state any other time.

Example: PUT https://10.10.10.10/api/v3/schedules/timespans/778668020368144

Response: An array of SettingspolicyApiDTOs that represent the policies using the specified schedule.

```
{
  "timeZone": "America/Chicago",
  "displayName": "Sample Schedule - Updated",
  "description": "Do nothing all week, except on Monday where the attached VMs should be powered off all
day",
  "timeSpans": {
    "type": "WeekDayTimeSpansApiDTO",
    "monday": [
```



```
{
    "policy": {
        "state": "OFF",
        "type": "ParkingItemApiDTO"
    },
    "begins": "00:00",
    "ends": "23:59"
    }
    ]
}
```

Constraints:

- displayName value must be unique.
- timeZone value must be consistent with the IANA Timezone Database (for example, UTC or America/New_York).
- begins and ends values are HH:MM representations of a 24-hour clock and are considered inclusive.
- If time spans (or days of the week) are omitted, the system behaves the same as if a corresponding time span with a policy state of IGNORE exists.
- Time spans may not overlap.

Deleting a Parking Schedule

Remove an unattached parking schedule.

Example: DELETE https://10.10.10.10/api/v3/schedules/timespans/778668020368144

Constraints: Parking schedules to be deleted must not be attached to any entity.

Search Endpoint

A search is a query performed on the entities that participate in the Workload Optimization Manager market. The most common use of search is to locate a particular object, service entity, or group of entities that share a characteristic.

Object and Entity refer to different items in your Workload Optimization Manager topology:

Using the search endpoint of the Workload Optimization Manager API, you can:

- Obtain criteria for use in detailed searching or building groups
- Get detailed information about any object in your Workload Optimization Manager environment

Search Utility Requests

Utility requests provide metadata that you can use to make related requests, assemble inputDTOs, or see the potential values of a particular DTO.

The search endpoint contains a utility request that shows the various criteria that you may use to search, for each entity type in the Workload Optimization Manager supply chain, and a second that shows the options for a specified criterion. You can then use this information to build your search criteria for more detailed groups.

The available filterTypes depend on the entity making up your search:

- VirtualMachine
 - vmsByName
 - vmsByPMName
 - vmsByStorage
 - vmsByNetwork
 - vmsByApplication
 - vmsByDatabaseServer

- vmsByDatabaseServerVersion
- vmsByDC
- vmsByVDC
- vmsByDCnested
- vmsByNumCPUs
- vmsByMem
- vmsByGuestName
- vmsByAltName
- vmsByClusterName
- vmsByDiskArrayName
- vmsByLogicalPoolName
- vmsByTag
- vmsByState
- vmsByBusinessAccountUuid
- vmsByResourceGroupUuid

■ VirtualDataCenter

- vdcsByName
- vdcsByVDCName
- vdcsByTag
- vdcsByState

PhysicalMachine

- pmsByName
- pmsByStorage
- pmsByNetwork
- pmsBySwitch
- pmsByNumVms
- pmsByDC
- pmsByMem
- pmsByNumCPUs
- pmsByVendorName
- pmsByCPUModel
- pmsByModel
- pmsByTimezone
- pmsByClusterName
- pmsByTag
- pmsByState

■ Storage

- storageByName
- storageByTag
- storageByVMs
- storageByDC
- storageByPMCluster
- storageByState
- volumeByDeletable

Application Component

- appSrvsByName
- appsByName

WebServer

- wbSrvsByName



- BusinessApplication
 - busAppsByName
- Database
 - databaseByName
 - databaseByTag
 - databaseByBusinessAccountUuid
 - databaseByResourceGroupUuid
- DatabaseServer
 - databaseServerByName
 - databaseServerByTag
 - databaseServerByBusinessAccountUuid
 - databaseServerByEngine
 - databaseServerByEdition
 - databaseServerByVersion
- VirtualApplication
 - vappsByName
- Cluster
 - clustersByName
 - clustersByTag
- DataCenter
 - datacentersByName
 - datacentersByTag
- Group
 - groupsByName
- StorageCluster
 - storageClustersByName
- DiskArray
 - diskarrayByName
- Zone
 - zonsByName
- Region
 - regsByName
- Network
 - netsByName
- LoadBalancer
 - IbsByName
- Chassis
 - chasByName
- StorageController
 - storagecontrollerByName
- DPod
 - dpodByName
- VPod
 - vpodByName
- LogicalPool
 - logicalPoolByName

- Switch
 - switchByName
- Container
 - containersByName
 - containersByPodName
 - containersByVMName
 - containersByNamespace
 - containerSpecsByName
- ContainerPod
 - containerPodsByName
 - containerPodsByNamespace
 - containerPodsByVMName
- ServiceEntity

NOTE: Groups of type ServiceEntity are the only groups that have multiple entity types, and are used exclusively for cloud targets.

- workloadByBusinessAccountUuid
- workloadByResourceGroupUuid
- Workload
 - workloadByBusinessAccountUuid
 - workloadByResourceGroupUuid
 - workloadControllersByName
 - workloadControllersByNamespace
 - workloadControllersByKind
 - ResourceGroup
 - resourceGroupByName
 - resourceGroupByUuid
 - resourceGroupByBusinessAccountUuid
- BusinessAccount
 - businessAccountByName
 - businessAccoutByUuid
 - subBusinessAccountOfUuid
 - businessAccountValidationStatus
 - businessAccountTargetName
 - businessAccountCloudProvider
- BillingFamily
 - billingFamilyByName
- ViewPod
 - viewPodByName
- DesktopPool
 - desktopPoolByName
 - desktopPoolByViewPod
- BusinessUser
 - businessUserByDesktopPool
 - businessUserByName
 - businessUserByViewPod
- Cloud-Specific Filters
 - computeTiersByName



- computeTiersByMem
- databaseTiersByName
- databaseTiersByDBMem
- databaseServerTiersByName
- databaseServerTiersByVMem

Example: GET https://10.10.10.10/api/v3/search/criteria

Response: An array of filter criteria, separated by entity type. For example, this is the filter criteria for Virtual Machine entities:

```
"VirtualMachine": {
    "criteria": [
      {
        "inputType": "*",
        "elements": "displayName",
        "filterCategory": "property",
        "filterType": "vmsByName"
     },
      {
        "inputType": "*",
        "elements": "HostedBy:displayName",
        "filterCategory": "entity",
        "filterType": "vmsByPMName"
     },
        "inputType": "*",
        "elements": "LayeredOver:Storage:displayName",
        "filterCategory": "entity",
        "filterType": "vmsByStorage"
     },
        "inputType": "*",
        "elements": "LayeredOver:Network:displayName",
        "filterCategory": "entity",
        "filterType": "vmsByNetwork"
      },
        "inputType": "*",
        "elements": "Hosts:Application:displayName",
        "filterCategory": "entity",
        "filterType": "vmsByApplication"
      },
      {
        "inputType": "*",
        "elements": "HostedBy:PhysicalMachine:HostedBy:DataCenter:displayName",
        "filterCategory": "entity",
        "filterType": "vmsByDC"
      },
      {
        "inputType": "*",
        "elements": "LayeredOver:VirtualDataCenter:displayName",
        "filterCategory": "entity",
        "filterType": "vmsByVDC"
      },
      {
```



```
"inputType": "*",
  "elements": "AllMemberOf: VirtualDataCenter: displayName",
  "filterCategory": "entity",
  "filterType": "vmsByDCnested"
},
{
  "inputType": "#",
  "elements": "ExtendedBy:VMTopoExt:numCpus",
  "filterCategory": "property",
  "filterType": "vmsByNumCPUs"
},
{
  "inputType": "#",
  "elements": "Commodities:VMem:capacity",
  "filterCategory": "property",
  "filterType": "vmsByMem"
},
{
  "inputType": "*",
  "elements": "ExtendedBy:VMTopoExt:guestName",
  "filterCategory": "property",
  "filterType": "vmsByGuestName"
},
{
  "inputType": "*",
  "elements": "ExtendedBy:VMTopoExt:altName",
  "filterCategory": "property",
  "filterType": "vmsByAltName"
},
{
  "inputType": "*",
  "elements": "HostedBy:PhysicalMachine:MemberOf:Cluster:displayName",\\
  "filterCategory": "entity",
  "filterType": "vmsByClusterName"
},
{
  "inputType": "*",
  "elements": "LayeredOver:Storage:LayeredOver:DiskArray:displayName",
  "filterCategory": "entity",
  "filterType": "vmsByDiskArrayName"
},
{
  "inputType": "*",
  "elements": "LayeredOver:Storage:LayeredOver:LogicalPool:displayName",
  "filterCategory": "entity",
  "filterType": "vmsByLogicalPoolName"
},
  "inputType": "*",
  "elements": "tags",
  "filterCategory": "property",
  "filterType": "vmsByTag"
},
{
```



```
"inputType": "*",
      "elements": "state",
      "filterCategory": "property",
      "filterType": "vmsByState"
    },
    {
      "inputType": "*",
      "elements": "belongsTo:uuid",
      "filterCategory": "entity",
      "filterType": "vmsByBusinessAccountUuid"
    },
    {
      "inputType": "*",
      "elements": "MemberOf:ResourceGroup:uuid",
      "filterCategory": "entity",
      "filterType": "vmsByResourceGroupUuid"
    }
  ]
}
```

Getting the Options for a Criterion

For a specific search criterion and entity type, you can get the possible values. For example, you may want to retrieve all tags for a particular group of hosts, or see the available state options for a particular group of virtual machines. This request takes the following parameters:

criteria_key

The criterion to retrieve options for. Currently, Workload Optimization Manager accepts the following criteria keys:

[state, tags]. Any other input that returns results should be considered internal or early access, and should not be relied on for scripting purposes.

scopes

The UUID of the scope to retrieve the criterion values for. For example, to retrieve all tags for virtual machines in a particular cluster, put the cluster UUID here.

entity_type

The entity whose state or tag options will be returned. For example, if scopes is passed with the UUID of a cluster, and this parameter is passed with a value of VirtualMachine, the request will return the options for each virtual machine in that cluster.

order_by

The field to order the results by. [creation_date, name, risk_category, savings, severity].

ascending

Default: true. When false, results will be in descending order.

environment_type

Returns only objects in the specified environment type. [Cloud, Hybrid, Onprem]

Example: GET https://10.10.10.10.10/api/v3/search/criteria/state/options? scopes=7c8d50fae46c09b68b00916411469770304226b4&entity_type=VirtualMachine

Response: A CriteriaOptionApiDTO with the available options. For example, the response below indicates that all virtual machines on the cluster whose UUID was passed are either in active or idle states.



```
"value": "IDLE"
}
```

Search Requests

Getting Object Information by UUID

Gets information about any object in your Workload Optimization Manager environment.

Object and Entity refer to different items in your Workload Optimization Manager topology:

NOTE:

For searches, the API paginates the returned data. If you do not specify a pagination limit, then the API returns pages set to the default limit of 100. You can set a maximum of 500 for the pagination limit. If you make no settings, and your search results include more than 100 entries, the results will be paginated. Your scripts should always check for a pagination cursor when processing search results.

You can change the default and max settings in the Workload Optimization Manager cr.yaml file. Find the entries for:

- apiPaginationDefaultLimit
- apiPaginationMaxLimit

If you set the objectType parameter has a value of Group, the response will include objects related to an entity that perform grouping. For example, resource groups and clusters both perform grouping, and will be included in the response.

To further refine your search, include a value for the <code>group_type</code> parameter. This parameter describes the membership of the group you are searching for. For example, a search with an <code>objectType</code> of <code>Group</code> and <code>group_type</code> of <code>VirtualMachine</code> will return all groups of virtual machines in the current scope.

Example: https://10.10.10.10/api/v3/search/Market

Response: A DTO with information about the retrieved object. In this example, the retrieved item is the real-time Market:

NOTE:

When making this request, you can use the <code>groupBy</code> parameter to order the results. The <code>/search</code> endpoint does not support the <code>utilization</code> value for the <code>groupBy</code> parameter. When this value is used, the API will return the results ordered by <code>displayName</code>.



Settings Endpoint

The settings endpoint can be used to change settings in a variety of settings managers. For example, using the actionscriptmanager, you can change action script settings, and using the automationmanager, you can change automation settings on your instance.

Using the settings endpoint of the Workload Optimization Manager API, you can:

- Get a list of available setting managers and settings
- Edit a setting

List of Settings Managers

The settings managers available to be modified are:

■ actionscriptmanager

Contains settings related to the use of action scripts.

automationmanager

Contains settings related to action modes for entities in your environment.

cloudsavingsmanager

Contains settings related to execution retention for cloud entities.

clusterHeadroomConfig

Contains settings related to the headroom plans generated by the system.

■ controlmanager

Contains settings related to workflows that replace native action handling for generated actions in your environment.

emailmanager

Contains settings related to SMTP email notifications.

■ hcisettingsmanager

Contains settings related to managing hyperconverged infrastructure.

■ marketsettingsmanager

Contains settings related to market analysis.

■ osmigrationmanager

Contains settings realted to operating system migration for cloud entities.

persistencemanager

Contains settings related to statistic retention data and reporting.

■ reservedinstancemanager

Contains settings related to reserved instances.

storagesettingsmanager

Contains settings related to storage entity statistics and analysis.

■ telemetrymanager

Contains settings related to telemetry opt-in and terms of service.

For more information about each settingsmanager, execute the GET https://lo.10.10.10/api/v3/settings request.

Settings Utility Requests

Utility requests provide metadata that you can use to make related requests, assemble inputDTOs, or see the potential values of a particular DTO.

The settings endpoint contains a utility request that shows each settings manager, and the settings available.

Example: GET https://10.10.10.10/api/v3/settings/



Response: An array of SettingsManagerApiDTOs, where each object is a settings manager and contains the settings for that manager.

Settings Requests

Getting Current Settings for a Specified Settings Manager

Gets the current settings for the specified settings manager. This request is often used to see the settings of a particular settings manager before updating.

Example: GET https://10.10.10.10/api/v3/settings/automationmanager

Response: A list of SettingApiDTOs representing the settings for the specified settings manager:

```
[
    "uuid": "startVM",
    "displayName": "Start",
    "value": "RECOMMEND",
    "defaultValue": "RECOMMEND",
    "valueType": "STRING",
    "options": [
        "label": "Disabled",
        "value": "DISABLED"
      },
        "label": "Recommend",
        "value": "RECOMMEND"
      },
      {
        "label": "Manual",
        "value": "MANUAL"
      },
        "label": "Automated",
        "value": "AUTOMATIC"
      }
    ],
    "entityType": "VirtualMachine",
    "sourceGroupName": "Global"
  },
    "uuid": "startPM",
    "displayName": "Start",
    "value": "RECOMMEND",
    "defaultValue": "RECOMMEND",
    "valueType": "STRING",
    "options": [
        "label": "Disabled",
        "value": "DISABLED"
      },
      {
        "label": "Recommend",
```



```
"value": "RECOMMEND"
    },
      "label": "Manual",
      "value": "MANUAL"
    },
      "label": "Automated",
      "value": "AUTOMATIC"
   }
  ],
  "entityType": "PhysicalMachine",
  "sourceGroupName": "Global"
},
  "uuid": "startDS",
  "displayName": "Start",
  "value": "RECOMMEND",
  "defaultValue": "RECOMMEND",
  "valueType": "STRING",
  "options": [
      "label": "Disabled",
      "value": "DISABLED"
    },
      "label": "Recommend",
      "value": "RECOMMEND"
    },
    {
      "label": "Manual",
      "value": "MANUAL"
   },
      "label": "Automated",
      "value": "AUTOMATIC"
    }
  ],
  "entityType": "Storage",
  "sourceGroupName": "Global"
},
```

Editing Settings

]

To edit a Setting, pass the new value in the body of this request. This request takes the following parameters:

- settingsManager_uuid
 - The UUID of the settingsmanager whose setting will be changed.
- setting_uuid

The setting whose value will be changed.

Example: PUT https://10.10.10.10/api/v3/settings/automationmanager/moveVM



Example Input: A SettingApiDTO. In this case, the value is being changed from MANUAL to RECOMMEND:

```
"uuid": "moveVM",
"displayName": "Move",
"value": "RECOMMEND",
"defaultValue": "MANUAL",
"valueType": "STRING",
"options": [
    "label": "Disabled",
    "value": "DISABLED"
  },
    "label": "Recommend",
    "value": "RECOMMEND"
  },
    "label": "Manual",
    "value": "MANUAL"
  },
    "label": "Automated",
    "value": "AUTOMATIC"
  }
],
"entityType": "VirtualMachine",
"sourceGroupName": "Global"
```

Response: The SettingApiDTO reflecting your changes:

```
"uuid": "moveVM",
"displayName": "Move",
"value": "RECOMMEND",
"defaultValue": "MANUAL",
"valueType": "STRING",
"options": [
  {
    "label": "Disabled",
    "value": "DISABLED"
  },
    "label": "Recommend",
    "value": "RECOMMEND"
  },
    "label": "Manual",
    "value": "MANUAL"
  },
    "label": "Automated",
    "value": "AUTOMATIC"
```



```
}
],
"entityType": "VirtualMachine",
"sourceGroupName": "Global"
```

Settings Policies Endpoint

A Settings Policy is the collection of settings that apply to an entity. In Workload Optimization Manager, there is a default policy for each type of entity. These global defaults are the base settings for entities, and any settings policies that you create will specify deltas to the defaults. Note that you can edit the global policies.

When you create a custom settings policy, you assign a scope to it – one or more groups of entities you want to affect with the policy. For these policies, you specify just the settings that will be different from the defaults.

In addition to global default policies and custom policies, Workload Optimization Manager also discovers groups that need special settings, and creates policies for those groups. For example, when Workload Optimization Manager discovers Azure Availability Sets and AWS Autoscaling Groups, it generates settings policies for those groups that turn on Consistent Resizing for the group.

Using the settings policies endpoint, you can:

- Get a listing of the settings policies in your environment
- Get details for a single settings policy
- Create settings policies
- Edit settings policies
- Delete settings policies

Settings Policies Requests

Getting Settings Policies

This call returns an array of SettingsPolicyApiDTOs for all the settings policies in your environment. You can pass entity types to limit the listing to policies for those types, and you can limit the list to only default policies.

This request takes the following parameters:

- only_defaults
 - If this is true, the call only gets the default settings policies
- entity_type

One or more entity types to limit the list of settings policies

Examples:

- Get all the settings policies: GET https://10.10.10.10/api/v3/settingspolicies
- Get all the default settings policies: GET https://10.10.10.10/api/v3/settingspolicies? only_defaults=true
- Get settings policies for VMs and Hosts: GET https://10.10.10.10/api/v3/settingspolicies? entity_type=VirtualMachine&entity_type=PhysicalMachine
- Get a single settings policy (pass the policy Uuid): GET https://10.10.10.10/api/v3/settingspolicies/ _aVDEwGegEemDFcIzuV5wcQ

Response: An array of SettingsPolicyApiDTOs. This listing shows the settings policies for Container entities.

```
{
    "uuid": "_vyMHEDnSEemHXrxYkw9y2Q",
```



```
"displayName": "Container defaults",
"entityType": "Container",
"settingsManagers": [
    "uuid": "marketsettingsmanager",
    "displayName": "Operational Constraints",
    "category": "Analysis",
    "settings": [
     {
       "uuid": "usedIncrement_Container_VMEM",
        "displayName": "Increment constant for Container VMem [MB]",
       "value": "64.0",
       "defaultValue": "64.0",
        "categories": [
          "resizeRecommendationsConstants"
       "valueType": "NUMERIC",
        "min": 0,
       "max": 10000000,
       "entityType": "Container",
       "sourceGroupName": "Global"
     },
      {
        "uuid": "usedIncrement_Container_VCPU",
       "displayName": "Increment constant for Container VCPU [MHz]",
       "value": "100.0",
       "defaultValue": "100.0",
        "categories": [
          "resizeRecommendationsConstants"
       ],
       "valueType": "NUMERIC",
       "min": 0,
       "max": 1000000,
       "entityType": "Container",
       "sourceGroupName": "Global"
     },
      {
       "uuid": "enforceConsistentResizingContainer",
       "displayName": "Consistent Resizing",
        "value": "false",
       "defaultValue": "false",
        "categories": [
          "resizeRecommendationsConstants"
       ],
       "valueType": "BOOLEAN",
       "entityType": "Container",
       "sourceGroupName": "Global"
     },
       "uuid": "resizeTargetUtilization_Container",
        "displayName": "Resize Target Utilization",
       "value": "0.0",
       "defaultValue": "0.0",
        "valueType": "NUMERIC",
```



```
"min": 0,
    "max": 100,
    "entityType": "Container",
    "sourceGroupName": "Global"
    }
    }
    ...
}
```

Creating a Settings Policy

Referenced Endpoint: Groups (on page 819)

To create a settings policy, you must do the following:

- Specify a policy name,
- Specify whether to enable or disable the policy in your market.
- Set the policy scope Specify one or more groups of a given entity type. This determines the entity type for the policy.
- For the of settings you want to make, specify the appropriate settings manager, and then specify an array of setting/value pairs.
- Optionally, specify a schedule window and/or action execution schedule for the policy.

To set the policy scope, you provide an array of objects that contain group Uuids. These objects are effectively abbreviated GroupApiDTOs. Note that the groups must all be for the same type of entity. This specifies the entity type for the settings policy. Use the Groups endpoint to get the Uuid values for the groups you want in the scope. For example, to set the scope to a single group of VMs, use the following scopes object:

To specify the actual settings, you provide an array of SettingsManagerApiDTOs. Each one contains an array of settings that you want to make. To see all the settings for a given entity type, refer to the user interface. The setting managers you can choose from are:

■ actionscriptmanager

Contains settings related to the use of action scripts.

automationmanager

Contains settings related to action modes for entities in your environment.

cloudsavingsmanager

Contains settings related to execution retention for cloud entities.

■ clusterHeadroomConfig

Contains settings related to the headroom plans generated by the system.

controlmanager

Contains settings related to workflows that replace native action handling for generated actions in your environment.

■ emailmanager

Contains settings related to SMTP email notifications.

hcisettingsmanager

Contains settings related to managing hyperconverged infrastructure.



- marketsettingsmanager
 - Contains settings related to market analysis.
- osmigrationmanager
 - Contains settings realted to operating system migration for cloud entities.
- persistencemanager
 - Contains settings related to statistic retention data and reporting.
- reservedinstancemanager
 - Contains settings related to reserved instances.
- storagesettingsmanager
 - Contains settings related to storage entity statistics and analysis.
- telemetrymanager
 - Contains settings related to telemetry opt-in and terms of service.

For example, to set the VM start action to AUTOMATED and to set the VCPU maximum to 16, use the following settingsManagers array:

You can set up a schedule window that determines when the settings policy takes effect. For that you provide a ScheduleApiDTO for the schedule details. It includes: the start and end dates, start and end times,

- Start and end dates.
- Start and end times.
- An optional RecurrenceApiDTO for schedule recurrence. If you don't provide this you will specify a one-time schedule window.

For example, use this to specify a "perpetual" schedule window (does not expire until 2099) that starts at 12:30 am and ends at 7:30 am every Saturday and Sunday.

```
"schedule": {
    "startDate": "2019-04-28T00:30:00-04:00",
    "endDate": "2099-12-31T07:30:00-05:00",
    "startTime": "2019-04-28T00:30:00-04:00",
    "endTime": "2019-04-28T07:30:00-04:00",
```



```
"recurrence": {
    "type": "WEEKLY",
    "daysOfWeek": [
        "Sat",
        "Sun"
    ]
}
```

An example complete data payload for a policy with a policy-level schedule, action execution instruction, and action execution schedule is as follows:

```
"disabled":false,
"entityType":"VirtualMachine",
"displayName": "TestPol",
"scopes":[
   {
      "uuid":"285041619454560"
   }
],
"settingsManagers":[
   {
      "uuid": "automationmanager",
      "displayName": "Action Mode Settings",
      "category": "Automation",
      "settings":[
         {
            "uuid": "storageMove",
            "value": "RECOMMEND",
            "valueType": "STRING",
            "valueObjectType": "String",
            "defaultValue": "RECOMMEND",
            "entityType":"VirtualMachine",
            "displayName": "Storage Move",
             "options":[
                {
                   "label": "Disabled",
                   "value": "DISABLED"
                   "label": "Recommend",
                   "value": "RECOMMEND"
                },
                   "label": "External Approval",
                   "value": "EXTERNAL_APPROVAL"
                },
                   "label": "Manual",
                   "value": "MANUAL"
                },
                   "label": "Automatic",
                   "value": "AUTOMATIC"
```



```
{
            "uuid": "storageMoveExecutionSchedule",
             "value":"285088800975856",
             "valueType": "LIST",
            "valueObjectType": "String",
             "entityType": "VirtualMachine",
             "displayName": "Execution window for Storage Move action"
         }
      ]
   }
],
"schedule":{
   "uuid": "285088797821136",
   "displayName": "TestSched",
   "endTime": "2021-05-24T16:00",
   "startTime":"2021-05-24T14:30",
   "timeZone": "America/Chicago",
   "recurrence":{
      "type": "MONTHLY",
      "interval":1,
      "daysOfMonth":[
      ]
   }
```

Example: Using the above payload, POST https://10.10.10.10/api/v3/settingspolicies

Response: The settings policy that you created. Use this response to get the policy Uuid.

Editing a Settings Policy

To edit a settings policy, you push a new set of data to the Settings Policies end point. The best way to do this is to copy the SettingsPolicyApiDTO that you want to edit, make changes to that DTO, and then push the DTO out to the API. To remove the policy from the scope, pass the SettingsPolicyApiDTO, and also pass reset_defaults=true as a parameter.

This request takes the following parameters:

- settingsPolicy_Uuid
 - The Uuid of the policy you want to edit
- reset_defaults

A boolean you can use to reset the policy to default. When $reset_defaults=true$, you remove the policy and reset that scope to default. When you use this setting, pass an empty object $\{\}$ as the data payload.

Examples:

- Assuming you copied a SettingsPolicyApiDTO and then made some changes to it, and pass that at the payload: PUSH https://10.10.10.10/api/v3/settingspolicies/_2-CbQGoNEemyOoIvFZyv1A? reset_defaults=false
- Assuming you want to remove the policy (and so you pass an empty object as the payload): PUSH https://10.10.10.10/api/v3/settingspolicies/_2-CbQGoNEemyOoIvFZyv1A? reset_defaults=true

 $\textbf{Response:} \ \textbf{The modified } \textbf{SettingsPolicyApiDTO}.$



Deleting a Settings Policy

Deletes the given settings policy.

Example: DELETE https://10.10.10.10/api/v3/settingspolicies/_aV5ucGoTEemyOoIvFZyv1A

Response: 200 for success.

Statistics Endpoint

Statistics Overview

Statistics are pieces of information that Workload Optimization Manager discovers while continuously analyzing your environment. The most common use of statistics is to look at a particular statistic over a specific time frame.

Using the stats endpoint of the Workload Optimization Manager API, you can:

- Get a list of stats requests in other endpoints
- Get a filtered list of statistics over a specific time frame
- Get a list of statistics for a specified entity
- Get a filtered list of statistics for a specified entity

Statistic Timings

Statistics associated to headroom and capacity planning are written to the Workload Optimization Manager database daily, with a timestamp of midnight. Other statistics are collected and stored in the database in ten-minute increments. When retrieving groups of statistics that include both headroom and actively-monitored information, the timestamps returned will reflect the last-written date for each statistic.

Statistics Utility Requests

Utility requests provide metadata that you can use to make related requests, assemble inputDTOs, or see the potential values of a particular DTO.

The stats endpoint contains a utility request that shows common entry points for statistic-related requests. These can be used to obtain statistics for particular entities or groups.

Example: GET https://10.10.10.10/api/v3/stats

Response: An array of Link objects, where each object contains a URL to get all statistics for a specified UUID, entity, or group.

Statistics Requests

Getting Statistics for an Entity

Gets all statistics for the specified entity. This request takes the following parameters:

entity_uuid

The entity whose statistics will be returned.

■ C

Used internally by Workload Optimization Manager.

NOTE:

When you retrieve statistics for a cluster, using the <code>/groups</code> endpoint will return the aggregated statistics for all applicable cluster entities. For individual stats per entity, use the <code>/stats</code> endpoint.

Some statistics are only valid for certain scopes. When you request given statistics for a scope that doesn't include them, the API does not return any data. For example, the numVMs statistic is valid in only the Market and Cluster scopes – the API omits numVMs data from the response when you query other scopes.



Example: https://10.10.10.10/api/v3/stats/423f26a7-1132-df1c-64e2-8a040480b046

Response: A list of StatSnapshotApiDTOs representing the current values of the statistics.

```
[
  {
    "displayName": "AdityaReplica",
    "date": "2019-04-24T20:09:46-04:00",
    "statistics": [
      {
        "name": "priceIndex",
        "relatedEntityType": "VirtualMachine",
        "values": {
          "max": 1.01,
          "min": 1.01,
          "avg": 1.01,
          "total": 1.01
        "value": 1.01
      },
      {
        "displayName": "CPUProvisioned/AdityaReplica",
        "name": "CPUProvisioned",
        "capacity": {
          "max": 3120000,
          "min": 3120000,
          "avg": 3120000,
          "total": 3120000
        },
        "relatedEntityType": "VirtualMachine",
        "filters": [
          {
            "type": "relation",
            "value": "bought"
          }
        ],
        "units": "MHz",
        "values": {
          "max": 5200,
          "min": 5200,
          "avg": 5200,
          "total": 5200
        },
        "value": 5200
      },
        "displayName": "Swapping/AdityaReplica",
        "name": "Swapping",
        "capacity": {
          "max": 40000000,
          "min": 40000000,
          "avg": 40000000,
          "total": 40000000
        },
        "relatedEntityType": "VirtualMachine",
```



```
"filters": [
          {
            "type": "relation",
            "value": "bought"
          }
        ],
        "units": "bit/sec",
        "values": {
          "max": 0,
          "min": 0,
          "avq": 0,
          "total": 0
        },
        "value": 0
      },
      {
        "displayName": "NumDisk/AdityaReplica",
        "name": "NumDisk",
        "capacity": {
          "max": 2147483650,
          "min": 2147483650,
          "avg": 2147483650,
          "total": 2147483650
        },
        "relatedEntityType": "VirtualMachine",
        "filters": [
            "type": "relation",
            "value": "bought"
          }
        ],
        "values": {
          "max": 1,
          "min": 1,
          "avg": 1,
          "total": 1
        },
        "value": 1
      },
    . . .
    1
 }
]
```

Getting a Filtered List of Statistics

Gets a list of statistics filtered by a StatPeriodApiInputDTO that you create. For more information about the criteria that make up the input for this request, see the Swagger documentation for this request, located at https://cyour_Workload Optimization Manager_IP>/swagger/external/index.html.

Example: POST https://10.10.10.10/api/v3/stats/423f26a7-1132-df1c-64e2-8a040480b046

Example Input: This input will return the values for the VMem, VCPU, and VStorage statistics of the specified entity, ordered first by key, then relatedEntity, then virtualDisk.



```
"statistics": [
  {
    "name": "VMem",
    groupBy: [
     "key",
      "relatedEntity",
      "virtualDisk"
   ]
  },
    "name": "VCPU",
    groupBy: [
     "key",
      "relatedEntity",
      "virtualDisk"
    ]
  },
    "name": "VStorage",
    "groupBy": [
     "key",
      "relatedEntity",
      "virtualDisk"
    ]
  }
]
```

Response: A list of StatSnapshotApiDTOs representing the filtered statistics for the entity:

```
[
  {
    "displayName": "AdityaReplica",
    "date": "2019-04-24T20:28:06-04:00",
    "statistics": [
     {
        "displayName": "AdityaReplica",
        "name": "VMem",
        "capacity": {
          "max": 1048576,
          "min": 1048576,
          "avg": 1048576,
          "total": 1048576
        },
        "relatedEntityType": "VirtualMachine",
        "filters": [
          {
            "type": "virtualDisk",
            "value": ""
          },
          {
            "type": "key",
```



```
"value": null
    },
      "type": "relation",
      "value": "sold"
  ],
  "relatedEntity": {
    "uuid": "5d2f7b69eb3bf506089feba37d31b0c376b02e34",
    "displayName": "GuestLoad[AdityaReplica]",
    "className": "Application"
  },
  "units": "KB",
  "values": {
    "max": 0,
    "min": 0,
    "avg": 0,
    "total": 0
  },
  "value": 0
},
  "displayName": "AdityaReplica",
  "name": "VCPU",
  "capacity": {
    "max": 5200,
    "min": 5200,
    "avg": 5200,
    "total": 5200
  },
  "relatedEntityType": "VirtualMachine",
  "filters": [
      "type": "virtualDisk",
      "value": ""
    },
      "type": "key",
      "value": null
    },
      "type": "relation",
      "value": "sold"
    }
  ],
  "relatedEntity": {
    "uuid": "5d2f7b69eb3bf506089feba37d31b0c376b02e34",
    "displayName": "GuestLoad[AdityaReplica]",
    "className": "Application"
  "units": "MHz",
  "values": {
    "max": 19,
    "min": 14.93,
```



```
"avg": 14.93,

"total": 14.93

},

"value": 14.93

}

]
```

Getting a Filtered List of Statistics for All Objects In a Specified Scope

For the specified scope, gets a filtered list of statistics for each entity. If you do not provide any statistics in the input, the response contains basic information about each entity. For more information about the criteria that make up the input for this request, see the Swagger documentation for this request, located at https://syour_Workload Optimization Manager_IP>/swagger/external/index.html.

Example: POST https://10.10.10.10/api/v3/stats?ascending=true

Example Input: This input will return the VMem values for each entity in the real-time market from a period of five days prior to the request, to one day prior to the request.

Response: A list of StatSnapshotApiDTOs representing the filtered statistics for the entities in the specified scope:



```
"avg": 16777216,
        "total": 33554432
      "relatedEntityType": "VirtualMachine",
      "filters": [
          "type": "relation",
          "value": "sold"
        }
      ],
      "units": "KB",
      "values": {
        "max": 1509949.5,
        "min": 335544.3,
        "avg": 587202.56,
        "total": 1174405.1
      },
      "value": 587202.56
    }
  ]
},
{
  "displayName": "vm-c67a1cdd-609e-4282-809c-e0def5cd0d7a",
  "date": "2019-04-20T00:00:00-04:00",
  "statistics": [
      "name": "VMem",
      "capacity": {
        "max": 16777216,
        "min": 16777216,
        "avg": 16777216,
        "total": 33554432
      },
      "relatedEntityType": "VirtualMachine",
      "filters": [
          "type": "relation",
          "value": "sold"
        }
      ],
      "units": "KB",
      "values": {
        "max": 1509949.5,
        "min": 369098.75,
        "avg": 587202.56,
        "total": 1174405.1
      "value": 587202.56
    }
  ]
},
  "displayName": "vm-c67a1cdd-609e-4282-809c-e0def5cd0d7a",
  "date": "2019-04-22T00:00:00-04:00",
```



```
"statistics": [
    {
      "name": "VMem",
      "capacity": {
        "max": 16777216,
        "min": 16777216,
        "avg": 16777216,
        "total": 33554432
      },
      "relatedEntityType": "VirtualMachine",
      "filters": [
        {
          "type": "relation",
          "value": "sold"
        }
      ],
      "units": "KB",
      "values": {
        "max": 12582912,
        "min": 0,
        "avg": 452984.84,
        "total": 905969.7
      },
      "value": 452984.84
  ]
},
{
  "displayName": "vm-c67a1cdd-609e-4282-809c-e0def5cd0d7a",
  "date": "2019-04-23T00:00:00-04:00",
  "statistics": [
    {
      "name": "VMem",
      "capacity": {
        "max": 16777216,
        "min": 16777216,
        "avg": 16777216,
        "total": 33554432
      "relatedEntityType": "VirtualMachine",
      "filters": [
        {
          "type": "relation",
          "value": "sold"
        }
      ],
      "units": "KB",
      "values": {
        "max": 838860.8,
        "min": 0,
        "avg": 167772.16,
        "total": 335544.3
      },
      "value": 167772.16
```



```
}
  ]
},
  "uuid": "39EBB726-41D9-4BC8-A41D-CA301854309C",
  "displayName": "Gilad_OM-38071_SMB_VM2",
  "className": "VirtualMachine",
  "environmentType": "ONPREM"
},
  "uuid": "97A3F420-B7AD-414D-A543-FD308AC774A6",
  "displayName": "Gilad_VMM_Test_VM_2",
  "className": "VirtualMachine",
  "environmentType": "ONPREM"
},
  "uuid": "4211f183-69a8-3676-3e53-0151365500ff",
  "displayName": "james-ubuntu-dc13",
  "className": "VirtualMachine",
  "environmentType": "ONPREM",
  "stats": [
    {
      "displayName": "james-ubuntu-dc13",
      "date": "2019-04-19T00:00:00-04:00",
      "statistics": [
        {
          "name": "VMem",
          "capacity": {
            "max": 1048576,
            "min": 1048576,
            "avg": 1048576,
            "total": 2097152
          },
          "relatedEntityType": "VirtualMachine",
          "filters": [
            {
              "type": "relation",
              "value": "sold"
            }
          ],
          "units": "KB",
          "values": {
            "max": 83886.08,
            "min": 8388.61,
            "avg": 18874.37,
            "total": 37748.73
          },
          "value": 18874.37
        }
      ]
    },
    {
```



```
"displayName": "james-ubuntu-dc13",
  "date": "2019-04-20T00:00:00-04:00",
  "statistics": [
      "name": "VMem",
      "capacity": {
        "max": 1048576,
        "min": 1048576,
        "avg": 1048576,
        "total": 2097152
      },
      "relatedEntityType": "VirtualMachine",
      "filters": [
        {
          "type": "relation",
          "value": "sold"
        }
      ],
      "units": "KB",
      "values": {
        "max": 62914.56,
        "min": 13631.49,
       "avg": 18874.37,
        "total": 37748.73
      "value": 18874.37
   }
  ]
},
{
  "displayName": "james-ubuntu-dc13",
  "date": "2019-04-21T00:00:00-04:00",
  "statistics": [
      "name": "VMem",
      "capacity": {
        "max": 1048576,
        "min": 1048576,
        "avg": 1048576,
        "total": 2097152
      },
      "relatedEntityType": "VirtualMachine",
      "filters": [
        {
          "type": "relation",
          "value": "sold"
        }
      ],
      "units": "KB",
      "values": {
        "max": 73400.32,
        "min": 11534.34,
        "avg": 17825.79,
        "total": 35651.59
```



```
},
      "value": 17825.79
  ]
},
{
  "displayName": "james-ubuntu-dc13",
  "date": "2019-04-22T00:00:00-04:00",
  "statistics": [
      "name": "VMem",
      "capacity": {
        "max": 1048576,
        "min": 1048576,
        "avg": 1048576,
        "total": 2097152
      "relatedEntityType": "VirtualMachine",
      "filters": [
          "type": "relation",
          "value": "sold"
        }
      ],
      "units": "KB",
      "values": {
        "max": 83886.08,
        "min": 8388.61,
        "avg": 19922.94,
        "total": 39845.89
      },
      "value": 19922.94
    }
  ]
},
  "displayName": "james-ubuntu-dc13",
  "date": "2019-04-23T00:00:00-04:00",
  "statistics": [
    {
      "name": "VMem",
      "capacity": {
        "max": 1048576,
        "min": 1048576,
        "avg": 1048576,
        "total": 2097152
      "relatedEntityType": "VirtualMachine",
      "filters": [
          "type": "relation",
          "value": "sold"
        }
      ],
```



```
"units": "KB",
          "values": {
            "max": 73400.32,
            "min": 3145.73,
            "avg": 18874.37,
            "total": 37748.73
          },
          "value": 18874.37
        }
      ]
    }
  ]
},
  "uuid": "421d2165-36cd-7f6a-3a43-08e09f6f4e0f",
  "displayName": "ACM-LexCorp-Control",
  "className": "VirtualMachine",
  "environmentType": "ONPREM",
  "stats": [
      "displayName": "ACM-LexCorp-Control",
      "date": "2019-04-19T00:00:00-04:00",
      "statistics": [
        {
          "name": "VMem",
          "capacity": {
            "max": 2097152,
            "min": 2097152,
            "avg": 2097152,
            "total": 4194304
          },
          "relatedEntityType": "VirtualMachine",
          "filters": [
              "type": "relation",
              "value": "sold"
            }
          ],
          "units": "KB",
          "values": {
            "max": 167772.16,
            "min": 18874.37,
            "avg": 37748.73,
            "total": 75497.47
          },
          "value": 37748.73
      ]
    },
      "displayName": "ACM-LexCorp-Control",
      "date": "2019-04-20T00:00:00-04:00",
      "statistics": [
        {
```



```
"name": "VMem",
      "capacity": {
        "max": 2097152,
        "min": 2097152,
        "avg": 2097152,
        "total": 4194304
      "relatedEntityType": "VirtualMachine",
      "filters": [
          "type": "relation",
          "value": "sold"
        }
      ],
      "units": "KB",
      "values": {
        "max": 125829.12,
        "min": 18874.37,
        "avg": 37748.73,
        "total": 75497.47
      },
      "value": 37748.73
    }
  ]
},
{
  "displayName": "ACM-LexCorp-Control",
  "date": "2019-04-21T00:00:00-04:00",
  "statistics": [
    {
      "name": "VMem",
      "capacity": {
        "max": 2097152,
        "min": 2097152,
        "avg": 2097152,
        "total": 4194304
      },
      "relatedEntityType": "VirtualMachine",
      "filters": [
        {
          "type": "relation",
          "value": "sold"
        }
      ],
      "units": "KB",
      "values": {
        "max": 104857.6,
        "min": 20971.52,
        "avg": 35651.59,
        "total": 71303.17
      },
      "value": 35651.59
    }
  ]
```



```
},
{
  "displayName": "ACM-LexCorp-Control",
  "date": "2019-04-22T00:00:00-04:00",
  "statistics": [
      "name": "VMem",
      "capacity": {
        "max": 2097152,
        "min": 2097152,
        "avg": 2097152,
        "total": 4194304
      },
      "relatedEntityType": "VirtualMachine",
      "filters": [
       {
          "type": "relation",
          "value": "sold"
        }
      ],
      "units": "KB",
      "values": {
        "max": 272629.75,
        "min": 20971.52,
        "avg": 73400.32,
        "total": 146800.64
      },
      "value": 73400.32
    }
  ]
},
{
  "displayName": "ACM-LexCorp-Control",
  "date": "2019-04-23T00:00:00-04:00",
  "statistics": [
      "name": "VMem",
      "capacity": {
        "max": 2097152,
        "min": 2097152,
        "avg": 2097152,
        "total": 4194304
      "relatedEntityType": "VirtualMachine",
      "filters": [
       {
          "type": "relation",
          "value": "sold"
        }
      ],
      "units": "KB",
      "values": {
        "max": 251658.23,
        "min": 23068.67,
```



```
"avg": 79691.77,
            "total": 159383.55
          "value": 79691.77
       }
      ]
    }
  ]
},
  "uuid": "420f3462-ca50-fedf-aa8f-223bd39b1852",
  "displayName": "shai-redhat",
  "className": "VirtualMachine",
  "environmentType": "ONPREM",
  "stats": [
   {
      "displayName": "shai-redhat",
      "date": "2019-04-19T00:00:00-04:00",
      "statistics": [
       {
          "name": "VMem",
          "capacity": {
            "max": 1048576,
            "min": 1048576,
            "avg": 1048576,
            "total": 2097152
          },
          "relatedEntityType": "VirtualMachine",
          "filters": [
            {
              "type": "relation",
              "value": "sold"
            }
          ],
          "units": "KB",
          "values": {
            "max": 20971.52,
            "min": 0,
            "avg": 1048.58,
            "total": 2097.15
          },
          "value": 1048.58
        }
      ]
    },
  ]
}
```

]



Complex Statistic Queries

Using the POST /stats request, you can retrieve a variety of statistics. For example, this is a complex query made by the Workload Optimization Manager UI:

```
"statistics":[
    "name": "CPU",
    "relatedEntityType": "PhysicalMachine",
    "groupBy":[
      "key",
      "virtualDisk"
    ],
    "filters":[
      {
        "type": "relation",
        "value": "sold"
      }
    ]
  },
    "name": "Mem",
    "relatedEntityType": "PhysicalMachine",
    groupBy":[
      "key",
      "virtualDisk"
    ],
    "filters":[
      {
        "type": "relation",
        "value": "sold"
      }
    ]
  },
    "name": "NetThroughput",
    "relatedEntityType": "PhysicalMachine",
    "groupBy":[
      "key",
      "virtualDisk"
    ],
    "filters":[
        "type": "relation",
        "value": "sold"
      }
    ]
  },
    "name": "IOThroughput",
    "relatedEntityType": "PhysicalMachine",
    groupBy":[
      "key",
      "virtualDisk"
```



```
],
  "filters":[
    {
      "type": "relation",
      "value": "sold"
    }
  ]
},
  "name":"Q1VCPU",
  "related \verb|EntityType|": "Physical Machine"|,
  groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
    {
      "type": "relation",
      "value": "sold"
    }
  ]
},
  "name":"Q2VCPU",
  "relatedEntityType": "PhysicalMachine",
  groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
   {
      "type": "relation",
      "value": "sold"
    }
  ]
},
  "name":"Q4VCPU",
  "relatedEntityType":"PhysicalMachine",
  "groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
      "type": "relation",
      "value": "sold"
    }
  ]
},
  "name":"Q8VCPU",
  "relatedEntityType": "PhysicalMachine",
  "groupBy":[
```



```
"key",
    "virtualDisk"
  "filters":[
      "type": "relation",
      "value": "sold"
  ]
},
  "name":"Q16VCPU",
  "relatedEntityType":"PhysicalMachine",
  "groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
      "type": "relation",
      "value": "sold"
  ]
},
  "name": "Q32VCPU",
  "relatedEntityType": "PhysicalMachine",
  groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
      "type": "relation",
      "value": "sold"
  ]
},
  "name": "Ballooning",
  "relatedEntityType": "PhysicalMachine",
  "groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
      "type": "relation",
      "value": "sold"
  ]
},
  "name": "Swapping",
```



```
"relatedEntityType": "PhysicalMachine",
  "groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
    {
      "type": "relation",
      "value": "sold"
  ]
},
  "name": "CPUProvisioned",
  "relatedEntityType": "PhysicalMachine",
  "groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
    {
      "type": "relation",
      "value":"sold"
  ]
},
  "name": "MemProvisioned",
  "relatedEntityType": "PhysicalMachine",
  groupBy:[
    "key",
    "virtualDisk"
  ],
  "filters":[
      "type": "relation",
      "value":"sold"
  ]
},
  "name": "Flow",
  "relatedEntityType": "PhysicalMachine",
  "groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
      "type": "relation",
      "value": "sold"
    }
  ]
},
```



```
"name": "FlowAllocation",
  "relatedEntityType":"PhysicalMachine",
  "groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
   {
      "type": "relation",
      "value": "sold"
  ]
},
  "name": "Cooling",
  "relatedEntityType": "PhysicalMachine",
  groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
    {
      "type": "relation",
      "value": "sold"
    }
  ]
},
  "name": "Power",
  "relatedEntityType": "PhysicalMachine",
  groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
    {
      "type": "relation",
      "value": "sold"
  ]
},
  "name": "Space",
  "relatedEntityType": "PhysicalMachine",
  groupBy":[
    "key",
    "virtualDisk"
  ],
  "filters":[
    {
      "type": "relation",
      "value": "sold"
    }
```



```
]
}
]
```

The previous request is made in context of a datacenter scope, so the response includes information for each host within that datacenter. The virtualDisk value for the groupBy parameter ensures that all virtual disks appear in the response as individual line items, rather than an aggregation.

Additionally, the "filters": [{"type": "relation", "value": "sold"}] found throughout the call indicates that the response includes those commodities *sold* by these hosts, rather than purchased from a lower level in the supply chain.

Supplychains Endpoint

Workload Optimization Manager models your environment as a market of buyers and sellers. It discovers different types of entities in your environment via the targets you have configured for your installation. Discovery maps these entities to the supply chain so Workload Optimization Manager can monitor them and manage the workloads they support. For example, for a hypervisor target Workload Optimization Manager discovers VMs, the hosts and datastores that provide resources to the VMs, and the applications that use VM resources. The entities in your environment form a chain of supply and demand where some entities provide resources while others consume the supplied resources.

Using the supplychains endpoint, you can:

- Get a full or filtered supply chain related to an entity in your environment
- Get the statistics for the supply chain related to an entity in your environment

Supplychains Requests

Getting a Supply Chain for the Specified Entity

Gets the full supply chain for the specified entity. For example, if the UUID of a virtual machine is used, you will see the applications that are hosted by that virtual machine, the hosts and datastores that it consumes from, the cluster or datacenter that the hosts consume from, the disk arrays and storage controllers that the datastores consume from, and so on.

In a supply chain, depth refers to the distance in the supply chain from the entity called. For example, if the UUID of a host is used, virtual machines consuming from that host will have a depth of -1, applications consuming from those virtual machines will have a depth of -2, other hosts that are in the supply chain will have a depth of 0, and the cluster of the host will have a depth of 1.

Example: GET https://10.10.10.10/api/v3/supplychains?uuids=Virtual_ESX_4238042f-7465-e92a-5c28-a7a929307247&health=false

Response: A SupplychainApiDTO representing the supply chain of the specified entity- in this case, a host. Note that when there is a single instance of an entity, Workload Optimization Manager will return the details of that entity. In the response, you can see this with the DPod and Storage Controller entities.

```
{
   "seMap":{
     "Application":{
        "depth":-2,
        "entitiesCount":12,
        "stateSummary":{
              "ACTIVE":5,
              "SUSPEND":1,
              "IDLE":6
        }
}
```



```
},
    "DPod":{
      "depth":-1,
      "entitiesCount":1,
      "stateSummary":{
        "ACTIVE":1
      },
      "instances":{
        "c15cef94af07fccf19e303884592a4ef211764f1":{
          "links":[
            {
              "rel": "self",
              "href": "https://10.10.10.10/api/v3/entities/c15cef94af07fccf19e303884592a4ef211764f1?inclu
de_aspects=false"
          ],
          "uuid": "c15cef94af07fccf19e303884592a4ef211764f1",
          "displayName": "DPOD-data-mycorp",
          "className": "DPod",
          "priceIndex":1e-12,
          "state": "ACTIVE",
          "severity": "Normal",
          "environmentType": "ONPREM"
      }
    },
 "StorageController":{
      "depth":3,
      "entitiesCount":1,
      "stateSummary":{
        "ACTIVE":1
      },
      "instances":{
        "be89058c-e786-11e4-82ba-dfc30ffeb3ee":{
          "links":[
            {
              "rel": "self",
              "href": "https://10.10.10.10/api/v3/entities/be89058c-e786-11e4-82ba-dfc30ffeb3ee?include_a
spects=false"
          ],
          "uuid": "be89058c-e786-11e4-82ba-dfc30ffeb3ee",
          "displayName": "dataontap-mycorp-cm1",
          "className": "StorageController",
          "priceIndex":20000,
          "state": "ACTIVE",
          "severity": "Normal",
          "discoveredBy":{
            "uuid":"_adGLMJwFEei_xJ5Ai6-rnQ",
            "displayName": "data-cluster.eng.mycorp.com",
            "type": "NetApp"
          },
          "remoteId": "be89058c-e786-11e4-82ba-dfc30ffeb3ee",
```



```
"environmentType":"ONPREM"
}
}
}
```

Getting Leaf Entities from a Supply Chain Root

Gets an array of entities that are top-most for a given supply chain scope. You provide an array of UUIDs to seed the starting scope. The request then traverses up the supply chain from those seed entities, until it finds entities that have no consumers. These are *leaf* entities for that seeded scope.

■ uuids

A list of UUIDs to seed the request scope. For example, you can give uuids for multiple VMs, and the request will find all leaf entities from all VMs in the list. If you give the uuid for a group, the request treats the group members as a list of entities.

filterEntityTypes

A list of entity types to filter out of the request. You can provide any valid entity class name. The request stops traversing the supply chain at the filtered entity. For example, assume you have a supply chain that grows from 1 VM > 4 ApplicationComponent > 2 Service > 1 BusinessApplication. A request starting from the VM would return the single Business Application. If you filter out BusinessApplication, it would return the two Service entities. If you filter out Service, it would return 4 ApplicationComponent entities. Note that the Swagger documentation for this call gives a list of valid filterEntityTypes.

cursor

When making subsequent calls to retrieve additional results, this is the cursor returned by the last call to this method.

limit

The maximum number of items to return. Must be a positive integer. If not set, the server will provide a service-specific maximum limit.

For example, in the Workload Optimization Manager user interface, you can search for the BussinessApplication entity named "App [app]". If you set the scope to that business application, then you can click in the Supply Chain to select the Namespace entity. Find the **Entity Information** chart and copy the ID value. That is the uuid for the app Namespace. If you get the leaf entities for that Namespace, you can see all the Service, ApplicationComponent, and BusinessApplication entities that support the Workload Optimization Manager application. For example, the following Service entry is for the Hyper-V target component:

```
{
  "uuid": "74626820648480",
  "displayName": "Service-app/mediation-hyperv",
  "className": "Service"
}
```

Now assume you want to use a VM group as the seeded scope, and you want to exclude any Service entities or higher in the Supply Chain:

Example: GET https://10.10.168.102/api/v3/supplychains/leafEntities?uuids=74626820647952&filterEntityTypes=Service

```
{
    "uuid": "74699295824896",
    "displayName": "App-app/cost-67b7b9bb4d-bl8kt/cost",
    "className": "Application Component"
},
{
    "uuid": "74699295824908",
```



```
"displayName": "App-app/mediation-vmax-6cd7f4ff-nzqp6/mediation-vmax",
    "className": "Application Component"
},
{
    "uuid": "74699295824897",
    "displayName": "App-app/mediation-azurebilling-c585c846f-mvnl7/mediation-azurebilling",
    "className": "Application Component"
},
...
```

Getting Statistics for a Supply Chain

Gets a list of statistics filtered by a user-created SupplyChainStatsApilnputDTO. For more information about the criteria that make up the input for this request, see the Swagger documentation for this request, located at /swagger/external/index.html">https://cyour_Workload-Optimization-Manager_IP>/swagger/external/index.html.

Example: POST https://10.10.168.102/api/v3/supplychains/stats

Example Input: This input will return the number of applications running on the specified UUID (in this case, a Datacenter):

```
{
   "uuids": [
     "e27e5c2f85d91107ac3f26fd63d4478e808f590b"
],
   "types": [
     "Application"
],
   "environmentType": "ONPREM"
}
```

Response: A list of StatSnapshotApiDTOs representing the filtered statistics for the entity:

Tags Endpoint

Tags Overview

Tags are metadata attached to resources that you can use to organize your environment. Tags are most often used to delineate resource groupings for technical, automation, business, or security purposes.



Workload Optimization Manager discovers tags for AWS, Azure, and vCenter resources.

Using the tags endpoint, you can:

- Get a list of available tags
- Get the members belonging to a specified tag

Additionally, you can use the tags-related requests in the entities endpoint to:

- Assign a tag to an entity
- Delete all tags or a single tag associated to an entity

Tags Requests

Pagination for Tags Requests

When you request tag data, the API uses pagination to return subsets of the data. You should always use pagination when available to make sure you get your data in manageable chunks. To paginate returned data, the limit, orderBy, and cursor parameters control how the APIs paginate their data. If you do not specify a limit for the following requests, the API will paginate the data to a default limit of records:

- GET /tags
- GET /tags/<tagKey>/entities

If your scripts make these requests without setting a limit, you should be sure they check for a pagination cursor in the returned data.

For general information about pagination, see Pagination in the Workload Optimization Manager API (on page 742).

Getting Tags

For a list of tags, the API returns a list of TagApiDTOs. Each TagApiDTO will contain the key/value pair of the tag. The key can be used to see the entities belonging to the tag.

Example: https://10.10.10.10/api/v3/tags

Response:

Filtering Tags by Scope, Entity, and Environment

Gets a filtered list of tags for the specified scope, entity type, and/or environment. For example, you can use this to find tags only in a particular cluster, tags that affect at least one VM, and/or limit your result to only cloud entities. This request accepts the following parameters:

scopes



A list of UUIDs representing the scope of the request. For example, providing Market as a scope will search the entire real-time market. If you provide the UUID of a host, only entities on that host would be in the response.

- entity_type
 - APPLICATION
 - APPLICATION_SERVER
 - BUSINESS_ACCOUNT
 - BUSINESS_UNIT
 - CHASSIS
 - CLOUD SERVICE
 - CONTAINER
 - CONTAINER POD
 - DATABASE
 - DATABASE_SERVER
 - DATACENTER
 - DISK_ARRAY
 - DPOD
 - IO_MODULE
 - LOAD_BALANCER
 - LOGICAL_POOL
 - NETWORK
 - PHYSICAL_MACHINE
 - STORAGE
 - STORAGE_CONTROLLER
 - SWITCH
 - VIRTUAL_APPLICATION
 - VIRTUAL_DATACENTER
 - VIRTUAL_MACHINE
 - VPOD
- environment_type

Returns only tags from entities in the specified environment type. [Cloud, Hybrid, Onprem]

Example: GET https://10.10.10.10.10/api/v3/tags?
scopes=Market&entity_type=VirtualMachine&environment_type=ONPREM

Response: a list of VMs running on-premises in the real-time market with tags.

Getting Entities For A Specified Tag

Referenced Endpoint: Entities (on page 791)

Gets a list of entities that have the specified tag. An entity is any device in your environment that Workload Optimization Manager manages, such as applications, physical machines, VMs, storage, and datacenters.. You can use this information to see where entities with the specified tag are located, what other tags are associated to those entities, and detailed information about each entity.

Example: GET https://10.10.10.10/api/v3/tags/owner/entities

Response: A list of entities that have the tag owner:

```
[
{
    "links":[
        {
            "rel":"self",
            "href":"https://10.10.10.10/api/v3/entities/azure::VM::375ddfb4-3127-44eb-9088-3c7645212f81?inclu
de_aspects=false"
     }
}
```



```
],
    "uuid": "azure:: VM:: 375ddfb4-3127-44eb-9088-3c7645212f81",
    "displayName": "oleg-westus2-unmanaged-std",
    "className": "VirtualMachine",
    "priceIndex": 3.2109845,
    "state": "ACTIVE",
    "severity": "Normal",
    "costPrice":0.024,
    "discoveredBy":{
      "uuid":"_GLpj4JwIEei_xJ5Ai6-rnQ",
      "displayName": "mycorp.management.core.windows.net",
      "type": "Azure"
   },
    "remoteId": "azure::VM::375ddfb4-3127-44eb-9088-3c7645212f81",
    "template":{
      "uuid": "azure:: VMPROFILE:: Basic_A0",
      "displayName": "Basic_A0",
      "discovered":false
   },
    "environmentType": "CLOUD",
    "tags":{
      "owner":[
        "PT_Azure"
      ],
      "AutoSuspend":[
        "false"
      ]
    }
 },
    "links":[
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/entities/azure::VM::c94e96bf-975e-47da-8c52-7ac90161cc87?inclu
de_aspects=false"
    ],
    "uuid": "azure:: VM:: c94e96bf-975e-47da-8c52-7ac90161cc87",
    "displayName": "oleg-westus2-managed-avail-set-1",
    "className": "VirtualMachine",
    "priceIndex": 2.446491,
    "state": "ACTIVE",
    "severity": "Normal",
    "costPrice":0.018,
    "discoveredBy":{
      "uuid": "_GLpj4JwIEei_xJ5Ai6-rnQ",
      "displayName": "mycorp.management.core.windows.net",
      "type": "Azure"
   },
    "remoteId": "azure::VM::c94e96bf-975e-47da-8c52-7ac90161cc87",
    "template":{
      "uuid": "azure::VMPROFILE::Standard_B1s",
      "displayName": "Standard_B1s",
      "discovered":false
```



```
},
  "environmentType":"CLOUD",
  "tags":{
      "owner":[
            "PT_Azure"
      ],
      "AutoSuspend":[
            "false"
      ]
    }
}
```

Targets Endpoint

A target is a service that performs management functions in your virtual environment. Workload Optimization Manager uses targets to monitor workload and to execute actions in your environment.

To discover entities in your environment, you add different targets to your Workload Optimization Manager installation. Workload Optimization Manager then uses these targets to collect data from your environment.

Workload Optimization Manager uses probes to connect to targets and discover their entities. The Workload Optimization Manager GUI provides forms for users to specify different target instances. Note that each probe may require different settings, and it's possible that different versions of Workload Optimization Manager supports different sets of probes.

For complete target information, review <u>Target Configuration (on page 135)</u>. You should not modify targets without a full understanding of how they interact with Workload Optimization Manager.

Using the targets endpoint of the Workload Optimization Manager API, you can:

- Get a single target or list of targets present in your environment
- Get a list of probes available in your Workload Optimization Manager installation
- Get the actions or statistics for a target
- Get the workflows discovered by a target
- Add or edit a target
- Trigger validation or rediscovery on a target
- Delete a target

Targets Utility Requests

Utility requests provide metadata that you can use to make related requests, assemble inputDTOs, or see the potential values of a particular DTO.

The targets endpoint contains a utility request called specs that shows the information required for probe registry for each target available to Workload Optimization Manager, including required input fields and expected target type and category values.

NOTE:

For a list of probes available to your specific Workload Optimization Manager installation, review your organization's licensing agreement.

Example: GET https://10.10.10.10/api/v3/targets/specs

Response: An array of TargetApiDTO objects, where each object contains an array of input fields. This example shows one entry for the JVM probe in the Application Server category.

[



```
{
     "category": "Application Server",
     "identifyingFields":[
       "nameOrAddress"
     ],
     "inputFields":[
         "displayName": "Scope/Address",
         "name": "nameOrAddress",
         "isMandatory":true,
         "isSecret":false,
         "valueType": "GROUP_SCOPE",
         "description": "The group of VMs or the address of the JVM server"
       },
         "displayName": "Port Number",
         "name": "targetPort",
         "defaultValue": "1099",
         "isMandatory":true,
         "isSecret":false,
         "valueType": "NUMERIC",
         "description": "The JMX port that connects with the JVM server"
       },
         "displayName": "Username",
         "name": "username",
         "isMandatory":true,
         "isSecret":false,
         "valueType": "STRING",
         "description": The JVM server JMX password, enter a space if the server has no security"
         "displayName": "Password",
         "name": "password",
         "isMandatory":true,
         "isSecret":true,
         "valueType": "STRING",
         "description": The JVM server JMX port, enter a space if the server has no security"
       }
     ],
     "type":"JVM"
   },
```

]



Targets Requests

Target requests handle creation, configuration, validation, rediscovery, and deletion of targets on your Workload Optimization Manager appliance.

Pagination for Targets Requests

When you request target entities, the API uses pagination to return subsets of the data. You should always use pagination when available to make sure you get your data in manageable chunks. To paginate returned data, the limit, orderBy, and cursor parameters control how the APIs paginate their data.

If you do not specify a limit for the GET /targets/<targetId>/entities request, the API will paginate the data to a default limit of records. If your script makes this request without setting a limit, you should be sure it checks for a pagination cursor in the returned data.

For general information about pagination, see Pagination in the Workload Optimization Manager API (on page 742).

Getting Targets

For a list of targets, the API returns an array of TargetApiDTO objects. Each TargetApiDTO object will contain the validation status, target type and category, and input field names and values. To get a single target, include the UUID of the target in the request.

This request takes the following parameters:

environment_type

Returns only targets in the specified environment type. [Cloud, Hybrid, Onprem]

Examples:

- All Targets: GET https://10.10.10.10/api/v3/targets
- Single Target: GET https://10.10.10.10/api/v3/targets/__xwWYAE33eku7PbzHdETIA

Response: A single entry in an array of targets. Notice that the password field is secret, so the response does not contain the password value.

```
"uuid": "__xwWYAE33eku7PbzHdETIA",
"category": "Hypervisor",
"type": "vCenter",
"status": "Validated",
"lastValidated": "2018-06-26T14:25:08-04:00",
"inputFields":[
  {
    "displayName": "Address",
    "name": "address",
    "value": "vsphere-demo.mycorp.com",
    "isMandatory":true,
    "isSecret":false,
    "valueType": "STRING",
    "description": "IP or address of vCenter Server",
    "verificationRegex": ".*"
 },
    "displayName": "Username",
    "name": "username",
    "value": "corp\\my.user",
    "isMandatory":true,
    "isSecret":false,
```



```
"valueType":"STRING",
  "description":"User name to use to connect to a target",
  "verificationRegex":".*"
},
{
  "displayName":"Password",
  "name":"password",
  "isMandatory":true,
  "isSecret":true,
  "valueType":"STRING",
  "description":"Password to use to connect to a target",
  "verificationRegex":".*"
}
```

Adding a Target

Adds a target to your Workload Optimization Manager installation. You must pass a completed TargetApiDTO object as an inputDTO. For more information about the required fields of the TargetApiDTO for the target you want to add, execute the /targets/specs utility request.

Example: POST https://10.10.10.10/api/v3/targets

Example inputDTO:

Rediscover or Validate All Targets

Manually triggers a full rediscovery or validation of all targets in your environment. This is often done to immediately see multiple changes that would normally not be reflected until a daily full discovery is performed, such as displaying updated Orchestrator workflows.

This call takes the following parameters:

- validate
 - When true, validates all targets in your environment
- rediscover



When true, performs a full rediscovery on all targets in your environment

Examples:

Rediscovery:

```
POST https://10.10.10.10/api/v3/targets?validate=true
```

Validation:

```
POST https://10.10.10.10/api/v3/targets?rediscover=true
```

Rediscover or Validate A Single Target

Manually triggers a full rediscovery or validation of a single target in your environment. This is often done to immediately see a change that would normally not be reflected until a daily full discovery is performed, such as displaying updated Orchestrator workflows.

This call takes the following parameters:

validate

When true, validates the specified target

rediscover

When true, performs a full rediscovery on the specified target

Examples:

- Rediscovery: https://10.10.10.10/api/v3/targets/__xwWYAE33eku7PbzHdETIA?rediscover=true
- Validation: https://10.10.10.10/api/v3/targets/__xwWYAE33eku7PbzHdETIA?validate=true

Response: The TargetApiDTO object of the specified target:

Editing Target Input Fields

Edits the input fields of an existing target, and accepts the modified TargetApiDTO as input.

NOTE: You can GET the target first using the GET /targets/specs to see the fields required for that target. Note that you must pass all input fields in the modified TargetApiDTO object.

Example: PUT https://10.10.10.10/api/v3/targets/_HgzQ4CdCEeaUWYEyo3vsyw

Example input, editing the username for a single target:



```
"name": "address",
        "value": "vsphere.mycorp.com",
        "isMandatory":true,
        "isSecret":false,
        "valueType": "STRING"
      },
      {
        "displayName": "Username",
        "name": "username",
        "value": "corp\\my.name.changed",
        "isMandatory":true,
        "isSecret":false,
        "valueType": "STRING"
      },
      {
        "displayName": "Password",
        "name": "password",
        "value": "Octopath",
        "isMandatory":true,
        "isSecret":true
      }
 }
]
```

Deleting a Target

Deletes the specified target and removes all entities managed by that target. This will also remove any pending actions related to the deleted target.

Example: DELETE https://10.10.10.10/api/v3/targets/__xwWYAE3EeiNKPbzHdETIA

Response: A successful deletion request returns a Response Code of 200.

Actions For a Specified Target

Referenced Endpoint: Actions (on page 753)

These requests get full or filtered lists of actions per target for use in reports, or to find a particular action.

NOTE: Once you have the action UUID, you can use requests from the actions endpoint to post changes to that action.

Getting an Unfiltered Array of Actions

Gets a list of current actions in your environment associated to entities discovered by the specified target.

Example: GET https://10.10.10.10/api/v3/targets/__xwWYAE3EeiNKPbzHdETIA/actions

Getting a Filtered Array of Actions

Gets a filtered list of actions discovered by a single target. Pass an inputDTO containing one or more of the following criteria:

- actionModeList
 - DISABLED:

Do not recommend or perform the action. When you disable an action, the user interface will no longer display actions of that type.

- RECOMMENDED:

Recommend the action so a user can execute it via the given hypervisor or by other external means

– MANUAL:



Recommend the action, and provide the option to execute that action through the Workload Optimization Manager user interface or an /actions API request.

AUTOMATED:

You have directed Workload Optimization Manager to execute the action automatically.

– COLLECTION (UNUSED):

Legacy action mode, no longer used.

actionStateList

- DISABLED:

An action whose policy has been disabled.

- RECOMMEND:

An action that cannot be automated due to policy settings or must be executed outside the system, such as the purchase of hardware.

PENDING ACCEPT:

When the action mode is set to manual, a recommended action that has not been accepted or cleared.

ACCEPTED

An action that has been accepted, but is not yet in progress.

- IN_PROGRESS:

An action that is being executed.

SUCCEEDED:

An action that was accepted and completed successfully.

- FAILED:

An action that was accepted and did not complete successfully.

- REJECTED:

When the action mode is set to manual, an action that has been rejected by the user.

CLEARED:

When the action mode is set to manual, an action that is no longer recommended by the market.

- ACCOUNTING:

For cloud entities, an action to resize in order to use a different instance template.

- QUEUED:

When more than 10 actions are to be executed for a single target, Workload Optimization Manager will place the 11th and all subsequent actions into a QUEUED state, and they will execute as the previous actions complete.

actionTypeList

- START:

Start an entity, and add it to the Workload Optimization Manager market.

MOVE:

Move an entity from one provider to another. For example, moving a VM between hosts, or a datastore between disk arrays.

- SUSPEND:

Suspend the entity to exclude its capacity from your environment. Suspend does not remove the entity from your environment, but the market does not include the entity in its analysis. Based on market conditions, analysis can recommend restarting suspended entities, which includes them in market analysis once again.

ADD PROVIDER:

This is equivalent to the START action, but for storage entities.

CHANGE:

Move a virtual machine's storage between datastores.

- PROVISION:

Add capacity to your environment.



RECONFIGURE:

Analysis recommends this when a VM is not able to correct a misconfiguration via another type of action. For example, analysis can recommend a RECONFIGURE action when a placement policy requires a VM to move to a host on a particular cluster, but cross-cluster moves are not permitted.

DELETE:

This is equivalent to the SUSPEND action, but for storage entities.

RESERVE ON PM:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular host.

- RESERVE_ON_DS:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular datastore.

- RESIZE_FOR_EFFICIENCY:

A resize that reduces the capacity of a commodity, such as vCPU, or vMEM.

- RESIZE FOR PERFORMANCE:

A resize that increases the capacity of a commodity, such as vCPU, or vMEM.

cleared

Default: false.

When true, actions that were removed from the action list before being executed will be returned.

costType

- Saving

An action that will decrease cloud spending.

Investment

An action that will increase cloud spending.

cumulative

Default: false.

When true, shows the savings for each action in a scope as a cumulative total, rather than showing the savings for individual actions.

environmentType

ONPREM:

Returns only actions related to entities that are part of your on-premises environment.

- CLOUD:

Returns only actions related to entities that are part of your cloud environment.

■ groupBy

You may group the actions returned by the following criteria: [actionModes, actionStates, actionTypes, risk, riskSeverity, riskSubCategory]

hasReservedInstance

Default: false.

When true, only actions that are related to reserved instances will be returned.

relatedEntityTypes

Returns only actions related to entities of these types within the scope. For example, if your scope is a virtual datacenter and you specify VirtualMachine as a related entity type, the request will include only those actions related to VMs in the specified virtual datacenter.

Choose from the following entity types: [Datacenter, PhysicalMachine, VirtualMachine, Storage, Application, Chassis, DiskArray, IOModule, StorageControl, Switch, VirtualDataCenter, VPod, DPod, Container, Database, DatabaseServerContainer, LogicalPool]

riskSeverityList

Returns only actions of the given severities: [Unknown, Normal, Minor, Major, Critical]

riskSubCategoryList



returns only actions of the given subcategories: [Performance Assurance, Efficiency Improvement, Prevention, Compliance]

Example: POST https://10.10.10.10/api/v3/targets/__xwWYAE3EeiNKPbzHdETIA/actions Example inputDto, filtering for actions that are pending acceptance:

```
{
   "actionStateList":[
     "PENDING_ACCEPT"
]
}
```

Response: An array of actions applicable to the specified target that are in the PENDING_ACCEPT state.

```
[
    "links":[
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/actions/_uictIJuHEeics6ASgJ-kdg"
      },
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/actions/2204259249360"
      }
    ],
    "uuid": "_uictIJuHEeics6ASgJ-kdg",
    "createTime":"2018-08-08T23:53:08-04:00",
    "actionType": "RIGHT_SIZE",
    "actionState": "PENDING_ACCEPT",
    "actionMode": "MANUAL",
    "details": "Scale down VMem for VirtualMachine btc-1 from 8 GB to 7 GB",
    "importance":0,
    "target":{
      "uuid": "4223dcd6-0b28-6ae6-1066-689912ced3a1",
      "displayName": "btc-1",
      "className": "VirtualMachine",
      "aspects":{
        "virtualMachineAspect":{
          "os": "Other Linux (64-bit)",
          "connectedNetworks":[
              "uuid": "74c91ba4fa390030f47f91e6e1ee77ff7b4db353",
              "displayName": "VM Network"
          ],
          "numVCPUs":1,
          "ebsOptimized":false
        }
      },
      "environmentType": "ONPREM"
    },
    "currentEntity":{
      "uuid": "_ui4yAZuHEeics6ASgJ-kdg",
```



```
"className": "VMem"
  },
  "newEntity":{
    "uuid": "_ui4yA5uHEeics6ASgJ-kdg",
    "className": "VMem"
  },
  "currentValue": "8388608.0",
  "newValue": "7340032.0",
  "resizeToValue": "7340032.0",
  "risk":{
    "uuid": "_ujB78ZuHEeics6ASgJ-kdg",
    "subCategory": "Efficiency Improvement",
    "description": "Underutilized VMem in Virtual Machine 'btc-1'",
    "severity": "MINOR",
    "reasonCommodity": "VMem",
    "importance":0
  },
  "stats":[
    {
      "name": "costPrice",
      "filters":[
          "type": "savingsType",
          "value": "savings"
      ],
      "units": "$",
      "value":50
    }
  ],
  "actionID":2204259249360
},
}
```

Entities For a Specified Target

Referenced Endpoint: Entities (on page 791)

Gets a list of entities discovered by the specified target. This is used most often for reporting, dashboard, or inventory purposes.

Getting An Array of Entities

]

Gets a list of all entities discovered by the specified target. An entity is any device in your environment that Workload Optimization Manager manages, such as applications, physical machines, VMs, storage, and datacenters.

Example:GET https://10.10.10.10/api/v3/targets/__xwWYAE3EeiNKPbzHdETIA/actions

Response: An array of EntityApiDTO objects belonging to a vCenter target:



```
"href": "https://10.10.10.10/api/v3/entities/vsphere-mycorp.com-ResourcePool-resgroup-8?include_a
spects=false"
    ],
    "uuid": "vsphere-mycorp.com-ResourcePool-resgroup-8",
    "displayName": "Resources-Cluster1",
    "className": "VirtualDataCenter",
    "priceIndex":1e-12,
    "state": "ACTIVE",
    "severity": "Normal",
    "discoveredBy":{
      "uuid":"__xwWYAE3EeiNKPbzHdETIA",
      "displayName": "vsphere-mycorp.com",
      "type": "vCenter"
    },
    "remoteId": "resgroup-8",
    "environmentType": "ONPREM"
  },
    "links":[
      {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/entities/vsphere-mycorp.com-GuestLo
ad-421ddc94-8d0c-504a-62f5-493802e96d0a?include_aspects=false"
    ],
    "uuid": "vsphere-mycorp.com-GuestLoad-421ddc94-8d0c-504a-62f5-493802e96d0a",
    "displayName": "GuestLoad[Nexus1000V]",
    "className": "Application",
    "priceIndex":1,
    "state": "ACTIVE",
    "severity": "Normal",
    "discoveredBy":{
      "uuid": "__xwWYAE3EeiNKPbzHdETIA",
      "displayName": "vsphere-mycorp.com",
      "type": "vCenter"
    },
    "remoteId": "vm-51",
    "environmentType": "ONPREM"
  },
  }
```

Templates Endpoint

Workload Optimization Manager uses templates to reserve resources and deploy workload in your environment, to calculate supply or demand changes in a plan, and to calculate workloads for cloud environments.

Using the templates endpoint, you can:

- Get a list of templates available to your Workload Optimization Manager appliance
- Get information needed to create templates, such as supported OSes and CPUs



- Create a template
- Edit and Delete templates

Templates Utility Requests

Utility requests provide metadata that you can use to make related requests, assemble inputDTOs, or see the potential values of a particular DTO.

The templates endpoint contains utility requests that show the possible values for several optional fields used to create detailed templates. These can be used to find the supported cloud OSes and CPU models.

Getting a List of CPU Models

Gets a list of valid CPU Models. If given a CPU Model, Workload Optimization Manager can more accurately reflect your CPU capacity in market decisions.

Example: GET https://10.10.10.10/api/v3/templates/physicalmachine/cpumodels

Result: A list of CpuModelApiDTOs, describing the cores, speed, and internal scaling factor for each CPU. This information will be used to provide more granular CPU data, if passed as part of a TemplateApilnputDTO:

```
{
    "numCores": 4,
    "speed": 3500,
    "scalingFactor": 1.116909571123129,
    "modelName": "AMD A10 PRO-7800B"
 },
    "numCores": 4,
    "speed": 3700,
    "scalingFactor": 0.9745581799084503,
    "modelName": "AMD A10 PRO-7850B"
 },
   {
    "numCores": 8,
    "speed": 1415,
    "scalingFactor": 1.1638948014750774,
    "modelName": "UltraSPARC T2 Plus"
]
```

Templates Requests

Template requests handle creation, configuration, editing and deletion of templates on your Workload Optimization Manager appliance.

Getting a List of Templates

Gets a list of templates available to your Workload Optimization Manager instance. This list will include both templates discovered from underlying targets and those created through the Workload Optimization Manager UI. To get a specific template, pass the template UUID as part of the request.

Examples:

■ All Templates: GET https://10.10.10.10/api/v3/templates



■ Single Target: GET https://10.10.10.10/api/v3/templates/_v0Q70MpiEd-hypXfJzX8Wg Response: A list of TemplateApiDTOs:

```
[
    "links": [
     {
        "rel": "self",
        "href": "https://10.10.10.10/api/v3/templates/_v0Q70MpiEd-hypXfJzX8Wg"
      }
    ],
    "uuid": "_v0Q70MpiEd-hypXfJzX8Wg",
    "displayName": "Small",
    "className": "PhysicalMachineProfile",
    "price": 5000,
    "computeResources": [
        "stats": [
            "name": "numOfCores",
            "value": 4
          },
            "name": "cpuSpeed",
            "units": "MHz",
            "value": 2992
          },
            "name": "ioThroughputSize",
            "units": "MB/s",
            "value": 890
            "name": "memorySize",
            "units": "MB",
            "value": 32759
          },
            "name": "networkThroughputSize",
            "units": "MB/s",
            "value": 512
        ]
      }
    ],
    "infrastructureResources": [
      {
        "stats": [
          {
            "name": "powerSize",
            "value": 1
          },
          {
            "name": "spaceSize",
```



```
"value": 1
        },
          "name": "coolingSize",
          "value": 1
    }
  ],
  "discovered": false
},
  "links": [
      "rel": "self",
      "href": "https://10.10.10.10/api/v3/templates/_v0Q70cpiEd-hypXfJzX8Wg"
   }
  ],
  "uuid": "_v0Q70cpiEd-hypXfJzX8Wg",
  "displayName": "Medium",
  "className": "PhysicalMachineProfile",
  "price": 10000,
  "computeResources": [
    {
      "stats": [
          "name": "numOfCores",
          "value": 4
        },
          "name": "cpuSpeed",
          "units": "MHz",
          "value": 2992
        },
        {
          "name": "ioThroughputSize",
          "units": "MB/s",
          "value": 1780
        },
          "name": "memorySize",
          "units": "MB",
          "value": 65519
        },
          "name": "networkThroughputSize",
          "units": "MB/s",
          "value": 512
      ]
    }
  ],
  "infrastructureResources": [
    {
```



```
"stats": [
          {
            "name": "powerSize",
            "value": 1
          },
            "name": "spaceSize",
            "value": 1
          },
             "name": "coolingSize",
            "value": 1
        ]
      }
    ],
    "discovered": false
  },
]
```

Creating a Template

Creates a template for use in your environment. You must pass a completed TemplateApilnputDTO as the inputDTO. You can create templates for virtual machines, physical machines, storage, and containers.

Example: POST https://10.10.10.10/api/v3/templates

Example inputs:

Container



Physical Machine

```
"cpuModel": "AMD A10-5700",
"computeResources":[
  {
    "stats":[
        "name": "ioThroughputSize",
        "value":1000
      },
        "name": "networkThroughputSize",
        "value":1000
      },
        "name": "memorySize",
        "value":8192
      },
        "name": "numOfCores",
        "value":4
      },
        "name": "cpuSpeed",
        "value":"3400"
    ]
  }
],
"price":0,
"className": "PhysicalMachineProfile",
"displayName": "HostTemplate1"
```

■ Storage

{



Virtual Machine

```
"computeResources":[
   "stats":[
        "name": "ioThroughput",
        "value":0
      },
        "name": "networkThroughput",
        "value":500
        "name": "memorySize",
        "value":4096
      },
        "name": "memoryConsumedFactor",
        "value":70
        "name": "numOfCpu",
        "value":2
        "name": "cpuSpeed",
        "value":1024
        "name": "cpuConsumedFactor",
        "value":75
      }
```



```
]
    }
  "storageResources":[
      "type": "disk",
      "stats":[
          "name": "diskIops",
          "value":50
        },
          "name":"diskSize",
          "value":20
        },
          "name": "diskConsumedFactor",
          "value":70
      ]
 ]
}
```

Response: The TemplateApiInputDTO for the template created. In this case, a virtual machine template:

```
"uuid": "_lmaQoLUtEei5nORDMStFGA",
"displayName": "VirtualMachineTemplate1",
"className": "VirtualMachineProfile",
"computeResources":[
    "stats":[
        "name": "numOfCpu",
        "value":2.0
        "name": "cpuSpeed",
        "units": "MHz",
        "value":1024.0
        "name": "cpuConsumedFactor",
        "units":"%",
        "value":75.0
      },
        "name": "memorySize",
        "units": "MB",
        "value":4096.0
      },
        "name": "memoryConsumedFactor",
```



```
"units":"%",
        "value":70.0
      },
        "name": "ioThroughput",
        "units": "MB/s",
        "value":0.0
      },
        "name": "networkThroughput",
        "units": "MB/s",
        "value":500.0
    ]
  }
],
"storageResources":[
  {
    "stats":[
      {
        "name": "diskIops",
        "value":50.0
        "name": "diskSize",
        "units": "GB",
        "value":20.0
      },
        "name": "diskConsumedFactor",
        "units":"%",
        "value":70.0
      }
    ],
    "type":"disk"
],
"deploymentProfile":{
  "uuid":"_llbZMrUtEei5nORDMStFGA",
  "displayName": "VirtualMachineTemplatel_DeploymentProfile",
  "className": "ServiceCatalogItem",
  "deployParameters":[
      "targetType":"vCenter",
      "providers":[
        {
          "provider":{
            "uuid": "dfe657268310d8b128d441b2a34ec0721e72ee7e",
            "displayName": "Development DC7",
            "className": "DataCenter",
            "discoveredBy":{
              "uuid":"_OjF3UJwFEei_xJ5Ai6-rnQ",
              "displayName": "vsphere-dc7.mycorp.com",
              "type": "vCenter"
```



Editing a Template

Edits a user-created template, given the template UUID and the edited DTO. To edit discovered templates, edit them on the target from which they originate. Note that you must pass a complete TemplateApiDTO with the edited fields.

Example: PUT https://10.10.10.10/api/v3/templates/_lmaQoLUtEei5nORDMStFGA

Example input: Note that both the displayName and diskConsumedFactor values were changed:

```
"computeResources":[
    "stats":[
      {
        "name": "ioThroughput",
        "value":0
      },
        "name": "networkThroughput",
        "value":500
      },
        "name": "memorySize",
        "value":4096
        "name": "memoryConsumedFactor",
        "value":70
      },
        "name": "numOfCpu",
        "value":2
```



```
"name": "cpuSpeed",
        "value":1024
      },
        "name": "cpuConsumedFactor",
        "value":75
    ]
  }
],
"storageResources":[
    "type": "disk",
    "stats":[
        "name": "diskIops",
        "value":50
      },
        "name": "diskSize",
        "value":20
      },
        "name": "diskConsumedFactor",
        "value":75
    ]
  }
],
"className": "VirtualMachineProfile",
"displayName": "VirtualMachineTemplate1_Modified",
"deploymentProfileId": "_llbZMrUtEei5nORDMStFGA"
```

Response: The modified TemplateApiDTO reflecting the submitted changes.

Deleting a Template

Deletes the specified template. This will not delete associated deployment profiles, and deployments already scheduled to use this template will not succeed.

Example: DELETE https://10.10.10.10/api/v3/templates/_lmaQoLUtEei5nORDMStFGA

Response: A successful deletion will return true.

Topology Definitions Endpoint

Workload Optimization Manager gives you the ability to create your own Business Applications, Business Transactions, and Services without the need to ingest additional application data into the Workload Optimization Manager platform. This is especially useful in cases where there are gaps in the application stack shown in the Workload Optimization Manager supply chain. For example, in the absence of an application monitoring target such as AppDynamics or Dynatrace, you will not see Business Applications in your supply chain. This feature addresses those gaps.

When you create a new application entity, you identify interrelated application entities and nodes in your existing environment for which you want to measure performance, so Workload Optimization Manager can link them in a supply chain and represent



them as a unified group. You can monitor overall performance for the group in the context of the new application entity, and drill down to the individual entities and nodes for finer details.

Using the topology definitions endpoint of the Workload Optimization Manager API, you can:

- Get a single topology definition or list of topology definitions present in your environment
- Create a topology definition
- Edit a topology definition
- Delete a topology definition

Topology Definition Requests

Topology definition requests handle creation, configuration, editing, and deletion of topology definitions on your Workload Optimization Manager appliance.

Getting Topology Definitions

For a list of topology definitions, the API returns an array of TopologyDataDefinitionApiDTO. Each TopologyDataDefinitionApiDTO will contain the UUID, entity type, and connection attributes for the defined topology. To get a single topology definition, include the UUID of the topology definition in the request.

Examples:

- All Topology Definitions: GET https://10.10.10.10/api/v3/topologydefinitions
- Single Topology Definition: GET https://10.10.10.10/api/v3/topologydefinitions/284711321829968

Response:

```
{
  "uuid":"284711313871856",
  "displayName":"Daltest1__App",
  "entityType":"BusinessApplication",
  "entityDefinitionData":{
      "namePrefix":"Daltest1_",
      "entityType":"VirtualMachine",
      "generationAndConnectionAttribute":{
            "expVal":"App",
            "expType":"EQ",
            "filterType":"virtualMachinesByTag",
            "caseSensitive":true,
            "entityType":null,
            "singleLine":false
      }
    }
}
```

Creating a Manual Topology Definition

To create a manual topology definition, you must provide the entityType of the definition, and manual mapping data to the entities to use. Consider the following input DTO to create a manual topology definition:

```
{
  "entityType":"BusinessApplication",
  "entityDefinitionData":{
    "manualConnectionData":{
    "BusinessTransaction":{
        "staticConnections":[
        "73585155548499",
```



```
"73585155548500"
      ]
   },
    "Service":{
      "staticConnections":[
        "73585155548487",
        "73585155608929"
      ]
   },
    "ApplicationComponent":{
      "staticConnections":[
        "73596151905427",
        "73596151905425",
        "73596151905428",
        "73596151905429"
      ]
   },
    "VirtualMachine":{
      "staticConnections":[
        "73586657216608",
        "73585300874097",
        "73586657216576"
      ]
   },
    "DatabaseServer":{
      "staticConnections":[
        "73585314633044",
        "73585314632869",
        "73585314632946"
      ]
   },
    "Container":{
      "staticConnections":[
        "73585323455544",
        "73582124234229",
        "73585385438946"
      ]
   },
    "ContainerPod":{
      "staticConnections":[
        "73585334243044",
        "73585314324535",
        "73585314533256"
      ]
    }
 }
"displayName": "DalManualtest_"
```

In the manualConnectionData parameter of the entityDefinitionData, the UUIDs of the related entities have been provided for each level of the supply chain for which the topology should be instantiated.

The creation can be as simple or complex as desired. For example, a simple manual topology may look like the following:



```
"entityType": "BusinessTransaction",
"entityDefinitionData":{
  "manualConnectionData":{
    "Service":{
      "staticConnections":[
        "73585155548487"
      ]
    },
    "Container":{
      "staticConnections":[
        "73596151905298"
      1
    }
  }
},
"uuid": "284711514573216",
"displayName": "DalManualSimple"
```

Creating an Automated Topology Definition

To create an automated topology definition, you must provide the entityType of the definition, and the data that makes up the regular expression used to determine dynamic group membership. Consider the following input DTO to create an automated topology definition:

```
{
   "entityType":"BusinessApplication",
   "entityDefinitionData":{
        "entityType":"VirtualMachine",
        "namePrefix":"Daltest1_",
        "generationAndConnectionAttribute":{
            "expType":"EQ",
            "expVal":"App",
            "filterType":"vmsByTag",
            "caseSensitive":false
        }
    }
}
```

In the generationAndConnectionAttribute parameter of the entityDefinitionData, the information that makes up the regular expression is sent. In this instance, it will match any virtual machine whose tag value equals "App".

Editing a Topology Definition

Edits the input fields of an existing topology definition, and accepts the modified TopologyDataDefinitionApiDTO as input.

NOTE: You can GET the topology definition first using the GET /topologydefinition/UUID request to see the current configuration. Note that you must pass all fields in the modified TopologyDataDefinitionApiDTO, not only the changed fields.

A successful edit will return the modified TopologyDataDefinitionApiDTO.

Example: PUT https://10.10.10.10/api/v3/topologydefinitions



Deleting a Topology Definition

Deletes the specified topology definition and removes all created entities. This will also remove any pending actions related to the deleted entities.

Example: DELETE https://10.10.10.10/api/v3/topologydefinitions/284711321829968

Response: A successful deletion request returns a Response Code of 200.

Workflows Endpoint

When added to your Workload Optimization Manager installation, Orchestrator targets assign workflows that execute multiple actions to make changes in your environment. Workload Optimization Manager discovers workflows that you have defined on the orchestrator. You can then set up an automation policy that maps workflows to actions. If the action mode is Manual or Automatic, then when Workload Optimization Manager recommends the action, it will direct the orchestrator to use the mapped workflow to execute it.

For more information about specific Orchestrator targets, see <u>Orchestrator Targets (on page 222)</u>. For more information about execution of workflows, see Action Orchestration (on page 688).

Using the workflows endpoint, you can:

- Get a list of all workflows
- Get detailed information about a specified workflow

Workflows Requests

Getting Workflows

For a list of workflows, the API returns an array of WorkflowApiDTOs. Each WorkflowApiDTO object will contain detailed information about that workflow, including description and parameters. To get a single workflow, include the UUID of the workflow in the request.

This call takes the following parameter:

type

Filters the request by type of workflow. [UCSD, AWS Service Catalog]

Examples:

- All Workflows: GET https://10.10.10.10/api/v3/workflows
- Single Workflow: GET https://10.10.10.10/api/v3/workflows/UCSD-WF-ucsd.eng.mycorp.com-103

Response:

```
{
   "links":[
      {
        "rel":"self",
        "href":"https://10.10.10.10/api/v3/workflows/UCSD-WF-ucsd.eng.mycorp.com-103"
    }
},
   "uuid":"UCSD-WF-ucsd.eng.mycorp.com-103",
   "displayName":"APIC Container Delete Firewall Rule Action",
   "className":"Workflow",
   "actionType":"NONE",
   "parameters":[
      {
            "name":"APIC_TENANT_L4L7_EPG_ACE_IDENTITY",
            "isMandatory":true,
```



```
"isSecret":false,
        "specificValueType": "ApicTenantL4L7EPGAceIdentity"
      },
      {
        "name": "L4L7Identity",
        "isMandatory":true,
        "isSecret":false,
        "specificValueType": "gen_text_input"
      },
      {
        "name": "ACLName",
        "isMandatory":true,
        "isSecret":false,
        "specificValueType": "gen_text_input"
      },
      {
        "name": "ACEName",
        "isMandatory":true,
        "isSecret":false,
        "specificValueType": "gen_text_input"
      }
    ],
    "discoveredBy":{
      "uuid": "___U1MIJv-Eei_xJ5Ai6-rnQ",
      "displayName": "ucsd.eng.mycorp.com",
      "type": "Cisco UCS Director"
    }
 ],
]
```

Getting Workflows of a Specific Type

By adding the type parameter to the /api/v3/workflows request, you can filter workflows from a specific source. For example, the response to this request will be an array of WorkflowApiDTOs discovered through UCS Director targets:

Example: GET https://10.10.10.10/api/v3/workflows?type=UCSD

Workload Optimization Manager Cookbook

Purpose

The Workload Optimization Manager cookbook is intended to assist in performing specific tasks using the API, and answering commonly-asked questions while presenting Workload Optimization Manager API best practices. This section of the API Guide is a living document, meaning that it is constantly being added to.

Cookbooks

Each cookbook contains one or more recipes. Each recipe will contain all the necessary information to complete the specified task, along with a basic script showing the functionality of the recipe.

Authenticating with the Workload Optimization Manager API (on page 1026)



- Plan Results Cookbook (on page 1028)
 - Seeing Changes to a Subset of Entities (on page 1029)

Authenticating With the API

Objective

To obtain an authentication token after logging in with the API, and use that token on subsequent API calls.

Authentication in the API

To use the API, you must have a valid user account on the Workload Optimization Manager instance. Also note that accounts can have different roles. The API will only execute commands that are valid for your user role. For example, to execute Workload Optimization Manager recommended actions, your account must have a role of either administrator, deployer, or automator.

To make API calls, you request an authentication token and pass it with each call to the Workload Optimization Manager API. The token request returns a cookie for your authentication. A common way to use this token is to store the cookie locally, and pass it with your API calls.

Example: curl -s -k -c /tmp/cookies -H 'accept: application/json' 'https://localhost/api/v3/login?hateoas=true' -d 'username=administrator&password=password'

Then, each request must use the -b cookie-filename parameter to use the session cookie delivered by the login request.

Another approach is to get the authentication header and parse out the authentication cookie. Then you can create a header for each API request that includes the cookie. For example, assume you store the value in a variable named token. You could use it like this:

```
headers = {'cookie': token}
r = requests.get('https://10.10.123.456/api/v3/targets/specs', headers=headers, verify=False, stream=True)
```

Prerequisites

In order to obtain an authentication token, you must have the following information:

- The IP address of the Workload Optimization Manager instance.
- The username and password of the user who will be logged in.

Procedure

To obtain an authentication token:

1. Construct the API payload.

The input body should be JSON, in the following format with your credentials in place of myUsername and myPassword:

```
{'username': 'myUsername', 'password': 'myPassword'}
```

Make the API request.

Use the POST https://[INSTANCE_IP]/api/v3/login request, with the input body constructed in the previous step.

3. Retrieve the authentication token from the response headers.

Example headers:

```
{
    'Server':'nginx',
```



```
'Date':'Mon, 01 Feb 2021 20:17:02 GMT',
'Content-Type':'application/json',
'Transfer-Encoding':'chunked',
'Connection':'keep-alive',
'Vary':'Accept-Encoding',
'Set-Cookie':'JSESSIONID=node0jzerbqte09pe1j29x6ypo92fh17.node0; Path=/; HTTPOnly; Secure',
'Expires':'Thu, 01 Jan 1970 00:00:00 GMT',
'X-Content-Type-Options':'nosniff',
'X-XSS-Protection':'1; mode=block',
'Strict-Transport-Security':'max-age=63072000; includeSubDomains',
'X-Frame-Options':'SAMEORIGIN',
'X-Turbo-Upstream':'API',
'Content-Encoding':'gzip'
}
```

The authentication token is the first ;-separated tocen in the value of the Set-Cookie header. In this example, it is JSESSIONID=node0jzerbqte09pe1j29x6ypo92fh17.node0.

Using the Authentication Token in Subsequent API Requests

Once you have obtained an authentication token, you can use that token to make further API requests. To do so, include a header in your request with the name of cookie and a value of the token. For example:

```
{'cookie': 'JSESSIONID=node0jzerbqte09pe1j29x6ypo92fh17.node0' }
```

Script Example

These listings show a function that gets the authentication token from the cookie, and a script that invokes the function and prints out the token value.

Function to get the token:

To invoke this function, pass the IP address, the username, and password as arguments. The function builds the authentication payload and requests the token from the given Workload Optimization Manager instance. It then parses out the first token in the Set-Cookie header and returns that value.

```
import json
import requests
import urllib3
urllib3.disable_warnings()

def get_cookie(ip, username, password):
  payload = {'username': username, 'password': password}
  r = requests.post(f'https://{ip}/api/v3/login', data=payload, verify=False)
  r.encoding = 'JSON'
  rh = r.headers
  token = rh['Set-Cookie'].split(';')[0]

return token
```

Script that calls the function:

Assume the script is saved as use_login.py. Also assume the function is in the file ./login.py. To invoke this script, open a shell at the script file location and enter:

```
./use-login.py <My_IP_Address> <My_Username> <My_Pwd>
```



where the three arguments are the IP address of your Workload Optimization Manager, your username, and your password, respectively. The script imports the ./login.py file and checks for four arguments (the script name and the three arguments you passed). It then executes the login.get_cookie() function. The function returns a token, which the script then prints out.

```
#!/usr/bin/env python3
import sys
import login

if len(sys.argv) != 4:
   print("Incorrect arguments list.")
   sys.exit()

token = login.get_cookie(sys.argv[1], sys.argv[2], sys.argv[3])
print(f'TOKEN IS: {token}')
```

Script Result

The result of this script displays the authentication token:

```
TOKEN IS: JSESSIONID=node0jzerbqte09pe1j29x6ypo92fh17.node0
```

Plan Results Cookbook

This cookbook explores plan markets in Workload Optimization Manager. Interpreting and parsing this plan market will enable you to better understand how and why Workload Optimization Manager has performed a certain action on a particular entity, how the resources- both used and available- have changed, and more as recipes are added to the cookbook.

NOTE: The Workload Optimization Manager UI has certain plan configuration options, available to present a base set of configuration changes to accomplish a particular goal. For example, the Add Workload plan is preconfigured to expect additional workloads to be provisioned. To see how Workload Optimization Manager creates these configurations, view the DTOs for the UI plan configurations at Scenario Examples (on page 912).

Related Endpoints

When interpreting plan results, the following endpoints are commonly used to retrieve and clarify data:

- Actions (on page 753): Retrieving the actions for the plan market will enable you to see what entities were directly affected during the run of the plan.
- Entities (on page 791): Retrieving the entities for the plan market will enable you to see a full listing of the entities involved in the plan.
- Groups (on page 819): Retrieving the groups for the plan market will enable you to more easily obtain UUID information for the entities in the specified group.
- Statistics (on page 973): Retrieving the market statistics for the plan market as a whole, a group, or an entity will enable you to easily see a broad overview of the state of the entity utilization after the plan has finished.

Use Case Index

The Plan Results Cookbook has the following recipes:

Seeing Changes to a Subset of Entities (on page 1029)



Seeing Changes to a Subset of Entities

Objective

After running a plan, you may want to see the effects of your plan on a particular entity or group of entities. This can help you better understand the effect your configuration changes would have on a subset of plan entities, or to explore why Workload Optimization Manager made specific action recommendations.

For example, assume that there is a virtual machine that shares dependencies with a number of other entities. Apart from the overal plan results, you might want to take a closer look at how the plan impacts this VM in particular.

Prerequisites

In order to investigate the changes to the specified entity, you need to know:

■ The UUID of a successfully completed plan market

To obtain this UUID, either get it from the API response sent when you POST a scenario to the market, or execute the GET /markets request, and find the market whose name corresponds with the name of the scenario. Alternately, you can find the scenario's UUID in the scenario parameter of the plan market. Verify that the state parameter has a value of SUCCEEDED. For example, the UUID of the scenario that created the following plan market is 214410933912976, and the UUID of the plan market itself is 214410933923968:

For cases where the same scenario has been applied to multiple plans, be sure to check the plan's runDate parameter corresponds to the time you expect the plan to have run.

For more information about creating and running scenarios, see Scenario DTO Breakdown (on page 900).

■ The UUID(s) of the entities you want to inspect

Entity UUIDs in a plan market are identical to their real-time market counterparts. This means you can get the UUIDs either from searching the plan market for a related field (for example, the displayName of the entity) or searching in the Workload Optimization Manager user interface to find the entity UUID.

You can also use the API's Search endpoint to search for entities by different criteria.

Related Endpoints

When interpreting plan results, the following endpoints are commonly used to retrieve and clarify data:

- Actions (on page 753): Retrieving the actions for the plan market will enable you to see what entities were directly affected during the run of the plan.
- Entities (on page 791): Retrieving the entities for the plan market will enable you to see a full listing of the entities involved in the plan.
- Groups (on page 819): Retrieving the groups for the plan market will enable you to more easily obtain UUID information for the entities in the specified group.



■ <u>Statistics (on page 973)</u>: Retrieving the market statistics for the plan market as a whole, a group, or an entity will enable you to easily see a broad overview of the state of the entity utilization after the plan has finished.

Procedure

To investigate changes to a particular subset of plan entities:

1. Get the list of UUIDs you want investigate.

To get all the entities in a market:

```
markets/{market_uuid}/entities
```

If the scope of the plan is small, you can use this to get all the entities in the plan, and then iterate through the results for other attributes such as entity type or display name.

```
markets/{market_uuid}/entities
```

For a large scope, you can use the Search endpoint to find VMs by specific criteria. This works because the plan market and the real-time market use the same UUID values for the same entities. For example, the following call gets all VMs that have the string FOO in their names:

```
\label{lem:https://10.123.456/api/v3/search?q=F00&types=VirtualMachine&entity\_types=VirtualMachine&query\_types=Contains
```

2. Get the list of plan actions.

Run GET /markets/{market_Uuid}/actions against the plan market. You can also use POST /markets/ {market_uuid}/actions to post a filter for advanced action queries, such as only returning actions of a particular type, or particular risk severity.

Another way to get plan actions is to use the Search endpoint. You can POST search parameters that limit the returned actions by text in the description, cost type, or other data. For example, the following search returns only actions on VMs:

```
searchSpec = {
  "actionRelationTypeFilter": [
    "NONE"
],
  "costType": "SAVING",
  "descriptionQuery": {
    "query": "Virtual Machine",
    "type": "CONTAINS",
    "caseSensitive": "true"
},
  "detailLevel": "STANDARD"
}
```

With the above payload, the following POST would return VM actions from the plan:

```
requests.post(f'https://{ip}/api/v3/markets/{marketUuid}/actions',
  headers=headers,
  json = searchSpec,
  verify=False,
  stream=True)
```

3. Search the API response and find the action(s) relevant to your entities.

Each action will have a target parameter, which will in turn have a unid. This UUID identifies the entity the action executed on. This is the best way to locate your entity in a list of actions.

If no actions have the specified target > uuid value, then no actions were performed on the entity in question.



NOTE: You can use GET <code>/markets/{market_Uuid}/entities</code> to verify that the UUID you are searching for exists in the plan market. If it does not, it means that the entity was not included in the scope of the plan, or the entity is considered an idle workload. An idle workload shows no utilization, so the plan cannot determine optimal placement or what percentage of allocated resources that workload will require when it restarts.

4. Analyze the results.

Each action contains the information detailed in the ActionApiDTO data, including the details of the action, old/new values for any changed resources, a record of deletion for DELETE actions, etc.

Search through this DTO and make note of any parameters important to you. (For a DTO reference, see <u>ActionApiDTO (on page 1071)</u>.)

Script Example

The following script searches through the list of actions for a virtual machine, and returns the requested fields for quick comparison. In this case, the UUID, type, state, reason, risk category, and risk subcategory are returned for the action, and paired with the display name, template UUID, and location of the entity.

This script is easily extensible- for example, if currentLocation > displayName is equal to newLocation > displayName, you may choose not to show either of those fields, as no change involving the VM location was made. You might also use these results to make further calls- for example, using the template UUID to make a GET /templates/ {template_Uuid} request to return more information about the template being used for a resize action.

Note that the script uses dot-notation to name the fields you want to inspect. It includes the <code>getFieldFromDict</code> function to convert those fields to nested Python dictionary values. Because the API returns JSON data, a function like this could be a generally useful utility.

```
#!/usr/bin/env python3
#
# Commandline args: platformIP, username, pwd, marketID, VmIDs as comma-sep string (no spaces)
# EXAMPLE: ./entity_changes.py 10.10.123.456 MyUser MyPwd 215426452602368
74635124762083,74635124762088,74635124762090
import json
import requests
import urllib3
import re
sys.path.append('../login') #This makes login visible...
import login
# This function takes json-like dot-notation fields and returns python dictionary values.
# That makes it easier to specify the DTO fields you want to view.
def getFieldFromDict(field, dict):
fToks = field.split('.')
l = len(fToks)
workingDict = dict
for item in fToks:
  if item in workingDict:
  ret = workingDict[item]
 else:
  return "ITEM NOT IN OBJECT"
  1 -= 1
```



```
if 1 == 0:
  return ret
  else:
   workingDict = ret
 return ret
# Ths list of fields you want to query, in dot-notation
RetrieveFields = [
"uuid",
"actionType",
"actionState",
"details",
"currentEntity.displayName",
"newEntity.displayName",
"template.uuid",
"risk.subCategory",
"risk.description",
"currentLocation.displayName",
"newLocation.displayName"
]
# A search spec to get actions that are on VMs.
searchSpec = {
  "actionRelationTypeFilter": [
    "NONE"
  ],
  "costType": "SAVING",
  "descriptionQuery": {
    "query": "Virtual Machine",
    "type": "CONTAINS",
    "caseSensitive": "true"
  },
  "detailLevel": "STANDARD"
# Make sure you have the correct count of arguments.
if len(sys.argv) != 6:
print("Incorrect arguments list.")
sys.exit()
# Get the args into well named vars, and also authenticate.
ip = sys.argv[1]
marketUuid = sys.argv[4]
ElemsToInspect = sys.argv[5].split(',')
token = login.get_cookie(ip, sys.argv[2], sys.argv[3])
```



```
headers = {'cookie': token}
# Search plan for actions on VMs
actions_r = requests.post(f'https://{ip}/api/v3/markets/{marketUuid}/actions', headers=headers, json = s
earchSpec, verify=False, stream=True)
if actions_r.status_code != 200:
    print(f'Market Request Status is {actions_r.status_code}.')
    sys.exit()
# For each action that targets one of the entities you pass in the command line,
# parse the object and display the field values.
print("Plan Changes for Entity(ies):")
print(sys.argv[5])
print("----")
r_json = actions_r.json()
for item in r_json:
target = item['target']
if 0 < ElemsToInspect.count(target["uuid"]):</pre>
 print(f'VM ACTION: {target["displayName"]}')
  for field in RetrieveFields:
  val = getFieldFromDict(field, item)
  print(f'
            {field}: {val}')
```

Script Result

The result of this script displays the requested information for each plan entity:

```
Plan Changes for Entity(ies):
74635124762083,74635124762088
______
VM ACTION: test-rosa-28tfg-worker-us-west-2a-5hr8j
   uuid: 145057709553360
   actionType: SCALE
   actionState: SUCCEEDED
   details: Scale Virtual Machine test-rosa-28tfg-worker-us-west-2a-5hr8j from m5.xlarge to r5a.large in
Advanced Engineering
   currentEntity.displayName: m5.xlarge
   newEntity.displayName: r5a.large
   template.uuid: 74635137532084
   risk.subCategory: Efficiency Improvement
   risk.description: Underutilized VCPU, Net Throughput
   currentLocation.displayName: aws-US West (Oregon)
   newLocation.displayName: aws-US West (Oregon)
VM ACTION: test-rosa-28tfg-infra-us-west-2a-mw867
   uuid: 145057709553376
   actionType: SCALE
```



```
actionState: SUCCEEDED

details: Scale Virtual Machine test-rosa-28tfg-infra-us-west-2a-mw867 from r5.xlarge to r5a.xlarge in

Advanced Engineering

currentEntity.displayName: r5.xlarge

newEntity.displayName: r5a.xlarge

template.uuid: 74635137531741

risk.subCategory: Efficiency Improvement

risk.description: Increase RI Utilization

currentLocation.displayName: aws-US West (Oregon)

newLocation.displayName: aws-US West (Oregon)
```

Seeing the Changes for a Group of Entities

You can easily modify this script to see the changes for a particular group of entities without needing to know each UUID.

To perform this modification, consume the result of a GET /groups/{group_uuid}/entities request. Example result:

```
[
    "uuid": "73422419372894",
    "displayName": "PT_RHEL",
    "className": "VirtualMachine",
    "priceIndex":4.33,
    "state": "ACTIVE",
    "severity": "Normal",
    "costPrice":0.24104111,
    "discoveredBy":{
      "uuid": "73422416392368",
      "displayName": "producttrust",
      "category": "Public Cloud",
      "type": "AWS",
      "readonly":false
    },
    . . .
 },
    "uuid":"73422419372988",
    "displayName": "PT_Resize_Up_Target",
    "className": "VirtualMachine",
    "priceIndex":10074.822,
    "state":"ACTIVE",
    "severity": "Normal",
    "costPrice":0.078387,
    "discoveredBy":{
      "uuid": "73422416392368",
      "displayName": "producttrust",
      "category": "Public Cloud",
      "type": "AWS",
      "readonly":false
    },
 },
```



```
"uuid":"73422419372921",
"displayName":"PT_Consistent_Scaling_VM_1",
"className":"VirtualMachine",
"priceIndex":100.357,
"state":"ACTIVE",
"severity":"Normal",
"costPrice":0.0159137,
"discoveredBy":{
    "uuid":"73422416392368",
    "displayName":"producttrust",
    "category":"Public Cloud",
    "type":"AWS",
    "readonly":false
},
....
}
```

Using this result, you can either use each UUID found, or filter based on entities. For example, to iterate through a group and get the UUID of all VM entities:

```
foreach (var entity in groupApiResponse)
{
   if (entity["className"] == VirtualMachine)
   {
      Console.Writeline(entity["uuid"])
   }
}
```

Creating a Static Group

Objective

To create a static group of entities.

A static group contains a fixed set of entities. This example creates a group of VMs, but you can create a group of any entity type.

The script will get the unique IDs of member entities by their display names, and add them to a list that it then uses to display the group members.

The script also sets up the group type and entity type when it creates the payload data. It then uses the API to create the group, and verify that the group contains the entities you specified.

Prerequisites

In order to create a static group, you must have the following information:

- The display names of the members in the group
- The entity type you will use for this group
- The IP address and login credentials for a Workload Optimization Manager instance



Related Endpoints

This recipe uses the following endpoints:

■ Groups (on page 819)

It uses the POST /groups request to create the group, and the GET /groups/{group_uuid} request to verify the group membership.

■ Search (on page 955)

It uses the GET /search request to obtain the UUIDs of the group members from the display names.

Script Setup

To set up the script, provide values from your environment for the following:

■ ip

The IP address of your Workload Optimization Manager instance.

■ username

The username for the account Workload Optimization Manager will use to access the API.

password

The password for the account Workload Optimization Manager will use to access the API.

names list

A list of display names for the entities you want to add to the group. Note that the entities must all be of the same type. If entities of more than one type are provided, group creation will fail.

group_name

The display name for the group. This name will appear in the user interface.

■ entity_type

The entity type for the group and its member entities. The script will use this in creating the Group input data, and also when executing a search for the entities' UUID.

NOTE:

Workload Optimization Manager does not support creation of groups with more than one entity type at this time.

Authentication

The first step of any script is to authenticate accesse to your Workload Optimization Manager instance, retrieve the authentication token and store it for use with subsequent calls. To authenticate, this script uses the values you set for ip, username, and password. For more detail, see the <u>Authentication Recipe (on page 1026)</u>.

API Request: https://{ip}/vmturbo/rest/login

UUID Retrieval

After it logs in, the script iterates through your list of entity names, passing each in turn to the GET /search request. It uses the returned EntityApiDTO to get the UUIDs for each matching entity.

The search response is an array of entity objects, and each entity object includes the entity's UUID. The script loops through the display names you provide in names_list, and executes a separate search request for each name. Each response should be an array of one item. The script adds the uuid of that item to the group_members_uuids list.

NOTE:

Another method to obtain the UUIDs is to execute a filtered POST /search request. This script uses repeated GET /search requests for simplicity.

Sample Request: GET https://10.10.10.10/api/v3/search? q=zrlinuxclone106&types=VirtualMachine&entityTypes=VirtualMachine

Sample Return:

[



```
"uuid": "74011863734144",
  "displayName": "zrlinuxclone106",
  "className": "VirtualMachine",
  "state": "ACTIVE",
  "severity": "Critical",
  "discoveredBy":{
    "uuid": "73935378522272",
    "displayName": "vsphere-dc23.eng.vmturbo.com",
    "category": "Hypervisor",
    "type": "vCenter",
    "readonly":false
  },
  "severityBreakdown":{
    "CRITICAL":1
  },
  "providers":[
    {
      "uuid":"73935378875792",
      "displayName": "hp-esx108.eng.vmturbo.com",
      "className": "PhysicalMachine"
    },
    {
      "uuid": "73935378875736",
      "displayName": "QS2_GRID01:DC23DS1",
      "className": "Storage"
    },
    {
      "uuid": "73995333587472",
      "displayName": "Resources-hp-esx108.eng.vmturbo.com",
      "className": "VirtualDataCenter"
    }
  ],
  "environmentType": "ONPREM",
  "vendorIds":{
    "vsphere-dc23.eng.vmturbo.com": "vm-2844"
}
```

Constructing the Input DTO and Creating the Group

Once the script has built the list of UUIDs for the group members, it can build a <code>GroupApiDTO</code> to describe the group you want. The DTO needs values for the following properties:

■ isStatic: true to create a static group

]

- displayName: The group name that you set for the group_name variable
- memberUuidList: The array of UUID strings that the script has created
- criteriaList: For a static group, pass an empty array
- groupType: The entity type for this group -- the value you set for the entity_type variable

Using the obtained UUIDs and the above information, the script will construct the input GroupApiDTO (on page 1132). The script creates a Python dictionary, which it passes as the input body of the POST /groups request.



Example Input DTO:

```
{
  "isStatic":"true",
  "displayName":"TestGrp2",
  "memberUuidList":[
     "74011863734144",
     "73997881750336"
],
  "criteriaList":[
],
  "groupType":"VirtualMachine"
}
```

Sample Request: POST https://{ip}/api/v3/groups/

The response to this request will be the GroupApiDTO for the created group.

Sample Response:

```
"uuid": "285123335341792",
"displayName": "TestGrp2",
"className": "Group",
"membersCount":2,
"entitiesCount":2,
"groupType": "VirtualMachine",
"severity": "CRITICAL",
"environmentType": "ONPREM",
"isStatic":true,
"logicalOperator": "AND",
"memberUuidList":[
  "74011863734144",
  "73997881750336"
],
"temporary": false,
"activeEntitiesCount":1,
"cloudType": "UNKNOWN",
"memberTypes":[
  "VirtualMachine"
],
"entityTypes":[
  "VirtualMachine"
],
"groupClassName": "GroupApiDTO"
```



Verification

To verify that the group was created successfully, the script uses the returned UUID to get the group data via the <code>/groups</code> endpoint. If the request gets the group, the returned DTO should be identical to the response from the request to create the group.

If the group does not exist for the given UUID, the API returns the request status 404, with the message, Group not found: <Passed_UUID>. This indicates that the script failed to create the group.

```
Sample Response: https://{ip}/api/v3/groups/{group_uuid}
```

You can choose to only use a subset of the provided response. For example, this script prints the displayName and UUID for each group member.

Sample Script Response:

```
Group Members:

Display name: boao.min-spare
OID: 73997881750336

Display name: zrlinuxclone106
OID: 74011863734144
```

Script Example

```
import json
import requests
import urllib3
import re
import sys
sys.path.append('../login') #This makes login visible...
import login
#
# Make sure you have the correct count of arguments.
if len(sys.argv) != 7:
print("Incorrect arguments list.")
sys.exit()
# Get the args into well named vars, and also authenticate.
ip = sys.argv[1]
groupName = sys.argv[4]
entityType = sys.argv[5]
entsListByName = sys.argv[6].split(',')
token = login.get_cookie(ip, sys.argv[2], sys.argv[3])
authHeader = {'cookie': token}
# Get UUIDs for entities in entsListByName
```



```
#
memberIds = []
for name in entsListByName:
response = requests.get(
 f'https://{ip}/api/v3/search?q={name}&types={entityType}&entity_types={entityType}&query_type=EXACT',
 headers=authHeader, verify=False)
if response.status_code == 200:
    response_json = json.loads(response.text)
    memberIds.append(response_json[0]['uuid'])
if response.status_code != 200:
    print(f'Search Request Status for {name} is {response.status_code}.')
# Assemble the payload object to create the group.
group_input_dto = {}
group_input_dto['isStatic'] = 'true'
group_input_dto['displayName'] = groupName
group_input_dto['memberUuidList'] = memberIds
group_input_dto['criteriaList'] = []
group_input_dto['groupType'] = entityType
# Create the group
response = requests.post(f'https://{ip}/api/v3/groups', json=group_input_dto, headers=authHeader, verif
y=False, stream=True)
if response.status_code != 200:
print(f'Create Group failed. StatusCode: {response.status_code}\n{response.text}')
sys.exit()
groupResponse_json = json.loads(response.text)
groupId = groupResponse_json['uuid']
# Inspect the group
groupCheck_response = requests.get(f'https://{ip}/api/v3/groups/{groupId}', headers=authHeader, verify=F
alse)
groupCheck_json = json.loads(groupCheck_response.text)
if groupCheck_json['uuid']:
verifiedId = groupCheck_json['uuid']
groupName = groupCheck_json['displayName']
print(f'Group \"{groupName}\" successfully created with a UUID of: {verifiedId}')
else:
print('Error in group creation, no UUID found.')
sys.exit()
# Get a list of Group members
response = requests.get(
f'https://{ip}/api/v3/groups/{groupId}/entities', headers=authHeader, verify=False)
if response.status_code != 200:
```



```
print(f'Could not get group members. Status is {response.status_code}.')
sys.exit()

groupMembers_json = json.loads(response.text)

# Print a list of group members
print('\nGroup Members:')
for item in groupMembers_json:
    print('Display name: ' + item['displayName'])
    print('OID: ' + item['uuid'])
```

Creating a Dynamic Group

Objective

To create a dynamic group of entities.

A dynamic group contains a set of entities discovered by filter criteria. In this case, the script will create a group of all virtual machines which reside on a specific host. As virtual machines are added and removed from the host, the membership of this group will reflect those changes.

The script will use the /search endpoint to get the unique ID of the host using its display name, and then retrieve a list of expected virtual machines to verify against. The script then creates the criteria list and inserts that value into the rest of the payload data before creating the group and verifying that the membership is as expected.

Prerequisites

In order to create a dynamic group, you must have the following information:

The display name of the host

The entity type you will use for this group

The IP address and login credentials for a Workload Optimization Manager instance

Related Endpoints

This recipe uses information from the following endpoints:

■ Groups (on page 819)

NOTE:

All possible criterion values can be found in the Groups Endpoint Tips (on page 845).

■ Search (on page 955)

Script Setup

To set up the script, provide values from your environment for the following:

■ in

The IP of your Workload Optimization Manager instance.

■ username

The username for the account Workload Optimization Manager will use to access the API.

password

The password for the account Workload Optimization Manager will use to access the API.

■ host_name

The display name of the host whose virtual machines will be added to the group.



■ group_name

The display name for the group. This name will appear in the user interface.

■ entity_type

The entity type for the member entities of the group. The script will use this in creating the Group input data, and also when verifying group membership.

NOTE:

Workload Optimization Manager does not support creation of groups with more than one entity type at this time.

Authentication

The first step of any script is to authenticate to your Workload Optimization Manager instance, retrieve the authentication token and store it for use with subsequent calls. To authenticate, this script uses the values you set for ip, username, and password. For more detail, see the <u>Authentication Recipe (on page 1026)</u>.

API Request: https://{ip}/vmturbo/rest/login

Get Expected Initial Membership

After it logs in, the displays a list of virtual machines that reside on the host. These will be the group members.

The script uses the /search endpoint and retrieves the EntityApiDTO for the host. Using the consumers parameter, you can see each entity that purchases resources from this host. The script lists the consumers with a className that matches the entity type.

```
Sample Request: GET https://{ip}/api/v3/search?
q={host_name}&types=PhysicalMachine'&detail_type=entity'
```

Create the Filter Criterion

To create a dynamic group, you pass filter criteria to identify matching entities. You pass these criteria as an array. For this script, we pass a single criterion in the array.

Example criteria_list:

```
{
    "expType":"RXEQ",
    "expVal":"host_name",
    "filterType":"vmsByPMName",
    "caseSensitive":"false"
}
```

Construct the input DTO and Create the Group

The script will take the criterion parameter and use it to construct the <u>GroupApiDTO (on page 1132)</u>, with the following parameters:

■ isStatic

When true, the created group is static. The script sets this parameter to false.

■ displayName

The display name for the group. This name will appear in the user interface. The script sets this parameter

memberUuidList

For a dynamic group, pass an empty array.

criteriaList



The filtering criteria used to determine group membership. The script sets this parameter equal to the criteria_list variable.

■ groupType

The entity type of the group members. The script sets this parameter equal to the group_entity_type variable.

```
API Request: POST https://{ip}/api/v3/groups/
```

The response to this request will be the GroupApiDTO for the created group.

Sample Response:

```
"uuid": "285126581114848",
"displayName": "TestGrp2",
"className": "Group",
"membersCount":3,
"entitiesCount":3,
"groupType": "VirtualMachine",
"severity": "CRITICAL",
"environmentType": "ONPREM",
"isStatic":false,
"logicalOperator": "AND",
"criteriaList":[
    "expVal": "hp-esx119.eng.vmturbo.com",
    "expType": "RXEQ",
    "filterType": "vmsByPMName",
    "caseSensitive":false,
    "entityType":null,
    "singleLine":false
],
"memberUuidList":[
  "73943582577376",
  "73943582577568",
  "73943582577744"
"temporary": false,
"activeEntitiesCount":2,
"cloudType": "UNKNOWN",
"memberTypes":[
  "VirtualMachine"
],
"entityTypes":[
  "VirtualMachine"
],
"groupClassName": "GroupApiDTO"
```

Verify the Group

To verify that the group was created successfully, the script uses the returned UUID to get the group data via the /groups endpoint. If the request gets the group, the membership of the group should match what was printed to the console in the *Get*



Expected Initial Membership portion of the script, assuming that no virtual machines have been added or removed since that time.

If the group does not exist for the given UUID, the API returns the request status 404, with the message, Group not found: <Passed_UUID>. This indicates that the script failed to create the group.

```
API Request: https://{ip}/api/v3/groups/{group_uuid}
```

You might choose to only use a subset of the provided response. For example, this script prints the displayName and UUID for each group member.

Sample Script Response:

```
Group Members:

Display name: DC26-P02-03
OID: 73943582577376
Display name: DC26-P02-02
OID: 73943582577568
Display name: DC26-P02-01
OID: 73943582577744
```

Script Example

```
# Commandline args: platformIP, username, pwd, group_name, entity_type, host_name
# EXAMPLE: ./entity_changes.py 10.10.123.456 MyUser MyPwd MyTestGroup VirtualMachine MyHost
import json
import requests
import urllib3
import re
import sys
sys.path.append('../login') #This makes login visible...
import login
#
# Make sure you have the correct count of arguments.
if len(sys.argv) != 7:
print("Incorrect arguments list.")
sys.exit()
# Get the args into well named vars, and also authenticate.
ip = sys.argv[1]
group_name = sys.argv[4]
entity_type = sys.argv[5]
host_name = sys.argv[6]
token = login.get_cookie(ip, sys.argv[2], sys.argv[3])
```



```
authHeader = { 'cookie': token}
# Get Expected Initial Membership
response = requests.get(
    f'https://{ip}/api/v3/search?q={host_name}&types=PhysicalMachine'
    f'&detail_type=entity',
   headers=authHeader, verify=False)
get_vms_response_json = json.loads(response.text)
print(f'CONSUMERS: {get_vms_response_json[0]["consumers"]}')
print(f'The {entity_type} members of this dynamic group will be:')
for entity in get_vms_response_json[0]['consumers']:
if entity['className'] == entity_type:
 print(entity)
# Create the filter criterion
criterion = {}
criterion['expType'] = "RXEQ"
criterion['expVal'] = host_name
criterion['filterType'] = "vmsByPMName"
criterion['caseSensitive'] = "false"
# Construct the Input DTO and Create the Group
group_input_dto = {}
group_input_dto['isStatic'] = 'false'
group_input_dto['displayName'] = group_name
group_input_dto['memberUuidList'] = []
group_input_dto['criteriaList'] = [criterion]
group_input_dto['groupType'] = entity_type
response = requests.post(
    f'https://{ip}/api/v3/groups', headers=authHeader, json=group_input_dto, verify=False, stream=True)
group_creation_response_json = json.loads(response.text)
group_uuid = group_creation_response_json['uuid']
# Verify the group
response = requests.get(
    f'https://{ip}/api/v3/groups/{group_uuid}/entities', headers=authHeader, verify=False)
group_members_response_json = json.loads(response.text)
# Print a list of group members
print('\nGROUP MEMBERS:')
for item in group_members_response_json:
    print('Display name: ' + item['displayName'])
   print('OID: ' + item['uuid'])
```



Reference: Internal Workload Optimization Manager API Requests

Internal Requests are requests that are used internally by Workload Optimization Manager, but are not intended for customer use. The structure data returned by these requests is subject to change without notice.

The following requests have been marked as Internal Only:

/entities

```
DELETE /entities/loggingEntities
PUT /entities/{entity_Uuids}/loggingEntities
GET /entities/{entity_Uuid}/aspects/{aspect_name}/actions
POST /entities/{entity_Uuid}/aspects/{aspect_name}/actions
GET /entities/{entity_Uuid}/aspects/{aspect_name}/stats
POST /entities/{entity_Uuid}/aspects/{aspect_name}/stats
POST /entities/{entity_Uuid}/tags
DELETE /entities/{entity_Uuid}/tags
DELETE /entities/{entity_Uuid}/tags/{tag_key}
```

■ /groups

```
GET /groups/{group_Uuid}/aspects/{aspect_name}/actions
POST /groups/{group_Uuid}/aspects/{aspect_name}/actions
GET /groups/{group_Uuid}/aspects/{aspect_name}/stats
POST /groups/{group_Uuid}/aspects/{aspect_name}/stats
POST /groups/{group_Uuid}/notifications/stats
POST /groups/{group_Uuid}/tags
DELETE /groups/{group_Uuid}/tags
DELETE /groups/{group_Uuid}/tags/{tag_key}
```

/markets

```
PUT /markets/{market_Uuid}/policies/{policy_Uuid}
```

/reports

```
POST /reports/templates
```

/scenarios

```
PUT /scenarios/{scenario_Uuid}
PUT /scenarios/{scenario_Uuid}/entities/{entity_Uuid}

DELETE /scenarios/{scenario_Uuid}/entities/{entity_Uuid}
PUT /scenarios/{scenario_Uuid}/groups/{group_Uuid}

PUT /scenarios/{scenario_Uuid}/policies

DELETE /scenarios/{scenario_Uuid}/policies/{policy_Uuid}

PUT /scenarios/{scenario_Uuid}/templates/{template_name}
```

/widgetsets

The entire /widgetsets endpoint is Internal Only.



Reference: Scenario Peak-of-Peak Full Scenario Input DTO

For reference purposes, see below for a complete input DTO for a Peak of Peaks plan.

```
"uuid": "XXXXDemo",
"displayName": "XXXXDemo",
"owners":[
    "uuid":"_4T_7kwY-Ed-WUKbEYSVIDw",
    "username": "administrator",
    "showSharedUserSC":false
],
"type": "PEAKOFPEAKS",
"scope":[
    "uuid": "_PE0v-YEUEee_hYfzgV9uYg",
    "displayName": "All On-prem Hosts",
    "className": "All On-prem Hosts"
],
"topologyChanges":{
},
"loadChanges":{
  "maxUtilizationList":[
      "maxPercentage":70,
      "projectionDay":0,
      "target":{
        "displayName": "All On-prem Hosts",
        "className": "Group",
        "uuid": "_PEOv-YEUEee_hYfzgV9uYg"
    }
  1
"overlayStatsList":[
    "uuid": "4223ae0c-c99b-f6ca-c1ef-3f367bdf5528",
    "displayName": "centos_imp_2",
    "className": "VirtualMachine",
    "environmentType": "ONPREM",
    "stats":[
        "displayName": "centos_imp_2",
        "date": "2019-02-01T00:00:00-05:00",
        "statistics":[
             "displayName": "centos_imp_2",
```



```
"date": "2019-03-14T15:12:36-04:00",
"statistics":[
    "name": "priceIndex",
    "values":{
      "max":20000,
      "min":20000,
      "avg":20000,
      "total":20000
    "value":20000
  },
  {
    "name": "CPUProvisioned",
    "capacity":{
      "max":104000,
      "min":104000,
      "avg":104000,
      "total":104000
    },
    "filters":[
      {
        "type": "relation",
        "value": "bought"
      }
    ],
    "relatedEntity":{
      "uuid": "Virtual_ESX_4238255f-86cc-4cb9-0f47-11ff689f0b22",
      "displayName": "hp-esx4.dev.mycorp.com",
      "className": "PhysicalMachine"
    },
    "units": "MHz",
    "values":{
      "max":5200,
      "min":5200,
      "avg":5200,
      "total":5200
    },
    "value":5200
  },
  {
    "name": "Mem",
    "capacity":{
      "max":16776692,
      "min":16776692,
      "avg":16776692,
      "total":16776692
    },
    "filters":[
        "type": "relation",
        "value": "bought"
      }
    ],
```



```
"relatedEntity":{
    "uuid": "Virtual_ESX_4238255f-86cc-4cb9-0f47-11ff689f0b22",
    "displayName": "hp-esx4.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "units":"KB",
  "values":{
    "max":3555836,
    "min":3554799.8,
    "avg":3554799.8,
    "total":3554799.8
  "value":3554799.8
},
{
  "name": "MemProvisioned",
  "capacity":{
    "max":167766912,
    "min":167766912,
    "avg":167766912,
    "total":167766912
  },
  "filters":[
    {
      "type": "relation",
      "value": "bought"
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238255f-86cc-4cb9-0f47-11ff689f0b22",
    "displayName": "hp-esx4.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "units": "KB",
  "values":{
    "max":4194304,
    "min":4194304,
    "avg":4194304,
    "total":4194304
  "value":4194304
},
{
  "name": "StorageAmount",
  "capacity":{
    "max":3301375,
    "min":3301375,
    "avg":3301375,
    "total":3301375
  },
  "filters":[
      "type": "relation",
      "value": "bought"
```



```
}
  ],
  "relatedEntity":{
    "uuid": "6f76b47e-e6f0a3fe",
    "displayName": "QSGRID01: ESXDC1DS1",
    "className": "Storage"
  },
  "units":"MB",
  "values":{
    "max":725.32,
    "min":725.32,
    "avg":725.32,
    "total":725.32
  "value":725.32
},
{
  "name": "NetThroughput",
  "capacity":{
    "max":3072000,
    "min":3072000,
    "avg":3072000,
    "total":3072000
  },
  "filters":[
      "type": "relation",
      "value": "bought"
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238255f-86cc-4cb9-0f47-11ff689f0b22",
    "displayName": "hp-esx4.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "units": "Kbit/sec",
  "values":{
    "max":0,
    "min":0,
    "avg":0,
    "total":0
  },
  "value":0
},
{
  "name": "MemAllocation",
  "capacity":{
    "max":52503552,
    "min":52503552,
    "avg":52503552,
    "total":52503552
  },
  "filters":[
    {
```



```
"type": "key",
      "value": "VirtualDataCenter::2332ba0f9dc14c07f11adb38e12df43c4bc8ca56"
    },
      "type": "relation",
      "value": "bought"
  ],
  "relatedEntity":{
    "uuid": "2332ba0f9dc14c07f11adb38e12df43c4bc8ca56",
    "displayName": "olga_do_not_touch_1",
    "className": "VirtualDataCenter"
  },
  "units": "KB",
  "values":{
    "max":3555836,
    "min":3554799.8,
    "avg":3554799.8,
    "total":3554799.8
  },
  "value":3554799.8
},
{
  "name": "VCPU",
  "capacity":{
    "max":5200,
    "min":5200,
    "avg":5200,
    "total":5200
  },
  "filters":[
    {
      "type": "relation",
      "value": "sold"
    }
  "units": "MHz",
  "values":{
    "max":5214,
    "min":5201.9,
    "avg":5201.9,
    "total":5201.9
  },
  "value":5201.9
},
{
  "name": "Ballooning",
  "capacity":{
    "max":16776692,
    "min":16776692,
    "avg":16776692,
    "total":16776692
  },
  "filters":[
```



```
"type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238255f-86cc-4cb9-0f47-11ff689f0b22",
    "displayName": "hp-esx4.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "units": "KB",
  "values":{
    {\tt "max":0},
    "min":0,
    "avg":0,
    "total":0
  },
  "value":0
},
{
  "name": "StorageAccess",
  "capacity":{
    "max":5000,
    "min":5000,
    "avg":5000,
    "total":5000
  },
  "filters":[
    {
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid":"6f76b47e-e6f0a3fe",
    "displayName":"QSGRID01:ESXDC1DS1",
    "className": "Storage"
  },
  "units":"IOPS",
  "values":{
    {\tt "max":0},
    "min":0,
    "avg":0,
    "total":0
  },
  "value":0
},
{
  "name": "CPUAllocation",
  "capacity":{
    "max":31096,
    "min":31096,
    "avg":31096,
    "total":31096
```



```
},
  "filters":[
    {
      "type": "key",
      "value": "VirtualDataCenter::2332ba0f9dc14c07f11adb38e12df43c4bc8ca56"
    },
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "2332ba0f9dc14c07f11adb38e12df43c4bc8ca56",
    "displayName": "olga_do_not_touch_1",
    "className": "VirtualDataCenter"
  },
  "units": "MHz",
  "values":{
    "max":5214,
    "min":5201.9,
    "avg":5201.9,
    "total":5201.9
  },
  "value":5201.9
},
{
  "name": "IOThroughput",
  "capacity":{
    "max":11264000,
    "min":11264000,
    "avg":11264000,
    "total":11264000
  },
  "reserved":{
    "max":9011200,
    "min":9011200,
    "avg":9011200,
    "total":9011200
  },
  "filters":[
      "type": "relation",
      "value": "bought"
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238255f-86cc-4cb9-0f47-11ff689f0b22",
    "displayName": "hp-esx4.dev.mycorp.com",
    "className": "PhysicalMachine"
  "units": "Kbit/sec",
  "values":{
    "max":0,
    "min":0,
```



```
"avg":0,
    "total":0
  "value":0
},
{
  "name": "StorageLatency",
  "capacity":{
    "max":100,
    "min":100,
    "avg":100,
    "total":100
  },
  "filters":[
    {
      "type": "relation",
      "value": "bought"
  ],
  "relatedEntity":{
    "uuid": "6f76b47e-e6f0a3fe",
    "displayName": "QSGRID01:ESXDC1DS1",
    "className": "Storage"
  },
  "units": "msec",
  "values":{
    "max":0.5,
    "min":0.5,
    "avg":0.5,
    "total":0.5
  },
  "value":0.5
},
{
  "name": "VMem",
  "capacity":{
    "max":4194304,
    "min":4194304,
    "avg":4194304,
    "total":4194304
  },
  "filters":[
      "type": "relation",
      "value": "sold"
    }
  "units":"KB",
  "values":{
    "max":3397384,
    "min":3233807,
    "avg":3233807,
    "total":3233807
  },
```



```
"value":3233807
},
{
  "name": "CPU",
  "capacity":{
    "max":10400,
    "min":10400,
    "avg":10400,
    "total":10400
  "filters":[
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238255f-86cc-4cb9-0f47-11ff689f0b22",
    "displayName": "hp-esx4.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "units": "MHz",
  "values":{
    "max":5214,
    "min":5201.9,
    "avg":5201.9,
    "total":5201.9
  },
  "value":5201.9
},
{
  "name": "VStorage",
  "capacity":{
    "max":2646,
    "min":1014,
    "avg":2238,
    "total":8952
  },
  "filters":[
    {
      "type": "key",
      "value": "VirtualMachine::08bb59f519b55c22415be8d623b5ccdf578b85cc"
    },
    {
      "type": "relation",
      "value": "sold"
    }
  ],
  "units": "MB",
  "values":{
    "max":1016.14,
    "min":142.4,
    "avg":797.71,
    "total":3190.82
```



```
"value":797.71
      ]
  ]
},
  "uuid": "4223bb37-0090-f332-0140-cc3cce7b3735",
  "displayName": "centos_imp_3",
  "className": "VirtualMachine",
  "environmentType":"ONPREM",
  "stats":[
    {
      "displayName": "centos_imp_3",
      "date": "2019-02-01T00:00:00-05:00",
      "statistics":[
          "displayName": "centos_imp_3",
          "date": "2019-03-14T15:12:36-04:00",
          "statistics":[
              "name": "priceIndex",
              "values":{
                "max":20000,
                "min":20000,
                 "avg":20000,
                 "total":20000
              },
              "value":20000
            },
              "name": "CPUProvisioned",
              "capacity":{
                "max":104000,
                 "min":104000,
                 "avg":104000,
                "total":104000
              },
              "filters":[
                   "type": "relation",
                   "value":"bought"
                 }
              ],
              "relatedEntity":{
                 "uuid": "Virtual_ESX_4238a511-8593-4469-2751-46611e09b6a8",
                 "displayName": "hp-esx1.dev.mycorp.com",
                 "className": "PhysicalMachine"
              },
              "units": "MHz",
              "values":{
                 "max":5200,
                 "min":5200,
```



```
"avg":5200,
    "total":5200
  },
  "value":5200
},
  "name": "Swapping",
  "capacity":{
    "max":40000000,
    "min":40000000,
    "avg":40000000,
    "total":40000000
  },
  "filters":[
    {
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238a511-8593-4469-2751-46611e09b6a8",
    "displayName": "hp-esx1.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "units": "bit/sec",
  "values":{
    "max":0,
    "min":0,
    "avg":0,
    "total":0
  },
  "value":0
},
  "name":"NumDisk",
  "capacity":{
    "max":2147483650,
    "min":2147483650,
    "avg":2147483650,
    "total":2147483650
  },
  "filters":[
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238a511-8593-4469-2751-46611e09b6a8",
    "displayName": "hp-esx1.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "values":{
    "max":1,
```



```
"min":1,
    "avg":1,
    "total":1
  },
  "value":1
},
  "name": "Mem",
  "capacity":{
   "max":16776692,
    "min":16776692,
    "avg":16776692,
    "total":16776692
  },
  "filters":[
   {
      "type": "relation",
      "value": "bought"
   }
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238a511-8593-4469-2751-46611e09b6a8",
    "displayName": "hp-esx1.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "units": "KB",
  "values":{
    "max":3069332,
    "min":3062497,
    "avg":3062497,
    "total":3062497
  },
  "value":3062497
},
  "name": "MemProvisioned",
  "capacity":{
   "max":167766912,
    "min":167766912,
    "avg":167766912,
    "total":167766912
  },
  "filters":[
   {
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238a511-8593-4469-2751-46611e09b6a8",
    "displayName": "hp-esx1.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "units":"KB",
```



```
"values":{
    "max":4194304,
    "min":4194304,
    "avg":4194304,
    "total":4194304
  },
  "value":4194304
},
{
  "name": "StorageAmount",
  "capacity":{
    "max":3301375,
    "min":3301375,
    "avg":3301375,
    "total":3301375
  },
  "filters":[
    {
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid":"6f76b47e-e6f0a3fe",
    "displayName": "QSGRID01: ESXDC1DS1",
    "className": "Storage"
  },
  "units": "MB",
  "values":{
    "max":719,
    "min":719,
    "avg":719,
    "total":719
  },
  "value":719
},
{
  "name": "NetThroughput",
  "capacity":{
    "max":3072000,
    "min":3072000,
    "avg":3072000,
    "total":3072000
  },
  "filters":[
    {
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238a511-8593-4469-2751-46611e09b6a8",
    "displayName": "hp-esx1.dev.mycorp.com",
    "className": "PhysicalMachine"
```



```
},
  "units": "Kbit/sec",
  "values":{
    "max":0,
    "min":0,
    "avg":0,
    "total":0
  },
  "value":0
},
{
  "name": "MemAllocation",
  "capacity":{
    "max":52503552,
    "min":52503552,
    "avg":52503552,
    "total":52503552
  },
  "filters":[
    {
      "type": "key",
      "value": "VirtualDataCenter::2332ba0f9dc14c07f11adb38e12df43c4bc8ca56"
    },
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "2332ba0f9dc14c07f11adb38e12df43c4bc8ca56",
    "displayName": "olga_do_not_touch_1",
    "className": "VirtualDataCenter"
  },
  "units": "KB",
  "values":{
    "max":3069332,
    "min":3062497,
    "avg":3062497,
    "total":3062497
  },
  "value":3062497
},
  "name": "VCPU",
  "capacity":{
    "max":5200,
    "min":5200,
    "avg":5200,
    "total":5200
  },
  "filters":[
      "type": "relation",
      "value": "sold"
```



```
}
  ],
  "units": "MHz",
  "values":{
    "max":5203,
    "min":5194.67,
    "avg":5194.67,
    "total":5194.67
  },
  "value":5194.67
},
  "name": "Ballooning",
  "capacity":{
    "max":16776692,
    "min":16776692,
    "avg":16776692,
    "total":16776692
  },
  "filters":[
    {
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238a511-8593-4469-2751-46611e09b6a8",
    "displayName": "hp-esx1.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "units": "KB",
  "values":\{
    "max":0,
    "min":0,
    "avg":0,
    "total":0
  },
  "value":0
},
  "name": "StorageAccess",
  "capacity":{
    "max":5000,
    "min":5000,
    "avg":5000,
    "total":5000
  },
  "filters":[
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
```



```
"uuid":"6f76b47e-e6f0a3fe",
    "displayName":"QSGRID01:ESXDC1DS1",
    "className": "Storage"
  },
  "units": "IOPS",
  "values":\{
    "max":0,
    "min":0,
    "avg":0,
    "total":0
  },
  "value":0
},
  "name": "CPUAllocation",
  "capacity":{
   "max":31096,
    "min":31096,
    "avg":31096,
    "total":31096
  },
  "filters":[
   {
      "type": "key",
      "value": "VirtualDataCenter::2332ba0f9dc14c07f11adb38e12df43c4bc8ca56"
   },
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "2332ba0f9dc14c07f11adb38e12df43c4bc8ca56",
    "displayName": "olga_do_not_touch_1",
    "className": "VirtualDataCenter"
  },
  "units": "MHz",
  "values":{
   "max":5203,
    "min":5194.67,
    "avg":5194.67,
    "total":5194.67
  },
  "value":5194.67
},
  "name": "IOThroughput",
  "capacity":{
   "max":11264000,
    "min":11264000,
    "avg":11264000,
    "total":11264000
  },
  "reserved":{
```



```
"max":9011200,
    "min":9011200,
    "avg":9011200,
    "total":9011200
  },
  "filters":[
    {
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238a511-8593-4469-2751-46611e09b6a8",
    "displayName": "hp-esx1.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "units": "Kbit/sec",
  "values":{
    "max":0,
    "min":0,
    "avg":0,
    "total":0
  },
  "value":0
},
  "name": "StorageLatency",
  "capacity":{
    "max":100,
    "min":100,
    "avg":100,
    "total":100
  },
  "filters":[
    {
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid":"6f76b47e-e6f0a3fe",
    "displayName":"QSGRID01:ESXDC1DS1",
    "className": "Storage"
  },
  "units": "msec",
  "values":{
    "max":0.33,
    "min":0.33,
    "avg":0.33,
    "total":0.33
  },
  "value":0.33
},
{
```



```
"name":"Q2VCPU",
  "capacity":{
    "max":20000,
    "min":20000,
    "avg":20000,
    "total":20000
  },
  "reserved":{
    "max":10000,
    "min":10000,
    "avg":10000,
    "total":10000
  },
  "filters":[
    {
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238a511-8593-4469-2751-46611e09b6a8",
    "displayName": "hp-esx1.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "units": "msec",
  "values":{
    "max":11,
    "min":11,
    "avg":11,
    "total":11
  },
  "value":11
},
  "name":"VMem",
  "capacity":{
    "max":4194304,
    "min":4194304,
    "avg":4194304,
    "total":4194304
  },
  "filters":[
      "type": "relation",
      "value": "sold"
    }
  "units":"KB",
  "values":{
    "max":2894068,
    "min":2747267,
    "avg":2747267,
    "total":2747267
  },
```



```
"value":2747267
},
  "name": "CPU",
  "capacity":{
    "max":10400,
    "min":10400,
    "avg":10400,
    "total":10400
  },
  "filters":[
      "type": "relation",
      "value": "bought"
    }
  ],
  "relatedEntity":{
    "uuid": "Virtual_ESX_4238a511-8593-4469-2751-46611e09b6a8",
    "displayName": "hp-esx1.dev.mycorp.com",
    "className": "PhysicalMachine"
  },
  "units": "MHz",
  "values":{
    "max":5203,
    "min":5194.67,
    "avg":5194.67,
    "total":5194.67
  },
  "value":5194.67
},
{
  "name": "VStorage",
  "capacity":{
    "max":2646,
    "min":1014,
    "avg":2238,
    "total":8952
  },
  "filters":[
    {
      "type": "key",
      "value": "VirtualMachine::199bb3ec4f8da89f01c126a6b3df4c1321c4b07d"
    },
    {
      "type": "relation",
      "value": "sold"
    }
  ],
  "units": "MB",
  "values":\{
    "max":1016.01,
    "min":142.4,
    "avg":797.61,
    "total":3190.42
```



Reference: Tables

Reference Tables Overview

This section contains reference tables for common API parameters, separated by endpoint. Note that filter tables may contain other reference tables for completeness.

Action Reference Tables

Action Mode:

■ DISABLED:

Do not recommend or perform the action. When you disable an action, the user interface will no longer display actions of that type.

■ RECOMMENDED:

Recommend the action so a user can execute it via the given hypervisor or by other external means

■ MANUAL:

Recommend the action, and provide the option to execute that action through the Workload Optimization Manager user interface or an /actions API request.

■ AUTOMATED:

You have directed Workload Optimization Manager to execute the action automatically.

■ COLLECTION (UNUSED):

Legacy action mode, no longer used.

Action State:

■ DISABLED:

An action whose policy has been disabled.

■ RECOMMEND:

An action that cannot be automated due to policy settings or must be executed outside the system, such as the purchase of hardware.

■ PENDING_ACCEPT:

When the action mode is set to manual, a recommended action that has not been accepted or cleared.

■ ACCEPTED

An action that has been accepted, but is not yet in progress.

■ IN_PROGRESS:

An action that is being executed.



■ SUCCEEDED:

An action that was accepted and completed successfully.

■ FAILED:

An action that was accepted and did not complete successfully.

■ REJECTED:

When the action mode is set to manual, an action that has been rejected by the user.

CLEARED:

When the action mode is set to manual, an action that is no longer recommended by the market.

■ ACCOUNTING:

For cloud entities, an action to resize in order to use a different instance template.

■ QUEUED:

When more than 10 actions are to be executed for a single target, Workload Optimization Manager will place the 11th and all subsequent actions into a QUEUED state, and they will execute as the previous actions complete.

Action Type:

■ START:

Start an entity, and add it to the Workload Optimization Manager market.

■ MOVE:

Move an entity from one provider to another. For example, moving a VM between hosts, or a datastore between disk arrays.

■ SUSPEND:

Suspend the entity to exclude its capacity from your environment. Suspend does not remove the entity from your environment, but the market does not include the entity in its analysis. Based on market conditions, analysis can recommend restarting suspended entities, which includes them in market analysis once again.

■ ADD PROVIDER:

This is equivalent to the START action, but for storage entities.

CHANGE:

Move a virtual machine's storage between datastores.

■ PROVISION:

Add capacity to your environment.

■ RECONFIGURE:

Analysis recommends this when a VM is not able to correct a misconfiguration via another type of action. For example, analysis can recommend a RECONFIGURE action when a placement policy requires a VM to move to a host on a particular cluster, but cross-cluster moves are not permitted.

■ DELETE:

This is equivalent to the SUSPEND action, but for storage entities.

■ RESERVE_ON_PM:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular host.

■ RESERVE_ON_DS:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular datastore.

■ RESIZE_FOR_EFFICIENCY:

A resize that reduces the capacity of a commodity, such as vCPU, or vMEM.

■ RESIZE_FOR_PERFORMANCE:

A resize that increases the capacity of a commodity, such as vCPU, or vMEM.

Action Filter Criteria:

- actionModeList
 - DISABLED:

Do not recommend or perform the action. When you disable an action, the user interface will no longer display actions of that type.



RECOMMENDED:

Recommend the action so a user can execute it via the given hypervisor or by other external means

– MANUAL:

Recommend the action, and provide the option to execute that action through the Workload Optimization Manager user interface or an /actions API request.

AUTOMATED:

You have directed Workload Optimization Manager to execute the action automatically.

COLLECTION (UNUSED):

Legacy action mode, no longer used.

actionStateList

- DISABLED:

An action whose policy has been disabled.

- RECOMMEND:

An action that cannot be automated due to policy settings or must be executed outside the system, such as the purchase of hardware.

- PENDING_ACCEPT:

When the action mode is set to manual, a recommended action that has not been accepted or cleared.

ACCEPTED:

An action that has been accepted, but is not yet in progress.

- IN PROGRESS:

An action that is being executed.

SUCCEEDED:

An action that was accepted and completed successfully.

– FAILED:

An action that was accepted and did not complete successfully.

REJECTED:

When the action mode is set to manual, an action that has been rejected by the user.

CLEARED:

When the action mode is set to manual, an action that is no longer recommended by the market.

- ACCOUNTING:

For cloud entities, an action to resize in order to use a different instance template.

OUEUED:

When more than 10 actions are to be executed for a single target, Workload Optimization Manager will place the 11th and all subsequent actions into a QUEUED state, and they will execute as the previous actions complete.

actionTypeList

- START:

Start an entity, and add it to the Workload Optimization Manager market.

- MOVE:

Move an entity from one provider to another. For example, moving a VM between hosts, or a datastore between disk arrays.

- SUSPEND:

Suspend the entity to exclude its capacity from your environment. Suspend does not remove the entity from your environment, but the market does not include the entity in its analysis. Based on market conditions, analysis can recommend restarting suspended entities, which includes them in market analysis once again.

- ADD PROVIDER:

This is equivalent to the START action, but for storage entities.

CHANGE:



Move a virtual machine's storage between datastores.

- PROVISION:

Add capacity to your environment.

- RECONFIGURE:

Analysis recommends this when a VM is not able to correct a misconfiguration via another type of action. For example, analysis can recommend a RECONFIGURE action when a placement policy requires a VM to move to a host on a particular cluster, but cross-cluster moves are not permitted.

DELETE:

This is equivalent to the SUSPEND action, but for storage entities.

RESERVE ON PM:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular host.

- RESERVE_ON_DS:

When using the reservation functionality, this is the action to reserve the resources of a VM on a particular datastore.

- RESIZE_FOR_EFFICIENCY:

A resize that reduces the capacity of a commodity, such as vCPU, or vMEM.

- RESIZE FOR PERFORMANCE:

A resize that increases the capacity of a commodity, such as vCPU, or vMEM.

cleared

Default: false.

When true, actions that were removed from the action list before being executed will be returned.

■ costType

- Saving

An action that will decrease cloud spending.

Investment

An action that will increase cloud spending.

cumulative

Default: false.

When true, shows the savings for each action in a scope as a cumulative total, rather than showing the savings for individual actions.

environmentType

ONPREM:

Returns only actions related to entities that are part of your on-premises environment.

- CLOUD:

Returns only actions related to entities that are part of your cloud environment.

■ groupBy

You may group the actions returned by the following criteria: [actionModes, actionStates, actionTypes, risk, riskSeverity, riskSubCategory]

hasReservedInstance

Default: false.

When true, only actions that are related to reserved instances will be returned.

relatedEntityTypes

Returns only actions related to entities of these types within the scope. For example, if your scope is a virtual datacenter and you specify VirtualMachine as a related entity type, the request will include only those actions related to VMs in the specified virtual datacenter.

Choose from the following entity types: [Datacenter, PhysicalMachine, VirtualMachine, Storage, Application, Chassis, DiskArray, IOModule, StorageControl, Switch, VirtualDataCenter, VPod, DPod, Container, Database, DatabaseServerContainer, LogicalPool]



riskSeverityList

Returns only actions of the given severities: [Unknown, Normal, Minor, Major, Critical]

- riskSubCategoryList
- returns only actions of the given subcategories: [Performance Assurance, Efficiency Improvement, Prevention, Compliance]

Entity Reference Tables

Entity State:

■ ACTIVE:

Entity is actively consuming resources.

■ EVACUATED:

Entity is ready to suspend and will not participate in the market, but will not generate a SUSPEND action.

NOTE: This state replaces the SUSPEND state, and requires additional configuration to enable. Workload Optimization Manager does not recommend enabling this state.

■ FAILOVER:

This entity is reserved for failover and will not participate in the market.

■ IDLE:

Entity is powered off and not actively consuming market resources.

■ LAUNCH:

Entity is starting.

■ MAINTENANCE:

Entity is in maintenance mode.

■ NOT_MONITORED:

Entity is not currently monitored by Workload Optimization Manager.

QUEUED:

Entity is in the process of changing from one state to another.

NOTE: This state is internal to Workload Optimization Manager and will not appear in the UI, but may appear in an API response if the call is executed at the precise moment the entity is changing state.

■ RESOURCE_ALLOCATION:

Cloud entity is being created.

■ RESOURCE_RELEASE:

Cloud Entity is being deleted.

■ SUSPEND:

Entity is suspended or the guest OS is in sleep, standby, or suspended state. The entity is not removed from the environment, but will not be used in market decisions. Based on market conditions, suspended entities can be started, readding them to the market.

■ SUSPEND PENDING:

Entity is making preparations to suspend, or is the next entity of its type to suspend.

■ TERMINATE PENDING:

Entity is in the process of being deleted.

UNKNOWN:

Workload Optimization Manager is unable to obtain the current state of the entity.

This occurs when the entity is reported to the hypervisor as having a state of <code>DISCONNECTED</code>, <code>ORPHANED</code>, or <code>INVALID</code>.

Entity Type:

- APPLICATION
- APPLICATION_SERVER



- BUSINESS_ACCOUNT
- BUSINESS_UNIT
- CHASSIS
- CLOUD_SERVICE
- CONTAINER
- CONTAINER_POD
- DATABASE
- DATABASE_SERVER
- DATACENTER
- DISK_ARRAY
- DPOD
- IO MODULE
- LOAD_BALANCER
- LOGICAL POOL
- NETWORK
- PHYSICAL MACHINE
- STORAGE
- STORAGE_CONTROLLER
- SWITCH
- VIRTUAL_APPLICATION
- VIRTUAL_DATACENTER
- VIRTUAL_MACHINE
- VPOD

Reference: DTO Index

Data transfer objects (DTOs) are used to encapsulate and send data to the Workload Optimization Manager API. The following DTOs are used by Workload Optimization Manager:

NOTE:

The DTO Index is a work in progress, and included in a draft stage for reference. The information contained in the Index is accurate, but may not be complete.

ActionApiDTO

Description

Model to describe an Action

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string



actionImpactID

type: integerformat: int64

description: The ID for the action, which will persist across restarts

marketID

type: integerformat: int64

description: The ID of the market for which the action was generated

createTime

type: string

description: Creation time

updateTime

type: string

description: Update time

clearTime

■ type: string

description: Execution time

actionType

■ type: string

description: Type

enum: ['START', 'MOVE', 'SCALE', 'ALLOCATE', 'SUSPEND', 'PROVISION', 'RECONFIGURE', 'RESIZE', 'DELETE', 'RIGHT_SIZE', 'BUY_RI']

actionState

■ type: string

description: Action State

enum: ['PENDING_ACCEPT', 'ACCEPTED', 'REJECTED', 'PRE_IN_PROGRESS', 'POST_IN_PROGRESS', 'IN_PROGRESS', 'SUCCEEDED', 'FAILED', 'RECOMMENDED', 'DISABLED', 'QUEUED', 'CLEARED', 'ACCOUNTING', 'READY', 'FAILING']

actionMode

■ type: string

description: Action Mode

enum: ['DISABLED', 'RECOMMEND', 'EXTERNAL_APPROVAL', 'MANUAL', 'AUTOMATIC', 'COLLECTION']

userName

type: string

 description: Username of the user that accepted the action [DEPRECATED - Use: userInfo.userName or scheduleInfo.scheduleName in executionStatus.executorInfo]

details

type: string

description: A user-readable string describing the action

importance

type: numberformat: float

description: Numeric value that describes the priority of the action

target

description: Target entity for an action. For example, the VM in a Resize Action, or the host for a VM move

■ ServiceEntityApiDTO (on page 1205)



currentEntity

- description: Current entity, such as the current host that a VM resides on for a VM move action
- ServiceEntityApiDTO (on page 1205)

newEntity

- description: Destination entity, such as the host that a VM will move to for a VM move action
- ServiceEntityApiDTO (on page 1205)

currentValue

- type: string
- description: Current value of a property, for example vMEM for a VM resize action

newValue

- type: string
- description: Calculated value to resize to, such as vMEM for a VM resize action

valueUnits

- type: string
- description: Units of the currentValue and newValue, such as KB for a VM vMEM resize action

resizeAttribute

- type: string
- description: The commodity attribute to be resized
- enum: ['CAPACITY', 'LIMIT', 'RESERVATION']

template

- description: Template used for the action, such as in a Cloud entity provision or move action
- TemplateApiDTO (on page 1230)

risk

- description: Cause of the action
- LogEntryApiDTO (on page 1145)

prerequisites

- type: array
- description: Description(s) of any prerequisite(s) that must occur before execution is possible. If this field is populated, the action would otherwise be executable but has been blocked by this prerequisite, and is displayed accordingly. If this field is not populated, no prerequisite has caused the action mode to be modified, and the action is displayed as normal.
- type: string

prioritizedAutomationOpportunities

- type: array
- description: The Action is generated using the 'Prioritze Automation' setting, indicating that it is possible to have more savings if these opportunities are satisfied
- type: string

stats

- type: array
- description: Statistics, such as Mem, vCPU, costPrice
 - StatApiDTO (on page 1216)

progress

- type: integerformat: int32
- description: Moved the 'progress' percentage value inside 'executionStatus', available when action detail level is 'EXECUTION' - [DEPRECATED - Use: executionStatus.progress]



currentLocation

- description: The region (DataCenter) where the current service entity is located, for cloud migration actions
- DiscoveredEntityApiDTO (on page 1124)

newLocation

- description: The region, represented as a DataCenter entity, where the target service entity will be located for cloud migration actions
- DiscoveredEntityApiDTO (on page 1124)

virtualDisks

- type: array
- description: Virtual Disk used for the action, for example in a storage move
- VirtualDiskApiDTO (on page 1242)

policy

- description: The policy associated with the action
- PolicyApiDTO (on page 1169)

relatedSettingsPolicies

- type: array
- description: The related settings policies associated with the action
- BaseApiDTO (on page 1088)

actionSchedule

- description: The schedule associated with the action
- ActionScheduleApiDTO (on page 1082)

compoundActions

- type: array
- description: Property for compound move actions
- ActionApiDTO (on page 1071)

reservedInstance

- description: The Reserved Instance associated with the action
- ReservedInstanceApiDTO (on page 1190)

reservedInstancePlatform

- type: string
- description: The platform of the recommended RI if the action has a supersaving

externalActionName

- type: string
- description: The name under which this action appears in third-party software or external approval backend

externalActionUrl

- tvpe: string
- description: URL to third-party software showing this action. Suitable for external action approval

executionStatus

- description: Status details of the execution of the Action. Include percentage progress, error messages and execution times.
- ActionExecutionAuditApiDTO (on page 1078)

executionCharacteristics

- description: Characteristics of the execution of the Action. Include disruptiveness and reversibility.
- ActionExecutionCharacteristicApiDTO (on page 1079)



relatedActionsCountByType

- type: object
- description: [BETA]: Map of related actions count by relationship type that have some relation to this Action
- additionalProperties: {'type': 'integer', 'format': 'int32'}

actionID

- type: integerformat: int64
- description: Id of the action

ActionApiInputDTO

Description

Model to describe a Filter for Actions

Required Parameters

startTime

- type: string
- description: Start time of the period to filter, based on Actions Creation Time

Optional Parameters

actionRelationTypeFilter

- type: array
- description: Filters the main list of actions based on the types of relationships they have to other actions.
- type: string
 - enum: ['NONE', 'BLOCKED_BY', 'BLOCKING', 'CAUSED_BY', 'CAUSING']

environmentType

- type: string
- description: Filter the actions by Environment Type
- enum: ['ONPREM', 'CLOUD']

costType

- type: string
- description: Filter the actions by cost Type
- enum: ['SAVING', 'INVESTMENT']

descriptionQuery

- description: This query will match the details field of the ActionApiDTO to return actions that match the specified expression.
- QueryInputApiDTO (on page 1178)

riskQuery

- description: This query will match the risk description field of the ActionApiDTO to return actions that match the specified expression.
- QueryInputApiDTO (on page 1178)

executionCharacteristics

- description: Characteristics of the execution of the action, including disruptiveness and reversibility.
- ActionExecutionCharacteristicInputApiDTO (on page 1079)



savingsAmountRange

- description: This field will match the costPrice statistic field of the ActionApiDTO to return actions that have a
 costPrice amount between minValue and maxValue, inclusive
- RangeInputApiDTO (on page 1180)

hasSchedule

- type: boolean
- description: If true, only actions that have an associated execution schedule will be returned.

hasPrerequisites

- type: boolean
- description: If true, only actions that have a prerequisite preventing execution of the action will be returned.

endTime

- type: string
- description: End time of the period to filter, based on Actions Creation Time

cleared

- type: boolean
- description: Filter by Actions Executed

cumulative

- type: boolean
- description: Show the action savings as cumulative values

hasReservedInstance

- type: boolean
- description: Filter the actions by whether having related reserved instance

excludeNotifications

- type: boolean
- description: Exclude the notifications from the result

limitEntities

- type: integer
- format: int32
- description: Limit number of entities in the result

detailLevel

- type: string
- description: Detail level of the Action, 'standard' is the default value
- enum: ['STANDARD', 'EXECUTION']

relatedEntityTypes

- type: array
- example: Selecting a VCD, and specifying '"related_entities": ["VirtualMachine"] will include the actions for any VM in the given VDC
- description: Related Entity Types to include from the supply chain for this entity
- tvpe: string

targetEntityTypes

- type: array
- example: Specifying "target_entities": ["VirtualMachine"] will include the actions where the target entity is a VM.
- description: Filter the actions where the target entity of the action matches the provided list of entity types
- type: string



relatedCloudServiceProviderIds

■ type: array

description: Filter the actions by the related Cloud Service Providers.

type: string

groupBy

■ type: array

description: Fields used to Group the Stats

type: string

instanceTypeFilter

- description: Filter the actions based on a list of Instance Type Uuids.
- InstanceTypeFilterApiDTO (on page 1140)

onDemandCostFilter

- description: Filter the actions based on a on-demand cost range.
- OnDemandCostFilterApiDTO (on page 1154)

actionTypeList

- type: array
- type: string
 - enum: ['NONE', 'START', 'MOVE', 'SCALE', 'ALLOCATE', 'SUSPEND', 'TERMINATE', 'SPAWN', 'ADD_PROVIDER', 'CHANGE', 'REMOVE_PROVIDER', 'PROVISION', 'RECONFIGURE', 'RESIZE', 'RESIZE_CAPACITY', 'WARN', 'RECONFIGURE_THRESHOLD', 'DELETE', 'RIGHT_SIZE', 'RESERVE_ON_PM', 'RESERVE_ON_DS', 'RESIZE_FOR_EFFICIENCY', 'RESIZE_FOR_PERFORMANCE', 'CROSS_TARGET_MOVE', 'MOVE_TOGETHER', 'ACTIVATE', 'DEACTIVATE', 'BUY_RI']

actionStateList

- type: array
- type: string
 - enum: ['PENDING_ACCEPT', 'ACCEPTED', 'REJECTED', 'PRE_IN_PROGRESS', 'POST_IN_PROGRESS', 'IN_PROGRESS', 'SUCCEEDED', 'FAILED', 'RECOMMENDED', 'DISABLED', 'QUEUED', 'CLEARED', 'ACCOUNTING', 'READY', 'FAILING']

actionModeList

- type: array
- - type: string
 - enum: ['DISABLED', 'RECOMMEND', 'EXTERNAL_APPROVAL', 'MANUAL', 'AUTOMATIC', 'COLLECTION']

riskSeverityList

- type: array
- - type: string

riskSubCategoryList

- type: array
- type: string

ActionDetailsApiDTO

Description

Parent class for action details. Implementing classes include: CloudResizeActionDetailsApiDTO, NoDetailsApiDTO, RIBuyActionDetailsApiDTO, CloudProvisionActionDetailsApiDTO, CloudSuspendActionDetailsApiDTO, OnPremResizeActionDetailsApiDTO and ReconfigureActionDetailsApiDTO.



Required Parameters

actionDetailType

■ type: string

actionType

■ type: string

ActionExecutionApiDTO

Description

Model to describe an Action Execution.

Required Parameters

acceptTime

- type: string
- description: Time when actions were accepted (in ISO8601 format YYYY-MM-DDTHH:MM:SS)

actionIds

- type: array
- description: List of action IDs
- - **type:** string
- maxItems: 2147483647
- minItems: 1

id

- type: string
- description: Action Execution ID

skippedActions

- type: array
- description: List of actions that were skipped in execution
- SkippedActionApiDTO (on page 1215)

ActionExecutionAuditApiDTO

Description

Model to describe an Action Execution status.

Required Parameters

executionTime

- type: string
- description: Start of the execution time

executorInfo

- description: Information about the executor
- **ExecutorInfoApiDTO** (on page 1128)



state

- type: string
- description: State of the execution
- enum: ['PENDING_ACCEPT', 'ACCEPTED', 'REJECTED', 'PRE_IN_PROGRESS', 'POST_IN_PROGRESS', 'IN_PROGRESS', 'SUCCEEDED', 'FAILED', 'RECOMMENDED', 'DISABLED', 'QUEUED', 'CLEARED', 'ACCOUNTING', 'READY', 'FAILING']

Optional Parameters

completionTime

- type: string
- description: End of the execution time

message

- type: string
- description: Status message, if the Action failed, it will contains the Error details

progress

- type: integerformat: int32
- **description:** Action execution progress value, from 0 to 100

ActionExecutionCharacteristicApiDTO

Description

Model to describe action execution characteristics

Optional Parameters

disruptiveness

- type: string
- description: whether action is disruptive.
- enum: ['DISRUPTIVE', 'NON_DISRUPTIVE']

reversibility

- **type:** string
- description: whether action is reversible.
- enum: ['REVERSIBLE', 'IRREVERSIBLE']

ActionExecutionCharacteristicInputApiDTO

Description

Model to describe action execution characteristics

Optional Parameters

disruptiveness

- type: string
- description: whether action is disruptive.
- enum: ['DISRUPTIVE', 'NON_DISRUPTIVE']



reversibility

■ type: string

description: whether action is reversible.

■ enum: ['REVERSIBLE', 'IRREVERSIBLE']

ActionExecutionInputApiDto

Description

Model to describe an Action Execution input.

Required Parameters

actionIds

■ type: array

description: List of action IDs

type: string

maxItems: 2147483647

minItems: 1

ActionResourceImpactStatApiInputDTO

Description

Model to describe an input for Action Resource Impact Stats

Required Parameters

actionResourceImpactStatList

■ type: array

description: List of Action Resource Impact Stat Inputs

ActionResourceImpactStatInput (on page 1081)

Optional Parameters

action Relation Type Filter

type: array

description: Filters the main list of actions based on the types of relationships they have to other actions.

type: string

enum: ['NONE', 'BLOCKED_BY', 'BLOCKING', 'CAUSED_BY', 'CAUSING']

environmentType

■ type: string

description: Filter the actions by Environment Type

enum: ['ONPREM', 'CLOUD']

costType

type: string

description: Filter the actions by cost Type

■ enum: ['SAVING', 'INVESTMENT']



descriptionQuery

- description: This query will match the details field of the ActionApiDTO to return actions that match the specified expression.
- QueryInputApiDTO (on page 1178)

riskQuery

- description: This query will match the risk description field of the ActionApiDTO to return actions that match the specified expression.
- QueryInputApiDTO (on page 1178)

executionCharacteristics

- description: Characteristics of the execution of the action, including disruptiveness and reversibility.
- ActionExecutionCharacteristicInputApiDTO (on page 1079)

savingsAmountRange

- description: This field will match the costPrice statistic field of the ActionApiDTO to return actions that have a costPrice amount between minValue and maxValue, inclusive
- RangeInputApiDTO (on page 1180)

hasSchedule

- type: boolean
- description: If true, only actions that have an associated execution schedule will be returned.

hasPrerequisites

- type: boolean
- **description:** If true, only actions that have a prerequisite preventing execution of the action will be returned.

actionStateList

- type: array
- type: string
 - enum: ['PENDING_ACCEPT', 'ACCEPTED', 'REJECTED', 'PRE_IN_PROGRESS', 'POST_IN_PROGRESS', 'IN_PROGRESS', 'SUCCEEDED', 'FAILED', 'RECOMMENDED', 'DISABLED', 'QUEUED', 'CLEARED', 'ACCOUNTING', 'READY', 'FAILING']

actionModeList

- type: array
- type: string
 - enum: ['DISABLED', 'RECOMMEND', 'EXTERNAL_APPROVAL', 'MANUAL', 'AUTOMATIC', 'COLLECTION']

riskSeverityList

- type: array
 - type: string

riskSubCategoryList

- type: array
- type: string

ActionResourceImpactStatInput

Description

Model to describe an Action Resource Impact Stat Input



Required Parameters

actionType

- type: string
- description: Action Type
- enum: ['NONE', 'START', 'MOVE', 'SCALE', 'ALLOCATE', 'SUSPEND', 'TERMINATE', 'SPAWN', 'ADD_PROVIDER', 'CHANGE', 'REMOVE_PROVIDER', 'PROVISION', 'RECONFIGURE', 'RESIZE', 'RESIZE_CAPACITY', 'WARN', 'RECONFIGURE_THRESHOLD', 'DELETE', 'RIGHT_SIZE', 'RESERVE_ON_PM', 'RESERVE_ON_DS', 'RESIZE_FOR_EFFICIENCY', 'RESIZE_FOR_PERFORMANCE', 'CROSS_TARGET_MOVE', 'MOVE_TOGETHER', 'ACTIVATE', 'DEACTIVATE', 'BUY_RI']

commodityType

- type: string
- example: VCPU
- description: Commodity Type that could be impacted by the action. For example, VCPU or VMEM for a Resize VM action.
- enum: ['ACTION_PERMIT', 'ACTIVE_SESSIONS', 'APPLICATION', 'BALLOONING', 'BUFFER_COMMODITY', 'CLUSTER', 'COLLECTION_TIME', 'COOLING', 'CONNECTION', 'COUPON', 'CPU', 'CPU_ALLOCATION', 'CPU_PROVISIONED', 'CPU_REQUEST_ALLOCATION', 'CROSS_CLOUD_MOVE_SVC', 'CROSS_CLUSTER_MOVE_SVC', 'DATACENTER', 'DATASTORE', 'DB_CACHE_HIT_RATE', 'DB_MEM', 'DISK_ARRAY_ACCESS', 'DRS_SEGMENTATION', 'DSPM_ACCESS', 'EXTENT', 'FLOW', 'FLOW_ALLOCATION', 'HEAP', 'HOST_LUN_ACCESS', 'IMAGE_CPU', 'IMAGE_MEM', 'IMAGE_STORAGE', 'INSTANCE_DISK_SIZE', 'INSTANCE_DISK_TYPE', 'IO_THROUGHPUT', 'LICENSE_ACCESS', 'MEM', 'MEM_ALLOCATION', 'MEM_REQUEST_ALLOCATION', 'MEM_PROVISIONED', 'NET_THROUGHPUT', 'NETWORK', 'NUM_DISK', 'NUMBER_CONSUMERS', 'NUM_VCORE', 'POOL_CPU', 'POOL_MEM', 'POOL_STORAGE', 'PORT_CHANNEL', 'POWER', 'Q16 VCPU', 'Q1 VCPU', 'Q2 VCPU', 'Q32 VCPU', 'Q4 VCPU', 'Q64 VCPU', 'Q8 VCPU', 'RESPONSE TIME'. 'SAME CLUSTER MOVE SVC'. 'SEGMENTATION'. 'SLA COMMODITY'. 'SOFTWARE_LICENSE_COMMODITY', 'SPACE', 'STORAGE_ACCESS', 'STORAGE_ALLOCATION', 'STORAGE AMOUNT', 'STORAGE CLUSTER', 'STORAGE LATENCY', 'STORAGE PROVISIONED', 'SWAPPING', 'THREADS', 'TRANSACTION', 'TRANSACTION_LOG', 'VCPU', 'VCPU_LIMIT_QUOTA', 'VCPU_REQUEST', 'VCPU_REQUEST_QUOTA', 'VDC', 'VMEM', 'VMEM_LIMIT_QUOTA', 'VMEM_REQUEST', 'VMEM_REQUEST_QUOTA', 'VMPM_ACCESS', 'VSTORAGE', 'ZONE', 'LICENSE_COMMODITY' 'Q3_VCPU', 'NUMBER_CONSUMERS_PM', 'Q6_VCPU', 'Q7_VCPU', 'QN_VCPU', 'RIGHT_SIZE_SVC' 'RIGHT_SIZE_DOWN', 'MOVE', 'Q5_VCPU', 'STORAGE', 'NUMBER_CONSUMERS_STORAGE', 'ACCESS', 'RIGHT_SIZE_UP', 'VAPP_ACCESS', 'HOT_STORAGE', 'HA_COMMODITY', 'NETWORK_POLICY', 'SERVICE_LEVEL_CLUSTER', 'PROCESSING_UNITS', 'TENANCY_ACCESS', 'TEMPLATE_ACCESS' 'BURST_BALANCE', 'DESIRED_COUPON', 'NETWORK_INTERFACE_COUNT', 'BICLIQUE', 'TAINT', 'LABEL', 'UNKNOWN']

targetEntityType

- type: string
- description: Target entity type for an action. For example, VirtualMachine for a resize virtual machine action
- enum: ['ApplicationComponent', 'VirtualMachine', 'Storage', 'DiskArray', 'Database', 'DatabaseServer', 'Container', 'LogicalPool']

ActionScheduleApiDTO

Description

Model to describe an Action Schedule.

Optional Parameters

uuid

type: string



displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

nextOccurrence

- type: string
- description: The time of the next occurrence represented in ISO8601 local time (YYYY-MM-DDTHH:MM:SS).
 For example, 2019-04-04T19:15.

nextOccurrenceTimestamp

- type: integerformat: int64
- description: The time of the next occurrence of this schedule represented in Timestamp in milliseconds. For example, 1562100619000

timeZoneId

- type: string
- description: The timezone of the schedule

mode

- type: string
- description: The action mode affected by the schedule
- enum: ['DISABLED', 'RECOMMEND', 'EXTERNAL_APPROVAL', 'MANUAL', 'AUTOMATIC', 'COLLECTION']

acceptedByUserForMaintenanceWindow

- type: boolean
- description: Boolean signifying acceptance or rejection of the action.

userName

- type: string
- **description:** The user who accepted the action for the maintenance window.

remaingTimeActiveInMs

- type: integerformat: int64
- description: The amount of time that the schedule is going to be active at the time of call in milliseconds. This field will not be populated if the schedule is not currently active.

ActionScopesApiInputDTO

Description

Model to describe the request for Actions in multiple Scopes

Required Parameters

actionInput

- description: List of requested actions
- ActionApilnputDTO (on page 1075)



Optional Parameters

scopes

type: array

description: List of uuid to use as scope

type: string

relatedType

■ type: string

description: Get the actions for the entity type related to the scopes

ActionScopesResourceImpactStatApiInputDTO

Description

Model to describe the request for Actions Resource Impacts in multiple Scopes

Required Parameters

actionResourceImpactStatApiInput

description: Requested action resource impact stats

ActionResourceImpactStatApiInputDTO (on page 1080)

scopes

type: array

description: List of uuid to use as scope

■ - type: string

ActiveDirectoryApiDTO

Description

Model to describe an Active Directory. It contains domain name and server name which are global to Turbonomic server.

Optional Parameters

uuid

■ type: string

displayName

■ type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

domainName

type: string

description: The domain name of current active directory

loginProviderURI

■ type: string

description: The server name of current active directory



isSecure

■ type: boolean

description: The server name of current active directory

groups

type: array

description: Active directory groups defined in Ops Mgr for current active directory

ActiveDirectoryGroupApiDTO (on page 1085)

ActiveDirectoryGroupApiDTO

Description

Model to describe an Active Dierctory Group. Active Directory groups are used to manage user authentication. You can specify role and scope for the group, and any member of the AD group can log into Turbonomic with those privileges.

Optional Parameters

uuid

type: string

displayName

type: string

■ **description:** A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

type

type: string

description: The user type for current active directory group

roleName

type: string

description: The user role name of current active directory group

scope

type: array

description: The scope of current active directory group

■ - GroupApiDTO (on page 1132)

AddObjectApiDTO

Description

Model to describe an add change in the scenario



Optional Parameters

projectionDays

■ type: array

description: List of projection days, indicate when to apply the changes

type: integerformat: int32

target

description: Target of the change, entity or group

■ BaseApiDTO (on page 1088)

count

type: integerformat: int32

description: How many times to apply the add change

targetEntityType

■ type: string

description: Type of entity to add from group target

AggregateCommodityFieldApiDTO

Description

Inherits From

This DTO inherits from FieldApiDTO (on page 1130)

Required Parameters

aggregation

■ type: string

description: The type of aggregation.

readOnly: True

enum: ['TOTAL', 'AVERAGE']

commodityAttribute

type: string

description: The commodity attribute.

readOnly: True

• enum: ['USED', 'CAPACITY', 'PEAK', 'CURRENT_UTILIZATION', 'WEIGHTED_HISTORICAL_UTILIZATION', 'PERCENTILE_HISTORICAL_UTILIZATION']



commodityType

- type: string
- **description:** The commodity name.
- readOnly: True
- enum: ['ACTION PERMIT'. 'ACTIVE SESSIONS'. 'APPLICATION'. 'BALLOONING'. 'BUFFER COMMODITY'. 'CLUSTER', 'COLLECTION TIME', 'COOLING', 'CONNECTION', 'COUPON', 'CPU', 'CPU ALLOCATION', 'CPU PROVISIONED', 'CPU REQUEST ALLOCATION', 'CROSS CLOUD MOVE SVC', 'CROSS CLUSTER MOVE SVC'. 'DATACENTER'. 'DATASTORE'. 'DB CACHE HIT RATE'. 'DB MEM'. 'DISK_ARRAY_ACCESS', 'DRS_SEGMENTATION', 'DSPM_ACCESS', 'EXTENT', 'FLOW', 'FLOW_ALLOCATION', 'HEAP', 'HOST_LUN_ACCESS', 'IMAGE_CPU', 'IMAGE_MEM', 'IMAGE_STORAGE', 'INSTANCE_DISK_SIZE', 'INSTANCE DISK TYPE', 'IO THROUGHPUT', 'LICENSE ACCESS', 'MEM', 'MEM ALLOCATION' 'MEM_REQUEST_ALLOCATION', 'MEM_PROVISIONED', 'NET_THROUGHPUT', 'NETWORK', 'NUM_DISK' 'NUMBER_CONSUMERS', 'NUM_VCORE', 'POOL_CPU', 'POOL_MEM', 'POOL_STORAGE', 'PORT_CHANNEL', 'POWER', 'Q16_VCPU', 'Q1_VCPU', 'Q2_VCPU', 'Q32_VCPU', 'Q4_VCPU', 'Q64_VCPU', 'Q8_VCPU', 'RESPONSE_TIME', 'SAME_CLUSTER_MOVE_SVC', 'SEGMENTATION', 'SLA_COMMODITY', 'SOFTWARE_LICENSE_COMMODITY', 'SPACE', 'STORAGE_ACCESS', 'STORAGE_ALLOCATION', 'STORAGE_AMOUNT', 'STORAGE_CLUSTER', 'STORAGE_LATENCY', 'STORAGE_PROVISIONED', 'SWAPPING', 'THREADS', 'TRANSACTION', 'TRANSACTION_LOG', 'VCPU', 'VCPU_LIMIT_QUOTA', 'VCPU_REQUEST', 'VCPU_REQUEST_QUOTA', 'VDC', 'VMEM', 'VMEM_LIMIT_QUOTA', 'VMEM_REQUEST', 'VMEM_REQUEST_QUOTA', 'VMPM_ACCESS', 'VSTORAGE', 'ZONE', 'LICENSE_COMMODITY' 'Q3_VCPU', 'NUMBER_CONSUMERS_PM', 'Q6_VCPU', 'Q7_VCPU', 'QN_VCPU', 'RIGHT_SIZE_SVC' 'RIGHT_SIZE_DOWN', 'MOVE', 'Q5_VCPU', 'STORAGE', 'NUMBER_CONSUMERS_STORAGE', 'ACCESS', 'RIGHT_SIZE_UP', 'VAPP_ACCESS', 'HOT_STORAGE', 'HA_COMMODITY', 'NETWORK_POLICY', 'SERVICE_LEVEL_CLUSTER', 'PROCESSING_UNITS', 'TENANCY_ACCESS', 'TEMPLATE_ACCESS' 'BURST_BALANCE', 'DESIRED_COUPON', 'NETWORK_INTERFACE_COUNT', 'BICLIQUE', 'TAINT', 'LABEL', 'UNKNOWN']

AggregatedHealthResponseDTO

Description

A DTO for a single aggregated health response item.

Required Parameters

healthState

- type: string
- description: The (aggregated) health state for the subcategory.
- enum: ['CRITICAL', 'MAJOR', 'MINOR', 'NORMAL']

numberOfItems

- type: integer
- format: int32
- **description:** Number of entities whose state matches healthState.

subcategory

- type: string
- description: Health subcategory.

Optional Parameters

recommendations

- type: array
- **description:** A list of recommendations specific for each problem (error) type.
- Recommendation (on page 1182)



AutomatedEntityDefinitionData

Description

Inherits From

This DTO inherits from IEntityDefinitionData (on page 1137)

Required Parameters

entityType

- type: string
- description: Connected entity type
- enum: ['ApplicationComponent', 'BusinessTransaction', 'Container', 'ContainerPod', 'DatabaseServer', 'Service', 'VirtualMachine']

namePrefix

- type: string
- **description:** Naming prefix for automated entity definition

Optional Parameters

generationAndConnectionAttribute

- description: Defined criteria of connected entities
- FilterApiDTO (on page 1131)

BaseApiDTO

Description

Basic information of an entity

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

BaseCommodityApiDTO

Description

Describes a commodity



Required Parameters

type

type: string

description: The type of the commodity

enum: ['ACTION PERMIT', 'ACTIVE SESSIONS', 'APPLICATION', 'BALLOONING', 'BUFFER COMMODITY', 'CLUSTER', 'COLLECTION_TIME', 'COOLING', 'CONNECTION', 'COUPON', 'CPU', 'CPU_ALLOCATION', 'CPU_PROVISIONED', 'CPU_REQUEST_ALLOCATION', 'CROSS_CLOUD_MOVE_SVC', 'CROSS_CLUSTER_MOVE_SVC', 'DATACENTER', 'DATASTORE', 'DB_CACHE_HIT_RATE', 'DB_MEM', 'DISK_ARRAY_ACCESS', 'DRS_SEGMENTATION', 'DSPM_ACCESS', 'EXTENT', 'FLOW', 'FLOW_ALLOCATION', 'HEAP', 'HOST_LUN_ACCESS', 'IMAGE_CPU', 'IMAGE_MEM', 'IMAGE_STORAGE', 'INSTANCE_DISK_SIZE', 'INSTANCE_DISK_TYPE', 'IO_THROUGHPUT', 'LICENSE_ACCESS', 'MEM', 'MEM_ALLOCATION' 'MEM_REQUEST_ALLOCATION', 'MEM_PROVISIONED', 'NET_THROUGHPUT', 'NETWORK', 'NUM_DISK', 'NUMBER_CONSUMERS', 'NUM_VCORE', 'POOL_CPU', 'POOL_MEM', 'POOL_STORAGE', 'PORT_CHANNEL', 'POWER', 'Q16_VCPU', 'Q1_VCPU', 'Q2_VCPU', 'Q32_VCPU', 'Q4_VCPU', 'Q64_VCPU', 'Q8_VCPU', 'RESPONSE_TIME', 'SAME_CLUSTER_MOVE_SVC', 'SEGMENTATION', 'SLA_COMMODITY', 'SOFTWARE_LICENSE_COMMODITY', 'SPACE', 'STORAGE_ACCESS', 'STORAGE_ALLOCATION', 'STORAGE_AMOUNT', 'STORAGE_CLUSTER', 'STORAGE_LATENCY', 'STORAGE_PROVISIONED', 'SWAPPING', 'THREADS', 'TRANSACTION', 'TRANSACTION_LOG', 'VCPU', 'VCPU_LIMIT_QUOTA', 'VCPU_REQUEST', 'VCPU_REQUEST_QUOTA', 'VDC', 'VMEM', 'VMEM_LIMIT_QUOTA', 'VMEM_REQUEST', 'VMEM_REQUEST_QUOTA', 'VMPM_ACCESS', 'VSTORAGE', 'ZONE', 'LICENSE_COMMODITY', 'Q3_VCPU', 'NUMBER_CONSUMERS_PM', 'Q6_VCPU', 'Q7_VCPU', 'QN_VCPU', 'RIGHT_SIZE_SVC' 'RIGHT_SIZE_DOWN', 'MOVE', 'Q5_VCPU', 'STORAGE', 'NUMBER_CONSUMERS_STORAGE', 'ACCESS', 'RIGHT_SIZE_UP', 'VAPP_ACCESS', 'HOT_STORAGE', 'HA_COMMODITY', 'NETWORK_POLICY', 'SERVICE LEVEL CLUSTER', 'PROCESSING UNITS', 'TENANCY ACCESS', 'TEMPLATE ACCESS' 'BURST_BALANCE', 'DESIRED_COUPON', 'NETWORK_INTERFACE_COUNT', 'BICLIQUE', 'TAINT', 'LABEL', 'UNKNOWN']

Optional Parameters

kev

■ type: string

description: The specific commodity

units

■ type: string

description: The units in which the commodity is measured, if any

BaseGroupApiDTO

Description

Base model to describe a Group.

Optional Parameters

uuid

■ type: string

displayName

type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string



membersCount

type: integerformat: int32

description: Number of members of the Group

BasicActionApiDTO

Description

Model to tersely describe an action, providing only a set of basic fields

Optional Parameters

actionType

■ type: string

description: Type

enum: ['START', 'MOVE', 'SCALE', 'ALLOCATE', 'SUSPEND', 'PROVISION', 'RECONFIGURE', 'RESIZE', 'DELETE', 'RIGHT_SIZE', 'BUY_RI']

details

type: string

description: A user-readable string describing the action

target

- description: Target entity for an action. For example, the VM in a Resize Action, or the host for a VM move
- DiscoveredEntityApiDTO (on page 1124)

currentEntity

- description: Current entity, such as the current host that a VM resides on for a VM move action
- DiscoveredEntityApiDTO (on page 1124)

newEntity

- description: Destination entity, such as the host that a VM will move to for a VM move action
- DiscoveredEntityApiDTO (on page 1124)

actionID

type: integerformat: int64

description: Id of the action

BillingFamilyApiDTO

Description

Inherits From

This DTO inherits from GroupApiDTO (on page 1132)

Optional Parameters

masterAccountUuid

type: string

description: The UUID of the master account.



businessUnitApiDTOList

- type: array
- description: List of business units, for all accounts in this billing family.
- BusinessUnitApiDTO (on page 1092)

BooleanConditionApiDTO

Description

Inherits From

This DTO inherits from ConditionApiDTO (on page 1108)

Required Parameters

value

- type: boolean
- description: The value of the field must be equal to this boolean value
- readOnly: True

BooleanFieldValueApiDTO

Description

Inherits From

This DTO inherits from FieldValueApiDTO (on page 1130)

Required Parameters

value

- type: boolean
- description: The value.
- readOnly: True

BulkActionRequestApiDTO

Description

BulkActionRequest

Optional Parameters

state

- type: string
- description: state
- enum: ['RUNNING', 'STOPPED', 'SUSPENDED', 'MAINTENANCE', 'FAILOVER', 'UNKNOWN', 'STARTING', 'STOPPING']



error

type: string

description: error

entityUUID

■ type: string

BulkActionRequestInputDTO

Description

BulkActionInput

Optional Parameters

action

type: string

description: action

enum: ['START', 'STOP']

entityUuids

■ type: array

description: entityUuids

■ - type: string

BusinessUnitApiDTO

Description

Model to describe the property of a business unit.

Optional Parameters

uuid

■ type: string

displayName

■ type: string

 description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

environmentType

■ type: string

description: Environment type

enum: ['CLOUD', 'ONPREM', 'HYBRID']

discount

type: number

■ format: float

description: Entity discount percentage



priceAdjustment

- description: Entity price adjustment percentage
- PriceAdjustmentDTO (on page 1173)

accountld

- type: string
- description: Account ID

master

- type: boolean
- description: Flag which shows whether this account is master or not

associatedTargetId

- type: integerformat: int64
- description: Target associated with this account, if workloads related to this account are being discovered. If no workloads are discovered for this account, the associatedTargetId will be empty.

budget

- description: Budget of the business unit, user only need to set value and units(monthly)
- StatApiDTO (on page 1216)

businessUnitType

- **type:** string
- description: Type of the business unit instance
- enum: ['BUDGET', 'DISCOUNT', 'PRICE_ADJUSTMENT', 'DISCOVERED']

cloudType

- type: string
- description: Type of the cloud target which is related to current business account.
- enum: ['AWS', 'AZURE', 'GCP', 'UNKNOWN']

accountType

- **type:** string
- description: The category of the current cloud account.
- enum: ['STANDARD', 'GOVERNMENT_US']

riSupported

- type: boolean
- description: Flag which shows whether this account is RI supported

childrenBusinessUnits

- type: array
- description: UUIDs of the discovered children business units that will share the budget or discounts configuration of this business unit.
- - type: string

targets

- **type:** array
- description: Targets associated with the business unit
- - TargetApiDTO (on page 1224)

costPrice

- type: numberformat: float
- description: Cost price per Hour



severity

type: string

description: Calculated using the highest severity of the member entities

enum: ['UNKNOWN', 'NORMAL', 'MINOR', 'MAJOR', 'CRITICAL']

membersCount

type: integerformat: int32

description: Number of members of the business unit

memberType

type: string

description: The type of service entities comprising the business unit

related

description: The rate card and the custom pricing information the business unit is using

BusinessUnitRelatedApiDTO (on page 1095)

resourceGroupsCount

type: integerformat: int32

description: The number of Resource Groups belonging to the business unit

displayable

type: boolean

description: Whether business unit is displayable or not

pricingldentifiers

type: object

description: Pricing idenifiers for the business unit

additionalProperties: {'type': 'string'}

BusinessUnitApiInputDTO

Description

Model to describe the parameters for creating a business unit.

Required Parameters

name

type: string

description: Name of the business unit

Optional Parameters

budget

description: Budget of the business unit, user only need to set value

■ StatApiDTO (on page 1216)

childrenBusinessUnits

type: array

 description: UUIDs of the discovered children business units, that will share the budget or discounts configuration of this business unit.

type: string



discount

type: numberformat: float

 description: Business unit enterprise-level discount percentage. It will come to effect if cloud service or template-level discounts are not configured.

priceAdjustment

- description: Business unit enterprise-level price adjustment percentage. It will come to effect if cloud service
 or template-level discounts are not configured.
- PriceAdjustmentDTO (on page 1173)

targets

type: arraytype: string

nameWithBusinessAccountType

■ type: string

BusinessUnitPriceAdjustmentApiDTO

Description

Price adjustment values for cloud services and templates related to a business unit. The price adjustment configured on an user-defined business unit apply tocloud services and templates offered by the children business units.

Optional Parameters

servicePriceAdjustments

- type: array
- description: Price adjustment information for the related cloud services and templates.
- CloudServicePriceAdjustmentApiDTO (on page 1104)

serviceDiscounts

- type: array
- description: Discount information for the related cloud services and templates
- CloudServicePriceAdjustmentApiDTO (on page 1104)

BusinessUnitRelatedApiDTO

Description

Model to describe relationship between a business unit and its related rate cards and price adjustments

Optional Parameters

rateCard

- description: Rate Card related to this Business Unit.
- BaseApiDTO (on page 1088)

priceAdjustment

- description: Price Adjustment related to this Business Unit.
- BaseApiDTO (on page 1088)



BusinessUserEntityAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

sessions

- type: array
- description: Information about sessions to entities (VM or other) established by this BusinessUser.
- BusinessUserSessionApiDTO (on page 1096)

BusinessUserSessionApiDTO

Description

Session information for a connection established by BusinessUser to an entity (VM or other)

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

businessUserUuid

- type: string
- description: UUID of the connected BusinessUser

connectedEntityUuid

- type: string
- **description:** UUID of the entity that user has a connection to

duration

- type: integerformat: int64
- description: Time elapsed since the session start in seconds- sessions are always timed

ChangePasswordApiDTO

Description



Optional Parameters

oldPassword

■ type: string

newPassword

■ type: string

ClientInputDTO

Description

Required Parameters

name

type: string

description: Name of client

supportedServices

■ type: array

description: List of supported services

type: string

ClientNetworkSitesMetadataApiDTO

Description

Optional Parameters

id

name

type: stringdescription: id

_ ___

■ type: string

description: name

ClientNetworkTokenApiDTO

Description

Optional Parameters

id

type: stringdescription: id

tokenData

type: string

description: Token data



ClientNetworkTokenInputDTO

Description

Optional Parameters

claimLimit

type: integerformat: int32example: 1

description: Claim Limit: Number of times the token can be reused

■ minimum: 1 ■ maximum: 999

expiration

type: integerformat: int32example: 15

description: Expiration time (in minutes) to claim the token

minimum: 1maximum: 9999

ClientNetworkTokensMetadataApiDTO

Description

Optional Parameters

id

type: stringdescription: id

created

■ type: string

description: Created

claimsMade

type: integerformat: int32

description: Claims Made

claimsRemaining

type: integerformat: int32

description: Claims Remaining

claimExpiration

■ type: string

description: Claim Expiration



ClientServiceApiDTO

Description

Optional Parameters

id

type: stringdescription: id

supportedServices

■ type: array

description: Supported services

■ - type: string

secret

■ type: string

description: Secret

name

■ type: string

description: Name of client

CloudAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

zone

- description: The zone of the cloud entity
- BaseApiDTO (on page 1088)

region

- description: The region of the cloud entity
- BaseApiDTO (on page 1088)

businessAccount

- description: The BusinessAccount of the cloud entity
- BaseApiDTO (on page 1088)

resourceGroup

- description: The ResourceGroup of the cloud entity
- BaseApiDTO (on page 1088)

template

- description: The template used to generate the entity
- BaseApiDTO (on page 1088)



billingType

type: string

■ description: The Cloud Billing type

tier

type: string

description: The Tier of the storage

riCoveragePercentage

type: numberformat: float

description: The RI coverage percentage

riCoverage

description: Used value stores VM coupons in use, capacity stores coupon capacity

StatApiDTO (on page 1216)

onDemandCost

type: numberformat: float

description: On-demand cost paid for workload per Hour (includes Compute and License on-demand costs)

enhancedNetworking

■ type: string

description: The type of Enhanced Networking supported. If the entity is an AWS VM, this field will be populated by a value describing what kind of enhanced networking, if any, the VM is currently using. If the entity is not an AWS VM, this field is not relevant and will not be populated or displayed.

■ enum: ['NONE', 'ENA']

enaActive

type: string

description: Whether ENA is active. If the entity is an AWS VM, this field will be populated by a value describing whether ENA is currently in use or not. If the entity is not an AWS VM, this field is not relevant and will not be populated or displayed.

■ enum: ['Active', 'Inactive']

virtualizationType

■ type: string

description: The virtualization type. If the entity is an AWS VM, this field will be populated by a value describing what kind of virtualization type, if any, the VM is currently using. If the entity is not an AWS VM, this field is not relevant and will not be populated or displayed.

■ enum: ['PVM', 'HVM']

architecture

type: string

description: If the entity is an AWS VM, this field will be populated by a value describing what is the
architecture of the VM.If the entity is not an AWS VM, this field is not relevant and will not be populated or
displayed.

enum: ['32-bit', '64-bit']

nvme

■ type: string

description: NVMe driver support. If the entity is an AWS VM, this field will be true if NVMe driver installed. If the entity is not an AWS VM, this field is not relevant and will not be populated or displayed.

enum: ['Installed', 'Not installed']



entityUptime

- description: The entity uptime
- **EntityUptimeApiDTO** (on page 1128)

tenancy

- type: string
- description: The tenancy type for VMs
- enum: ['DEFAULT', 'DEDICATED', 'HOST']

CloudCommitmentAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

startTimeInMilliseconds

- type: integerformat: int64
- description: The start time of the Cloud Commitment in UTC.

expirationTimeInMilliseconds

- type: integerformat: int64
- **description:** The expiration time of the Cloud Commitment in UTC.

termInMilliseconds

- type: integerformat: int64
- description: The term of the Cloud Commitment.

cloudCommitmentScopeType

- type: string
- description: The scope of the Cloud Commitment.
- enum: ['FamilyScoped', 'FamilyAndOSScoped', 'CloudServiceScoped']

cloudCommitmentScopeDTO

- **description:** The info about the scope of the cloud commitment.
- CloudCommitmentScopeDTO (on page 1102)

${\bf cloud Commitment Capacity ApiDTO}$

- **description:** The capacity specific info of the cloud commitment.
- CloudCommitmentCapacityApiDTO (on page 1102)

payment

- type: string
- description: Payment option of the cloud commitment.
- enum: ['ALL_UPFRONT', 'PARTIAL_UPFRONT', 'NO_UPFRONT']



providerSpecificType

■ type: string

description: The provider specific type.

■ enum: ['SAVINGS_PLAN', 'COMMITTED_USE']

commitmentStatus

■ type: string

description: The cloud commitment status.

enum: ['Unknown', 'Pending', 'Active', 'Expired', 'Canceled']

CloudCommitmentCapacityApiDTO

Description

Model to describe cloud commitment capacity

Optional Parameters

instanceCapacity

type: integer

■ format: int64

description: The instance capacity of the cloud commitment.

spendCapacity

type: numberformat: double

description: The spend capacity of the cloud commitment.

commoditiesBought

■ type: object

description: The capacity for each type commodity bought by the commitment.

additionalProperties: {'type': 'number', 'format': 'double'}

CloudCommitmentScopeDTO

Description

Model to describe cloud committment scope.

Optional Parameters

cloudFamilyReferenceApiDTO

- description: The family scoped type specific info of the cloud commitment. If null, indicates service scoped cloud commitment
- CloudFamilyReferenceApiDTO (on page 1102)

CloudFamilyReferenceApiDTO

Description

Model describe a reference to a cloud family



Optional Parameters

family

type: string

description: The family of the Cloud Commitment.

entityType

type: string

description: The entity type the Cloud Commitment applies to.

enum: ['Application', 'ApplicationComponent', 'ApplicationServer', 'AvailabilityZone', 'BusinessAccount', 'BusinessApplication', 'BusinessTransaction', 'BusinessUser', 'Chassis', 'CloudService', 'ComputeTier', 'Container', 'ContainerPod', 'ContainerSpec', 'DatabaseServer', 'DatabaseServerTier', 'DatabaseTier', 'DataCenter', 'DesktopPool', 'DiskArray', 'DPod', 'HClPhysicalMachine', 'HypervisorServer', 'Internet', 'IOModule', 'LoadBalancer', 'LogicalPool', 'Namespace', 'Network', 'PhysicalMachine', 'ProcessorPool', 'Region', 'ReservedInstance', 'Service', 'ServiceProvider', 'Storage', 'StorageController', 'StorageTier', 'Switch', 'Unknown', 'ViewPod', 'VirtualApplication', 'VirtualDataCenter', 'VirtualMachine', 'VirtualVolume', 'VPod', 'WorkloadController', 'ContainerPlatformCluster', 'CloudCommitment', 'ApplicationComponentSpec', 'VirtualMachineSpec', 'DocumentCollection']

CloudProvisionActionDetailsApiDTO

Description

Inherits From

This DTO inherits from ActionDetailsApiDTO (on page 1077)

Optional Parameters

onDemandRate

type: numberformat: float

onDemandCost

type: numberformat: float

subType

■ type: string

CloudResizeActionDetailsApiDTO

Description

Inherits From

This DTO inherits from ActionDetailsApiDTO (on page 1077)

Optional Parameters

onDemandRateBefore

type: numberformat: float



onDemandRateAfter

type: numberformat: float

onDemandCostBefore

type: numberformat: floatonDemandCostAfter

type: numberformat: float

riCoverageBefore

- description: RI coupons used and capacity of the target entity before action
- StatApiDTO (on page 1216)

riCoverageAfter

- description: RI coupons used and capacity of the target entity after action
- StatApiDTO (on page 1216)

entityUptime

- description: The entity uptime which was taken into account when generating the action
- **EntityUptimeApiDTO** (on page 1128)

subType

■ type: string

CloudServicePriceAdjustmentApiDTO

Description

Price adjustments for cloud service and related templates specified for a certain pricing model.

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

environmentType

- type: string
- description: Environment type
- enum: ['CLOUD', 'ONPREM', 'HYBRID']

discount

- type: numberformat: float
- description: Entity discount percentage



priceAdjustment

- description: Entity price adjustment percentage
- PriceAdjustmentDTO (on page 1173)

pricingModel

- type: string
- description: Pricing model, 'On demand' for time-based, 'Reserved' for coupon-based, 'Spot' for customer bidding
- enum: ['ON_DEMAND', 'RESERVED', 'SPOT']

templateDiscounts

- type: array
- description: Discount values for the templates offered by the cloud service under certain pricing model.
- - TemplatePriceAdjustmentDTO (on page 1233)

templatePriceAdjustments

- type: array
- description: Price adjustment values for the templates offered by the cloud service under certain pricing model.
- TemplatePriceAdjustmentDTO (on page 1233)

CloudServicePricingModelApiDTO

Description

Cloud service + pricing model pair that is available for a business unit.

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

environmentType

- type: string
- description: Environment type
- enum: ['CLOUD', 'ONPREM', 'HYBRID']

discount

- type: numberformat: float
- description: Entity discount percentage

priceAdjustment

- description: Entity price adjustment percentage
- PriceAdjustmentDTO (on page 1173)



pricingModel

- type: string
- description: Pricing model, 'On demand' for time-based, 'Reserved' for coupon-based, 'Spot' for customer bidding
- enum: ['ON_DEMAND', 'RESERVED', 'SPOT']

CloudSuspendActionDetailsApiDTO

Description

Inherits From

This DTO inherits from ActionDetailsApiDTO (on page 1077)

Optional Parameters

onDemandRate

type: numberformat: float

onDemandCost

type: numberformat: float

subType

■ type: string

CommodityFieldApiDTO

Description

Inherits From

This DTO inherits from FieldApiDTO (on page 1130)

Required Parameters

commodityAttribute

- type: string
- description: The commodity attribute.
- readOnly: True
- enum: ['USED', 'CAPACITY', 'PEAK', 'CURRENT_UTILIZATION', 'WEIGHTED_HISTORICAL_UTILIZATION', 'PERCENTILE_HISTORICAL_UTILIZATION']



commodityType

- type: string
- **description:** The commodity name.
- readOnly: True
- enum: ['ACTION PERMIT'. 'ACTIVE SESSIONS'. 'APPLICATION'. 'BALLOONING'. 'BUFFER COMMODITY'. 'CLUSTER', 'COLLECTION TIME', 'COOLING', 'CONNECTION', 'COUPON', 'CPU', 'CPU ALLOCATION', 'CPU PROVISIONED', 'CPU REQUEST ALLOCATION', 'CROSS CLOUD MOVE SVC', 'CROSS_CLUSTER_MOVE_SVC', 'DATACENTER', 'DATASTORE', 'DB_CACHE_HIT_RATE', 'DB_MEM', 'DISK_ARRAY_ACCESS', 'DRS_SEGMENTATION', 'DSPM_ACCESS', 'EXTENT', 'FLOW', 'FLOW_ALLOCATION', 'HEAP', 'HOST_LUN_ACCESS', 'IMAGE_CPU', 'IMAGE_MEM', 'IMAGE_STORAGE', 'INSTANCE_DISK_SIZE', 'INSTANCE DISK TYPE', 'IO THROUGHPUT', 'LICENSE ACCESS', 'MEM', 'MEM ALLOCATION'. 'MEM_REQUEST_ALLOCATION', 'MEM_PROVISIONED', 'NET_THROUGHPUT', 'NETWORK', 'NUM_DISK', 'NUMBER_CONSUMERS', 'NUM_VCORE', 'POOL_CPU', 'POOL_MEM', 'POOL_STORAGE', 'PORT_CHANNEL', 'POWER', 'Q16_VCPU', 'Q1_VCPU', 'Q2_VCPU', 'Q32_VCPU', 'Q4_VCPU', 'Q64_VCPU', 'Q8_VCPU', 'RESPONSE_TIME', 'SAME_CLUSTER_MOVE_SVC', 'SEGMENTATION', 'SLA_COMMODITY', 'SOFTWARE_LICENSE_COMMODITY', 'SPACE', 'STORAGE_ACCESS', 'STORAGE_ALLOCATION', 'STORAGE_AMOUNT', 'STORAGE_CLUSTER', 'STORAGE_LATENCY', 'STORAGE_PROVISIONED', 'SWAPPING', 'THREADS', 'TRANSACTION', 'TRANSACTION_LOG', 'VCPU', 'VCPU_LIMIT_QUOTA', 'VCPU_REQUEST', 'VCPU_REQUEST_QUOTA', 'VDC', 'VMEM', 'VMEM_LIMIT_QUOTA', 'VMEM_REQUEST', 'VMEM_REQUEST_QUOTA', 'VMPM_ACCESS', 'VSTORAGE', 'ZONE', 'LICENSE_COMMODITY' 'Q3_VCPU', 'NUMBER_CONSUMERS_PM', 'Q6_VCPU', 'Q7_VCPU', 'QN_VCPU', 'RIGHT_SIZE_SVC', 'RIGHT_SIZE_DOWN', 'MOVE', 'Q5_VCPU', 'STORAGE', 'NUMBER_CONSUMERS_STORAGE', 'ACCESS', 'RIGHT_SIZE_UP', 'VAPP_ACCESS', 'HOT_STORAGE', 'HA_COMMODITY', 'NETWORK_POLICY', 'SERVICE_LEVEL_CLUSTER', 'PROCESSING_UNITS', 'TENANCY_ACCESS', 'TEMPLATE_ACCESS' 'BURST_BALANCE', 'DESIRED_COUPON', 'NETWORK_INTERFACE_COUNT', 'BICLIQUE', 'TAINT', 'LABEL', 'UNKNOWN']

ComputeTierAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Required Parameters

instanceStorageSize

- type: number
- **format:** float
- description: Size per instance storage in GB. This will be 0 if no instance storage's are present for compute tier.

numInstanceStorages

- type: number
- format: float
- description: Number of instance storage disks. Compute tiers can have 0 or more instance storage disks.

tierFamily

- type: string
- description: Family of compute tier (for example 'M4' for M4.large)

ConditionApiDTO

Description

A condition on a field of an entity or group.

Required Parameters

conditionType

- type: string
- description: Type of compared values.
- readOnly: True
- enum: ['NUMBER', 'TEXT', 'INCLUSION', 'INTEGER', 'BOOLEAN']

field

- description: Field to compare.
- readOnly: True
- FieldApiDTO (on page 1130)

operator

- type: string
- description: Operator to use.
- readOnly: True
- enum: ['EQ', 'NEQ', 'GT', 'LT', 'GE', 'LE', 'LIKE', 'IN']

ConfigChangesApiDTO

Description

Policies and Settings changes in the scenario

Optional Parameters

addPolicyList

- type: array
- description: List of Placement Policies to add
- - PolicyApiDTO (on page 1169)

removePolicyList

- type: array
- description: List of Placement Policies to remove
- - PolicyApiDTO (on page 1169)

automationSettingList

- type: array
- description: List of automation settings
- SettingApiDTOString (on page 1210)

removeConstraintList

- type: array
- description: List of constraints to remove
- RemoveConstraintApiDTO (on page 1187)



riSettingList

- type: array
- description: List of Reserved Instance settings
- SettingApiDTO (on page 1212)

osMigrationSettingList

- type: array
- description: List of OS migration settings
- SettingApiDTOString (on page 1210)

includedCoupons

- description: List of Included Coupons (RIs) and related information
- IncludedCouponsApiDTO (on page 1138)

subscription

- description: Subscription
- BusinessUnitApiDTO (on page 1092)

ConstraintApiDTO

Description

Model to describe the property of constraints, corresponding to entities constraints view in ui.

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

relation

- type: string
- enum: ['sold', 'bought']

entityType

- type: string
- description: entity type of providers or consumers

relatedEntities

- type: array
- description: if relation is sold they are consumers, if bought they are providers
- ServiceEntityApiDTO (on page 1205)

numPotentialEntities

- type: integer
- format: int32
- description: how many other providers/consumers can fulfill the constraint



placementOptions

- type: array
- description: A list of constraints prevent finding better placement for an entity
- - PlacementOptionApiDTO (on page 1166)

ConstraintApiInputDTO

Description

Model to describe the property of constraints

Optional Parameters

relation

- type: string
- enum: ['sold', 'bought']

placementOptions

- type: array
- description: A list of constraints prevent finding better placement for an entity
- PlacementOptionApilnputDTO (on page 1167)

entityTypeFilter

- type: string
- description: potential entity type filter
- enum: ['Application', 'ApplicationComponent', 'ApplicationServer', 'AvailabilityZone', 'BusinessAccount', 'BusinessApplication', 'BusinessTransaction', 'BusinessUser', 'Chassis', 'CloudService', 'ComputeTier', 'Container', 'ContainerPod', 'ContainerSpec', 'DatabaseServer', 'DatabaseServerTier', 'DatabaseTier', 'DataCenter', 'DesktopPool', 'DiskArray', 'DPod', 'HCIPhysicalMachine', 'HypervisorServer', 'Internet', 'IOModule', 'LoadBalancer', 'LogicalPool', 'Namespace', 'Network', 'PhysicalMachine', 'ProcessorPool', 'Region', 'ReservedInstance', 'Service', 'ServiceProvider', 'Storage', 'StorageController', 'StorageTier', 'Switch', 'Unknown', 'ViewPod', 'VirtualApplication', 'VirtualDataCenter', 'VirtualMachine', 'VirtualVolume', 'VPod', 'WorkloadController', 'ContainerPlatformCluster', 'CloudCommitment', 'ApplicationComponentSpec', 'VirtualMachineSpec', 'DocumentCollection']

ContainerPlatformContextAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

namespace

- type: string
- description: The namespace that a container platform entity belong to [DEPRECATED Use: namespaceEntity]



containerPlatformCluster

- type: string
- description: The container platform cluster name that an entity belongs to [DEPRECATED Use: containerClusterEntity]

workloadControllerEntity

- description: The workload controller entity that an entity belongs to
- BaseApiDTO (on page 1088)

namespaceEntity

- **description:** The namespace entity that an entity belongs to
- BaseApiDTO (on page 1088)

containerClusterEntity

- description: The container platform cluster entity that an entity belongs to
- BaseApiDTO (on page 1088)

CostInputApiDTO

Description

Model to describe the request for Cost Statistics by a Time range

Optional Parameters

tagFilters

- type: array
- description: List of Tag Filters. NOTE: Required non-empty when used with costGroupBys set to "TAG"
- TagApiDTO (on page 1224)

costGroupBys

- type: array
- description: List of values to group the results by. NOTE: When used non-empty tagFilters required
- type: string
 - enum: ['TAG', 'TAG_GROUP', 'ENTITY', 'ENTITY_TYPE', 'ACCOUNT', 'REGION', 'CLOUD_SERVICE', 'SERVICE_PROVIDER', 'CLOUD_TIER_PROVIDER', 'COST_CATEGORY', 'PRICE_MODEL']

startDate

- type: string
- description: Start time of the period to filter. If startDate and endDate not provided current stats will be processed

endDate

- type: string
- description: End time of the period to filter. If startDate and endDate not provided current stats will be processed

CpuModelApiDTO

Description

Model to describe a Template: contains the resources used to Deploy a VM or to Add Workload/Supply in a Plan



Optional Parameters

uuid

type: string

displayName

type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

numCores

type: integerformat: int32

description: Number of Cores

speed

type: integerformat: int32description: Speed

scalingFactor

type: numberformat: double

description: Scaling Factor

modelName

■ type: string

CriteriaOptionApiDTO

Description

Generic model used to describe a search criteria option

Optional Parameters

value

■ type: string

description: value

displayName

type: string

description: value to display, more readable

subValues

■ type: array

description: possible sub-values associated with the main value

type: string



DBEntityAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

dbEngine

■ type: string

description: The Database engine

dbEdition

■ type: string

■ description: The Database edition

dbVersion

■ type: string

description: The Database engine version

licenseModel

■ type: string

description: The license model of the database engine

deploymentType

type: string

description: The deployment type of the database engine

maxConcurrentWorkers

type: integerformat: int32

description: Maximum concurrent workers allowed for the DB

maxConcurrentSessions

type: integerformat: int32

description: Maximum concurrent sessions allowed for the DB

pricingModel

type: stringexample: DTU

description: Database Pricing Model.

enum: ['DTU', 'vCore', 'DWU', 'RU']

replicationRole

■ type: string

example: Primary

description: Replication role if DB is part of geo replicated DB. Currently applies to Azure DB only.

enum: ['Primary', 'Secondary', 'None']

storageTier

type: stringexample: GP2

description: Storage Tier



dbServerName

■ type: string

description: The server name of a database

serviceTier

type: string

example: Hyperscale

- description: The service tier of a database, generally defines the storage architecture, space and I/O limits, and business continuity options related to availability and disaster recovery.
- enum: ['Free', 'Basic', 'Standard', 'Premium', 'GeneralPurpose', 'BusinessCritical', 'Hyperscale']

computeTier

type: string

■ example: Provisioned Compute

 description: The compute tier of a database. Compute tier options include the provisioned and serverless compute tiers

hardwareGeneration

type: string

example: Gen4

description: Database hardware generation. The generation of hardware that underlies the DB instance

backupPolicy

■ type: string

example: Enabled

description: The policy to backup and restore a database.

workspace

type: string

description: The resource group where the database is located.

idleTime

■ type: integer

■ format: int64

description: Time duration for a database being idle in milliseconds.

poolType

type: string

description: Type of database pool.

resourceld

type: string

description: Resource identifier of the database. For example, the resource id in Azure, the ARN in AWS, or the full resource name in GCP.

serverConfiguration

type: string

description: The Database server configuration

DatabaseServerEntityAspectApiDTO

Description



Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

dbEngine

■ type: string

description: The Database engine

dbEdition

■ type: string

description: The Database edition

dbVersion

■ type: string

description: The Database engine version

licenseModel

■ type: string

description: The license model of the database engine

deploymentType

■ type: string

description: The deployment type of the database engine

maxConcurrentWorkers

type: integerformat: int32

description: Maximum concurrent workers allowed for the DB

maxConcurrentSessions

type: integerformat: int32

description: Maximum concurrent sessions allowed for the DB

pricingModel

type: stringexample: DTU

description: Pricing Model followed by DB.

storageTier

type: stringexample: GP2

description: Storage Tier

clusterRole

■ type: string

description: Cluster Role

■ enum: ['Writer', 'Reader']

hourlyBilledOps

type: numberformat: double

description: Hourly Billed Ops - Count of operations per hour



featureStateMap

■ type: object

description: Features

additionalProperties: {'type': 'string', 'enum': ['Enabled', 'Disabled', 'Unknown']}

resourceld

type: string

description: Resource identifier of the database server. For example, the resource id in Azure, the ARN in AWS, or the full resource name in GCP.

creationTimeStamp

type: integerformat: int64

description: Timestamp in milliseconds for the creation of the database server.

serverConfiguration

■ type: string

description: The Database server configuration

DatabaseServerTierAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Required Parameters

tierFamily

type: string

description: Family of database server tier (for example 'M5' for db.M5.large)

DatabaseTierAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Required Parameters

tierFamily

type: string

description: Family of database tier (for example 'S' for S4)



DemandEntityInfoDTO

Description

Model to describe a reservation entity

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

template

■ BaseApiDTO (on page 1088)

deploymentProfile

■ BaseApiDTO (on page 1088)

operationalCost

■ type: string

placements

■ PlacementInfoDTO (on page 1166)

DemandReservationApiDTO

Description

Basic information of an entity

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

prefix

type: string

count

type: integerformat: int32



status

■ type: string

reserveDateTime

■ type: string

expireDateTime

type: string

deployDateTime

■ type: string

reserveCount

type: integerformat: int32

deployCount

type: integerformat: int32

placementExpirationDateTime

type: string

placementResultMessage

■ type: string

description: Details of placement during failure or success

constraintInfos

■ type: array

- description: The constraints user specified when running reservation which limit where templates could be placed.
- ReservationConstraintApiDTO (on page 1189)

reservationDeployed

type: boolean

 description: When true, the reservation will be included in the system and will keep utilizing the resources from host and storage until the corresponding virtual machine utilization starts to reflect on the historically computed utilization.

mode

type: string

- description: Demand related behavior for reservation of NO_GROUPING/AFFINITY. This value interacts with the grouping value which is specifying the type of grouping that the demand should consider the mode for. NO_GROUPING and NONE must be paired together and cannot be paired with other values. Combinations such as: (NO_GROUPING - NONE), (AFFINITY - CLUSTER) are valid. Examples of invalid combinations are (NO_GROUPING - CLUSTER), (AFFINITY - NONE).
- enum: ['NO_GROUPING', 'AFFINITY']

grouping

type: string

- description: Grouping related behavior for reservation of NONE and CLUSTER. This value interacts with the mode value.
- enum: ['NONE', 'CLUSTER']



scope

type: array

description: List of unids of groups (currently limited to Clusters or Host Groups) whose members are the only possible providers of that type of entity. These are further constrained by the constraintlds passed in placement parameters. If multiple groups of providers are specified then it is possible that entities will be placed within different groups.

■ - type: string

demandEntities

■ type: array

DemandEntityInfoDTO (on page 1117)

DemandReservationApiInputDTO

Description

Required Parameters

action

type: string

description: Action requested for the reservation

enum: ['RESERVATION']

demandName

■ type: string

description: Name of the reservation

minLength: 1

maxLength: 2147483647

parameters

■ type: array

description: Reservation Parameters

DemandReservationParametersDTO (on page 1120)

maxItems: 1minItems: 1

Optional Parameters

mode

type: string

- description: Demand related behavior for reservation of NO_GROUPING/AFFINITY. This value interacts with the grouping value which is specifying the type of grouping that the demand should consider the mode for. NO_GROUPING and NONE must be paired together and cannot be paired with other values. Combinations such as: (NO_GROUPING - NONE), (AFFINITY - CLUSTER) are valid. Examples of invalid combinations are (NO_GROUPING - CLUSTER), (AFFINITY - NONE).
- enum: ['NO_GROUPING', 'AFFINITY']

grouping

type: string

 description: Grouping related behavior for reservation of NONE and CLUSTER. This value interacts with the mode value.

enum: ['NONE', 'CLUSTER']



reserveDateTime

■ type: string

description: Date to specify when to reserve the Demand

expireDateTime

■ type: string

description: Date to specify when the Demand request will expire, required if action = RESERVATION

deployDateTime

type: string

description: Date to specify when to deploy the Demand

scope

type: array

description: List of unids of groups (currently limited to Clusters or Host Groups) whose members are the only possible providers of that type of entity. These are further constrained by the constraintlds passed in placement parameters. If multiple groups of providers are specified then it is possible that entities will be placed within different groups.

type: string

DemandReservationParametersDTO

Description

Required Parameters

placementParameters

description: Placement parameters

PlacementParametersDTO (on page 1168)

Optional Parameters

deploymentParameters

description: Deployment parameters, required if action = DEPLOYMENT, RESERVATION

■ DeploymentParametersDTO (on page 1120)

DeploymentParametersDTO

Description

Optional Parameters

deploymentProfileID

type: string

description: Deployment Profile uuid

highAvailability

■ type: boolean

description: High availability



priority

■ type: string

description: Workload priority

■ enum: ['LOW', 'NORMAL', 'MISSION_CRITICAL']

DeploymentProfileApiDTO

Description

Model to describe a Deployment Profile, including target and provider entity parameters

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

account

- description: Business account related to the Deployment Profile
- BaseApiDTO (on page 1088)

deployParameters

- type: array
- description: Target and Provider parameters of the Deployment Profile
- DeploymentProfileTargetApiDTO (on page 1122)

DeploymentProfileParamApiDTO

Description

Provider-specific Deployment Profile parameters

Optional Parameters

parameterType

- type: string
- description: Parameter type. For vCenter, this can be a folder, osConfiguration, or image. For all other technologies, this must be an image.
- enum: ['image', 'folder', 'osConfiguration']

properties

- type: array
- description: A NameValueInputDTO describing the name and value of the parameter.
- NameValueInputDTO (on page 1152)



DeploymentProfileProviderApiDTO

Description

Deployment profile Provider properties

Optional Parameters

provider

- description: Provider UUID
- BaseApiDTO (on page 1088)

parameters

- type: array
- description: A DeploymentProfileParamApiDTO describing the parameters for the provider entities
- DeploymentProfileParamApiDTO (on page 1121)

DeploymentProfileTargetApiDTO

Description

Deployment Profile Target properties

Optional Parameters

targetType

- **type:** string
- description: Target type for the deployment profile
- enum: ['vCenter', 'AWS', 'Azure', 'Softlayer']

providers

- type: array
- description: DeploymentProfileProviderApilnputDTO describing the provider entity parameters
- DeploymentProfileProviderApiDTO (on page 1122)

DesktopPoolEntityAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

cloneType

- type: string
- description: Type of a clone provided by the DesktopPool
- enum: ['FULL', 'LINKED', 'INSTANT']



provisionType

■ type: string

description: How clones are provisioned in the DesktopPool

enum: ['UPFRONT', 'ON_DEMAND']

assignmentType

type: string

description: Whether the same clone is assigned each time when user logs back in

enum: ['PERSISTENT', 'DYNAMIC']

masterTemplateUuid

type: string

 description: UUID of a master template that is used to create clones. Only one of master VM and master template can be set.

masterVirtualMachineUuid

type: string

 description: UUID of a master virtual machine that is used to create clones. Only one of master VM and master template can be set.

masterVirtualMachineSnapshot

■ type: string

description: Name of the snapshot of a master virtual machine that is used to create clones.

getvCenterClusterName

■ type: string

description: Name of the vCenter cluster that this DesktopPool draws resources from.

vendorld

■ type: string

description: Vendor Identifier for the DesktopPool.

DetailDataApiDTO

Description

A single entity detail, represented as key-value pair

Required Parameters

kev

type: string

description: Detail key

value

type: string

description: Detail value

Optional Parameters

critical

type: boolean



DiscoveredEntityApiDTO

Description

Model to describe a discovered entity in the system

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

environmentType

- type: string
- description: Environment type
- enum: ['CLOUD', 'ONPREM', 'HYBRID']

discoveredBy

- description: Target that discovered the entity
- TargetApiDTO (on page 1224)

vendorlds

- type: object
- description: The mapping of target identifier to vendor-provided identity of this entity on the remote target
- additionalProperties: {'type': 'string'}

EntityActionsApiDTO

Description

Basic informations of an entity + actions

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

realtimeMarketReference

- description: In case of a Plan Market Entity, this contains the original entity from the Real Time Market
- BaseApiDTO (on page 1088)



actions

■ type: array

description: List of actions for this entity

ActionApiDTO (on page 1071)

EntityAspect

Description

Parent class for entity aspects

Required Parameters

type

type: string

EntityCountRequestApiDTO

Description

A query used to fetch entity counts.

Optional Parameters

groupBy

■ type: array

description: Criteria to group the results by.

■ readOnly: True

type: string

enum: ['ENTITY_TYPE', 'ENVIRONMENT_TYPE']

EntityDetailsApiDTO

Description

Model to describe an entity with all its details

Required Parameters

uuid

type: integer

■ format: int64

description: The internal UUID of the entity

Optional Parameters

details

type: array

description: A list of details, represented as key-value

DetailDataApiDTO (on page 1123)



EntityMetadataRequestApiDTO

Description

A query used to fetch entity metadata.

Required Parameters

entityType

- type: string
- description: Entity type to fetch metadata for.
- readOnly: True
- enum: ['Application', 'ApplicationComponent', 'ApplicationServer', 'AvailabilityZone', 'BusinessAccount', 'BusinessApplication', 'BusinessTransaction', 'BusinessUser', 'Chassis', 'CloudService', 'ComputeTier', 'Container', 'ContainerPod', 'ContainerSpec', 'DatabaseServer', 'DatabaseServerTier', 'DatabaseTier', 'DataCenter', 'DesktopPool', 'DiskArray', 'DPod', 'HCIPhysicalMachine', 'HypervisorServer', 'Internet', 'IOModule', 'LoadBalancer', 'LogicalPool', 'Namespace', 'Network', 'PhysicalMachine', 'ProcessorPool', 'Region', 'ReservedInstance', 'Service', 'ServiceProvider', 'Storage', 'StorageController', 'StorageTier', 'Switch', 'Unknown', 'ViewPod', 'VirtualApplication', 'VirtualDataCenter', 'VirtualMachine', 'VirtualVolume', 'VPod', 'WorkloadController', 'ContainerPlatformCluster', 'CloudCommitment', 'ApplicationComponentSpec', 'VirtualMachineSpec', 'DocumentCollection']

EntityPriceDTO

Description

Context-specific price. For example the base rate of a template in the context of certain business unit.

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

price

- type: numberformat: float
- description: Price in the context of a related entity

EntityQueryApiDTO

Description

A query used to search topology entities.



Required Parameters

select

description: Information to be fetched for each entity.

■ readOnly: True

■ SelectEntityApiDTO (on page 1204)

Optional Parameters

where

description: Conditions that each retrieved entity must satisfy.

■ readOnly: True

■ WhereApiDTO (on page 1247)

pagination

description: Pagination information.

readOnly: True

■ PaginationApiDTO (on page 1158)

EntityStatsApiDTO

Description

Basic informations of an entity + statistics

Optional Parameters

uuid

■ type: string

displayName

■ type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

environmentType

■ type: string

description: Environment type

■ enum: ['CLOUD', 'ONPREM', 'HYBRID']

realtimeMarketReference

- description: In case of a Plan Market Entity, this contains the original entity from the Real Time Market
- BaseApiDTO (on page 1088)

stats

■ type: array

description: Collected monitoring statistics

StatSnapshotApiDTO (on page 1220)



EntityUptimeApiDTO

Description

Model to describe the uptime of an entity

Optional Parameters

creationTimestamp

type: integerformat: int64

description: The creation timestamp of the entity

uptimeDurationInMilliseconds

type: integerformat: int64

description: Uptime duration in milliseconds for the total analyzed duration

totalDurationInMilliseconds

type: integerformat: int64

description: Total analyzed duration in milliseconds for which uptime is calculated

uptimePercentage

type: numberformat: double

description: The uptime of the entity as a percentage

EnumFieldValueApiDTO

Description

Inherits From

This DTO inherits from FieldValueApiDTO (on page 1130)

Required Parameters

value

type: string

description: The string representation of the value.

■ readOnly: True

ExecutorInfoApiDTO

Description

Model to describe the entity that triggered action execution. such as a user or a schedule.



Required Parameters

type

type: string

description: The type of the executor, such as a user or a schedule.

enum: ['USER', 'SCHEDULE']

Optional Parameters

scheduleInfo

- description: Information about the schedule that triggered this action. Omitted if the action was not triggered by a schedule.
- ExecutorScheduleApiDTO (on page 1129)

userInfo

- description: Information about the user who triggered this action. Omitted if the action was not triggered by a
 user.
- **ExecutorUserApiDTO** (on page 1129)

ExecutorScheduleApiDTO

Description

Model to describe the Schedule that executed the action.

Required Parameters

scheduleName

■ type: string

description: Name of the schedule

ExecutorUserApiDTO

Description

Model to describe the user who triggered this action.

Required Parameters

userName

type: string

description: Name of the user

FailedResourceApiDTO

Description

A description of the resource that caused an entity to be unplaced



Required Parameters

commodity

- description: The commodity that caused the entity to be unplaced
- BaseCommodityApiDTO (on page 1088)

requestedAmount

- type: numberformat: double
- description: The requested amount of the commodity that caused the entity to be unplaced

Optional Parameters

maxAvailable

- type: numberformat: double
- description: The maximum available amount of the requested commodity. Populated only if there are one or more entities selling the requested commodity.

FieldApiDTO

Description

A field of an entity or group.

Optional Parameters

fieldType

- type: string
- description: The kind of the field.
- enum: ['PRIMITIVE', 'COMMODITY', 'RELATED_ENTITY', 'RELATED_GROUP', 'RELATED_ACTION', 'AGGREGATE_COMMODITY', 'MEMBER']

FieldValueApiDTO

Description

A field of an entity or group with its value.

Required Parameters

field

- description: Field to compare.
- readOnly: True
- FieldApiDTO (on page 1130)

valueType

- type: string
- description: Type of compared values.
- readOnly: True
- enum: ['NUMBER', 'TEXT', 'ENUM', 'INTEGER', 'BOOLEAN', 'MULTI_TEXT']



FieldValueTypeApiDTO

Description

A field of an entity or group associated with the type of its values.

Required Parameters

field

description: Field for which information is presented.

readOnly: True

■ FieldApiDTO (on page 1130)

valueType

type: string

description: Type of values of this field.

■ readOnly: True

enum: ['NUMBER', 'TEXT', 'ENUM', 'INTEGER', 'BOOLEAN', 'MULTI_TEXT']

Optional Parameters

allowableValues

■ type: array

description: Allowable string values for this field.

readOnly: Truetype: string

FilterApiDTO

Description

Model used to filter Groups or Entities, every filter is built using a filterType + expType + expVal

Required Parameters

caseSensitive

■ type: boolean

description: Whether the regex is case sensitive

expType

■ type: string

description: Type of comparator used while building a filter, the allowable values are 'EQ', 'NEQ', 'RXEQ', 'RXNEQ' for strings, 'EQ', 'NEQ', 'GT', 'LT', 'GTE', 'LTE' for numbers

enum: ['EQ', 'NEQ', 'GT', 'LT', 'GTE', 'LTE', 'RXEQ', 'RXNEQ']

expVal

type: string

description: Regex to be searched for

filterType

■ type: string

description: Internal name for criterion such as pmsByName, pmsByDC, storageByPMCluster



Optional Parameters

entityType

■ type: string

description: The entity type which this filter should be applied on

singleLine

type: boolean

description: Whether the regex dot matches all characters including line break characters. Defaults to false.

GroupApiDTO

Description

Model to describe a Group: a collection of Entities. Subclasses include BillingFamilyApiDTO and ResourceGroupApiDTO.

Required Parameters

groupClassName

■ type: string

groupType

■ type: string

description: The type of service entities comprising the group

isStatic

type: boolean

■ description: True if group is static

Optional Parameters

uuid

■ type: string

displayName

type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

membersCount

■ type: integer

■ format: int32

description: Number of members of the Group

entitiesCount

■ type: integer

format: int32

description: Number of entities of the Group

costPrice

■ type: number

format: float

■ description: Cost of the Group per Hour: sum of the costs of the member entities



severity

- type: string
- description: Calculated using the highest severity of the member entities
- enum: ['UNKNOWN', 'NORMAL', 'MINOR', 'MAJOR', 'CRITICAL']

state

- type: string
- description: Calculated using the state of the member entities
- enum: ['UNKNOWN', 'ACTIVE']

environmentType

- type: string
- description: Environment type
- enum: ['HYBRID', 'CLOUD', 'ONPREM', 'UNKNOWN']

scope

- type: array
- **description:** Scope within which the criteria have to be applied to the list of specific entity type
- - type: string

logicalOperator

- type: string
- description: Logical operator to be applied across all the criteria used to create dynamic group. It can take values 'AND', 'OR', 'XOR'

criteriaList

- type: array
- description: Criteria list of elements, expression type, expression value, seType needed to create a dynamic group
- FilterApiDTO (on page 1131)

memberUuidList

- type: array
- **description:** Uuid list for members of the group if group is static
- - type: string

realtimeMarketReference

- description: In case of a Plan Market Group, this contains the original group from the Real Time Market
- BaseApiDTO (on page 1088)

stats

- type: array
- description: Collected monitoring statistics
- StatSnapshotApiDTO (on page 1220)

temporary

- type: boolean
- description: The Group is only valid for a limited period of time, it will be removed automatically

activeEntitiesCount

- type: integer
- format: int32
- description: The active entities count of a group



cloudType

- type: string
- **description:** Type of the Cloud if environmentType = CLOUD.
- enum: ['AWS', 'AZURE', 'GCP', 'HYBRID', 'UNKNOWN']

source

- description: The Source of the Group
- TargetApiDTO (on page 1224)

memberTypes

- type: array
- **description:** The types for immediate members of the group.
- type: string

entityTypes

- type: array
- description: The types of entities contained in the group. This includes types of entities in nested levels of the group if the group is nested.
 - type: string

aspects

- type: object
- description: Additional info about the Group categorized as Aspects
- additionalProperties: {'\$ref': '#/definitions/EntityAspect'}

vendorlds

- type: object
- description: The mapping of target identifier to vendor-provided identity of this group, if the group is discovered
- additionalProperties: {'type': 'string'}

groupOrigin

- type: string
- description: Origin of entities and groups
- enum: ['DISCOVERED', 'USER', 'SYSTEM']

GroupCountRequestApiDTO

Description

A query used to fetch group counts.

Optional Parameters

groupBy

- type: array
- description: Criteria to group the results by.
- readOnly: True uniqueltems: True
- type: string
 - enum: ['GROUP_TYPE', 'ORIGIN']



GroupMetadataRequestApiDTO

Description

A query used to fetch group metadata.

Required Parameters

groupType

- type: string
- description: Group type to fetch metadata for.
- readOnly: True
- enum: ['Group', 'Resource', 'Cluster', 'VMCluster', 'StorageCluster', 'BusinessAccountFolder', 'BillingFamily', 'NodePool']

GroupQueryApiDTO

Description

A query used to search groups.

Required Parameters

select

- description: Information to be fetched for each group.
- readOnly: True
- SelectGroupApiDTO (on page 1205)

Optional Parameters

where

- description: Conditions that each retrieved group must satisfy.
- readOnly: True
- WhereApiDTO (on page 1247)

pagination

- description: Pagination information.
- readOnly: True
- PaginationApiDTO (on page 1158)

HealthCategoryResponseDTO

Description

A DTO to collect the aggregated health data for one health category.

Required Parameters

categoryDisplayName

- type: string
- description: The reported health category name.



categoryHealthState

■ type: string

description: The health state for the reported category.

enum: ['CRITICAL', 'MAJOR', 'MINOR', 'NORMAL']

healthCategory

■ type: string

description: The reported health category.enum: ['TARGET', 'ACTION', 'COMPONENT']

Optional Parameters

responseltems

■ type: array

description: A list of individual health response items for this health category.

AggregatedHealthResponseDTO (on page 1087)

HttpProxyDTO

Description

Model to describe http proxy settings, like username, password, port number and host

Required Parameters

isProxyEnabled

■ type: boolean

description: Whether proxy is enabled or not

Optional Parameters

uuid

type: string

displayName

type: string

 description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

proxyHost

■ type: string

■ description: Proxy host

proxyPortNumber

■ type: integer

■ format: int32

description: Proxy port number

userName

type: string

description: Proxy username



password

■ type: string

description: Proxy password

HttpServletResponse

Description

Optional Parameters

status

type: integerformat: int32

headerNames

■ type: array

type: string

bufferSize

type: integerformat: int32

contentType

■ type: string

outputStream

■ ServletOutputStream (on page 1207)

locale

■ Locale (on page 1144)

writer

■ PrintWriter (on page 1174)

characterEncoding

■ type: string

committed

■ type: boolean

IEntityDefinitionData

Description

Parent class for topology data definition

Required Parameters

definitionType

type: string

enum: ['MANUAL', 'AUTOMATED']



IManualConnectionsData

Description

Parent class for manual connections.

Required Parameters

connectionType

■ type: string

■ enum: ['DYNAMIC', 'STATIC', 'GROUP']

IncludedCouponsApiDTO

Description

Included RI/Coupon and related information in the scenario

Optional Parameters

includedCouponOidsList

type: array

description: User selected list of RIs to be included in plans

type: integerformat: int64

iswhiteList

■ type: boolean

InclusionConditionApiDTO

Description

Inherits From

This DTO inherits from ConditionApiDTO (on page 1108)

Required Parameters

value

type: array

description: A set of strings. The value must belong to one of those.

readOnly: Truetype: string

InputFieldApiDTO

Description

Basic information of an entity



Required Parameters

name

type: string

description: Name of the field, used for field identification.

Optional Parameters

uuid

type: string

displayName

type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

value

type: string

description: Field value. Used if field holds primitive value (String, number or boolean

defaultValue

type: string

description: Default value of the field

isMandatory

■ type: boolean

description: Whether the field is mandatory. Valid targets must have all the mandatory fields set.

isSecret

type: boolean

 description: Whether the field is secret. This means, that field value is stored in an encrypted value and not shown in any logs.

isMultiline

■ type: boolean

 description: Whether the field can have multiline values. Can be only true when the valueType field is set to STRING.

isTargetDisplayName

type: boolean

description: Whether the field is used as a target display name.

valueType

■ type: string

description: Type of the value this field holds

• enum: ['STRING', 'BOOLEAN', 'NUMERIC', 'INTEGER', 'LIST', 'OBJECT', 'GROUP_SCOPE']

specificValueType

■ type: string

description: A specific Type of the value that can't be described in valueType

description

type: string

description: Additional information about what the input to the field should be



verificationRegex

■ type: string

description: The regex pattern that needs to be satisfied for the input field text

groupProperties

■ type: array

description: Group scope structure, filled if this field represents group scope value

type: array
 type: string

allowedValues

■ type: array

description: Potential values for this field. If nonempty, value must be one of the choices in the list.

type: string

dependencyKey

type: string

description: A key of a dependency account value field. If this value is not set, field is declared without any dependencies. If an annotated account value field has a dependency it means that it's presence is logically driven by the dependency field. This field is expected to be available ONLY when field specified by {@code dependencyKey} has value {@code dependencyValue}. If this field is not available because of unmet dependency, this field will not be validated and stored in target configuration data. If a dependency for this field is unmet value of this field will be null

dependencyValue

type: string

example: one|two|four

description: Value of a field of account values referenced by {@code dependencyKey} to enable (activate) the annotated field. Value is specified using a regular expression. Specifying just a string will also work correctly. If a referenced account value field is a boolean field, only "true" or "false" are supported as values. If a referenced account value is an enumeration ({@code allowedValues} is specified) this value is only restricted to contain a subset of the allowed values united using a pipe {@code one|two|four}.

InstanceTypeFilterApiDTO

Description

Model to describe instanceType filter information for the action filtering.

Optional Parameters

currentInstanceTypeFilter

- description: Filter the actions by matching current instanceType and given the instanceType Unid list.
- InstanceTypeIdsApiDTO (on page 1140)

newInstanceTypeFilter

- description: Filter the actions by matching new instanceType and given the instanceType Uuid list.
- InstanceTypeIdsApiDTO (on page 1140)

InstanceTypeIdsApiDTO

Description

Model to describe instanceType Uuid list and operator for the action filtering.



Optional Parameters

instanceTypelds

■ type: array

■ **description:** InstanceType Uuid list for the action filter.

type: string

operator

type: string

description: Operator for instanceType Uuid filter.the allowable values are 'EQ' and 'NEQ'

■ enum: ['EQ', 'NEQ']

IntegerConditionApiDTO

Description

Inherits From

This DTO inherits from ConditionApiDTO (on page 1108)

Required Parameters

value

type: integerformat: int64

description: Value to compare against.

readOnly: True

IntegerFieldValueApiDTO

Description

Inherits From

This DTO inherits from FieldValueApiDTO (on page 1130)

Required Parameters

value

type: integerformat: int64

description: The value.

readOnly: True

Optional Parameters

units

type: string

description: Units of measurement.

■ readOnly: True



LicenseApiDTO

Description

Model to describe properties of a license

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

licenseOwner

- type: string
- description: The owner of current license

email

- type: string
- description: The email of current license

customerId

- type: string
- description: The customer id

expirationDate

- type: string
- description: The expiration date of current license

features

- type: array
- description: List of features contained in current license
- uniqueltems: Truetype: string

numLicensedEntities

- type: integerformat: int32
- description: The number of licensed sockets

numInUseEntities

- type: integerformat: int32
- description: The number of sockets in use

edition

- type: string
- description: The edition of the current license

filename

- type: string
- description: The name of the uploaded file



countedEntity

■ type: string

description: Indicates which entity type is counted with respect to licensing

enum: ['VM', 'SOCKET']

maxReportEditorsCount

type: integerformat: int32

description: Maximum number of report editors

expirationDateTime

type: stringformat: date-time

errorReasons

■ type: array

description: Indicate why the license is invalid

uniqueltems: Truetype: string

isValid

type: boolean

description: Indicate if current license is valid or not

readOnly: True

isExpired

type: boolean

description: Indicate if current license is expired

■ readOnly: True

Link

Description

Optional Parameters

rel

■ type: string

■ xml: {'attribute': True}

href

■ type: string

xml: {'attribute': True}

LoadChangesApiDTO

Description

Workload utilization changes in the scenario



Optional Parameters

baselineDate

■ type: string

■ description: Baseline date

peakBaselineList

■ type: array

description: List of peak baseline changes

PeakBaselineApiDTO (on page 1166)

utilizationList

■ type: array

description: List of utilization changes

■ - <u>UtilizationApiDTO (on page 1240)</u>

maxUtilizationList

type: array

description: List of max utilization changes

MaxUtilizationApiDTO (on page 1150)

overlayStatsList

■ type: array

description: List of stat changes to override the plan commodities values with the provided input

■ - EntityStatsApiDTO (on page 1127)

Locale

Description

Optional Parameters

language

type: string

script

■ type: string

country

■ type: string

variant

type: string

extensionKeys

■ type: array

uniqueltems: True

type: string

unicodeLocaleAttributes

■ type: array

uniqueltems: True

type: string



unicodeLocaleKeys

■ type: array

uniqueItems: Truetype: string

iso3Language

■ type: string

iso3Country

■ type: string

displayLanguage

■ type: string

displayScript

■ type: string

displayCountry

■ type: string

displayVariant

■ type: string

displayName

■ type: string

LogEntryApiDTO

Description

Basic information of an entity

Optional Parameters

uuid

■ type: string

displayName

■ type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

logActionTime

type: integerformat: int64

targetSE

■ type: string

targetUuid

■ type: string

currentSE

■ type: string



currentSEUuid

■ type: string

newSE

■ type: string

newSEUuid

■ type: string

category

■ type: string

subCategory

■ type: string

description

■ type: string

shortDescription

■ type: string

state

■ type: string

severity

■ type: string

count

type: integer

■ format: int64

total

type: integer

format: int64

user

■ type: string

type

■ type: string

importance

type: numberformat: float

reasonCommodities

type: array

description: The distinct set of commodities that were the reason for the action. Not all actions are driven by commodities. So its possible that this can be an empty list.

■ uniqueltems: True

type: string

reasonCommodityRelationType

type: string

description: Relation type (bought/sold) of the reason commodity

enum: ['sold', 'bought']

logDBld

type: integerformat: int64



LoggingApiDTO

Description

Model to describe the component logging level

Optional Parameters

componentLoggingLevel

- type: object
- description: A map from component name to logging level, component could be Discovery,
 Monitoring, Presentation, Abstraction, Analysis, Extension; logging levels could be INFO, WARN, DEBUG, TRACE
- additionalProperties: {'type': 'string', 'enum': ['FATAL', 'ERROR', 'WARN', 'INFO', 'DEBUG', 'TRACE', 'UNKNOWN']}

ManualDynamicConnections

Description

Inherits From

This DTO inherits from IManualConnectionsData (on page 1138)

Optional Parameters

dynamicConnectionCriteria

- type: array
- description: Connection criteria to define dynamically connected entities.
- - FilterApiDTO (on page 1131)

ManualEntityDefinitionData

Description

Inherits From

This DTO inherits from IEntityDefinitionData (on page 1137)

Required Parameters

manualConnectionData

- type: object
- description: Entity connections set manually
- additionalProperties: {'\$ref': '#/definitions/IManualConnectionsData'}

ManualGroupConnections

Description



Inherits From

This DTO inherits from IManualConnectionsData (on page 1138)

Required Parameters

connectedGroup

- **description:** Group for a connection.
- BaseGroupApiDTO (on page 1089)

ManualStaticConnections

Description

Inherits From

This DTO inherits from IManualConnectionsData (on page 1138)

Optional Parameters

staticConnections

- type: array
- description: Oids to be statically connected to the created entity
- type: string

MarketApiDTO

Description

Model to describe a Market

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

state

- type: string
- description: State
- enum: ['CREATED', 'READY_TO_START', 'RUNNING', 'COPYING', 'SUCCEEDED', 'STOPPING', 'STOPPED', 'DELETING']

stateProgress

- type: integer
- format: int32
- description: State progress indicated by a percentage, used in RUNNING state



scenario

- description: Scenario used to create the Plan, only for Plan Market
- ScenarioApiDTO (on page 1198)

saved

- type: boolean
- description: Shows if a Plan Market is saved

unplacedEntities

- type: boolean
- description: Unplaced entities, shows if there are entities that could not be placed in the Plan Market

runDate

- type: string
- description: Shows when a Plan Market started running

runCompleteDate

- type: string
- description: Shows when a Plan Market was completed

violations

- type: array
- description: Violations generated in a Plan Market
- ServiceEntityApiDTO (on page 1205)

relatedPlanMarkets

- type: array
- description: Related Plan Markets generated by particular Scenarios
- MarketApiDTO (on page 1148)

environmentType

- type: string
- description: Environment type
- enum: ['HYBRID', 'CLOUD', 'ONPREM']

planDestination

- description: Plan destination where the plan results would be stored, only for Plan Market.
- BaseApiDTO (on page 1088)

MasterImageEntityAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

displayName

- type: string
- description: DisplayName of the masterImage used to create new VMs



numVcpus

type: integerformat: int32

description: The number of vCPUs allocated to each VM generated from the master image

mem

type: numberformat: float

description: The amount of Mem allocated to each VM generated from the master image

storage

type: numberformat: float

description: The amount of Storage allocated to each VM generated from the master image

MaxUtilizationApiDTO

Description

Model to describe a max utilization change in the scenario

Optional Parameters

projectionDay

type: integerformat: int32

description: Projection day, indicate when to apply the change

target

description: Target of the change, entity or group. If empty, assumes global scope

■ BaseApiDTO (on page 1088)

maxPercentage

type: integerformat: int32

description: Max utilization threshold percentage change

selectedEntityType

■ type: string

description: Type of entity to select in global scope configuration

globalScope

■ type: boolean

MemberFieldApiDTO

Description

Inherits From

This DTO inherits from FieldApiDTO (on page 1130)



Required Parameters

property

■ type: string

description: The property of interest.

readOnly: Trueenum: ['COUNT']

Optional Parameters

entityType

type: string

description: Restricts the property to entities of this type.

readOnly: True

enum: ['Application', 'ApplicationComponent', 'ApplicationServer', 'AvailabilityZone', 'BusinessAccount', 'BusinessApplication', 'BusinessTransaction', 'BusinessUser', 'Chassis', 'CloudService', 'ComputeTier', 'Container', 'ContainerPod', 'ContainerSpec', 'Database', 'DatabaseServer', 'DatabaseServerTier', 'DatabaseTier', 'DataCenter', 'DesktopPool', 'DiskArray', 'DPod', 'HCIPhysicalMachine', 'HypervisorServer', 'Internet', 'IOModule', 'LoadBalancer', 'LogicalPool', 'Namespace', 'Network', 'PhysicalMachine', 'ProcessorPool', 'Region', 'ReservedInstance', 'Service', 'ServiceProvider', 'Storage', 'StorageController', 'StorageTier', 'Switch', 'Unknown', 'ViewPod', 'VirtualApplication', 'VirtualDataCenter', 'VirtualMachine', 'VirtualVolume', 'VPod', 'WorkloadController', 'ContainerPlatformCluster', 'CloudCommitment', 'ApplicationComponentSpec', 'VirtualMachineSpec', 'DocumentCollection']

direct

type: boolean

description: Whether this field refers to direct or indirect members (default = direct).

readOnly: True

MigrateObjectApiDTO

Description

Model to describe a replace change in the scenario

Optional Parameters

projectionDay

type: integer

■ format: int32

description: Projection day, indicate when to apply the change

source

description: Source of the migration, entity or group - [DEPRECATED - Use: sources]

■ BaseApiDTO (on page 1088)

destination

description: Destination of the migration - [DEPRECATED - Use: destinations]

■ BaseApiDTO (on page 1088)

sources

type: array

description: Sources of the migration, entities or groups.

BaseApiDTO (on page 1088)



destinations

- type: array
- **description:** Destinations of the migration, entities or groups.
- BaseApiDTO (on page 1088)

destinationEntityType

- type: string
- description: Entity type of migration destination, default is VirtualMachine. Case 1, migration source VirtualMachine: destination entity must be VirtualMachine. Case 2, migration source Database Server: destination entity can be VirtualMachine or DatabaseServer.
- enum: ['VirtualMachine', 'DatabaseServer']

removeNonMigratingWorkloads

- type: boolean
- description: If true, remove the existing Virtual Machines, Databases and Database Servers from the scope that are not migrating, so that only the newly migrated entities are included in the plan results.

MultiTextFieldValueApiDTO

Description

Inherits From

This DTO inherits from FieldValueApiDTO (on page 1130)

Required Parameters

value

- type: array
- description: The values associated with the field.
- readOnly: Truetype: string

NameValueInputDTO

Description

Deployment Profile provider parameters

Optional Parameters

name

- type: string
- description: Parameter type. For vCenter, this can be a name or id. For all other target types, this must be an id
- enum: ['name', 'id']

value

type: string



NumberConditionApiDTO

Description

Inherits From

This DTO inherits from ConditionApiDTO (on page 1108)

Required Parameters

value

type: numberformat: double

description: Value to compare against.

readOnly: True

NumberFieldValueApiDTO

Description

Inherits From

This DTO inherits from FieldValueApiDTO (on page 1130)

Required Parameters

value

type: numberformat: double

description: The value.

readOnly: True

Optional Parameters

units

type: string

description: Units of measurement.

■ readOnly: True

OAuthDataApiDTO

Description

Required Parameters

authorizationServerUrl

type: string

description: The URL of the authorization server.



clientId

■ type: string

description: The client id used for oAuth authorization.

clientSecret

■ type: string

description: The client secret used for oAuth authorization.

grantType

type: string

description: The oAuth grant type.

■ enum: ['CLIENT_CREDENTIALS']

Optional Parameters

scope

■ type: string

description: The oAuth scope.

OnDemandCostFilterApiDTO

Description

Model to describe on-demand cost range for action filtering.

Optional Parameters

currentOnDemandCostRange

- description: Filter the actions by the range for current on-demand cost.
- RangeInputApiDTO (on page 1180)

newOnDemandCostRange

- description: Filter the actions by the range for destination on-demand cost. Applicable only for scale actions.
- RangeInputApiDTO (on page 1180)

OnPremResizeActionDetailsApiDTO

Description

Inherits From

This DTO inherits from ActionDetailsApiDTO (on page 1077)

Optional Parameters

vcpuBefore

type: integerformat: int32

description: vCPUs before the change



vcpuAfter

type: integerformat: int32

description: vCPUs after the change

socketsBefore

type: integerformat: int32

description: sockets before the change

socketsAfter

type: integerformat: int32

description: sockets after the change

coresPerSocketBefore

type: integerformat: int32

description: cores per socket before the change

coresPerSocketAfter

type: integerformat: int32

description: cores per socket after the change

nonDisruptiveMaxPU

type: numberformat: double

description: Non-disruptive Processing Units max resize constraint

nonDisruptiveMinPU

type: numberformat: double

description: Non-disruptive Processing Units min resize constraint

subType

■ type: string

OrderByApiDTO

Description

A field to order results by.

Required Parameters

field

description: The field to order by.

■ readOnly: True

■ FieldApiDTO (on page 1130)



ascending

■ type: boolean

description: Whether the order is ascending (defaults to false).

■ readOnly: True

PMDiskAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

diskCapacity

type: integerformat: int64

■ description: Disk Capacity

diskRole

■ type: string

description: Disk Role

■ enum: ['CAPACITY', 'CACHE']

PMDiskGroupAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

disks

type: array

description: Disks

PMDiskAspectApiDTO (on page 1156)

PMEntityAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)



diskGroups

■ type: array

description: Disk Groups

PMDiskGroupAspectApiDTO (on page 1156)

dedicatedFailoverHost

type: boolean

description: If true, this host is a failover host.

cpuModel

■ type: string

■ example: Intel(R) Xeon(R) CPU E5-2670 0 @ 2.60GHz

description: The CPU model of the host

connectedNetworks

type: array

example: Broadcom BCM5708C NetXtreme II GigE

description: Connected Networks

type: string

automationLevel

■ type: string

example: Fully Automated

description: Vendor provided automation level

enum: ['FULLY_AUTOMATED', 'PARTIALLY_AUTOMATED', 'NOT_AUTOMATED', 'DISABLED']

migrationLevel

■ type: string

example: Conservative

description: Vendor provided migration level

machine Type And Model

■ type: string

■ example: 9040-MR9

description: Machine Type and Model

serialNumber

■ type: string

example: 130330X

description: Serial Number

totalInstalledPhysicalProcessorUnits

type: integerformat: int32

example: 80

description: Total Installed Physical Processor Units

supportedProcessorCompatibilityModes

■ type: string

■ example: POWER7, POWER8, POWER9

description: Supported Processor Compatibility Modes



latestSupportedProcessorGeneration

type: stringexample: 9

description: Latest Supported Processor Generation

totalInstalledPhysicalMemory

type: integerformat: int32example: 4096

description: Total Installed Physical Memory

hypervisorUsedMemory

type: integerformat: int32example: 4096

description: Hypervisor Used Memory

memoryAssignedToVMs

type: integerformat: int32example: 4096

description: Memory Assigned To VMs

logicalMemoryBlockSize

type: integerformat: int32example: 256

description: Logical Memory Block Size

processorPools

type: arraytype: string

PaginationApiDTO

Description

Pagination parameters.

Optional Parameters

orderBy

■ type: array

description: Order by these fields.

readOnly: True

OrderByApiDTO (on page 1155)

cursor

■ type: string

description: Cursor for the next batch.

readOnly: True



limit

type: integerformat: int32

description: Maximum number of records to fetch.

readOnly: True

ParkableEntityApiDTO

Description

Parkable Entity

Optional Parameters

uuid

■ type: string

displayName

■ type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

environmentType

type: string

description: Environment type

enum: ['CLOUD', 'ONPREM', 'HYBRID']

accountOID

type: integerformat: int64

example: 74613608411667

description: Unique ID of the account

accountName

type: string

■ example: dev-account

description: Display name of the account

provider

type: stringexample: AWS

description: Name of the cloud provider

enum: ['AWS', 'AZURE', 'GCP', 'HYBRID', 'UNKNOWN']

state

type: string

example: STOPPED

description: Last known state of the entity

enum: ['RUNNING', 'STOPPED', 'SUSPENDED', 'MAINTENANCE', 'FAILOVER', 'UNKNOWN', 'STARTING', 'STOPPING']



parkable

type: booleanexample: True

description: Signifies whether the entity can be parked

entityType

■ type: string

■ example: COMPUTE

description: Type of the entity

• enum: ['VirtualMachine', 'DatabaseServer']

regionOID

type: integerformat: int64

example: 74613608411668

description: Unique ID of the region, the entity belongs to

regionName

■ type: string

example: us-east-1

description: Name of the region

instanceType

type: string

example: t3.micro

description: Type of the instance

cost

type: numberformat: doubleexample: 10.24

description: On demand hourly cost of the entity

tags

type: array

description: List of tags attached to the entity

■ - TagApiDTO (on page 1224)

schedules

type: array

description: List of schedules attached to the entity

ParkableEntityScheduleApiDTO (on page 1162)

groups

■ type: array

description: List of the Groups attached to the entity

ParkableEntityGroupApiDTO (on page 1161)

guestOSName

type: stringexample: Linux

description: Guest OS Name of the entity



ParkableEntityEnforcementPauseApiDTO

Description

represents the partial failure per entity for enforcement pause on list of parkable entities

Optional Parameters

error

- type: string
- example: entityUuid not found
- description: error indicating the reason for failure

entityUUID

■ type: string

ParkableEntityEnforcementPauseInputDTO

Description

represents the enforcement pause on list of parkable entities either until a given time or in duration of minutes

Optional Parameters

until

- type: string
- **example:** 2022-11-29T01:02:03+00:00
- description: Time when the enforcement pause on parkable entities ends. Should be in ISO 8601 format

durationMinutes

- type: integerformat: int32example: 60
- description: duration in minutes to keep enforcement pause on parkable entities

entityUuids

- type: array
- description: list of parkable entities to pause enforcement on
- type: string

ParkableEntityGroupApiDTO

Description

represents groups which are attached to the parkable entity

Optional Parameters

uuid

■ type: string



displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

groupType

- type: string
- example: Resource
- description: Type of the Group
- enum: ['RESOURCE']

ParkableEntityInputDTO

Description

Optional Parameters

entityTypes

- type: array
- - type: string
 - enum: ['VirtualMachine', 'DatabaseServer']

status

- type: array
- type: string
 - enum: ['RUNNING', 'STOPPED', 'SUSPENDED', 'MAINTENANCE', 'FAILOVER', 'UNKNOWN', 'STARTING', 'STOPPING']

providers

- type: array
- description: Parking Cloud Providers
- - type: string
 - enum: ['AWS', 'AZURE', 'GCP', 'HYBRID', 'UNKNOWN']

criteriaList

- type: array
- FilterApiDTO (on page 1131)

logicalOperator

- type: string
- description: Logical operator to be applied across all the criteria. It can take values 'AND', 'OR'. If omitted, defaults to 'AND'
- **enum:** ['AND', 'OR']

ParkableEntityScheduleApiDTO

Description

Represents time span based schedule display name and uuid of the time span based schedule attached to the parkable entity



displayName

■ type: string

■ example: Up 7-5 on weekdays

description: Display name of the time span based schedule the parkable entities is attached to

uuid

type: string

example: 74613608411667

description: UUID of the time span based schedule the parkable entities are attached to

pauseEnforcementUntil

type: integerformat: int64

example: 1673273639

description: Pause Enforcement time over the entity, in epoch time format

attachedBy

description: Details of the user/policy responsible for attaching the schedule to entity

ParkingEntitySchedulerApiDTO (on page 1163)

ParkableEntityUUIDSetDTO

Description

list of parkable entity uuids

Required Parameters

entityUuids

type: array

description: list of parkable entity uuids

type: string

ParkingEntitySchedulerApiDTO

Description

Represents the details of the user/policy responsible for attaching the schedule to parkable entity

Optional Parameters

uuid

type: string

displayName

type: string

■ **description:** A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string



type

type: stringexample: POLICY

description: Whether user or policy was responsible for attaching the schedule

■ enum: ['USER', 'POLICY']

ParkingItemApiDTO

Description

Inherits From

This DTO inherits from ScheduleItemApiDTO (on page 1201)

Required Parameters

state

type: string

description: expected state during the time span

■ enum: ['IGNORE', 'ON', 'OFF']

ParkingPolicyApiDTO

Description

Model to describe a parking policy, used to assign timespan based schedules to entities based on global, cloud provider, account and resource group level filters

Required Parameters

level

■ type: string

description: Specifies the level at which the policy is applicable.

enum: ['GLOBAL', 'CLOUD_PROVIDER', 'ACCOUNT', 'RESOURCE_GROUP']

timespanSchedule

description: timespan based schedule to be/attached to policy.

■ BaseApiDTO (on page 1088)

Optional Parameters

uuid

type: string

displayName

tyne: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string



scopes

- type: array
- description: List of scope object to which the parking policy is applicable, like details of account for account level policies.
- BaseApiDTO (on page 1088)

criteriaList

- type: array
- description: List of filters to get the desired the entities to which the policy is applicable.
- - FilterApiDTO (on page 1131)

priority

- type: integerformat: int32
- description: Priority is used to identify the applicable priority if there are multiple policies at same level

PatchedTargetDataApiDTO

Description

Model to describe a patched target data.

Required Parameters

patchedFields

- type: array
- description: Patched target fields.
 - PatchedTargetFieldApiDTO (on page 1165)

probeType

- type: string
- **description:** Probe type of the patched target.

PatchedTargetFieldApiDTO

Description

Model to describe a field in patched target data.

Optional Parameters

fieldName

- type: string
- description: Patched field name.

fieldValue

- type: string
- description: Patched field value.



PeakBaselineApiDTO

Description

Model to describe a peak baseline change in the scenario

Optional Parameters

date

- type: string
- description: Date of the utilization peak

target

- description: Target of the change
- BaseApiDTO (on page 1088)

PlacementInfoDTO

Description

Optional Parameters

computeResources

- type: array
- description: Compute resources that the reservation is placed in
- ResourceApiDTO (on page 1194)

storageResources

- type: array
- description: Storage resources that the reservation is placed in
- ResourceApiDTO (on page 1194)

networkResources

- type: array
- **description:** Network resources that the reservation is placed in
- ResourceApiDTO (on page 1194)

failureInfos

- type: array
- **description:** Details about why the reservation failed. This will only be populated if the reservation failed.
- ReservationFailureInfoDTO (on page 1189)

invalidInfo

- description: Details about why the reservation is invalid. This will only be populated if the reservation is invalid.
- ReservationInvalidInfoApiDTO (on page 1190)

PlacementOptionApiDTO

Description

Model to describe the property of provider options.



uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

constraintType

- type: string
- description: constraint type, if a commodity is AccessCommodity, then the class name of that commodity is a constraint type
- enum: ['ApplicationCommodity', 'ClusterCommodity', 'DataCenterCommodity', 'DatastoreCommodity etc']

scope

- description: scope or placement policy
- BaseApiDTO (on page 1088)

target

- description: for placement policy, if it's an user placement policy is null.
- TargetApiDTO (on page 1224)

numPotentialEntities

- type: integer
- format: int32
- description: example: other VMs, which buys this constraint but not on this host

key

- type: string
- description: commodity key, this information is needed when trying to retrieve the intersaction of providers or consumers

currentEntities

- type: array
- description: for consumers only. example: VMs, which are currently on this host per constraint they are buying
- ServiceEntityApiDTO (on page 1205)

PlacementOptionApiInputDTO

Description

Model to describe the property of provider options.

Optional Parameters

constraintType

- type: string
- description: constraint type, if a commodity is AccessCommodity, then the class name of that commodity is a constraint type
- enum: ['ApplicationCommodity', 'ClusterCommodity', 'DataCenterCommodity', 'DatastoreCommodity etc']



key

- type: string
- description: commodity key, this information is needed when trying to retrieve the intersection of providers or consumers

PlacementParametersDTO

Description

Required Parameters

count

type: integerformat: int32

description: Number of Virtual Machines to Place

Optional Parameters

templateID

type: string

description: Template Uuid used for the Placement

entityNames

■ type: array

description: Name of the Placed Virtual Machine

type: string

constraintIDs

type: array

description: List of unids that will define the constraints that new VMs should be compliant to, allowed unids are: Cluster, Datacenter, VirtualDataCenter, Network, Placement Policy. The possible providers are the intersection of all constraints passed.

uniqueltems: Truetype: string

geographicRedundancy

■ type: boolean

description: Enable Geographic Redundancy

PlanDestinationApiDTO

Description

Model to describe a plan destination. A plan destination is an external destination where plan results can be uploaded.

Required Parameters

businessUnit

- description: Business account to plan destination.
- BaseApiDTO (on page 1088)



exportDescription

type: string

description: Plan export description message on this plan destination.

exportProgressPercentage

type: integerformat: int32

description: Plan export progress percentage on this plan destination.

exportState

■ type: string

description: Plan export state on this plan destination.

enum: ['NONE', 'REJECTED', 'IN_PROGRESS', 'SUCCEEDED', 'FAILED']

hasExportedData

type: boolean

description: Boolean, true if this plan destination has uploaded data.

market

description: Plan market currently uploaded to plan destination.

BaseApiDTO (on page 1088)

numErrors

type: integerformat: int32

description: Number of errors on the plan destination.

Optional Parameters

uuid

■ type: string

displayName

type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

PolicyApiDTO

Description

Model to describe a Workload policy, used to manage the entities in the Environment. e.g. Restrict the number of VMs that can use a given datastore, Limit VM mobility by restricting a collection of VMs to a specified cluster or group of hosts, Expand VM mobility by merging a number of clusters, Keep workload running on hosts that have the required licenses

Required Parameters

type

type: string

■ description: Placement Policy Type

enum: ['AT_MOST_N', 'BIND_TO_GROUP', 'BIND_TO_COMPLEMENTARY_GROUP', 'MUST_RUN_TOGETHER', 'AT_MOST_N_BOUND', 'MERGE', 'BIND_TO_GROUP_AND_LICENSE', 'MUST_NOT_RUN_TOGETHER', 'EXCLUSIVE_BIND_TO_GROUP']



uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

name

- type: string
- description: Name of the policy

enabled

- type: boolean
- description: Shows if the policy is enabled

capacity

- type: integer
- format: int32
- description: Indicate the max workload entities at the same time per placement entites, used when type is AT_MOST_N_BOUND

commodityType

- type: string
- description: Commodity type used for the policy

mergeType

- type: string
- description: Type of Group that is merged, used only when type is MERGE
- enum: ['Cluster', 'StorageCluster', 'DataCenter', 'DesktopPool']

consumerGroup

- description: Consumer Group, used when type is any but MERGE
- BaseApiDTO (on page 1088)

provider Group

- description: Provider Group, used when type is any but MERGE
- BaseApiDTO (on page 1088)

mergeGroups

- type: array
- description: List of Groups to merge, used when type is MERGE
- BaseApiDTO (on page 1088)



providerEntityType

- type: string
- description: The entity type for the provider. This property is only applicable when policy type is set to MUST_RUN_TOGETHER or MUST_NOT_RUN_TOGETHER. When policy type is set to MUST_RUN_TOGETHER or MUST_NOT_RUN_TOGETHER, this field should be set with type of provider where members of consumer group must run or must not run together on it depending on the policy type.
- enum: ['Application', 'ApplicationComponent', 'ApplicationServer', 'AvailabilityZone', 'BusinessAccount', 'BusinessApplication', 'BusinessTransaction', 'BusinessUser', 'Chassis', 'CloudService', 'ComputeTier', 'Container', 'ContainerPod', 'ContainerSpec', 'Database', 'DatabaseServer', 'DatabaseServerTier', 'DatabaseTier', 'DataCenter', 'DesktopPool', 'DiskArray', 'DPod', 'HClPhysicalMachine', 'HypervisorServer', 'Internet', 'IOModule', 'LoadBalancer', 'LogicalPool', 'Namespace', 'Network', 'PhysicalMachine', 'ProcessorPool', 'Region', 'ReservedInstance', 'Service', 'ServiceProvider', 'Storage', 'StorageController', 'StorageTier', 'Switch', 'Unknown', 'ViewPod', 'VirtualApplication', 'VirtualDataCenter', 'VirtualMachine', 'VirtualVolume', 'VPod', 'WorkloadController', 'ContainerPlatformCluster', 'CloudCommitment', 'ApplicationComponentSpec', 'VirtualMachineSpec', 'DocumentCollection']

PolicyApiInputDTO

Description

Model to describe a Placement Policy

Required Parameters

policyName

- type: string
- description: Name of the policy

type

- type: string
- description: Placement Policy Type
- enum: ['AT_MOST_N', 'BIND_TO_GROUP', 'BIND_TO_COMPLEMENTARY_GROUP', 'MUST_RUN_TOGETHER', 'AT_MOST_N_BOUND', 'MERGE', 'BIND_TO_GROUP_AND_LICENSE', 'MUST_NOT_RUN_TOGETHER', 'EXCLUSIVE_BIND_TO_GROUP']

Optional Parameters

sellerUuid

- type: string
- description: Uuid of the provider Group in a Placement Policy

buyerUuid

- type: string
- description: Uuid of the consumer Group in a Placement Policy

mergeUuids

- type: array
- description: Uuids of the Groups in a Merge Policy
- type: string

mergeType

- type: string
- description: Group Type in a Merge Policy
- enum: ['Cluster', 'StorageCluster', 'DataCenter', 'DesktopPool']



capacity

type: integerformat: int32

 description: For an AT_MOST_N or AT_MOST_N_BOUND policy, the number of consumers to allow on a provider entity

enabled

■ type: boolean

description: Whether to enable the policy

providerEntityType

type: string

- description: The entity type for the provider. This property is only applicable when the policy type is set to MUST_RUN_TOGETHER or MUST_NOT_RUN_TOGETHER. This field is set with the provider type (for example, PhysicalMachine) the policy should respect.
- enum: ['Application', 'ApplicationComponent', 'ApplicationServer', 'AvailabilityZone', 'BusinessAccount', 'BusinessApplication', 'BusinessTransaction', 'BusinessUser', 'Chassis', 'CloudService', 'ComputeTier', 'Container', 'ContainerPod', 'ContainerSpec', 'DatabaseServer', 'DatabaseServerTier', 'DatabaseTier', 'DatabaseTier', 'DesktopPool', 'DiskArray', 'DPod', 'HCIPhysicalMachine', 'HypervisorServer', 'Internet', 'IOModule', 'LoadBalancer', 'LogicalPool', 'Namespace', 'Network', 'PhysicalMachine', 'ProcessorPool', 'Region', 'ReservedInstance', 'Service', 'ServiceProvider', 'Storage', 'StorageController', 'StorageTier', 'Switch', 'Unknown', 'ViewPod', 'VirtualApplication', 'VirtualDataCenter', 'VirtualMachine', 'VirtualVolume', 'VPod', 'WorkloadController', 'ContainerPlatformCluster', 'CloudCommitment', 'ApplicationComponentSpec', 'VirtualMachineSpec', 'DocumentCollection']

PortChannelApiDTO

Description

Model to describe a Port Channel

Optional Parameters

uuid

■ type: string

displayName

type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

capacity

description: Capacity values

StatValueApiDTO (on page 1221)

values

description: Contains Average, Min, Max, Total

StatValueApiDTO (on page 1221)

units

type: string

description: Units, used for Commodities stats. E.G. \$/h



ports

- type: array
- description: List of ports in the channel
- StatApiDTO (on page 1216)

filters

- type: array
- description: describe the grouping options used to generate the output
- StatFilterApiDTO (on page 1218)

PortsAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

portChannels

- type: array
- description: Port Channels
- PortChannelApiDTO (on page 1172)

ports

- type: array
- description: Independent ports
- StatApiDTO (on page 1216)

PriceAdjustmentDTO

Description

Optional Parameters

type

- type: string
- enum: ['DISCOUNT', 'INCREASE']

value

type: numberformat: float

PrimitiveFieldApiDTO

Description



Inherits From

This DTO inherits from FieldApiDTO (on page 1130)

Required Parameters

fieldName

type: string

description: The name of the primitive field.

■ readOnly: True

PrintWriter

Description

This is an unspecified object.

ProbeApiDTO

Description

Model to describe a probe.

Required Parameters

category

■ type: string

description: Probe category.

id

type: integerformat: int64

description: Probe id.

type

type: string

description: Probe type.

Optional Parameters

uuid

type: string

displayName

type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

error

type: string

description: Unexpected error while collecting probe information



ProbePropertyApiDTO

Description

Model to describe a probe property

Required Parameters

name

type: string

description: Probe property name.

value

type: string

description: Probe property value.

Optional Parameters

probeld

type: integerformat: int64

description: Probe id.

targetId

type: integerformat: int64

description: Target id.

ProbePropertyNameValuePairApiDTO

Description

Model to describe a name/value pair for probe properties.

Required Parameters

name

type: string

description: Probe property name.

value

type: string

description: Probe property value.

ProductCapabilityDTO

Description

Model to describe Product Capability information.



deploymentMode

■ type: string

description: Deployment mode, affects hiding / showing multiple UI views, options

enum: ['HYBRID_SAAS', 'SERVER', 'SAAS_TRIAL']

searchApiEnabled

type: boolean

description: Controls use of new search api

parkingEnabled

■ type: boolean

description: Controls hiding/showing parking related pages in UI

parkingPoliciesEnabled

■ type: boolean

description: [BETA]: Controls hiding/showing parking policies related features in UI

frontEndTelemetryEnabled

■ type: boolean

description: Controls enabling/disabling front end telemetry in UI

jdbcHttpSessionEnabled

■ type: boolean

description: Controls use of JDBC persistent HTTP Session

saasReportingEnabled

■ type: boolean

description: Controls hiding/showing SaaS reports page in UI

trialExpirationTime

■ type: string

description: [BETA]: When the user's trial expires in ISO 8601 Format. For SAAS_TRIAL deploymentMode

reportingEnabled

■ type: boolean

ProductVersionDTO

Description

Contains version information about the running Turbonomic instance.



versionInfo

type: string

- example: "versionInfo": "Turbonomic Operations Manager 8.0.1-SNAPSHOT (Build \"20200922092548000\") \"2020-09-22 20:10:04\"\n\naction-orchestrator: 8.0.1-SNAPSHOT\napi: 8.0.1-SNAPSHOT\nauth: 8.0.1-SNAPSHOT\ncost: 8.0.1-SNAPSHOT\nextractor: 8.0.1-SNAPSHOT\ngroup: 8.0.1-SNAPSHOT\nhistory: 8.0.1-SNAPSHOT\nmediation-actionscript: 8.0.1-SNAPSHOT\nmediation-appdynamics: 8.0.1-SNAPSHOT\nmediation-appinsights: 8.0.1-SNAPSHOT\nmediation-aws: 8.0.1-SNAPSHOT\nmediation-awsibilling: 8.0.1-SNAPSHOT\nmediation-awscost: 8.0.1-SNAPSHOT\nmediation-azure: 8.0.1-SNAPSHOT\nmediation-azurecost: 8.0.1-SNAPSHOT\nmediation-azureca: 8.0.1-SNAPSHOT\nmediation-dynatrace: 8.0.1-SNAPSHOT\nmediation-azurevolumes: 8.0.1-SNAPSHOT\nmediation-hyperv: 8.0.1-SNAPSHOT\nmediation-netapp: 8.0.1-SNAPSHOT\nmediation-nutanix: 8.0.1-SNAPSHOT\nmediation-oneview: 8.0.1-SNAPSHOT\nmediation-vcenter: 8.0.1-SNAPSHOT\nmediat
- description: A multi-line string describing the version information, including that of the various internal components.

version

type: string

example: 8.0.1-SNAPSHOT

description: The Operations Manager product version, including major and minor versions

build

type: string

example: 20200922211058775

description: The build number associated with this deployment.

commit

■ type: string

example: 1183dd2

description: The commit associated with this deployment.

branch

type: stringexample: 8.0.1

description: The branch associated with this deployment.

gitDescription

type: string

example: 1183dd2bb8ebca3dbcaf708e0c323cabc7b8e352

description: Specific source control information associated with this deployment.

updates

type: string

description: Description of available updates--not yet implemented in XL.

marketVersion

type: integerformat: int32example: 2

description: The version of the market



apiVersion

type: stringexample: 3.1

description: The version of the REST API.

PurchaseProfileDTO

Description

Model to describe a set of preferences for purchasing RIs

Required Parameters

cloudType

■ type: string

description: Cloud type

enum: ['AWS', 'AZURE', 'GCP', 'HYBRID', 'UNKNOWN']

paymentOption

■ type: string

description: Preferred payment option

enum: ['ALL_UPFRONT', 'PARTIAL_UPFRONT', 'NO_UPFRONT']

reservedInstanceType

type: string

description: Preferred offering class (Standard or Convertible)

■ enum: ['STANDARD', 'CONVERTIBLE']

termYears

type: integerformat: int32

description: Number of years in preferred term

QueryInputApiDTO

Description

Model to describe an input query

Required Parameters

query

type: string

 description: Query string. The format of this depends on the QueryType chosen. For example, for a REGEX QueryType, this should be a regular expression.

type

■ type: string

■ description: Query type

enum: ['EXACT', 'REGEX', 'CONTAINS']



caseSensitive

- type: boolean
- description: If true, the query string will match case-sensitivity. This field is only used when QueryType is not REGEX.

RIBuyActionDetailsApiDTO

Description

Inherits From

This DTO inherits from ActionDetailsApiDTO (on page 1077)

Optional Parameters

estimatedOnDemandCost

type: numberformat: float

estimatedRICoverage

type: numberformat: float

historicalDemandDataset

■ type: array

StatSnapshotApiDTO (on page 1220)

subType

■ type: string

RIPurchaseProfilesSettingApiDTO

Description

Inherits From

This DTO inherits from SettingApiDTO (on page 1212)

Required Parameters

value

- description: Value of the RI Purchase Profiles of type ReservedInstancePurchaseSettingsDTO.
- ReservedInstancePurchaseSettingsDTO (on page 1193)

Optional Parameters

defaultValue

- description: Default value before any change
- readOnly: True
- ReservedInstancePurchaseSettingsDTO (on page 1193)



RangeApiDTO

Description

Model to describe the Range of a Value in the Settings

Optional Parameters

step

type: numberformat: double

description: The Step scale factor of the slider

labels

type: array

description: Labels to show in the values of the slider

■ - **type:** string

customStepValues

■ type: array

■ description: Custom step values when the slider step is not constant - [DEPRECATED - Use: stepValues]

type: integerformat: int32

stepValues

type: array

description: Custom step values when the slider step is not constant

type: numberformat: float

RangeInputApiDTO

Description

Model to describe an input range. Either minValue or maxValue needs to be defined.

Optional Parameters

minValue

type: numberformat: float

description: Minimum value of the input range

maxValue

type: numberformat: float

description: Maximum value of the input range



RateCardApiDTO

Description

Model to describe a ratecard.

Required Parameters

info

- description: List of business unit UUID's related to this rate card.
- RateCardInfoApiDTO (on page 1181)

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

type

- type: string
- description: Type of rate card", example = "AWS, Azure"
- enum: ['AWS', 'AZURE', 'GCP', 'HYBRID', 'UNKNOWN']

related

- description: List of business units related to this rate card.
- RateCardRelatedApiDTO (on page 1182)

validation

- description: Rate card validation.
- RateCardValidationApiDTO (on page 1182)

valid

type: boolean

default

type: boolean

fileName

■ type: string

RateCardInfoApiDTO

Description

Model to describe the attributes of a rate card.



Required Parameters

businessUnitsIds

■ type: array

description: List of business units associated to this rate card.

type: string

RateCardRelatedApiDTO

Description

Model to describe the related business units of this ratecard.

Optional Parameters

businessUnits

■ type: array

description: List of business units related to the ratecard

BusinessUnitApiDTO (on page 1092)

RateCardValidationApiDTO

Description

Model to validate the RateCard

Optional Parameters

name

type: string

description: Name of the rate card file

status

■ type: string

example: VALID, INVALID
 description: Validation Status
 enum: ['VALID', 'INVALID']

message

■ type: string

example: Validation was successful, Validation failed

description: Reason for validation failure or success.

Recommendation

Description

A DTO for a single recommendation to an error.



Required Parameters

description

■ type: string

description: The recommended user action to investigate/mitigate the problem.

errorType

■ type: string

description: The problem this recommendation is produced for.

ReconfigureActionDetailsApiDTO

Description

Inherits From

This DTO inherits from ActionDetailsApiDTO (on page 1077)

Optional Parameters

vcpuBefore

type: integerformat: int32

description: vCPUs before the change

vcpuAfter

type: integerformat: int32

description: vCPUs after the change

socketsBefore

type: integerformat: int32

description: sockets before the change

socketsAfter

type: integerformat: int32

description: sockets after the change

coresPerSocketBefore

type: integerformat: int32

description: cores per socket before the change

coresPerSocketAfter

type: integerformat: int32

description: cores per socket after the change



RecurrenceApiDTO

Description

Model to describe the Schedule for a Settings Policy

Required Parameters

type

- type: string
- description: Type of the recurrence, Enum: DAILY, WEEKLY, MONTHLY
- enum: ['DAILY', 'WEEKLY', 'MONTHLY']

Optional Parameters

daysOfWeek

- type: array
- description: The day of week that the recurrence will occur. Required if the type of recurrence is WEEKLY, or if the type is MONTHLY and a week for the monthly recurrence has been set.
- type: string
 - enum: ['Sun', 'Mon', 'Tue', 'Wed', 'Thu', 'Fri', 'Sat']

daysOfMonth

- type: array
- description: When recurrence type is MONTHLY, the date to apply the monthly recurrence
- - **type:** integer
 - format: int32

weekOfTheMonth

- type: array
- description: When recurrence type is MONTHLY, which week of the month to apply the recurrence. A value of
 1 indicates last week, 0 indicates this week, and so on.
- - type: integer
 - format: int32

interval

- **type:** integer
- format: int32
- **description:** Frequency of the recurrence based on the recurrence type. For example, an interval of '2' with a recurrence type of MONTHLY will occur every two months.

RegionAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)



latitude

type: numberformat: double

description: The latitude of the region used along with longitude to determine physical location.

longitude

type: numberformat: double

description: The longitude of the region used along with latitude to determine physical location.

numWorkloads

type: integerformat: int32

description: Number of workloads (VMs, databases, etc.) in this region.

RelatedActionApiDTO

Description

Model to describe the relationship between two actions

Optional Parameters

action

description: The basic action DTO for the related action

■ BasicActionApiDTO (on page 1090)

actionRelationType

■ type: string

description: Action relation type

■ enum: ['BLOCKED_BY', 'BLOCKING', 'CAUSED_BY', 'CAUSING']

RelatedEntityFieldApiDTO

Description

Inherits From

This DTO inherits from FieldApiDTO (on page 1130)

Required Parameters

property

type: string

description: The related entity property of interest.

■ readOnly: True

enum: ['NAMES', 'COUNT']



relatedEntityType

- type: string
- description: The type of related entities of interest.
- readOnly: True
- enum: ['Application', 'ApplicationComponent', 'ApplicationServer', 'AvailabilityZone', 'BusinessAccount', 'BusinessApplication', 'BusinessTransaction', 'BusinessUser', 'Chassis', 'CloudService', 'ComputeTier', 'Container', 'ContainerPod', 'ContainerSpec', 'DatabaseServer', 'DatabaseServerTier', 'DatabaseTier', 'DataCenter', 'DesktopPool', 'DiskArray', 'DPod', 'HClPhysicalMachine', 'HypervisorServer', 'Internet', 'IOModule', 'LoadBalancer', 'LogicalPool', 'Namespace', 'Network', 'PhysicalMachine', 'ProcessorPool', 'Region', 'ReservedInstance', 'Service', 'ServiceProvider', 'Storage', 'StorageController', 'StorageTier', 'Switch', 'Unknown', 'ViewPod', 'VirtualApplication', 'VirtualDataCenter', 'VirtualMachine', 'VirtualVolume', 'VPod', 'WorkloadController', 'ContainerPlatformCluster', 'CloudCommitment', 'ApplicationComponentSpec', 'VirtualMachineSpec', 'DocumentCollection']

RelatedGroupFieldApiDTO

Description

Inherits From

This DTO inherits from FieldApiDTO (on page 1130)

Required Parameters

property

- type: string
- **description:** The related group property of interest.
- readOnly: True
- enum: ['NAMES', 'COUNT']

relatedGroupType

- type: string
- **description:** The type of related groups of interest.
- readOnly: True
- enum: ['Group', 'Resource', 'Cluster', 'VMCluster', 'StorageCluster', 'BusinessAccountFolder', 'BillingFamily', 'NodePool']

RelievePressureObjectApiDTO

Description

Model to describe a relieve pressure change in the scenario: minimum amount of Actions Moves that will relieve the pressure on the over-utilized clusters

Optional Parameters

projectionDay

- type: integer
- format: int32
- description: Projection day, indicate when to apply the change



sources

- type: array
- description: Sources of the change, List of Clusters that are overloaded
- BaseApiDTO (on page 1088)

destinations

- type: array
- description: Destinations of the change, List of Clusters where VMs can move to
- BaseApiDTO (on page 1088)

RemoveConstraintApiDTO

Description

Model to describe a constraint change in the scenario

Optional Parameters

constraintType

- type: string
- description: Type of the constraint to remove. To ignore all constraints use AllCommodities. This will ignore
 all constraints not just Network/Cluster/StorageCluster/DC. GloballgnoreConstraint deprecated use
 AllCommodities instead.
- enum: ['DataCenterCommodity', 'ClusterCommodity', 'NetworkCommodity', 'DatastoreCommodity', 'StorageClusterCommodity', 'GloballgnoreConstraint', 'AllCommodities']

projectionDay

- type: integerformat: int32
- description: Projection day, indicate when to apply the change

target

- description: Target of the change, when not provided change applied to plan scope
- BaseApiDTO (on page 1088)

targetEntityType

- type: string
- **description:** EntityType to target with constraint configuration
- enum: ['VirtualMachine', 'Container', 'ContainerPod']

RemoveObjectApiDTO

Description

Model to describe a remove change in the scenario

Optional Parameters

projectionDay

- type: integer
- format: int32
- **description:** Projection day, indicate when to apply the change



targetEntityType

■ type: string

description: Type of entity to remove from group target

target

description: Target of the change, entity or group

■ BaseApiDTO (on page 1088)

ReplaceObjectApiDTO

Description

Model to describe a migration change in the scenario

Optional Parameters

projectionDay

type: integerformat: int32

description: Projection day, indicate when to apply the change

target

description: Target of the change, entity or group

■ BaseApiDTO (on page 1088)

template

description: Template used for the replace

■ BaseApiDTO (on page 1088)

targetEntityType

■ type: string

■ **description:** Type of entity to remove from group target

RequestHeader

Description

Required Parameters

name

type: string

description: Request header name

value

type: string

description: Request header value



ReservationConstraintApiDTO

Description

The constraints user specified when running reservation which limit where templates could be placed.

Required Parameters

constraintType

- type: string
- description: Type of constraint
- enum: ['CLUSTER', 'DATA_CENTER', 'VIRTUAL_DATA_CENTER', 'POLICY', 'NETWORK']

uuid

- type: string
- description: UUID of the constraint

Optional Parameters

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

ReservationFailureInfoDTO

Description

Failure information when reservation fails

Required Parameters

closestSeller

- description: provider that came closest to meeting the requirements
- BaseApiDTO (on page 1088)

closestSellerCluster

- **description:** Closest provider's cluster information
- BaseApiDTO (on page 1088)

maxQuantityAvailable

- type: number
- format: double
- description: Quantity of resource available on closestSeller

quantityRequested

- type: number
- format: double
- description: Quantity of resource requested



resource

■ type: string

description: Most constrained resource

timespan

type: string

description: Failure is in historical or current

enum: ['HISTORICAL', 'CURRENT', 'PROJECTED', 'PLAN_SOURCE', 'PLAN_PROJECTED']

Optional Parameters

units

type: string

description: Units for the resource

ReservationInvalidInfoApiDTO

Description

The reason the reservation is invalid

Optional Parameters

invalidReason

type: string

description: The reason why the reservation is invalid

enum: ['MARKET_CONNECTIVITY_ERROR', 'MARKET_NOT_READY', 'INVALID_CONSTRAINTS']

ReservedInstanceApiDTO

Description

Model to describe a Reserved Instance

Required Parameters

cloudType

type: string

description: Cloud Type

■ enum: ['AWS', 'AZURE', 'GCP', 'HYBRID', 'UNKNOWN']

Optional Parameters

uuid

type: string

displayName

type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string



template

- description: Related template
- BaseApiDTO (on page 1088)

platform

- type: string
- description: Platform name
- enum: ['UNKNOWN', 'LINUX', 'RHEL', 'SUSE', 'WINDOWS', 'WINDOWS_WITH_SQL_STANDARD', 'WINDOWS_WITH_SQL_WEB', 'WINDOWS_WITH_SQL_SERVER_ENTERPRISE', 'LINUX_WITH_SQL_STANDARD', 'LINUX_WITH_SQL_WEB', 'LINUX_WITH_SQL_SERVER_ENTERPRISE']

type

- type: string
- description: Reserved instance typeenum: ['STANDARD', 'CONVERTIBLE']

location

- description: Location, either a zone or a data center if zone is not available
- BaseApiDTO (on page 1088)

accountld

- type: string
- description: Account ID

accountDisplayName

- type: string
- description: Account display name

targetId

- type: string
- description: The associated target ID of the account

masterAccountId

- type: string
- description: Master account ID

term

- description: Term, unit is Year
- StatApiDTO (on page 1216)

payment

- type: string
- description: Payment option
- enum: ['ALL_UPFRONT', 'PARTIAL_UPFRONT', 'NO_UPFRONT']

onDemandPrice

- description: On-demand price, saving is RI price minus on-demand price
- StatApiDTO (on page 1216)

costPrice

- description: Total monthly cost
- StatApiDTO (on page 1216)

coupons

- description: Total coupons and used coupons, utilization = numOfCouponsUsed / numOfCoupons
- StatApiDTO (on page 1216)



totalCoupons

type: numberformat: float

description: Total coupons provided by the cbtp the vm matched with

expDate

■ type: string

description: Expiration date

instanceCount

type: integerformat: int32

description: Number of reserved instance with the same type, template, platform etc...

tenancy

type: string

description: Tenancy

■ enum: ['DEFAULT', 'DEDICATED', 'HOST']

upFrontCost

type: numberformat: double

■ description: Up front cost

actualHourlyCost

type: numberformat: double

description: Actual hourly cost

effectiveHourlyCost

type: numberformat: double

description: Effective hourly cost

isExpired

type: boolean

description: Whether the RI be expired by a date provided

expDateEpochTime

type: integerformat: int64

description: Expiration Date in epoch time

scopeType

■ type: string

description: Whether the RI scope is Single or Shared (Azure)

■ enum: ['SINGLE', 'SHARED', 'UNKNOWN']

appliedScopes

type: array

description: List of applied scope UUIDs- only provided when scope is Single (Azure)

type: string

orderID

type: string

description: The Order ID of the RI (Azure)



trueID

type: string

description: The ID of the RI

coveredEntityCount

type: integerformat: int32

description: Count of workload entities covered by the reserved instance

undiscoveredAccountsCoveredCount

type: integerformat: int32

description: Count of undiscovered accounts covered by the reserved instance

sizeFlexible

■ type: boolean

toBuy

type: boolean

ReservedInstancePurchaseSettingsDTO

Description

Optional Parameters

awsProfile

■ PurchaseProfileDTO (on page 1178)

azureProfile

■ PurchaseProfileDTO (on page 1178)

ResizeActionDetailsApiDTO

Description

Parent class for resize action details. Implementing classes include: CloudResizeActionDetailsApiDTO.

Required Parameters

actionDetailType

■ type: string

actionType

■ type: string

Optional Parameters

subType

type: string



ResourceApiDTO

Description

Model to describe the Resources of a Template

Optional Parameters

stats

- type: array
- description: Statistics, e.g. Number of CPU, Memory size, Disk size, ...
- StatApiDTO (on page 1216)

provider

- description: Entity provider
- BaseApiDTO (on page 1088)

type

- type: string
- description: Type of the resource

template

- type: string
- description: Template used to fulfill the resources

relatedResources

- type: array
- description: ID of resources related to this resource
- - type: string

linkedResources

- type: array
- description: resources related to this resource. For now, this will only contain the cluster
- - BaseApiDTO (on page 1088)

ResourceGroupApiDTO

Description

Inherits From

This DTO inherits from GroupApiDTO (on page 1132)

Optional Parameters

parentUuid

- type: string
- **description:** Parent Business Account uuid (e.g subscription in Azure) where the Resource Group belongs to.

parentDisplayName

- type: string
- description: Parent Business Account display name (e.g subscription in Azure) where the Resource Group belongs to.



RoleApiDTO

Description

Model to describe a User Role, it describe the permissions of an user over the Ops. Manager capabilities

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

name

- type: string
- description: Name of the role

SAMLIdpApiDTO

Description

Model to describe an SAML IDP. It contains IDP URL and is SAML ONLY enabled or not.

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

idpURL

type: string

description: The SAML IDP URL

isSAMLOnly

type: booleanisSingleLogoutEnabledtype: boolean



STEntityAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

displayName

■ type: string

description: Display Name

name

■ type: string

description: Name

productName

■ type: string

description: Product Name

productType

■ type: string

description: Product Type

deviceld

type: string

description: Device ID

deviceName

type: string

description: Device Name

externalNames

■ type: array

description: External Names

type: string

altName

type: string

description: Alternative Name

ssdDiskCount

■ type: integer

■ format: int64

description: SSD Disk Count

rpm7200DiskCount

■ type: integer

■ format: int64

description: RPM 7200 Disk Count



rpm10KDiskCount

type: integerformat: int64

■ description: RPM 10K Disk Count

rpm15KDiskCount

type: integerformat: int64

description: RPM 15K Disk Count

getvSeriesDiskCount

type: integerformat: int64

description: VSeries Disk Count

ssdDiskIOPSCapacity

type: numberformat: double

description: SSD Disk IOPS Capacity

rpm7200DiskIOPSCapacity

type: numberformat: double

description: RPM 7200 Disk IOPS Capacity

rpm10KDiskIOPSCapacity

type: numberformat: double

description: RPM 10K Disk IOPS Capacity

rpm15KDiskIOPSCapacity

type: numberformat: double

■ description: RPM 15K Disk IOPS Capacity

getvSeriesDiskIOPSCapacity

type: numberformat: double

description: VSeries Disk IOPS Capacity

technologyType

■ type: string

■ description: HCl Technology Type

rawCapacity

type: integerformat: int64

description: HCI Raw Capacity

rawFreespace

type: integerformat: int64

description: HCI Raw Freespace



rawUncommitted

type: integerformat: int64

description: HCI Raw Uncommitted

redundancyMethod

type: string

description: HCI Redundancy Method

failuresToTolerate

type: integerformat: int32

description: HCI Failures To Tolerate

spaceReservationPct

type: integerformat: int32

■ description: HCI Space Reservation Percentage

ScenarioApiDTO

Description

Model to describe a What-If Scenario, composed by a list of changes

Optional Parameters

uuid

■ type: string

displayName

type: string

 description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

owners

■ type: array

description: Users that owns the scenario

■ - <u>UserApiDTO (on page 1239)</u>

type

type: string

description: Type of the scenario

scope

type: array

description: List of entities/group that define the Scope

BaseApiDTO (on page 1088)



projectionDays

■ type: array

description: List of days that define when the scenario should run

type: integerformat: int32

topologyChanges

description: Changes to apply to the topology of the plan market

<u>TopologyChangesApiDTO (on page 1236)</u>

loadChanges

description: Workload utilization changes in the scenario

■ LoadChangesApiDTO (on page 1143)

configChanges

description: Configuration changes in the scenario

■ ConfigChangesApiDTO (on page 1108)

timebasedTopologyChanges

■ <u>TimeBasedTopologyChangesApiDTO (on page 1235)</u>

ScheduleApiDTO

Description

Model to describe the Schedule for a Settings Policy

Required Parameters

endTime

■ type: string

format: date-time

example: 2019-04-04T19:15

 description: End time in hours and minutes for the scheduled period in ISO8601. For example, 2019-04-04T19:15

startDate

type: string

format: date-time

example: 2019-04-04T19:15

description: Start date of the schedule period, expressed using ISO8601 Format (YYYY-MM-DDTHH:MM:SS).
 This date is local to the timezone of the instance.

startTime

type: string

■ format: date-time

example: 2019-04-04T19:15

 description: Start time in hours and minutes for the scheduled period in ISO8601. For example, 2019-04-04T17:15

Optional Parameters

uuid

■ type: string



displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

endDate

type: stringformat: date

example: 2019-04-04

description: End date of the schedule period, expressed using ISO8601 Format (YYYY-MM-DDTHH:MM:SS). This date is local to the timezone of the instance.

recurrence

description: Recurrence setup

■ RecurrenceApiDTO (on page 1184)

timeZone

■ type: string

description: The time zone name based on tz database

nextOccurrence

■ type: string

■ **description:** The date and time of the next occurence of this schedule represented in ISO8601 local time (YYYY-MM-DDTHH:MM:SS). For example, 2019-04-04T19:15

nextOccurrenceTimestamp

type: integer

■ format: int64

■ **description:** The date and time of the next occurrence of this schedule represented in Timestamp in milliseconds. For example, 1562100619000

remaingTimeActiveInMs

■ type: integer

format: int64

description: The amount of time that the schedule is going to be active at the time of call in milliseconds. This field will not be populated if the schedule is not currently active.

ScheduleEntityResponseApiDTO

Description

represents a response of the attach/detach time span schedule to/from the parkable entity

Optional Parameters

error

type: string

example: entityUuid not found

description: error indicating the reason for failure

entityUUID

■ type: string



ScheduleItemApiDTO

Description

Base model to describe a ScheduleItem.

Required Parameters

type

- type: string
- example: ParkingItemApiDTO
- description: Scheduleltem type discriminator. Describes which subclass of Scheduleltem is returned.

ScheduleTimeSpansApiDTO

Description

Parking time span schedule

Required Parameters

timeZone

- type: string
- example: America/New_York
- description: Timezone for the time spans in this schedule. Should be chosen from the IANA Timezone
 Database here: [https://www.iana.org/time-zones]. See the list in wikipedia here: [https://en.wikipedia.org/wiki/List_of_tz_database_time_zones]

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

description

- type: string
- example: Up 7-5 on weekdays
- description: Description of the schedule

timeSpans

- description: Weekly schedule time spans
- <u>TimeSpanGroupApiDTO (on page 1236)</u>



ScopeUuidsApiInputDTO

Description

Model to describe the request by UUIDs

Required Parameters

uuids

type: array

description: List of uuids

■ - **type:** string

maxItems: 2147483647

minItems: 1

Optional Parameters

marketId

■ type: string

description: Market ID associated with the requested items

SearchAllQueryApiDTO

Description

A query used to search across the entire topology (entities and groups)

Required Parameters

select

description: Defines what subset of types (entities and groups) should be returned.

readOnly: True

■ SelectAllApiDTO (on page 1203)

where

description: Conditions that each retrieved object must satisfy (currently only name is supported).

■ readOnly: True

■ WhereApiDTO (on page 1247)

Optional Parameters

pagination

description: Pagination information.

■ readOnly: True

■ PaginationApiDTO (on page 1158)

SearchCountRecordApiDTO

Description

A count of entities.



Required Parameters

count

type: integerformat: int32

description: Count of entities.

■ readOnly: True

groupBys

type: array

• description: List of fields describing the groupBys that this count represents

■ readOnly: True

FieldValueApiDTO (on page 1130)

SearchQueryRecordApiDTO

Description

A record with information about an entity or a group.

Required Parameters

oid

type: integerformat: int64

description: Unique identifier for the entity or group.

■ readOnly: True

values

■ type: array

description: Information about the entity or group.

■ readOnly: True

FieldValueApiDTO (on page 1130)

SelectAllApiDTO

Description

Specification of what subset of types (entities and groups) should be returned.



Optional Parameters

entityTypes

■ type: array

description: Entity types to include in the response.

readOnly: Truetype: string

enum: ['Application', 'ApplicationComponent', 'ApplicationServer', 'AvailabilityZone', 'BusinessAccount', 'BusinessApplication', 'BusinessTransaction', 'BusinessUser', 'Chassis', 'CloudService', 'ComputeTier', 'Container', 'ContainerPod', 'ContainerSpec', 'DatabaseServer', 'DatabaseServerTier', 'DatabaseTier', 'DataCenter', 'DesktopPool', 'DiskArray', 'DPod', 'HCIPhysicalMachine', 'HypervisorServer', 'Internet', 'IOModule', 'LoadBalancer', 'LogicalPool', 'Namespace', 'Network', 'PhysicalMachine', 'ProcessorPool', 'Region', 'ReservedInstance', 'Service', 'ServiceProvider', 'Storage', 'StorageController', 'StorageTier', 'Switch', 'Unknown', 'ViewPod', 'VirtualApplication', 'VirtualDataCenter', 'VirtualMachine', 'VirtualVolume', 'VPod', 'WorkloadController', 'ContainerPlatformCluster', 'CloudCommitment', 'ApplicationComponentSpec', 'VirtualMachineSpec', 'DocumentCollection']

groupTypes

type: array

description: Group types to include in the response.

readOnly: Truetype: string

enum: ['Group', 'Resource', 'Cluster', 'VMCluster', 'StorageCluster', 'BusinessAccountFolder', 'BillingFamily', 'NodePool']

SelectEntityApiDTO

Description

Specification of what fields should be fetched in an entity search response.

Required Parameters

entityType

type: string

description: Entity Type

readOnly: True

enum: ['Application', 'ApplicationComponent', 'ApplicationServer', 'AvailabilityZone', 'BusinessAccount', 'BusinessApplication', 'BusinessTransaction', 'BusinessUser', 'Chassis', 'CloudService', 'ComputeTier', 'Container', 'ContainerPod', 'ContainerSpec', 'DatabaseServer', 'DatabaseServerTier', 'DatabaseTier', 'DataCenter', 'DesktopPool', 'DiskArray', 'DPod', 'HClPhysicalMachine', 'HypervisorServer', 'Internet', 'IOModule', 'LoadBalancer', 'LogicalPool', 'Namespace', 'Network', 'PhysicalMachine', 'ProcessorPool', 'Region', 'ReservedInstance', 'Service', 'ServiceProvider', 'Storage', 'StorageController', 'StorageTier', 'Switch', 'Unknown', 'ViewPod', 'VirtualApplication', 'VirtualDataCenter', 'VirtualMachine', 'VirtualVolume', 'VPod', 'WorkloadController', 'ContainerPlatformCluster', 'CloudCommitment', 'ApplicationComponentSpec', 'VirtualMachineSpec', 'DocumentCollection']

Optional Parameters

fields

type: array

description: Fields to fetch.

readOnly: True

FieldApiDTO (on page 1130)



SelectGroupApiDTO

Description

Specification of what fields should be fetched in a group search response.

Required Parameters

groupType

- type: string
- description: Group Type.
- readOnly: True
- enum: ['Group', 'Resource', 'Cluster', 'VMCluster', 'StorageCluster', 'BusinessAccountFolder', 'BillingFamily', 'NodePool']

Optional Parameters

fields

- type: array
- **description:** Fields to fetch.
- readOnly: True
- FieldApiDTO (on page 1130)

ServiceEntityApiDTO

Description

Model to describe an Entity, e.g. Virtual Machine, Physical Machine, Storage

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

environmentType

- type: string
- description: Environment type
- enum: ['CLOUD', 'ONPREM', 'HYBRID']

discoveredBy

- description: Target that discovered the entity
- TargetApiDTO (on page 1224)

vendorlds

- type: object
- description: The mapping of target identifier to vendor-provided identity of this entity on the remote target
- additionalProperties: {'type': 'string'}



priceIndex

- type: numberformat: float
- description: Price index of the Entity

state

- type: string
- description: State
- enum: ['IDLE', 'RESOURCE_ALLOCATION', 'LAUNCH', 'ACTIVE', 'RESOURCE_RELEASE', 'SUSPEND', 'SUSPEND_PENDING', 'TERMINATE_PENDING', 'NOT_MONITORED', 'MAINTENANCE', 'FAILOVER', 'UNKNOWN', 'EVACUATED', 'QUEUED']

severity

- type: string
- description: Highest severity of the Actions related to this entity
- enum: ['UNKNOWN', 'NORMAL', 'MINOR', 'MAJOR', 'CRITICAL']

unplacementDetails

- description: Additional information provided for unplaced entities in a plan
- UnplacementDetailsApiDTO (on page 1237)

placedOn

- type: string
- description: The comma-separated classNames of entities successfully placed on, used for Unplaced entities in a Plan Market - [DEPRECATED - Use: unplacementDetails.placedOn]

notPlacedOn

- type: string
- description: The comma-separated classNames of entities could not be placed on, used for Unplaced entities in a Plan Market - [DEPRECATED - Use: unplacementDetails.reasons]

unplacedExplanation

- type: string
- description: The reason(s) the entity could not be placed [DEPRECATED Use: unplacementDetails.reasons]

costPrice

- type: number
- format: float
- description: Cost price per Hour

severityBreakdown

- **type:** object
- description: A Map of severity along with their count. E.g. {CRITICAL: 1, NORMAL: 10}
- additionalProperties: {'type': 'integer', 'format': 'int64'}

remoteld

- type: string
- description: The identifier of this instance on the remote target from which it was discoveredc -[DEPRECATED - Use: vendorlds]

realtimeMarketReference

- description: In case of a Plan Market Entity, this contains the original entity from the Real Time Market
- BaseApiDTO (on page 1088)



providers

■ type: array

description: List of Providers

BaseApiDTO (on page 1088)

consumers

■ type: array

description: List of Consumers

BaseApiDTO (on page 1088)

template

■ description: Related Template

■ TemplateApiDTO (on page 1230)

numRelatedVMs

type: integerformat: int32

description: Number of related VMs

connectedEntities

type: array

- description: Limited list of connected entities relevant to the service entity. This will not contain all connected entities.
- - BaseApiDTO (on page 1088)

aspects

type: object

description: Additional info about the Entity categorized as Aspects

additionalProperties: {'\$ref': '#/definitions/EntityAspect'}

tags

■ type: object

description: Tags are the metadata defined in name/value pairs. Each name can have multiple values.

additionalProperties: {'type': 'array', 'items': {'type': 'string'}}

onDemandRateBefore

type: numberformat: float

description: On-demand rate before actions

onDemandRateAfter

type: numberformat: float

description: On-demand rate after actions

staleness

■ type: string

 description: [BETA]: Whether the entity is outdated, i.e. discovered too long ago to be considered for analytical purposes

enum: ['CURRENT', 'STALE']

ServletOutputStream

Description



Optional Parameters

ready

■ type: boolean

SettingActivePolicyApiDTO

Description

Model to describe a Settings Policy that affect the value of a Setting

Required Parameters

numEntities

- type: integerformat: int32
- description: Number of entities affected by the Settings Policy value

settingsPolicy

- description: Settings Policy that affects the final value of a Setting
- BaseApiDTO (on page 1088)

value

- type: string
- description: Setting value declared in the Settings Policy

SettingApiDTOSerializable

Description

Generic model to describe a Setting. Sub types include StringSettingApiDTO and RIPurchaseProfilesSettingApiDTO.

Required Parameters

value

- description: Value of the setting. Type indicated by the `valueObjectType` field. The default type is `String`
- \$ref: #/definitions/object

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string



valueDisplayName

■ type: string

description: Display Name of the Value, in case the value is a Template or another entity

readOnly: True

defaultValue

description: Default value before any change

readOnly: True

\$ref: #/definitions/object

categories

■ type: array

description: Category and sub categories of the setting

readOnly: Truetype: string

valueType

■ type: string

description: Define the type of the value

enum: ['STRING', 'NUMERIC', 'INTEGER', 'BOOLEAN']

valueObjectType

type: string

description: The type of complex object values. Defaults to 'String'.

• enum: ['String', 'ReservedInstancePurchaseSettingsDTO']

options

type: array

description: List of allowable value for this setting

readOnly: True

SettingOptionApiDTO (on page 1214)

min

■ type: number

format: double

description: If type is NUMERIC, this define the min limit

readOnly: True

max

type: number

format: double

description: If type is NUMERIC, this define the max limit

■ readOnly: True

entityType

type: string

description: Entity type for this Setting

range

description: Range options for the value of the setting

■ readOnly: True

■ RangeApiDTO (on page 1180)



scope

type: string

 description: Define the visibility of the setting. E.G. a Local Setting is only visible when associated with an Entity/Group

■ readOnly: True

enum: ['GLOBAL', 'LOCAL']

activeSettingsPolicies

■ type: array

description: List of Settings Policies that are affecting the final value of this setting

SettingActivePolicyApiDTO (on page 1208)

sourceGroupName

type: string

description: Source group name for setting value

sourceGroupUuid

type: string

description: Source group uuid for setting value

SettingApiDTOString

Description

Generic model to describe a Setting. Sub types include StringSettingApiDTO and RIPurchaseProfilesSettingApiDTO.

Required Parameters

value

description: Value of the setting. Type indicated by the `valueObjectType` field. The default type is `String`

■ \$ref: #/definitions/object

Optional Parameters

uuid

type: string

displayName

■ type: string

 description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

valueDisplayName

■ type: string

description: Display Name of the Value, in case the value is a Template or another entity

readOnly: True

defaultValue

description: Default value before any change

■ readOnly: True

\$ref: #/definitions/object



categories

■ type: array

description: Category and sub categories of the setting

readOnly: Truetype: string

valueType

type: string

description: Define the type of the value

■ enum: ['STRING', 'NUMERIC', 'INTEGER', 'BOOLEAN']

valueObjectType

■ type: string

description: The type of complex object values. Defaults to 'String'.

enum: ['String', 'ReservedInstancePurchaseSettingsDTO']

options

■ type: array

description: List of allowable value for this setting

readOnly: True

SettingOptionApiDTO (on page 1214)

min

type: number

format: double

■ **description:** If type is NUMERIC, this define the min limit

readOnly: True

max

type: number

format: double

description: If type is NUMERIC, this define the max limit

readOnly: True

entityType

■ type: string

■ **description:** Entity type for this Setting

range

description: Range options for the value of the setting

readOnly: True

RangeApiDTO (on page 1180)

scope

type: string

description: Define the visibility of the setting. E.G. a Local Setting is only visible when associated with an Entity/Group

■ readOnly: True

enum: ['GLOBAL', 'LOCAL']

activeSettingsPolicies

type: array

description: List of Settings Policies that are affecting the final value of this setting

SettingActivePolicyApiDTO (on page 1208)



sourceGroupName

■ type: string

description: Source group name for setting value

sourceGroupUuid

■ type: string

description: Source group uuid for setting value

SettingApiDTO

Description

Generic model to describe a Setting. Sub types include StringSettingApiDTO and RIPurchaseProfilesSettingApiDTO.

Required Parameters

value

- description: Value of the setting. Type indicated by the `valueObjectType` field. The default type is `String`
- \$ref: #/definitions/object

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

valueDisplayName

- type: string
- description: Display Name of the Value, in case the value is a Template or another entity
- readOnly: True

defaultValue

- description: Default value before any change
- readOnly: True
- \$ref: #/definitions/object

categories

- type: array
- description: Category and sub categories of the setting
- readOnly: True
- type: string

valueType

- type: string
- description: Define the type of the value
- enum: ['STRING', 'NUMERIC', 'INTEGER', 'BOOLEAN']



valueObjectType

- type: string
- **description:** The type of complex object values. Defaults to 'String'.
- enum: ['String', 'ReservedInstancePurchaseSettingsDTO']

options

- type: array
- description: List of allowable value for this setting
- readOnly: True
- SettingOptionApiDTO (on page 1214)

min

- type: numberformat: double
- **description:** If type is NUMERIC, this define the min limit
- readOnly: True

max

- type: numberformat: double
- description: If type is NUMERIC, this define the max limit
- readOnly: True

entityType

- type: string
- **description:** Entity type for this Setting

range

- description: Range options for the value of the setting
- readOnly: True
- RangeApiDTO (on page 1180)

scope

- type: string
- description: Define the visibility of the setting. E.G. a Local Setting is only visible when associated with an Entity/Group
- readOnly: True
- enum: ['GLOBAL', 'LOCAL']

activeSettingsPolicies

- type: array
- description: List of Settings Policies that are affecting the final value of this setting
- SettingActivePolicyApiDTO (on page 1208)

sourceGroupName

- type: string
- description: Source group name for setting value

sourceGroupUuid

- type: string
- description: Source group uuid for setting value



SettingOptionApiDTO

Description

Optional Parameters

label

type: string

value

■ type: string

SettingsManagerApiDTO

Description

Model to describe a Category Manager for the settings

Required Parameters

category

■ type: string

description: Category of the Manager

settings

■ type: array

description: List of Settings contained in the Manager

SettingApiDTOSerializable (on page 1208)

Optional Parameters

uuid

type: string

displayName

■ type: string

 description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

SettingsPolicyApiDTO

Description

Model to describe a Setting Policy: a group of Settings that are applied based on Scope and/or Schedule

Optional Parameters

uuid

type: string



displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

entityType

- type: string
- **description:** Type of the Settings Policy. E.G. VirtualMachine, PhysicalMachine, ...

scopes

- type: array
- description: List of scopes where the settings are applied, on create/edit, only Uuid is required. If null it's considered Global scope
- GroupApiDTO (on page 1132)

settingsManagers

- type: array
- description: List of groups of Settings to activate in this Policy
- SettingsManagerApiDTO (on page 1214)

schedule

- description: Schedule to define when the settings are applied
- ScheduleApiDTO (on page 1199)

disabled

- type: boolean
- description: Control if the policy is Enabled or Disabled

note

- type: string
- description: Note for this Policy

readOnly

- type: boolean
- description: If true, prevents users from deleting or modifying the SettingPolicy.

default

■ type: boolean

SkippedActionApiDTO

Description

Model to describe an action that was skipped in execution.

Required Parameters

actionId

- type: string
- description: Action ID



Optional Parameters

reason

■ type: string

description: Reason why action was skipped

StatApiDTO

Description

Model to describe a Statistic

Optional Parameters

uuid

■ type: string

displayName

■ type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

name

■ type: string

description: Name

capacity

■ description: Capacity values, used for Commodities stats

StatValueApiDTO (on page 1221)

reserved

description: Reserved values, used for Commodities stats

■ StatValueApiDTO (on page 1221)

relatedEntityType

type: string

description: E.G.virtual machine

filters

type: array

description: describe the grouping options used to generate the output

StatFilterApiDTO (on page 1218)

relatedEntity

description: Provider or Consumer of the Statistic, 'relatedEntity' and 'numRelatedEntities' are mutually exclusive

BaseApiDTO (on page 1088)

numRelatedEntities

type: integerformat: int32

description: Number of providers or consumers for this statistic, 'relatedEntity' and 'numRelatedEntities' are mutually exclusive



units

■ type: string

description: Units, used for Commodities stats. E.G. \$/h

values

description: Contains Average, Min, Max, Total

StatValueApiDTO (on page 1221)

value

type: numberformat: float

description: Simple value, equal to values.avg.

commoditySource

- description: Source for a commodity's capacity and usage, used for Commodities stats
- StatCommoditySourceApiDTO (on page 1218)

histUtilizations

- type: array
- description: Commodity historical utilization values
- StatHistUtilizationApiDTO (on page 1219)

StatApiInputDTO

Description

Model to describe the request of a Stat. Please note that the costPrice stat is deprecated and will EOL in 8.10.1. Use the dedicated 'cost' endpoints in /entities, /groups and /markets instead.

Optional Parameters

name

type: string

description: Name of the stat

relatedEntityType

■ type: string

 description: Used to get stats from different entity types in the supply chain of {uuid} E.G.costPrice of the VMs where the scope is a PM

filters

type: array

- description: Filters to apply to the requested stats. Commodities supported values: key = {commodity_key}, relation = sold|bought, virtualDisk = {uuid}. Cost Price supported values: cumulative = true|false, cloudService = {uuid}, target = {uuid}, CSP = {name}, category = {name}, businessUnit = {uuid}, costComponent = COMPUTE|IP|LICENSE|STORAGE, costComponentArtifact = {key}. Please note that the costPrice stat is deprecated and will EOL in 8.10.1. Use the dedicated 'cost' endpoints in /entities, /groups and /markets instead.Action stats supported values: actionTypes = {actionType}, actionModes: {action_mode}, actionStates: {action_state}, riskSubCategory: Performance Assurance|Efficiency Improvement|Prevention|Compliance, riskSeverity: UNKNOWN|NORMAL|MINOR|MAJOR|CRITICAL
- StatFilterApiDTO (on page 1218)



groupBy

- type: array
- description: Execute a groupBy on the values of the stats. Commodities supported values: key, relatedEntity, virtualDisk. Cost Price supported values: cloudService, target, CSP, category, businessUnit, costComponent, costComponentArtifact. Please note that the costPrice stat is deprecated and will EOL in 8.10.1. Use the dedicated 'cost' endpoints in /entities, /groups and /markets instead.Action stats supported values: actionTypes, actionModes, actionStates, risk, riskSubCategory, riskSeverity
- - type: string

historyType

- type: string
- description: Query the histUtilization table for these historyTypes
- enum: ['Percentile', 'Smoothed']

StatCommoditySourceApiDTO

Description

Model to describe commodity source for a single statistic, e.g. commodity source for VCPU (capacity and usage)

Optional Parameters

capacityCommoditySource

- type: string
- description: Commodity source for capacity

usedCommoditySource

- **type:** string
- description: Commodity source for usage

StatFilterApiDTO

Description

Model to describe the filter applied to a Statistic

Required Parameters

type

- type: string
- description: type of the filter, E.G: actionTypes, category, ...

Optional Parameters

value

- type: string
- description: value of the filter



StatHistUtilizationApiDTO

Description

Model to describe a historical utilization statistic, e.g. the P95 vCPU or P95 vMEM of a VM over (up to) NN days observation period.

Optional Parameters

type

type: string

description: Historical utilization type

usage

type: numberformat: float

description: Historical usage

capacity

type: numberformat: float

description: Historical capacity

resizeMaxScalingObservationPeriod

type: numberformat: float

 description: Resize max scaling observation period. Affects on amount of data points considered for action generation process. Value in days.

resizeScalingAggressiveness

type: numberformat: float

■ **description:** Resize scaling aggressiveness. Describes how aggressively Turbonomic will resize in response of resource utilization. Value in percents. 100% least aggressive, 95% most aggressive.

StatPeriodApiInputDTO

Description

Model to describe the request for Statistics by a Time range

Required Parameters

statistics

type: array

description: List of requested statistics, if empty all stats will be processed

StatApilnputDTO (on page 1217)

Optional Parameters

startDate

type: string

description: Start time of the period to filter, if empty the current stats will be processed



endDate

■ type: string

description: End time of the period to filter, if empty the current stats will be processed

StatScopesApiInputDTO

Description

Model to describe the request for Statistics in multiple Scopes

Optional Parameters

scopes

type: array

description: List of uuid to use as scope

type: string

period

description: List of requested statistics

StatPeriodApiInputDTO (on page 1219)

relatedType

type: string

description: Get the stats for the entity type related to the scopes

StatSnapshotApiDTO

Description

Model to describe the Statistics of a snapshot, contains a list of Statistics for a moment in time

Required Parameters

statistics

type: array

■ description: List of statistics, e.g. Price Index, Commodities values, Cost price, Number of VMs in a Group, ...

StatApiDTO (on page 1216)

Optional Parameters

uuid

type: string

displayName

type: string

 description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

date

type: string

description: When the statistics were recorded



epoch

- type: string
- description: An indicator of whether the snapshot represents historical, projected or plan data. Should be used in conjunction with the date field to understand the context of this stat snapshot.
- enum: ['HISTORICAL', 'CURRENT', 'PROJECTED', 'PLAN_SOURCE', 'PLAN_PROJECTED']

StatValueApiDTO

Description

Model to describe a single statistic, e.g. the CPU of a PM Group

Optional Parameters

max

type: numberformat: float

description: Max value

min

type: numberformat: float

■ description: Min value

avg

type: numberformat: float

description: Average value

total

type: numberformat: float

description: Total value - sum of average values in a group

totalMax

type: numberformat: float

description: Total max value - sum of max values in a group

totalMin

type: numberformat: float

description: Total min value - sum of min values in a group

StringSettingApiDTO

Description

Inherits From

This DTO inherits from SettingApiDTO (on page 1212)



Required Parameters

value

- type: string
- **description:** Value of the setting. Type indicated by the `valueObjectType` field. The default type is `String`

Optional Parameters

defaultValue

- type: string
- description: Default value before any change
- readOnly: True

SupplyChainStatsApiInputDTO

Description

Model to describe a Filter for Entities

Required Parameters

uuids

- type: array
- description: List of uuids used to build the supply chain
- type: string
- maxItems: 2147483647
- minItems: 1

Optional Parameters

types

- type: array
- description: List of Types to filter
- type: string

states

- type: array
- description: List of States to filter
- type: string
 - enum: ['IDLE', 'RESOURCE_ALLOCATION', 'LAUNCH', 'ACTIVE', 'RESOURCE_RELEASE', 'SUSPEND', 'SUSPEND_PENDING', 'TERMINATE_PENDING', 'NOT_MONITORED', 'MAINTENANCE', 'FAILOVER', 'UNKNOWN', 'EVACUATED', 'QUEUED']

groupBy

- type: array
- description: List of fields used to group the Stats
- type: string
 - enum: ['entityType', 'state', 'severity', 'riskSubCategory', 'template', 'target', 'businessUnit', 'resourceGroup', 'nodePool']

environmentType

- type: string
- description: Filter the actions by Environment Type
- enum: ['ONPREM', 'CLOUD']



SupplychainApiDTO

Description

Model to describe the Supply Chain: the Environment is described as a chain between Producers and Consumers

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

seMap

- type: object
- description: Model to describe the type of Entity associated with a SupplyChainEntry
- **additionalProperties:** {'\$ref': '#/definitions/SupplychainEntryDTO'}

SupplychainEntryDTO

Description

Model to describe a Supply Chain Entry

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

depth

- type: integer
- format: int32
- description: Number to indicate the level of depth of the Entity type in the Supply Chain

entitiesCount

- type: integer
- format: int32
- description: Number of entity in this level of depth



healthSummary

■ type: object

description: Entities count by Severity

additionalProperties: {'type': 'integer', 'format': 'int32'}

stateSummary

■ type: object

description: Entities count by State

additionalProperties: {'type': 'integer', 'format': 'int32'}

connectedProviderTypes

type: array

description: List of provider types connected to this level of depth

uniqueltems: Truetype: string

connectedConsumerTypes

■ type: array

description: List of consumer types connected to this level of depth

uniqueltems: Truetype: string

instances

■ type: object

description: List of entities in this level of depth

additionalProperties: {'\$ref': '#/definitions/ServiceEntityApiDTO'}

TagApiDTO

Description

Tag information

Optional Parameters

key

type: string

description: Tag key

values

■ type: array

■ description: Tag value

■ - type: string

TargetApiDTO

Description

Model to describe a Target. Targets are used to discover the components to create a connected virtual environment



Required Parameters

type

type: string

description: Probe type. Turbonomic ships with the following probe types: AppDynamics, Dynatrace, Datadog, Arista, AWS, Azure, Cisco APIC, Cisco HyperFlex, Cisco UCS Central, Cisco UCS Director, Cisco UCS Manager, CloudFoundry, CloudStack, Dell Compellent, EMC ScaleIO, EMC VMAX, EMC VNX, EMC VPLEX, EMC XtremIO, Hitachi Vantara, HP OneView, HPE 3PAR, Hyper-V, IBM PowerVM, Instana, JBoss, JVM, MSExchange, MySQL, NetApp, NetFlow, NetScaler, Nutanix, OpenStack, Oracle, Pivotal Ops Manager, Pure, Red Hat Virtualization Manager, sFlow, SNMP, SoftLayer, SQLServer, Tetration, Tomcat, vCenter, vCloudDirector, VMM, WebLogic, WebSphere, WMI, XenServer,

Optional Parameters

uuid

■ type: string

displayName

■ type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

category

type: string

■ example: Hypervisor

description: Probe category.

uiCategory

■ type: string

- example: Application Server, Billing, Cloud Management, Applications and Databases, Fabric and Network, Guest OS Processes, HYPERCONVERGED, HYPERVISOR, Load Balancer, Operations Manager Appliance, ORCHESTRATOR, PaaS, Storage, Storage Browsing, WINDOWS APPLICATION. There are also categories Custom and UNKNOWN to be used for new probe development.
- description: Probe UI category.

identifyingFields

■ type: array

- **description:** Array of field names used to differentiate probes of the same category. Most typically either the name/address field, or a combination of address and port.
- type: string

inputFields

type: array

- description: List of all InputFieldApiDTO objects for the target, analogous to the target addition form fields in the GUI.
- InputFieldApiDTO (on page 1138)

lastValidated

type: string

 description: Date of the last validation - [DEPRECATED - Use: healthSummary.timeOfLastSuccessfulDiscovery]



status

- type: string
- example: Validated, VALIDATION FAILED, UNKNOWN
- description: Description of the status of the most recent Validation Operation [DEPRECATED Use: healthSummary.healthState]

derivedTargets

- type: array
- description: Targets derived (created by discovery of) from this target. Populated depending on the TargetRelationship parameter.
- - TargetApiDTO (on page 1224)

patchedTargets

- type: array
- description: Targets patched by this target
- PatchedTargetDataApiDTO (on page 1165)

parentTargets

- type: array
- description: Targets that created this target. Populated depending on the TargetRelationship parameter.
- TargetApiDTO (on page 1224)

readonly

- type: boolean
- description: Whether the target cannot be changed through public APIs.

health

- description: [BETA]: A summary of the overall health of the target. Only returned if TargetDetailLevel is HEALTH or HEALTH_DETAILS
- TargetHealthApiDTO (on page 1227)

lastTargetOperationStages

- type: array
- description: [BETA]: The status at each stage of the most recent validation or discovery, which ever was more recent. Only returned if TargetDetailLevel is HEALTH_DETAILS
- TargetOperationStageApiDTO (on page 1228)

lastEditTime

- type: string
- example: 2021-07-07T20:33:49Z
- description: [BETA]: The last time the target was edited in ISO-8601 Format (YYYY-MM-DDTHH:MM:SSZ).
 For example 2021-07-07T20:33:49Z

lastEditUser

- type: string
- description: [BETA]: The username for last user who edited the target.

healthSummary

- **description:** The health summary of the target.
- TargetHealthSummaryApiDTO (on page 1228)

TargetErrorDetailsApiDTO

Description

Additional details related to a target error.



Required Parameters

targetErrorDetailsClass

■ type: string

TargetHealthApiDTO

Description

A DTO that describes the health of a single target.

Required Parameters

healthCategory

■ type: string

description: The type of the health checks that are done.

enum: ['TARGET', 'ACTION', 'COMPONENT']

healthClassDiscriminator

■ type: string

example: TargetHealthApiDTO

description: Health type discriminator. Describes which subclass of BaseHealthApiDTO is returned.

rollupState

■ type: string

example: NORMAL

description: The health state of the target including its derived targets.

■ enum: ['CRITICAL', 'MAJOR', 'MINOR', 'NORMAL']

targetName

type: string

description: Target display name.

uuid

type: string

description: UUID of the target.

Optional Parameters

errorText

■ type: string

description: Error text (if there's any).

timeOfFirstFailure

type: string

 description: Time of first failure of validation/discovery (if the target is in failed state; ISO-8601 formatted String).

timeOfLastSuccessfulDiscovery

■ type: string

example: 2021-07-07T20:33:49Z

description: [BETA]: The last time a successful discovery finished on the target in ISO-8601 Format (YYYY-MM-DDTHH:MM:SSZ). For example 2021-07-07T20:33:49Z



targetErrorDetails

- type: array
- description: Error details related to a target. Supports multiple errors details.
- TargetErrorDetailsApiDTO (on page 1226)

targetStatusSubcategory

- type: string
- enum: ['DISCOVERY', 'VALIDATION', 'DUPLICATION', 'DELAYED_DATA']

healthState

- type: string
- enum: ['CRITICAL', 'MAJOR', 'MINOR', 'NORMAL']

TargetHealthSummaryApiDTO

Description

A DTO that describes target health.

Required Parameters

healthState

- type: string
- example: NORMAL
- **description:** The target health state.
- enum: ['CRITICAL', 'MAJOR', 'MINOR', 'NORMAL']

rollupState

- type: string
- example: NORMAL
- description: The health state of the target including its derived targets.
- enum: ['CRITICAL', 'MAJOR', 'MINOR', 'NORMAL']

Optional Parameters

timeOfLastSuccessfulDiscovery

- type: string
- example: 2021-07-07T20:33:49Z
- description: The last time a successful discovery finished on the target in ISO-8601 Format (YYYY-MM-DDTHH:MM:SSZ). For example 2021-07-07T20:33:49Z

TargetOperationStageApiDTO

Description

Holds all information related to a stage of discovery or validation.

Optional Parameters

description

- type: string
- **description:** The description of what this stage is doing (ideally in less that 70 characters). Example of description are "validating credentials" or "retrieving business applications".



status

- description: Holds all the information of this particular instance of the discovery or validation stage.
- TargetOperationStageStatusApiDTO (on page 1229)

TargetOperationStageStatusApiDTO

Description

Holds all the information of this particular instance of the discovery or validation stage.

Optional Parameters

state

- type: string
- description: The state of this stage at the end of the discovery or validation.
- enum: ['DID NOT RUN', 'SUCCESS', 'FAILURE']

summary

- type: string
- description: The short message (ideally 70 characters or less) explaining the stage status. Example of such messages are "invalid credentials" or "4 business application retrieved".

fullExplanation

- type: string
- description: The full message explaining the stage status. This explanation may include the instructions or hints on how to address issue if there is one.

TargetThirdPartyErrorDetailsApiDTO

Description

Inherits From

This DTO inherits from TargetErrorDetailsApiDTO (on page 1226)

Optional Parameters

targetErrorType

- type: string
- description: Target validation/discovery error type.

errorCode

- type: string
- **example:** 0x423232, 404, 400
- description: Error code related to the failure.

endPoint

- type: string
- description: End point which caused the third party api failure. This can be a complete URLor a method name while using the third party SDK.



TelemetryDTO

Description

Model to describe the status of telemetry

Optional Parameters

telemetryTermsViewed

- type: boolean
- description: Controls when an administrator should be shown the telemetry opt in

telemetryEnabled

- type: boolean
- description: Controls whether analytics and telemetry are enabled

TemplateApiDTO

Description

Model to describe a Template: contains the resources used to Deploy a VM or to Add Workload/Supply in a Plan

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

price

- type: number
- format: float
- description: The estimated cost of the template. Used for Physical Machine and Storage templates where the hardware cost is known.

model

- type: string
- example: Cisco UCS B200 M5 (Intel Xeon Gold 5115, 2.40 GHz), PowerEdge R940 (Intel Xeon Gold 6136, 3.00 GHz), etc.
- **description:** The model of the entire Physical Machine system.

cpuModel

- type: string
- example: Intel Xeon Gold 6130, AMD Opteron 6166 HE, etc.
- description: The model of the CPU in the Physical Machine.



vendor

■ type: string

■ example: Cisco, Microsoft, HP, Novell

description: Vendor of the templated entity

description

■ type: string

description: Description

image

■ type: string

description: Container Profile image

imageTag

type: string

description: (UNUSED) Container Profile image tag

cmdWithArgs

■ type: string

description: (UNUSED) Container command with Arguments

dbEngine

■ type: string

example: PostgreSql, AuroraMySQL, SqlServer

description: Database engine, used for Database templates

dbEdition

■ type: string

example: Standard One, Enterprise, Premium_P2

description: Database edition, used for Database templates

computeResources

■ type: array

description: ResourceApiDTO describing the compute resources. Max 1 per template.

ResourceApiDTO (on page 1194)

maxItems: 1minItems: 0

storageResources

■ type: array

description: ResourceApiDTO describing the storage resources

ResourceApiDTO (on page 1194)

networkResources

■ type: array

■ description: ResourceApiDTO describing the network resources

ResourceApiDTO (on page 1194)

infrastructureResources

type: array

description: ResourceApiDTO describing the infrastructure resources. Max 1 per template

ResourceApiDTO (on page 1194)

maxItems: 1minItems: 0



deploymentProfile

- description: Deployment profile associated with the template
- DeploymentProfileApiDTO (on page 1121)

discovered

type: booleanexample: False

description: Indicates if the template is discovered or manually created

enum: [True, False]

family

■ type: string

■ example: standardDSv2Family, standardNCFamily, r5d, r3

description: For cloud templates, the instance family.

enableMatch

type: booleanexample: False

 description: Add to Infrastructure Cost Policy. Infrastructure Cost policies group hardware devices according to their cost

TemplateApiInputDTO

Description

Model to describe a Template: contains the resources used to Deploy a VM or to Add Workload/Supply in a Plan

Optional Parameters

displayName

■ type: string

description: Name of the template

className

■ type: string

description: className

enum: ['VirtualMachine', 'PhysicalMachine', 'Storage', 'Container']

price

type: numberformat: float

description: Cost price

model

type: string

 description: The Model of the entire Physical Machine system. For example: Cisco UCS B200 M5 (Intel Xeon Gold 5115, 2.40 GHz) vs. PowerEdge R940 (Intel Xeon Gold 6136, 3.00 GHz)

cpuModel

type: string

■ **description:** The model of the CPU in the Physical Machine. This is separate from the model of the entire Physical Machine. For example: Intel Xeon Gold 6130 vs. AMD Opteron 6166 HE

vendor

type: string

description: Vendor



description

■ type: string

description: Description

image

type: string

description: Profile image, used for Container templates

imageTag

type: string

description: Profile image tag, used for Container templates

cmdWithArgs

type: string

description: Command with Arguments, used for Container templates

computeResources

type: array

description: Compute resources: Number of CPU, CPU speed, Memory size, ...

ResourceApiDTO (on page 1194)

maxItems: 1minItems: 0

storageResources

type: array

description: Storage resources: Disk I/O, Disk Size, Percentage of Disk consumed

ResourceApiDTO (on page 1194)

networkResources

■ type: array

description: Network resources

ResourceApiDTO (on page 1194)

infrastructureResources

■ type: array

description: Infrastructure resources: Power, Size, Cooling

ResourceApiDTO (on page 1194)

maxItems: 1minItems: 0

deploymentProfileId

type: string

description: Ids of the Deployment Profiles associated with this Template

enableMatch

type: boolean

 description: Add to Infrastructure Cost Policy. Infrastructure Cost policies group hardware devices according to their cost

TemplatePriceAdjustmentDTO

Description

Price adjustment information for a template within a business unit and specified pricing model.



Optional Parameters

uuid

type: string

displayName

type: string

 description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

environmentType

■ type: string

description: Environment type

enum: ['CLOUD', 'ONPREM', 'HYBRID']

discount

type: numberformat: float

description: Entity discount percentage

priceAdjustment

description: Entity price adjustment percentage

■ PriceAdjustmentDTO (on page 1173)

family

type: string

 description: Family of a template, group of similar purpose templates. Available only for virtual machine templates.

pricesPerDatacenter

type: array

description: Template base rates per data center, provided for information purpose.

EntityPriceDTO (on page 1126)

TextConditionApiDTO

Description

Inherits From

This DTO inherits from ConditionApiDTO (on page 1108)

Required Parameters

value

type: string

description: A regular expression to be matched against the value of the field.

readOnly: True



TextFieldValueApiDTO

Description

Inherits From

This DTO inherits from FieldValueApiDTO (on page 1130)

Required Parameters

value

type: string

description: The value.

■ readOnly: True

TimeBasedTopologyChangesApiDTO

Description

Topology changes based on a timeframe in the scenario

Optional Parameters

includeReservation

type: boolean

description: Add the workload that is currently reserved

reservationCount

type: integerformat: int32

description: # of currently reserved VMs

readOnly: True

addHistoryVMs

■ type: boolean

description: Should historical vmNetGrowth be considered

vmNetGrowth

type: integerformat: int32

description: Number of workloads added during the last month

■ readOnly: True

TimeSpanApiDTO

Description

Schedule Time span information



Required Parameters

begins

■ type: string

description: Start time of the time span

pattern: ^([0-1]?[0-9]|2[0-3]):[0-5][0-9]\$

ends

type: string

description: End time of the time span

■ pattern: ^([0-1]?[0-9]|2[0-3]):[0-5][0-9]\$

policy

description: policy to be applied during this time span

■ ScheduleItemApiDTO (on page 1201)

TimeSpanGroupApiDTO

Description

Base model to describe a TimeSpanGroup.

Required Parameters

type

■ type: string

example: WeekDayTimeSpansApiDTO

 description: TimeSpan group type discriminator. Describes which subclass of TimeSpanGroupApiDTO is returned.

TopologyChangesApiDTO

Description

Topology changes in the scenario

Optional Parameters

addList

■ type: array

description: List of add changes in the Topology

AddObjectApiDTO (on page 1085)

removeList

■ type: array

description: List of remove changes in the Topology

RemoveObjectApiDTO (on page 1187)

replaceList

type: array

description: List of replace changes in the Topology

ReplaceObjectApiDTO (on page 1188)



migrateList

- type: array
- description: List of migrate changes in the Topology
- MigrateObjectApiDTO (on page 1151)

relievePressureList

- type: array
- description: List of relieve pressure changes in the Topology
- RelievePressureObjectApiDTO (on page 1186)

TopologyDataDefinitionApiDTO

Description

Model to describe a user-defined topology definition.

Required Parameters

entityDefinitionData

- description: Entity definition data
- <u>IEntityDefinitionData (on page 1137)</u>

entityType

- type: string
- description: The type of service entity being defined
- enum: ['BusinessApplication', 'BusinessTransaction', 'Service']

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

contextBased

- type: boolean
- description: Defines if this Definition is Context-Based.

UnplacementDetailsApiDTO

Description

Additional information provided for entities in a plan that are unplaced



Required Parameters

reasons

- type: array
- description: Detailed information about why the entity could not be placed
- UnplacementReasonApiDTO (on page 1238)

Optional Parameters

placedOn

- type: array
- **description:** For Unplaced entities in a Plan Market, the providers that this entity was able to place on
- BaseApiDTO (on page 1088)

UnplacementReasonApiDTO

Description

Details to describe why an entity could not be placed

Optional Parameters

failedResources

- type: array
- description: A list of resources that caused the entity not to be placed
- FailedResourceApiDTO (on page 1129)

resourceOwner

- description: The entity owning the resources that caused unplacement, if different than this entity. For example, a volume that caused a VM to be unplaced.
- BaseApiDTO (on page 1088)

providerType

- type: string
- description: The entity type that sells the commodities that caused unplacement.
- enum: ['Application', 'ApplicationComponent', 'ApplicationServer', 'AvailabilityZone', 'BusinessAccount', 'BusinessApplication', 'BusinessTransaction', 'BusinessUser', 'Chassis', 'CloudService', 'ComputeTier', 'Container', 'ContainerPod', 'ContainerSpec', 'DatabaseServer', 'DatabaseServerTier', 'DatabaseTier', 'DataCenter', 'DesktopPool', 'DiskArray', 'DPod', 'HClPhysicalMachine', 'HypervisorServer', 'Internet', 'IOModule', 'LoadBalancer', 'LogicalPool', 'Namespace', 'Network', 'PhysicalMachine', 'ProcessorPool', 'Region', 'ReservedInstance', 'Service', 'ServiceProvider', 'Storage', 'StorageController', 'StorageTier', 'Switch', 'Unknown', 'ViewPod', 'VirtualApplication', 'VirtualDataCenter', 'VirtualMachine', 'VirtualVolume', 'VPod', 'WorkloadController', 'ContainerPlatformCluster', 'CloudCommitment', 'ApplicationComponentSpec', 'VirtualMachineSpec', 'DocumentCollection']

closestSeller

- description: The seller that came closest to satisfying the commodities. This information is not always available.
- BaseApiDTO (on page 1088)

placementProblem

- **type:** string
- description: Categorizes the reason which caused unplacement
- enum: ['COSTS_NOT_FOUND', 'NOT_CONTROLLABLE', 'UNSATISFIED_COMMODITIES']



UserApiDTO

Description

Model to describe an User

Optional Parameters

uuid

type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

username

- type: string
- description: Username

password

- type: string
- description: Encoded password

roles

- type: array
- description: Roles assigned to the user.
- RoleApiDTO (on page 1195)

loginProvider

- type: string
- description: Provider for the login
- enum: ['Local', 'LDAP']

type

- type: string
- description: type
- enum: ['DedicatedCustomer', 'SharedCustomer']

scope

- type: array
- description: List of scopes that the User is allowed to see
- GroupApiDTO (on page 1132)

features

- type: array
- description: List of features that the user is allowed to see
- type: string

authToken

- type: string
- description: The secured user token

showSharedUserSC

■ type: boolean



UtilizationApiDTO

Description

Model to describe a utilization change in the scenario

Optional Parameters

projectionDay

type: integerformat: int32

description: Projection day, indicate when to apply the change

target

description: Target of the change, entity or group

■ BaseApiDTO (on page 1088)

percentage

type: integerformat: int32

description: Utilization percentage change

VMEntityAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

os

type: string

■ description: The operating system type. E.G. 'Linux', 'Windows' and 'Unknown' if not found.

ip

■ type: array

description: The IP address. Can be IPv4 or IPv6

■ - type: string

connectedNetworks

■ type: array

description: The connected Networks

BaseApiDTO (on page 1088)

numVCPUs

type: integerformat: int32

description: Number of vCPUs



coresPerSocketRatio

type: integerformat: int32

description: Cores per socket ratio

processorPoolName

type: string

description: Processor Pool

hasDedicatedProcessors

type: booleanexample: True

description: Has Dedicated Processors

processorCompatibilityMode

type: string

example: POWER8

description: Processor Compatibility Mode

activeMemoryExpansionEnabled

type: booleanexample: True

description: Active Memory Expansion Enabled

resourceMonitoringControlState

type: stringexample: active

description: Resource Monitoring Control (RMC) State

sharingMode

■ type: string

example: uncapped

description: Sharing Mode

${\bf dedicated Sharing Mode}$

type: string

example: share_idle_pros

description: Dedicated Sharing Mode

nonDisruptiveMaxPU

type: numberformat: double

description: Non-disruptive Processing Units max resize constraint

nonDisruptiveMinPU

type: numberformat: double

description: Non-disruptive Processing Units min resize constraint

ebsOptimized

■ type: boolean

description: EBS Optimized

sessions

type: array

description: Information about sessions established by a BusinessUser to this VirtualMachine.

BusinessUserSessionApiDTO (on page 1096)



vendorToolsVersion

■ type: string

description: Vendor Tools Version

resourceld

type: string

description: Resource identifier of the virtual machine. For example, the resource id in Azure, the ARN in AWS, or the full resource name in GCP.

creationTimeStamp

type: integerformat: int64

description: Timestamp in milliseconds for the creation of the virtual machine.

vgpuProfile

type: string

description: vGPU profile used by virtual machine.

ahublicense

■ type: boolean

VirtualDiskApiDTO

Description

Model to describe a Virtual Disk

Optional Parameters

uuid

type: string

displayName

■ type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

tier

type: string

description: The tier of the Virtual Disk

actions

type: array

description: The related action: Move or Delete

ActionApiDTO (on page 1071)

stats

type: array

description: The related statistics

StatApiDTO (on page 1216)

attachedVirtualMachine

description: The Virtual Machine if the disk is attached

■ BaseApiDTO (on page 1088)



provider

- description: The Storage provider
- BaseApiDTO (on page 1088)

dataCenter

- description: The DataCenter where the VirtualDisk resides
- BaseApiDTO (on page 1088)

environmentType

- type: string
- description: Environment type
- enum: ['CLOUD', 'ONPREM', 'HYBRID']

lastModified

- type: integerformat: int64
- description: Last Modified

businessAccount

- description: Business Account
- BaseApiDTO (on page 1088)

resourceGroup

description: Resource GroupBaseApiDTO (on page 1088)

creationTime

- type: string
- description: Creation time

skuName

- type: string
- description: Sku name

snapshotld

- type: string
- description: Snapshot id

encryption

- type: string
- description: Encryption

attachmentState

- type: string
- description: Attachment state
- enum: ['AVAILABLE', 'IN_USE', 'UNKNOWN']

name

- type: string
- description: Name

ephemeral

- type: string
- description: Ephemeral

lastAttachedVm

- type: string
- **description:** Name of the VM this volume was last attached to.



numDaysUnattached

■ type: string

description: Number of days ago this volume was last attached.

hourlyBilledOps

type: numberformat: double

description: Average number of billed operations per hour.

creationTimeStamp

type: integerformat: int64

description: Timestamp in milliseconds for the creation of the virtual disk.

attachedVMStorageCompatibility

type: string

description: Storage compatibility for virtualDisks's attached VM(s). The compatibility will affect scale analysis
for the volume. If an attached VM is not PREMIUM compatible, the volume will never scale to a premium
StorageTier

■ enum: ['PREMIUM', 'STANDARD']

storageUsageType

■ type: string

description: Usage type for the volume, i.e., what the volume is used for.

■ enum: ['SITE_RECOVERY', 'BACKUP', 'STANDARD']

resourceld

type: string

description: Resource identifier of the volume. For example, the resource id in Azure, the ARN in AWS, or the full resource name in GCP.

VirtualDisksAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

virtualDisks

■ type: array

description: List of Virtual Disks

VirtualDiskApiDTO (on page 1242)

VirtualVolumeEntityAspectApiDTO

Description



Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

files

- type: array
- description: Files comprised in the volume
- type: string

WebhookApiDTO

Description

Inherits From

This DTO inherits from WorkflowAspect (on page 1251)

Required Parameters

method

- type: string
- description: The http method used to make the request.
- enum: ['GET', 'POST', 'PUT', 'DELETE', 'PATCH']

url

- type: string
- description: The URL that HTTP request is made to.

Optional Parameters

template

- type: string
- description: The template for the body of request.

authenticationMethod

- type: string
- description: The authentication method to use for the request.
- enum: ['NONE', 'BASIC', 'OAUTH']

username

- type: string
- description: The username for the authenticated request.

password

- type: string
- description: The password for the authenticated request.

trustSelfSignedCertificates

- type: boolean
- description: If true, self-signed certificates will be trusted when using HTTPS connections. Defaults to 'false'.



headers

- type: array
- description: The request headers.
- RequestHeader (on page 1188)

oauthData

OAuthDataApiDTO (on page 1153)

WeekDayTimeSpansApiDTO

Description

Inherits From

This DTO inherits from TimeSpanGroupApiDTO (on page 1236)

Optional Parameters

sunday

- type: array
- description: Schedule time spans information for sunday
- TimeSpanApiDTO (on page 1235)

monday

- type: array
- description: Schedule time spans information for monday
- TimeSpanApiDTO (on page 1235)

tuesday

- type: array
- description: Schedule time spans information for tuesday
- TimeSpanApiDTO (on page 1235)

wednesday

- type: array
- description: Schedule time spans information for wednesday
- - TimeSpanApiDTO (on page 1235)

thursday

- type: array
- description: Schedule time spans information for thursday
- TimeSpanApiDTO (on page 1235)

friday

- type: array
- description: Schedule time spans information for friday
- TimeSpanApiDTO (on page 1235)

saturday

- type: array
- description: Schedule time spans information for saturday
- TimeSpanApiDTO (on page 1235)



WhereApiDTO

Description

Filter for entity or group queries.

Optional Parameters

relatedToScopes

- type: array
- description: Restrict to entities related to these scopes.
- readOnly: Truetype: integer
 - format: int64

conditions

- type: array
- description: Restrict to entities satisfying these conditions.
- readOnly: True
- ConditionApiDTO (on page 1108)

WidgetApiDTO

Description

Basic information of an entity

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

type

type: string

scope

BaseApiDTO (on page 1088)

startPeriod

■ type: string

endPeriod

■ type: string

row

type: integerformat: int32



column

type: integerformat: int32

sizeRows

type: integerformat: int32

sizeColumns

type: integerformat: int32

widgetsetld

type: integerformat: int64

widgetElements

■ type: array

WidgetElementApiDTO (on page 1248)

widgetSource

type: string

■ enum: ['UI_DEFAULT', 'USER']

WidgetElementApiDTO

Description

Basic information of an entity

Optional Parameters

uuid

■ type: string

displayName

type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

type: string

row

type: integerformat: int32

column

type: integerformat: int32

type

■ type: string

widgetld

type: integerformat: int64



properties

■ type: object

additionalProperties: {'type': 'string'}

stats

■ type: array

StatApilnputDTO (on page 1217)

datasets

type: arraytype: string

WidgetsetApiDTO

Description

Basic information of an entity

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

scope

type: string

startPeriod

■ type: string

endPeriod

■ type: string

widgets

- type: array
- WidgetApiDTO (on page 1247)

category

■ type: string

scopeType

■ type: string

username

■ type: string

isSharedWithAllUsers

■ type: boolean



WorkflowApiDTO

Description

Model to describe a Workflow

Required Parameters

discoveredBy

- description: Target that discovered this workflow
- TargetApiDTO (on page 1224)

type

- type: string
- description: The type of this workflow
- enum: ['UCSD', 'ACTION_SCRIPT', 'SERVICENOW', 'ACTIONSTREAM_KAFKA', 'WEBHOOK']

Optional Parameters

uuid

■ type: string

displayName

- type: string
- description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

description

- type: string
- description: Description of the workflow

entityType

- type: string
- description: Type of the entity associated

actionType

- type: string
- description: Type of the action associated

parameters

- type: array
- description: Input parameters for the workflow
- InputFieldApiDTO (on page 1138)

scriptPath

- type: string
- description: Full path to workflow script (e.g. path to an ActionScript executable

actionPhase

- **type:** string
- description: Action Phase to which workflow applies



timeLimitSeconds

type: integerformat: int64

description: Time limit for workflow execution, in seconds

typeSpecificDetails

description: The information about this workflow that is specific to its type.

■ WorkflowAspect (on page 1251)

WorkflowAspect

Description

Parent model to describe a type-specific workflow details

Required Parameters

type

type: string

WorkflowOperationRequestApiDTO

Description

The details of the requested operation on the workflow.

Required Parameters

actionId

type: integerformat: int64

description: The ID of the action that we perform the workflow operation on

operation

■ type: string

description: The operation that is being performed on the workflow

enum: ['TEST']

WorkflowOperationResponseApiDTO

Description

Result of a workflow operation.

Required Parameters

succeeded

type: boolean

description: True if the workflow operation has succeeded.



Optional Parameters

uuid

type: string

displayName

type: string

description: A user readable name of the api object. Cannot be blank. The UTF-8 encoding must be at most 255 bytes.

className

■ type: string

details

type: string

description: Details of workflow operation result.

WorkloadControllerAspectApiDTO

Description

Inherits From

This DTO inherits from EntityAspect (on page 1125)

Optional Parameters

controllerType

type: string

- description: Information about workload controller type.
- enum: ['CRON_JOB_INFO', 'CUSTOM_CONTROLLER_INFO', 'DAEMON_SET_INFO', 'DEPLOYMENT_INFO', 'JOB_INFO', 'REPLICA_SET_INFO', 'REPLICATION_CONTROLLER_INFO', 'STATEFUL_SET_INFO']

customControllerType

- type: string
- description: Information about custom controller type. Only set when the controllerType is CUSTOM_CONTROLLER_INFO.

controllerReplicaCount

type: integer

format: int32

description: The number of active replicas controlled by the workload controller.

Reference: Entity Statistics

Workload Optimization Manager monitors the following statistics for entities in your environment:

ApplicationComponent Statistics

Heap

Produces



RemainingGcCapacity

ResponseTime

Threads

Transaction

VCPU

VMem

BusinessApplication Statistics

Produces

Not Implemented: The number of entities connected to this provider, used in calculating pricing.

ResponseTime

Response time, measured in ms.

Transaction

Transactions per second

BusinessTransaction Statistics

Produces

ResponseTime

Transaction

BusinessUser Statistics

ActiveSessions

Number of active sessions in a desktop pool, expressed as a percentage of the pool's capacity

ImageCPU

Measurement of CPU that is utilized by a user's desktop images, expressed as a percentage of CPU capacity

ImageMem

Measurement of memory that is utilized by a user's desktop images, expressed as a percentage of memory capacity

ImageStorage

Measurement of storage that is utilized by a user's desktop images, expressed as a percentage of storage capacity

PoolCPU

Measurement of CPU that is utilized by active sessions in a desktop pool

PoolMem

Measurement of memory that is utilized by active sessions in a desktop pool

PoolStorage



Measurement of storage that is utilized by active sessions in a desktop pool

Produces

Not implemented

TotalSessions

Number of active and disconnected (non-terminated) sessions in a desktop pool, expressed as a percentage of the pool's capacity

Chassis Statistics

Cooling

Allocated cooling indicates the highest acceptable running temperature for a physical device, such as a chassis in a compute fabric.

Power

A measure of the power that is consumed by a physical device.

priceIndex

The degree of risk for the chassis.

Produces

Not Implemented: The number of entities connected to this provider, used in calculating pricing.

Space

When known, the amount of physical hardware that can be used in conjunction with this entity. For example, the number of spaces in a server rack.

ContainerPlatformCluster Statistics

NumberConsumers

Produces

VCPU

VCPURequest

VMem

VMemRequest

ContainerPod Statistics

NumberConsumers

Produces

StorageAmount

VCPU



VCPULimitQuota

VCPURequest

VCPURequestQuota

VMem

VMemLimitQuota

VMemRequest

VMemRequestQuota

VStorage

ContainerSpec Statistics

Produces

VCPU

VCPURequest

VCPUThrottling

VMem

VMemRequest

Container Statistics

Produces

Not Implemented: The number of entities connected to this provider, used in calculating pricing.

VCPU

The percentage utilization of the VCPU allocated for the hosting entity.

VCPULimitQuota

VCPURequest

VCPURequestQuota

VCPUThrottling

VMem

The percentage utilization of the VMem allocated to the hosting VM.

VMemLimitQuota

VMemRequest

VMemRequestQuota



DataCenter Statistics

Ballooning

Ballooning capacity, measured in KBytes. This capacity is the greater of 65% of the VMem configured for all powered-on VMs that the PM hosts, or the physical memory capacity

Cooling

Allocated cooling indicates the highest acceptable running temperature for a physical device, such as a chassis in a compute fabric.

CPU

Host CPU capacity, measured in MHz. This shows what percentage of CPU cycles are devoted to processing instructions.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

CPUAllocation

DESCRIPTION

CPUProvisioned

The aggregate Overprovisioned CPU capacity and utilization on the host, in KB. Capacity is a function of the overprovisioning percentage specified for the host.

HostLunAccess

HotStorage

IOThroughput

The data rate through the PM's IO adapters, measured in Kbytes per second.

Mem

The aggregate percentage of the PM's memory that is reserved or in use, measured in Kbytes.

MemAllocation



DESCRIPTION

MemProvisioned

Overprovisioned MEM capacity and utilization on the host, in KB. Capacity is a function of the overprovisioning percentage specified for the host.

NetThroughput

The aggregate data rate through the PM's network adapters

numCPUs

Host CPU capacity, measured in MHz. This shows what percentage of CPU cycles are devoted to processing instructions

numHosts

The number of hosts in the Datacenter

numSockets

The number of sockets in the Datacenter

Power

A measure of the power that is consumed by a physical device.

priceIndex

The degree of risk for the datacenter

Produces

Not Implemented: The number of entities connected to this provider, used in calculating pricing.

Q16VCPU

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Q1VCPU

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Q2VCPU

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Q32VCPU

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Q4VCPU



Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Q64VCPU

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Q8VCPU

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Space

When known, the amount of physical hardware that can be used in conjunction with this entity. For example, the number of spaces in a server rack.

StorageAccess

IOPS capacity and utilization

StorageLatency

Swapping

DESCRIPTION

DatabaseServer Statistics

Connection

DBCacheHitRate

DBMem

priceIndex

Produces

ResponseTime

Transaction

TransactionLog

VCPU

VMem

VStorage

Database Statistics

costPrice

DESCRIPTION



DTU

LicenseAccess

priceIndex

The degree of risk for the database

Produces

Not Implemented: The number of entities connected to this provider, used in calculating pricing.

StorageAmount

DesktopPool Statistics

ActiveSessions

CPUAllocation

ImageCPU

ImageMem

ImageStorage

MemAllocation

PoolCPU

PoolMem

PoolStorage

priceIndex

Produces

TotalSessions

DiskArray Statistics

Extent

priceIndex

Produces

IOModule Statistics

Cooling

Allocated cooling indicates the highest acceptable running temperature for a physical device, such as a chassis in a compute fabric.

NetThroughput



The data rate through the entity's network adapters, measured in Kbytes/second

PortChannel

DESCRIPTION

Power

A measure of the power that is consumed by a physical device.

priceIndex

The degree of risk for the IO Module

Produces

Not Implemented: The number of entities connected to this provider, used in calculating pricing.

LogicalPool Statistics

DiskArrayAccess

Not implemented

Extent

Not implemented

Produces

Not implemented

StorageAccess

Per-second measurement of read and write access operations on a storage entity

StorageAmount

Measurement of storage capacity that is in use

StorageLatency

Measurement of storage latency

StorageProvisioned

Utilization of the entity's storage capacity, including overprovisioning

Namespace Statistics

priceIndex

Produces

VCPU

VCPULimitQuota

VCPURequest

VCPURequestQuota

VMem

VMemLimitQuota



VMemRequest

VMemRequestQuota

PhysicalMachine Statistics

Ballooning

Ballooning capacity, measured in KBytes. This capacity is the greater of 65% of the VMem configured for all powered-on VMs that the PM hosts, or the physical memory capacity.

Cooling

CPU

CPU capacity, CPU reserved, and CPU utilized, in MHz.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

CPUAllocation

CPU capacity, as allocated to the host, in MHz.

CPUProvisioned

Overprovisioned CPU capacity and utilization on the host, in MHz. Capacity is a function of the overprovisioning percentage specified for the host.

HostLunAccess

IOThroughput

Capacity and utilization of data rate through the host's IO adapter, measured in Kbits/sec.

Mem

The percentage of the PM's memory that is reserved or in use, measured in Kbytes.

MemAllocation

Allocation and utilization of host memory, measured in KB.

MemProvisioned



Overprovisioned MEM capacity and utilization on the host, in KB. Capacity is a function of the overprovisioning percentage specified for the host.

NetThroughput

Capacity and utilization of data rate through the host's Network adapter, measured in Kbits/sec.

numCPUs

The number of CPUs on the host.

numSockets

The number of sockets discovered on this host.

Power

priceIndex

The degree of risk for the host.

Produces

Not Implemented: The number of entities connected to this provider, used in calculating pricing.

Q16VCPU

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Q1VCPU

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Q2VCPU

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Q32VCPU

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Q4VCPU

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Q64VCPU

Q8VCPU

Ready queue capacity and wait time, measured in ms. Workload Optimization Manager monitors 1-CPU, 2-CPU, 4-CPU, up to 32-CPU ready queues.

Space



StorageAccess

StorageLatency

Swapping

The capacity, reserved capacity, and utilization for rate of memory swapping to disk, in bits per second.

Service Statistics

NumberReplicas

priceIndex

Produces

StorageController Statistics

priceIndex

The degree of risk for the disk array.

Produces

Not Implemented: The number of entities connected to this provider, used in calculating pricing.

StorageAmount

The storage capacity, reserved storage, and utilized storage for this entity's storage in MB

StorageTier Statistics

StorageAccess

IOPS capacity and utilization

StorageAmount

The storage capacity, reserved storage, and utilized storage for this entity in MB

StorageClusterCommodity

StorageLatency

The capacity, reserved amount, and utilized amount of latency for storage transactions, in msecs.

StorageProvisioned

Overprovisioned storage capacity and utilization on the entity, in MB. Capacity is a function of the overprovisioning percentage specified for the entity.

Storage Statistics

Extent

priceIndex

The degree of risk for the storage entity.



Produces

Not Implemented: The number of entities connected to this provider, used in calculating pricing.

StorageAccess

IOPS capacity and utilization

StorageAmount

The storage capacity, reserved storage, and utilized storage for this entity in MB

StorageLatency

The capacity, reserved amount, and utilized amount of latency for storage transactions, in msecs.

StorageProvisioned

Overprovisioned storage capacity and utilization on the entity, in MB. Capacity is a function of the overprovisioning percentage specified for the entity.

Switch Statistics

NetThroughput

The data rate through the entity's network adapters, measured in Kbytes/second.

PortChannel

The data rate through the port channel, measured in Kbytes/second.

priceIndex

The degree of risk for the Switch.

Produces

Not Implemented: The number of entities connected to this provider, used in calculating pricing.

ViewPod Statistics

ActiveSessions

Number of active sessions in a desktop pool, expressed as a percentage of the pool's capacity

Produces

Not implemented

TotalSessions

Number of active and disconnected (non-terminated) sessions in a desktop pool, expressed as a percentage of the pool's capacity



VirtualDataCenter Statistics

CPUAllocation

Host CPU capacity, measured in MHz. This shows what percentage of CPU cycles are devoted to processing instructions

MemAllocation

DESCRIPTION

priceIndex

The degree of risk for the virtual datacenter

Produces

Not Implemented: The number of entities connected to this provider, used in calculating pricing.

VirtualMachine Statistics

Ballooning

Ballooning capacity, measured in KBytes. This capacity is the greater of 65% of the VMem configured for all powered-on VMs that the PM hosts, or the physical memory capacity

CPU

Host CPU capacity, measured in MHz. This shows what percentage of CPU cycles are devoted to processing instructions

The percentage utilization of the VCPU allocated for the hosting VM.

CPUAllocation

DESCRIPTION

CPUProvisioned

Overprovisioned CPU capacity and utilization on the entity, in Mhz. Capacity is a function of the overprovisioning percentage specified for the entity.

IOThroughput

DESCRIPTION

Mem

The percentage of the PM's memory that is reserved or in use by the VM, measured in Kbytes.

The percentage utilization of the VMem allocated by the host.

MemAllocation

DESCRIPTION

MemProvisioned



Overprovisioned Mem capacity and utilization on the entity, in Kbytes. Capacity is a function of the overprovisioning percentage specified for the entity.

NetThroughput

The data rate through the entity's network adapters, measured in Kbytes/second

numVCPUs

DESCRIPTION

priceIndex

The degree of risk for the Virtual Machine

Produces

Not Implemented: The number of entities connected to this provider, used in calculating pricing.

StorageAccess

IOPS capacity and utilization

StorageAmount

The storage capacity, reserved storage, and utilized storage for this entity's storage in MB

StorageLatency

DESCRIPTION

StorageProvisioned

Overprovisioned storage capacity and utilization on the entity, in MB. Capacity is a function of the overprovisioning percentage specified for the entity.

Swapping

DESCRIPTION

VCPU

The percentage utilization of the VCPU allocated for the hosting VM.

VMem

The percentage utilization of the VMem allocated by the host.

VStorage

Virtual storage allocated to a VM, measured in Kbytes.

VirtualVolume Statistics

costPrice

IOThroughput



Produces

StorageAccess

StorageAmount

StorageLatency

StorageProvisioned

WorkloadController Statistics

priceIndex

Produces

VCPULimitQuota

VCPURequestQuota

VMemLimitQuota

VMemRequestQuota



Integration - Embedded Reporting

IMPORTANT:

Embedded Reporting powered by the Grafana observability platform will be retired in 2023. Guidance on migrating to the new SaaS Reporting feature powered by ThoughtSpot will be available in a future release.

The Workload Optimization Manager platform includes an Embedded Reporting component that you can choose to enable when you install the platform. Embedded Reporting stores a history of your managed environment and then presents selective snapshots of this history with a set of standard dashboards and reports.

Embedded Reporting runs as its own component, as part of the Workload Optimization Manager platform. This architecture enhances performance and reduces storage requirements. You can create your own dashboards and reports to focus on other areas of concern.

Dashboards and charts in Workload Optimization Manager Embedded Reporting are powered by the Grafana observability platform. With Grafana, it's easy to navigate the existing dashboards, and to make your own charts and dashboards with no coding required. You can also create custom reports via SQL queries against the Embedded Reporting database.

To compose custom reports, open the user interface, navigate to the Reports view, and then explore the Timescale database. From there, you can assemble queries to populate your custom reports. To help you build these queries, this documentation describes the schema tables, and provides some sample queries against them.

The Embedded Reporting feature uses a TimescaleDB service to manage the reporting data. The default installation of Workload Optimization Manager includes its own installation of TimescaleDB. This documentation also includes instructions to deploy an external TimescaleDB service. You can use this as an alternative to the default deployment.

For instructions to enable Embedded Reporting, see "Enabling Embedded Reporting" in the Workload Optimization Manager Installation Guide.

Enabling Embedded Reporting

The Workload Optimization Manager platform includes an Embedded Reporting component that you can choose to enable when you install the platform. Use Embedded Reporting to understand application resource management trends, and to share insights with stakeholders through reports and dashboards.

Embedded Reporting runs as its own component, as part of the Workload Optimization Manager platform. This architecture enhances performance and reduces storage requirements. It stores a history of your managed environment and then presents selective snapshots of this history through a set of standard dashboards and reports. You can create your own dashboards and reports to focus on other areas of concern.



The method that you use to enable embedded reports depends on the version status of your Workload Optimization Manager instance, as follows:

■ Script Interface (on page 1269)

You installed Workload Optimization Manager version 3.0.0 or later as a new VM image (OVA or VHD; see <u>Installing on a Virtual Machine Image (on page 39)</u>). In this case, you can run the enable_reporting.py script to set up embedded reporting.

■ Editing the Workload Optimization Manager cr.yaml File (on page 1270)

You installed Workload Optimization Manager as a Kubernetes cluster, not using the VM image for your Workload Optimization Manager installation.

In these cases, you manually edit the <code>charts_vlalphal_xl_cr.yaml</code> file for your installation of Workload Optimization Manager.

Using the Script Interface

If you installed Workload Optimization Manager as a VM image for version 3.0.0 or later, the script to enable Embedded Reports is already installed on your installation at /opt/local/bin/enable reporting.py.

To run this script:

1. Open an SSH terminal session to your Workload Optimization Manager instance.

Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Password: [your_private_password]
- Go to the script directory.

```
cd /opt/local/bin
```

Run the script.

```
./enable_reporting.py
```

The script prompts you for two passwords:

Grafana admin password

This password enables access to Grafana from external URLs and also from the extractor component that feeds data to Grafana.

Do not use special characters.

IMPORTANT:

This step is the only time that you should change the Grafana Admin password. If you later change the Grafana Admin password, the Embedded Reporting components cannot communicate properly with the other components in the platform, and you should contact your Support representative.

Grafana database password

This password enables communication between Grafana and the Postgres database that stores the reporting data.

After you supply the passwords, the script displays a confirmation message similar to the following example:

```
Successfully applied new changes to /opt/turbonomic/kubernetes/operator/deploy/crds/charts_v1alp hal_xl_cr.yaml. Backup written to /opt/turbonomic/kubernetes/operator/deploy/crds/charts_v1alphal_xl_cr.yaml.bak
```

This indicates that the script successfully updated the Workload Optimization Manager configuration. The script then applies the changed configuration to enable the Embedded Reports feature. It should display messages similar to the following example:

```
Applying CR file /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalpha1_xl_cr.yaml Warning: kubectl apply should be used on resource created by either kubectl create --save-config or kubectl apply
```



```
xl.charts.helm.k8s.io/xl-release configured
Waiting for changes to take effect...
Restarting api pod to apply configuration changes.
pod "api-65cf47986f-jxszd" deleted
Changes have been successfully applied. Embedded reporting is now enabled.
```

4. Verify your installation.

```
./enable_reporting.py --validate
```

If Embedded Reports are successfully enabled, the script output should be similar to the following example:

No obvious embedded reporting installation errors detected.

Editing the Workload Optimization Manager YAML File

These instructions describe how to locate and edit the <code>charts_vlalphal_xl_cr.yaml</code> for the VM image installation. If you installed on a Kubernetes node cluster, then the file can be in a different location.

To enable Embedded Reports, complete the following tasks:

- Enable the processes that implement the embedded reporting.
- Update the API pod to enable new search and data ingestion capabilities.
- Double-check the installation.
- Optionally enable email subscriptions.

Enable the Grafana Exporter, TimescaleDB, and data extraction processes by editing the charts_vlalphal_xl_cr.yaml file.

1. Open an SSH terminal session to your Workload Optimization Manager instance.

Log in with the System Administrator that you set up when you installed Workload Optimization Manager:

- Username: turbo
- Password: [your_private_password]
- 2. Open the following file in a text editor:

 $/ {\tt opt/turbonomic/kubernetes/operator/deploy/crds/charts_v1alpha1_xl_cr.yaml}$

3. Specify the IP address of the Workload Optimization Manager instance for external access to the TimescaleDB database.

In the global: section of the file, add the following line, where <Platform_IP> is the IP address of your instance:

```
global:
   externalTimescaleDBIP: <Platform_IP>
```

4. Enable the Grafana process.

Find the grafana: section in the crds/charts_vlalphal_xl_cr.yaml file, and uncomment the line, enabled: true.

Enable Postgres as the database type.

Enabling Postgres sets persistent storage of historical data for Embedded Reports. In the grafana: section, find the subsection for grafana.ini: database: and uncomment the line, type: postgres.

The changes that you have made so far should be similar to:

```
global:
    externalTimescaleDBIP: <Platform_IP>
    ...

grafana:
    enabled: true
    adminPassword: admin
```



```
grafana.ini:
  database:
    type: postgres
    ...
```

6. Change the admin and database passwords.

It is good practice to change any passwords, and not keep their default values.

IMPORTANT:

Use only alpha-numeric characters for these passwords.

These passwords enable communication between the various Embedded Reports components. Some of the components accept only alpha-numeric characters. If you use special characters, then the components cannot communicate. Further, the steps to correct these passwords require assistance from your Support representative.

To set the passwords:

Set the Grafana admin password.

This password enables access to Grafana from external URLs and also from the extractor component that feeds data to Grafana. In the grafana: section, change the value of adminPassword.

Do not use special characters.

Assume that your password is MyNewGrafanaPassword. Then, you would set adminPassword: MyNewGrafanaPassword

IMPORTANT:

This step is the only time that you should change the Grafana Admin password. If you later change the Grafana Admin password, the Embedded Reporting components cannot communicate properly with the other components in the platform, and you should contact your Support representative.

Set the Grafana database password.

This password enables communication between Grafana and the Postgres database that stores the reporting data. In the grafana: section, find the subsection for grafana.ini: database: password: and change the password value.

7. Enable the reporting processes.

Just after the properties: section that you added, and at the same level to it, add the following entries to enable the reporting processes:

```
reporting:
   enabled: true
timescaledb:
   enabled: true
extractor:
   enabled: true
```

It is important that you align these entries with the indentation for the grafana: section and the properties: section. The changes that you have made should now be similar to:

```
global:
    externalTimescaleDBIP: <Platform_IP>
    ...

grafana:
    enabled: true
    adminPassword: MyNewGrafanaPassword
    grafana.ini:
    database:
    type: postgres
    password: MyNewDatabasePassword
```

enabled: true



```
properties:
    extractor:
        grafanaAdminPassword: MyNewGrafanaPassword
reporting:
    enabled: true
timescaledb:
    enabled: true
extractor:
```

- 8. When you are done editing the charts_vlalphal_xl_cr.yaml file, save and apply your changes.
 - Save your changes and guit the text editor.
 - Run the command to apply the changes.

```
kubectl apply -f \
   /opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml
```

Delete the api and extractor pods.

Deleting these pods triggers them to restart, which loads the changes you made.

Run the following command to get the full pod names, run the command,

```
kubectl get pods -n turbonomic
```

Find the entries for the pods that begin with api and extractor. For example, assume that the entries are:

```
... api-7887c66f4b-shndq 1/1 Running 0 ... extractor-5b86976bc8-vxwz4 1/1 Running 0
```

Run the following commands:

```
kubectl delete pod -n turbonomic api-7887c66f4b-shndq
kubectl delete pod -n turbonomic extractor-5b86976bc8-vxwz4
```

9. In an SSH terminal session for your Workload Optimization Manager instance, set the password for Postgres and enable access to psql on the appliance's localhost. Run the following commands:

```
sudo -iu postgres psql -c "ALTER ROLE postgres WITH PASSWORD 'vmturbo'"

sudo -iu postgres psql -c "CREATE ROLE turbo WITH SUPERUSER CREATEDB CREATEROLE LOGIN REPLICATION BYP

ASSRLS PASSWORD 'vmturbo'"
```

- 10. Verify your installation.
 - Verify that the Embedded Reports pods are running.

```
kubectl get pods -n turbonomic
```

The output is similar to the following example:

NAME	READY	STATUS	RESTARTS
extractor-7759dbcb47-vs6hr	1/1	Running	0



```
grafana-84ccb4bfb-17sp7 1/1 Running
```

Verify that Postgres is running.

The Postgres database should be running as a daemon on the Workload Optimization Manager server machine. To check the status, run the command:

```
sudo systemctl status postgresql-12.service
```

The output is similar to the following example:

```
postgresql-12.service - PostgreSQL 12 database server
Loaded: loaded (/usr/lib/systemd/system/postgresql-12.service; enabled; vendor preset: disabled)
Active: active (running) since Wed 2020-07-29 06:39:43 UTC; 14h ago
     Docs: https://www.postgresql.org/docs/12/static/
Process: 1536 ExecStartPre=/usr/pgsql-12/bin/postgresql-12-check-db-dir ${PGDATA} (code=exited, s
tatus=0/SUCCESS)
Main PID: 1562 (postmaster)
   Tasks: 15
   Memory: 145.5M
   CGroup: /system.slice/postgresql-12.service
           ## 419 postgres: TimescaleDB Background Worker Scheduler
           ## 1562 /usr/pgsql-12/bin/postmaster -D /var/lib/pgsql/12/data/
           ## 1928 postgres: logger
           ## 1986 postgres: checkpointer
           ## 1988 postgres: background writer
           ## 1989 postgres: walwriter
           ## 1990 postgres: autovacuum launcher
           ## 1991 postgres: stats collector
           ## 1992 postgres: TimescaleDB Background Worker Launcher
           ## 1994 postgres: logical replication launcher
           ## 4054 postgres: grafana_backend grafana 10.233.90.172(33038) idle
           ## 4884 postgres: grafana_backend grafana 10.233.90.172(35814) idle
           ## 4912 postgres: grafana_reader extractor 10.233.90.172(33898) idle
           ##11365 postgres: grafana_reader extractor 10.233.90.172(40728) idle
           ##32367 postgres: TimescaleDB Background Worker Scheduler
```


Navigating to the Embedded Reports Page

After you have completed the steps to enable Embedded Reports, open the Workload Optimization Manager user interface and click **Reports** in the navigation bar.



This opens dashboards and charts in a new browser tab.





You can search for specific dashboards or browse folders to find the dashboards you want. You can also create custom reports.

Dashboards and charts are powered by the Grafana® observability platform. With Grafana, it's easy to navigate the existing dashboards, and to make your own charts and dashboards with no coding required. If you are new to Grafana and need help getting started, read the documentation available at:

https://grafana.com/docs/grafana/latest/

NOTE

Starting with version 3.4.1, Workload Optimization Manager no longer has an agreement to use the Enterprise license of Grafana, and ships the open-source Community license instead. After you update an earlier version of Workload Optimization Manager to version 3.4.1 or later, Grafana automatically switches to the Community license and you should be able to use Embedded Reporting as usual. However, be aware that the Community license does not support PDF reports. Please contact your Workload Optimization Manager representative for guidance on PDF reports.

Creating Custom Reports

To create custom reports, you must run SQL Server queries against the Embedded Reports database (Turbo Timescale).



The database schema includes certain tables against which you can run queries. For detailed documentation for the schema, see Integration - Embedded Reporting (on page 1268).

(Optional) Report Editing

To create and edit reports, a user must have Report Editor privileges. This user can have any role, as long as it is not a *shared* or *scoped* role. Only one user per Workload Optimization Manager instance is allowed to have Report Editor privileges (by default, the local **administrator** user). You can grant these privileges to another user.



To create a user account with Report Editor privileges:

- In the Workload Optimization Manager user interface, navigate to Settings / User Management.
- Choose the user account that you want to configure as a Report Editor. You can either edit an existing account or create a new one.
- 3. Choose a role for the user. The user can have any role, as long as it is not a shared or scoped role.
- 4. Under Options, choose DESIGNATE AS REPORT EDITOR.
- 5. Set any other properties for the user account that you want, and save the user account.

NOTE:

It can take up to 30 minutes before the Reports page shows the Report Editor username. This usually occurs if you have changed the Report Editor multiple times.

To access reports from the user interface, a user must have the Administrator or Site Administrator role, or a non-administrator role without a defined scope. For example, a user with the Observer role but without a scope can access reports.

The default Shared Observer and Shared Adviser roles require scopes, so users with these roles cannot access reports.

Embedded Reports Storage Requirement Estimates

The Embedded Reports feature uses a TimescaleDB server to manage the chart data. This is a PostgreSQL server running with the TimescaleDB extension. You must configure the datastore for your Workload Optimization Manager instance so it has enough space to support the TimescaleDB requirements.

When you initially enable Embedded Reports, you should estimate the storage you will need, and configure the platform storage accordingly. If you have already enabled Embedded Reports, you should check your current storage configuration and decide whether it meets your needs now and into the future.

The storage that your TimescaleDB requires depends on:

- Data retention period
 - How long to store the TimescaleDB data.
- The size of your environment

The count of entities Workload Optimization Manager manages in your environment. This count changes over time. You should think of it as the average number of entities in your environment over the given data retention period.

Also note that increased entity count increases the data requirement, as does other activity. Storage requirements can increase over time for reasons such as:

- You add entities such as workloads, application components, storage, or hosts to your environment.
- You configure new targets.

Storage Estimates Lookup Tables

We have investigated the TimescaleDB storage requirements for different topologies and retention periods. The following table lists the estimates that we have calculated. Please be aware that your environment could have different requirements.

	Number of Entities						
Retention Period	10k	25k	50k	100k	250k	500k	1000k
6 months	36GB	91GB	182GB	364GB	910GB	1.8TB	3.6TB
1 year	72GB	181GB	361GB	723GB	1.8TB	3.5TB	7TB
2 years	144GB	361GB	721GB	1.4TB	3.5TB	7.2TB	14TB



Note that the default installation grants a disk quota of 200GB to the TimescaleDB. For the default installation, we estimate that the database can support the following entity counts:

Retention Period	Entity Count
6 months	55k
1 year	27k
2 years	14k

Setting the Data Retention Period

By default, Workload Optimization Manager sets the retention period for Embedded Reports to be 365 days. You can see the currently set retention period, and change it in the Workload Optimization Manager user interface.

To execute these actions, navigate to the Maintenance Options page:

1. Navigate to the Settings Page.



Click to navigate to the Settings Page.

2. Choose Maintenance Options.



Maintenance Options

Set the data retention period for Embedded Reports.

In the **Data Retention** group of controls, find the field for **Saved Reporting Data**. This displays the current data retention period for Embedded Reports, in days. The default is 365 days.

To change the retention period, enter a different number of days, and then click Apply Settings.

Increasing Storage Capacity for TimescaleDB

If you estimate the storage requirements for Embedded Reports after you have installed Workload Optimization Manager, you might learn that you need to increase the storage capacity that is available to the TimescaleDB.

The platform uses Logical Volume Management (LVM) to manage the VM disks. To increase database storage, you should add a new disk to the VM, and then use it to extend the LVM logical volume, $/\text{dev}/\text{turbo}/\text{var_lib_mysql}$. This logical volume serves both the historical database and the Embedded Reports database. When you have done that, you will increase the quota for the TimescaleDB.

For more information, see Increasing Available Disk Space (on page 51)

Estimating Entity Count

To get a sense of entity count in your environment, search the Workload Optimization Manager log file for an INFO message that lists the number of entities for each discovery cycle. You can search for the string INFO [Stages\$BroadcastStage]. The INFO string should be similar to:

topology-processor-6f6486df64-zf 2021-09-27 20:51:33,724 INFO [Stages\$BroadcastStage] : Successfully sent 1505 entities within topology...

This example shows that you have 1505 entities in the topology. You should consider how your inventory changes over time. For example, you can check the entity count over time to see whether it increases regularly.

Custom Reports

To get the most out of Embedded Reports, you will display custom reports on the Grafana dashboard page. You can import reports from the Turbonomic Open Source site, or you can create your own using SQL Server queries into the data sets.



Importing Reports

You can find a set of custom reports to import on the Workload Optimization Manager Open Source site at https://github.com/turbonomic/visualization/tree/main/embedded-visualization. This page lists different categories of reports that you can use to track your environment.

To import a custom report:

1. In the Embedded Reports page, create a folder to store your imported JSON files.

In Embedded Reports page, navigate to **Dashboards / Browse**. on that page, click **New Folder** to create a folder for you imported JSON files.

For example, create a folder named {{ site.data.vars.Product_Short }}_Github_Reports.

After you create the folder, navigate back to the **Dashboards / Browse** page.

2. Navigate to the report you want to import.

Go to https://github.com/turbonomic/visualization/tree/main/embedded-visualization and browse to find the report you want.

Copy the JSON file to the clipboard.

In the report entry, navigate to the JSON file. In GitHub, display the file as **Raw JSON**, then select the JSON and copy it to the clipboard.

4. Import the JSON file into your Reports.

In the Embedded Reports page, click **Import**, and then paste the JSON you copied into the **Import Via Panel JSON** field. Then click **Load**.

To complete the import:

- Give the name you want for the report.
- Choose the folder that you just created to store the report.
- If you want to share this report with other Grafana installations, make a note of the UID, or change it to a value you can remember.
- Click Import.

The Embedded Reports page now displays your imported report.

Creating Reports

To compose custom reports, your Workload Optimization Manager user account must have **Report Editor** permission. When you navigate from Workload Optimization Manager to the Grafana Reports page, in addition to browsing dashboards, you can create new dashboards. To create a custom report:

1. Create a new dashboard.

Navigate to the Grafana Dashboards page, then click the + icon in the left-hand menu bar to create a new dashboard.

Click to create a new panel.

The page for the new panel includes a tabbed section with a Query tab.

3. In the Query tab, set the Data Source field to Turbo Timescale.

This sets up the panel to display data from the {{ site.data.vars.Product_Short }} Timescale database.

Edit the panel's query.

The panel will display a default query. You can edit this query to change the data the panel displays. At the bottom of the default query, click **Edit SQL**. This displays a field where you can enter the SQL that you want.

For information about experimenting with different queries, see Exploring SQL Queries (on page 1278)

To help you build these queries, this document describes the schema tables, and provides some sample queries against them.



Exploring SQL Queries

To work with SQL queries, your {{ site.data.vars.Product_Short }} user account must have **Report Editor** permission. To explore queries:

- Navigate to the Explore page.
 - The page displays with a sample query already in place
- 2. Choose to explore Turbo Timescale.
 - Next to the page title, **Explore**, you can choose which database to work with. Choose the database Turbo Timescale.
 - If you have installed an external TimescaleDB, be sure to choose th name that you gave to that database.
- Edit the Explore query.
 - The page displays a default query. You can edit this query to change the data the page displays. At the bottom of the default query, click **Edit SQL**. This displays a field where you can enter the SQL that you want.
 - To test your query, click **Run Query**. If your query includes data points over time, you can choose **Format As: Time Series**. For tabular data, choose **Format As: Table**.
 - To help you build these queries, this document describes the schema tables, and provides some sample queries against them.

Schema Tables

The Embedded Reports data set includes the following Schema Tables to represent Workload Optimization Manager data.

action_group Table

Data Object	Туре	Nullable	Primary	Description	Reference
id	int	False	False		
type	enum	False	False	The specific action type - Provision, Reconfigure, Scale, etc.	action_type (on page 1303)
category	enum	False	False	The category of the given action.	action_category (on page 1302)
state	enum	False	False	That action type.	action_state (on page 1303)
mode	enum	False	False	The action mode - automated, manual, etc.	action_mode (on page 1303)
risks	text[]	True	False	An array of strings to describe the risks that drive the action.	

cloud_service_cost Table

For a given cloud service that is associated with a cloud target, the cost of that service.



Data Object	Туре	Nullable	Primary	Description	Reference
time	timestamp with time zone	False	True		
account_oid	bigint	False	True	The ID of the cloud account or subscription this service is associated with.	
cloud_service_oid	bigint	False	True	The ID of the cloud service.	
cost	real	False	False	The cost of the service.	

completed_action Table

This table lists the current set of completed actions. A completed action is an action that completed its execution, whether the action succeeded or failed.

This table does not contain "in progress" or "queued" actions.

Data Object	Туре	Nullable	Primary	Description	Reference
recommendation_ti	m e mestamp with time zone	False	False	When analysis recommended the action.	
acceptance_time	timestamp with time zone	False	False	For manual actions, when the action was accepted for execution.	
completion_time	timestamp with time zone	False	False	When the action completed. Can be for success or failure.	
action_oid	bigint	False	False	The ID of the action. Use this to get action details.	
type	enum	False	False	The action type.	action_type (on page 1303)
severity	enum	False	False	The action severity.	severity (on page 1312)
category	enum	False	False	The action category.	action_category (on page 1302)
target_entity_id	bigint	False	False	The ID of the entity that the action affects. For example, for a VMem resize, the VM that is resized.	



Data Object	Type	Nullable	Primary	Description	Reference
involved_entities	bigint[]	True	False	An array of IDs for entities involved in the action. This includes the target entity.	
description	text	False	False	The text description of the action.	
savings	double precision	False	False	The cost savings this action results in. A negative savings indicates an investment.	
final_state	enum	False	False	Whether the action succeded or failed.	terminal_state (on page 1312)
final_message	text	False	False	A message for the final state. If the action failed, this should contain an error message.	
attrs	jsonb	True	False	Additional (often type-specific) info for the action. For example, in resizes this will contain the commodity type and from/to amounts.	action.attrs (on page 1301)

Sample Use Cases

To get the target entities for all the completed actions, join this table with the entities table. This example lists the completed action type and time, and the entity name type:

select completed_action.type AS action_type, completed_action.completion_time AS time, entity.name, entit
y.type AS ent_type
FROM completed_action
INNER JOIN entity ON completed_action.target_entity_id=entity.oid

entity Table

The Entity table contains information about which entities appear in the topologies and when. This table gets updated with each market cycle.

Data Object	Туре	Nullable	Primary	Description	Reference
oid	bigint	False	True	The entity ID.	



Data Object	Туре	Nullable	Primary	Description	Reference
type	enum	False	False	The entity type.	entity_type (on page 1304)
name	text	False	False	The current display name for the entity. While display names may change over time, this is always the most recent display name.	
environment	enum	True	False	Whether the entity is in an on-prem, cloud, or hybrid environment.	environment_type (on page 1306)
attrs	jsonb	True	False	Additional data for the entity.	entity.attrs (on page 1298) group.attrs (on page 1300)
first_seen	timestamp with time zone	False	False	When the entity was first discovered in the topology.	
last_seen	timestamp with time zone	False	False	When the entity last existed in the topology. For an entity that still exists, the value is 9999-12-31T23:59	:59.

Sample Use Cases

Count entities that meet specific criteria:

For a given time interval, count the number of PHYSICAL_MACHINE entities that have 4 CPUS.

```
select count(*)
from entity e
where e.type = 'PHYSICAL_MACHINE'
   and attrs->'num_cpus'= '4'
   and ('2021-02-01T05:00:00Z','2021-02-18T04:59:59Z') OVERLAPS (e.first_seen, e.last_seen)
```


Find clusters that were configured for a given time range:

Queries like this are common to generate values for grafana variables that you can run reports against.

```
SELECT name, oid
FROM entity
WHERE
  entity.type = 'COMPUTE_CLUSTER'
  AND ('2021-02-01T05:00:00z','2021-02-18T04:59:59Z') OVERLAPS (first_seen, last_seen)
ORDER BY 1
```

For example, here's a list of variables that a user is choosing:





entity_cost Table

For a given cloud entity (a workload such as a VM or a DB service), this table represents a given cost associated with that entity.

Data Object	Туре	Nullable	Primary	Description	Reference
time	timestamp with time zone	False	False		
entity_oid	bigint	False	False	The entity ID.	
category	enum	False	False	The category of service cost - IP service, storage service, on-demand or RI compute, etc.	cost_category (on page 1304)
source	enum	False	False	The type of billing data that provides the cost data.	cost_source (on page 1304)
cost	real	False	False	The calculated cost.	

entity_savings Table

Workload Optimization Manager tracks actions that result in savings or investments in your environment. Actions that add resources usually require an investment, and actions that suspend or reduce resources usually give you a saving. This table describes the cost change of an action in either case.

This table can be in an action whether you have already executed the action or not. The <code>savings_type</code> field describes:

- Whether the action is a saving or investment
- Whether the action has been executed or not

Data Object	Туре	Nullable	Primary	Description	Reference
time	timestamp with time zone	False	True	For a realized saving or	



Data Object	Type	Nullable	Primary	Description	Reference
				investment, when the action was executed. For a missed saving or investment, when the action was last recommended.	
entity_oid	bigint	False	True	The object ID for the entity that has seen a saving or investment.	
savings_type	enum	False	True	Whether the action resulted in an investment or saving, and whether the action executed or not.	savings_type (on page 1312)
stats_value	real	False	False	The value of the investment or saving for the related action.	

entity_types_with_cost Table

This table lists the types of entities that can have costs associated with them. (For costs associated with entities, see entity_cost Table (on page 1282).)

Data Object	Туре	Nullable	Primary	Description	Reference
type	enum	True	False	The entity type.	entity_type (on page 1304)

file Table

This table stores the paths to files in the environment, as well as properties of the files such as last modification or file size.

Data Object	Туре	Nullable	Primary	Description	Reference
volume_oid	bigint	False	True	If present, the ID of the volume that stores this file.	
path	text	False	True	The path to the file.	
type	enum	False	False	The file type - ISO, log file, snapshot, etc.	file_type (on page 1306)
file_size_kb	bigint	True	False	The file size in kb.	
modification_time	timestamp with time zone	True	False	When the file was last modified.	



Data Object	Туре	Nullable	Primary	Description	Reference
storage_oid	bigint	False	False	If present, the ID of the disk that stores this file.	
is_attached	boolean	False	False	Whether the file is attached or unattached.	
hash	bigint	False	False		

historical_entity_attrs Table

This table tracks the historical attributes associated with an entity. Each row represents the value of a particular attribute of an entity at a particular point in time. New rows are written when the value of a property changes between topologies, and at regular intervals (e.g. daily) to keep a recent value available within a reasonable time range.

Data Object	Туре	Nullable	Primary	Description	Reference
time	timestamp with time zone	False	False	When this attribute was recorded.	
entity_oid	bigint	False	False	The ID of the entity this attribute pertains to.	
type	enum	False	False	The attribute type.	attr_type (on page 1304)
bool_value	boolean	True	False	If the attribute is boolean, the boolean value.	
int_value	int	True	False	If the attribute is an integer, the integer value. If the attribute is an enum, this is the OID of the enum in the pg_enum table (to guard against name or order changes). The int_value should be castable to the enum via a custom cast (e.g. int_value::entity_state = 'POWERED_ON').	ate
long_value	bigint	True	False	If the attribute is a long, the long value.	



Data Object	Туре	Nullable	Primary	Description	Reference
double_value	double precision	True	False	If the attribute is a double, the double value.	
string_value	text	True	False	If the attribute is a string, the string value.	
int_arr_value	int[]	True	False	If the attribute is a list of ints, the list values. If the attribute is a list of enums, these are the OIDs of the enums in the pg_enum table (to guard against name or order changes).	
long_arr_value	bigint[]	True	False	If the attribute is a list of longs, the long values.	
string_arr_value	text[]	True	False	If the attribute is a list of strings, the string values.	
double_arr_value	float8[]	True	False	If the attribute is a list of doubles, the double values.	
json_value	jsonb	True	False	If the attribute is a JSON object, the given object.	

Sample Use Cases

Get All Powered On Entities:

This query returns all the entities in the historical_entity_attrs that do not have a powered_off state given a certain time range.

```
select *
from historical_entity_attrs h1
where h1.type = 'ENTITY_STATE' and h1.int_value::entity_state != 'POWERED_OFF' AND h1.time between $__tim
eFrom() and $__timeTo()
```

Gap-filling data:

Data in this table are not written at every broadcast. Because of this, if we ask for those data in a time range, we might only get few data points. Consider this query in which we get the values for one entity in a time range:


```
SELECT * FROM historical_entity_attrs h1
where h1.type = 'ENTITY_STATE'
   and entity_oid ='73864029152384'
   and time between (timestamptz '2021-03-01T01:00:00Z' - interval '24 hour') and '2021-03-03T04:59:59Z'
   order by time;
```





In order to solve this problem we use a timescaledb function that fills the time ranges with data, as if those data were written at a constant interval. This means that if we want data every interval t but we only have data at t1 and t4, with this function we can generate data at t2 and t3 with the same value of t1. The function that we use is called $time_bucket_gapfill$ and here's a sample query. Notice how in the result we have data points at a constant interval of 10 minutes:

```
SELECT
   time_bucket_gapfill('10 min', time) AS minutes,
   locf(max(h1.int_value::entity_state))
FROM historical_entity_attrs h1
where h1.type = 'ENTITY_STATE'
--   AND h1.int_value::entity_state = 'POWERED_ON'
   and entity_oid ='73864029152384'
   and time between (timestamptz '2021-03-01T01:00:00Z' - interval '24 hour') and '2021-03-03T04:59:59Z'
GROUP BY minutes
```




Casting Entity States to Integers:

Entity States are internally represented as integers. This means that a property such as POWERED_OFF is stored as a number. In order to work with this the queries need to cast the integer to the corresponding entity state. This is done with the following cast, supported by Postgres: int_value::entity_state . So for example, take a look at the two queries below, the first one without the cast, and the second query with it:

```
SELECT time, entity_oid, entity_state FROM historical_entity_attrs h1
where h1.type = 'ENTITY_STATE'
   and entity_oid ='73864029152384'
   and time between (timestamptz '2021-03-01T01:00:00Z' - interval '24 hour') and '2021-03-03T04:59:59Z'
   order by time;
```





```
SELECT time, entity_oid, int_value::entity_state FROM historical_entity_attrs h1
where h1.type = 'ENTITY_STATE'
   and entity_oid ='73864029152384'
   and time between (timestamptz '2021-03-01T01:00:00Z' - interval '24 hour') and '2021-03-03T04:59:59Z'
   order by time;
```



metric Table

This table contains metric values for entities that appeared in the topology. Most metrics are values associated with commodities bought or sold by the entity. Bought and sold commodities appear in separate records - one for the buyer and one for the seller. In addition to topology metrics, this table contains headroom properties, which are generated daily by headroom plans.

Data Object	Туре	Nullable	Primary	Description	Reference
time	timestamp with time zone	False	False	When analysis discovered thIS metric. For headroom metrics, when the headroom plan was created.	
entity_oid	bigint	False	False	The ID of the entity this metric pertains to.	
type	enum	False	False	The metric type.	metric_type (on page 1307)



Data Object	Туре	Nullable	Primary	Description	Reference
provider_oid	bigint	True	False	The ID of the entity that provides this metric. For example, for VMem, the ID of the host that provides the memory.	
key	text	True	False	The commodity key. This value can be null if no key is present.	
current	double precision	True	False	Current utilization of commodity in provider entity.	
capacity	double precision	True	False	The capacity of the commodity in the provider entity.	
utilization	double precision	True	False	Overall utilization of the commodity in the provider entity.	
consumed	double precision	True	False	Amount of commodity currently used by consumer entity.	
peak_current	double precision	True	False	Peak amount of current used commodity in the provider entity.	
peak_consumed	double precision	True	False	Peak amount of commodity currently used by the consumer entity.	
entity_type	enum	False	False	The type of the consumer entity.	entity_type (on page 1304)

Sample Use Cases

VMem utilization for a Virtual Machine over time:

This query returns all the VM memory metrics collected for a specified virtual machine for a given time interval. The time interval is truncated to the hour.



```
WHERE m.entity_oid = s.oid
    and m.time BETWEEN s.from_time AND s.to_time
AND m.type = 'VMEM'
AND m.provider_oid IS NULL
AND m.time BETWEEN $__timeFrom()::timestamptz - interval '24 hour' AND date_trunc('hour', $__timeT
o()::timestamptz)
GROUP BY 1
```

Storage Amount of Physical Machines Running On a Cluster:

This query returns the max values of storage amounts for all the physical machines running in a cluster. Note that the only parameter given to the query other than the time range, is the cluster_id. We then have an internal function in Postgres that is able to translate the cluster_id to all the oids of the physical machines.

```
date_trunc('day', m.time) as time,
    m.entity_oid,
    MAX(current) FILTER (WHERE m.type = 'STORAGE_AMOUNT') as stor_used,
    MAX(capacity) FILTER (WHERE m.type = 'STORAGE_AMOUNT') as stor_cap,
    MAX(current) FILTER (WHERE m.type = 'STORAGE_PROVISIONED') as stor_prov
FROM
    metric m,
    scope_to($__timeFrom(), $__timeTo(), 'STORAGE', ARRAY[$CluserId+0]::bigint[], $CluserId = '0') s
WHERE
    m.entity_oid = s.oid
    AND m.time BETWEEN s.from_time AND s.to_time
    AND m.type in ('STORAGE_AMOUNT', 'STORAGE_PROVISIONED')
    AND m.time between $__timeFrom() and $__timeTo()
GROUP BY 1, 2
```

Physical Machine Average Memory Utilization - Week Over Week By Day:

Returns the average daily memory utilization for virtual machines both for the current week and the past week.

```
WITH metrics AS (
 SELECT m.time, m.utilization
   FROM metric m,
    scope_to($__timeFrom()::timestamptz - INTERVAL '7 day', $__timeTo(), 'PHYSICAL_MACHINE', ARRAY[0]::b
igint[], '0' = '0') s
   WHERE
     m.entity_oid = s.oid
     AND m.time BETWEEN s.from_time AND s.to_time
     AND m.type = 'MEM'
     AND m.time BETWEEN ($__timeFrom()::TIMESTAMPTZ - interval '7 day') AND date_trunc('day', $__timeT
o()::TIMESTAMPTZ)
   GROUP BY m.time, m.entity_oid, m.utilization
),
DATA AS (
 SELECT m.time, avg(m.utilization) AS avg_util
 FROM metrics m
 GROUP BY m.time
)
SELECT
 INTERVAL '1 DAY' + CASE
   WHEN time BETWEEN date_trunc('day', $__timeFrom()::TIMESTAMPTZ - interval '7 day')
     AND date_trunc('day', $__timeTo()::TIMESTAMPTZ - interval '7 day')
   THEN date_trunc('day', time + interval '7 day')
```



```
ELSE date_trunc('day', time)
END as "time",
CASE
   WHEN time BETWEEN date_trunc('day', $__timeFrom()::TIMESTAMPTZ - interval '7 day')
        AND date_trunc('day', $__timeTo()::TIMESTAMPTZ - interval '7 day')
   THEN 'Previous Week'
   ELSE 'Week Ending ' || DATE($__timeTo()::TIMESTAMPTZ)::TEXT
   END as metric,
   avg(avg_util)
FROM data
GROUP BY 1, 2
ORDER BY 1, 2
```

Representation of Powered Off Virtual Machines:

Ideally, metrics of a turned off Virtual Machine will still be written on the table, assuming that the probe will send them in the entity dto. Most used values for commodities will have NULL values, we do this, instead of having 0's, in order not to affect potential averages over time, while the capacity should have the same value, independent of the state of the machine. Still, some used values for commodities won't be NULL, such as storage, since those are consumed by the machine even in a powered off state.

pending_action Table

This table lists the latest actions that have been recommended by the market. The table repopulates at a configurable interval (not necessarily every 10-minute market cycle). When it repopulates, all actions are replaced with the latest action recommendations.

This table does not include actions that are in progress.

Data Object	Туре	Nullable	Primary	Description	Reference
recommendation_ti	imtimestamp with time zone	False	False	When analysis recommended this action.	
action_oid	bigint	False	False	The action ID. Use this to get more action details.	
type	enum	False	False	the action type.	action_type (on page 1303)
severity	enum	False	False	The action severity	severity (on page 1312)
category	enum	False	False	The action category	action_category (on page 1302)
target_entity_id	bigint	False	False	The ID of the entity this action affects.	
involved_entities	bigint[]	True	False	An array of IDs for all the entities involved in the action. Includes the target entity.	
description	text	False	False	The text description of the action.	



Data Object	Туре	Nullable	Primary	Description	Reference
savings	double precision	False	False	The cost savings this action results in. A negative savings indicates an investment.	
attrs	jsonb	True	False	Additional (often type-specific) info for the action. For example, in resizes this will contain the commodity type and from/to amounts.	action.attrs (on page 1301)

Sample Use Cases

To get the target entities for all the pending actions, join this table with the entities table. This example lists the pending action type, entity name, and the entity type:

select pending_action.type AS action_type, entity.name, entity.type AS ent_type
FROM pending_action
INNER JOIN entity ON pending_action.target_entity_id=entity.oid

pending_action_stats Table

Data Object	Туре	Nullable	Primary	Description	Reference
time	timestamp with time zone	False	False		
scope_oid	bigint	False	False		
entity_type	enum	False	False		entity_type (on page 1304)
environment_type	enum	False	False		environment_type (on page 1306)
action_group	int	False	False		
prior_action_count	int	False	False		
cleared_action_cou	ntint	False	False		
new_action_count	int	False	False		
involved_entity_cou	ntnt	False	False		
savings	real	False	False		
investments	real	False	False		

run_health_checks Table

This table lists the health checks that are current in the {{ site.data.vars.Product_Short }} notifications.



Data Object	Туре	Nullable	Primary	Description	Reference
check_name	text	True	False	The display name of the health check.	
passed	boolean	True	False	Whether the health check passed or failed.	
messages	text[]	True	False	The text description of the health check results.	

scope Table

The Scope table tracks the association of two entities as they are related in each other's scope. The <code>seed_oid</code> identifies the containing entity (the entity that defines the scope), and the <code>scoped_oid</code> identifies the entity that is within the given scope. This table updates with each market cycle.

Data Object	Туре	Nullable	Primary	Description	Reference
seed_oid	bigint	False	True	The ID of the entity whose scope is the subject of the given record. For example, for a cluster-to-host relationship, the seed can be the cluster, and the scoped entity would be the host.	
scoped_oid	bigint	False	True	ID of the entity that is part of the seed scope.	
scoped_type	enum	False	False	Entity type for the scoped entity.	entity_type (on page 1304)
start	timestamp with time zone	False	True	When this relationship first appeared in the topology. This covers the initial appearance, or an appearance after a gap (the relationship was temporarily broken).	
finish	timestamp with time zone	False	False	WHEN this relationship LAST appeared IN THE TOPOLOGY. A value of	



Data Object	Туре	Nullable	Primary	Description	Reference
				9999-12-31T23:59 means the relationship is not yet known to have terminated.	:59

Examples

Example 1:

seed_oid	scoped_oid	scoped_type	start	finish
111	999	PHYSICAL_MACHINE	2021-01-01T05:00:00Z	9999-12-31T23:59:59
999	111	COMPUTE_CLUSTER	2021-01-01T05:00:00Z	9999-12-31T23:59:59

The first row indicates that cluster_1 (oid: 111) contains Physical Machine_1 (oid: 999). The start time indicates the first time the entity was discovered. This relationship is ongoing and this is represented by a finish timestamp of 9999-12-31T23:59:59. Row 2 shows that Physical Machine_1 is contained by Cluster_1.

Example 2:

seed_oid	scoped_oid	scoped_type	start	finish
111	999	PHYSICAL_MACHINE	2021-01-01T05:00:00Z	2021-01-31T05:00:00Z
999	111	COMPUTE_CLUSTER	2021-01-01T05:00:00Z	2021-01-31T05:00:00Z
222	999	PHYSICAL_MACHINE	2021-01-31T05:00:00Z	9999-12-31T23:59:59
999	222	COMPUTE_CLUSTER	2021-01-31T05:00:00Z	9999-12-31T23:59:59

These records show that Physical_Machine_1 moved to Cluster_2 (oid: 2222) on January 31. Note that the timestamp for the end of the relationship with Cluster_1 is the same as the timestamp for the start of the relationship with Cluster_2.

Sample Use Cases

Count Physical Machines in Clusters Over A Given Time Interval

```
WITH all_relationships AS (
   select
       e.name cluster_name, s.seed_oid cluster_oid, s.scoped_oid pm_oid
   FROM
       entity e
   JOIN scope s on e.oid = s.seed_oid
       and s.scoped_type = 'PHYSICAL_MACHINE'
   WHERE e.type = 'COMPUTE_CLUSTER'
       AND ('2021-02-01T05:00:00Z','2021-02-18T04:59:59Z') OVERLAPS (s.start, s.finish)
), non_duplicate_relationships AS (
     The same relationships between 2 entities can exist in given time interval if they move in and out
of each others scopes
     We account for these duplicates entries at varying time intervals
   select *
   from all_relationships
   GROUP BY cluster_name, cluster_oid, pm_oid
select cluster_name, count(*)
from non_duplicate_relationships
group by cluster_name
```



scope_to Table

Data Object	Туре	Nullable	Primary	Description	Reference
oid	bigint	True	False		
from_time	timestamp with time zone	True	False		
to_time	timestamp with time zone	True	False		
seed	bigint	True	False		

scope_to_types Table

Data Object	Туре	Nullable	Primary	Description	Reference
oid	bigint	True	False		
from_time	timestamp with time zone	True	False		
to_time	timestamp with time zone	True	False		
seed	bigint	True	False		
e_type	enum	True	False		entity_type (on page 1304)

topology_stats Table

Data Object	Туре	Nullable	Primary	Description	Reference
time	timestamp with time zone	False	False		
attrs	jsonb	True	False		

wasted_file Table

This table stores the paths to the current wasted files in the environment, as well as properties of the files such as last modification or file size.

Data Object	Туре	Nullable	Primary	Description	Reference
path	text	True	False	The file path.	
file_size_kb	bigint	True	False	The file size.	
modification_time	timestamp with time zone	True	False	When the file was last modified.	
storage_oid	bigint	True	False	The ID of the storage that contains the file.	



Data Object	Туре	Nullable	Primary	Description	Reference
storage_name	text	True	False	The name of the storage (denormalized for reporting).	

Sample Use Cases

Get information about storage files for a data store:

The query returns the storage name, the file path, the site of the file and the last modified time for each file of a data store. The query accepts the \$storage_oid as a parameter.

JSON Data Objects

The following JSON objects represent data about specific entities in your environment.

ActionCommodity JSON

The capacity and utilization of a commodity that is affected by a given action.

Data Object	Description	Туре
capacity	The available capacity of the given commodity.	float
percentileUtilization	For entities and resources that support it, the calculated percentile of utilization.	Double
used	The amount of the resource currently in use.	float
utilization	The percentage of capacity in use.	float

ActionEntity JSON

For a given action, a description of the entity this action changes.

Data Object	Description	Туре	Reference	Repeated
oid	The ID of the entity.	Long		
name	The entity name. This corresponds to the	String		



Data Object	Description	Туре	Reference	Repeated
	name that displays in the user interface.			
type	The entity type.	entity_type (on page 1304)	entity_type (on page 1304)	
attrs		JSON	entity.attrs (on page 1298)	
newMetric		JSON		True
newRelated		JSON		True

ActionImpactedCost JSON

For cloud entities, the on-demand costs or RI coverage that is affected by a given action. The action shows one object for the cost before the action, and another for the cost after the action.

Data Object	Description	Туре
onDemandCost	For on-demand billing, the entity cost.	Float
onDemandRate	For on-demand billing, the rate of cost.	Float
riCoveragePercentage	For RIs, the percentage of RI coverage.	Float

ActionImpactedCosts JSON

For a given action, descriptions of the Before and After costs.

Data Object	Description	Туре	Reference
afterActions	A description of what the cost will be after the action executes.	ActionImpactedCost (on page 1296)	ActionImpactedCost (on page 1296)
beforeActions	A description of the current cost, before the action executes.	ActionImpactedCost (on page 1296)	ActionImpactedCost (on page 1296)

ActionImpactedEntity JSON

For a given action, a description of an entity that is affected by that action.

Data Object	Description	Туре	MapKeyType	Reference
affectedCosts	A description of the before and after costs for this entity.	ActionImpactedCosts (on page 1296)		ActionImpactedCosts (on page 1296)
affectedMetrics	A description of the before and after metrics for this entity.	ImpactedMetric (on page 1300)	metric_type (on page 1307)	ImpactedMetric (on page 1300)
name	The entity name.	String		
oid	The entity ID.	Long		



Data Object	Description	Туре	MapKeyType	Reference
settings	For entities that support percentile calculations, the aggressiveness and observation period for this entity.	EntitySettings (on page 1300)		EntitySettings (on page 1300)
type	The entity type.	entity_type (on page 1304)		entity_type (on page 1304)
attrs		JSON		entity.attrs (on page 1298)
newMetric		JSON		True
newRelated		JSON		True

BuyRiInfo JSON

The information that analysis can use to calculate Buy RI actions.

Data Object	Description	Туре	Reference
computeTier	The compute tier, or workload family for the action. The ActionEntity object will be for an entity of type COMPUTE_TIER.	ActionEntity (on page 1295)	ActionEntity (on page 1295)
count		Integer	
masterAccount	The account that manages the RI billing.	ActionEntity (on page 1295)	ActionEntity (on page 1295)
region	The region that will host the RIs.	ActionEntity (on page 1295)	ActionEntity (on page 1295)
target	The cloud account or subscription that will manage the RIs.	ActionEntity (on page 1295)	ActionEntity (on page 1295)

CommodityChange JSON

The change (from - to) of an entity's commodity that is proposed for a given action.

Data Object	Description	Type	Reference
attribute		String	
commodityType	The type of commodity the action will change - MEM, IO_THROUGHPUT, etc.	metric_type (on page 1307)	metric_type (on page 1307)
from	The commodity value before the action executes.	Float	
percentileChange	For entities and commodities that support percentile calculations, the before and	CommodityPercentileChange (on page 1298)	CommodityPercentileChange (on page 1298)



Data Object	Description	Туре	Reference
	after values for percentile utilization and settings.		
target	A description of the entity this action will change.	ActionEntity (on page 1295)	ActionEntity (on page 1295)
to	The commodity value after the action executes.	Float	
unit	The displayed units of measurement.	String	

CommodityPercentileChange JSON

If an action changes a commodity that participates in percentile-based analysis, the percentile settings, and the commodity values before and after the action.

Data Object	Description	Туре
after	The percentile utilization after the action executes	Double
aggressiveness	The aggressiveness setting used to calculate the percentile.	Integer
before	The percentile utilization before the action executes.	Double
observationPeriodDays	The observation period used to calculate the percentile.	Integer

DeleteInfo JSON

A description of a file is unattached and should be deleted.

Data Object	Description	Туре	Format
filePath	The path to the file.	String	
fileSize	The size of the file.	Double	
lastModifiedTimestamp	When the file was last modified.	String	yyyy-MM-dd'T'HH:mm:ss'Z'
unattachedDays	How many days the file has been unattached.	Integer	
unit	The displayed unit of measure for the file size.	String	

entity.attrs JSON

Additional descriptions for a given entity. The values an instance of this object can have are different for different entity types.

Data Object	Description	Туре	SupportedEntityTypes	Repeated	Reference
attachment_state	Whether a given	AttachmentState (on page 1302)	VIRTUAL_VOLUME	False	AttachmentState (on page 1302)



Data Object	Description	Type	SupportedEntityTypes	Repeated	Reference
	volume is attached or unattached.				
connected_networks	A list of network names that a given VM is connected to.	MULTI_TEXT	VIRTUAL_MACHINE	True	
cpu_model	For a physical host, the model of CPU on that host.	TEXT	PHYSICAL_MACHINE	False	
guest_os_name	The name of the OS running on a given VM.	TEXT	VIRTUAL_MACHINE	False	
guest_os_type	The specific type for the OS running on a given VM.	OSType (on page 1302)	VIRTUAL_MACHINE	False	OSType (on page 1302)
is_local	Whether a storage is local to the machine, or networked.	BOOLEAN	STORAGE	False	
model	The specific model of the given physical host.	TEXT	PHYSICAL_MACHINE	False	
num_cpus	The number of CPUs on the given physical host.	NUMBER	PHYSICAL_MACHINE	False	
tags	A list of tags that are assigned to the given entity.	TEXT_MULTIMAP (Embedded Reporting) or List (Data Exporter)	ALL	False	
targets	The target that manages	Target (on page 1301)	ALL	True	Target (on page 1301)



Data Object	Description	Туре	SupportedEntityTypes	Repeated	Reference
	the given entity.				
timezone	The timezone that is set for the clock on the physical machine.	TEXT	PHYSICAL_MACHINE	False	
vendor_id		TEXT	VIRTUAL_VOLUME,BUSINESS_ACCOUNT		

EntitySettings JSON

For an entity that participates in percentile-based analysis, the aggressiveness setting and observation period.

Data Object	Description	Туре
percentileAggressiveness	The current aggressiveness setting.	Integer
percentileObservationPeriodDays	The current observation period.	Integer

group.attrs JSON

Additional descriptions for a given group.

Data Object	Description	Туре	Repeated	Reference	SupportedEntityTypes
dynamic	Whether this group is static or dynamic. true for dynamic.	BOOLEAN	False		STORAGE_CLUSTER,COMPUTE_CLUSTER,GROUP,K8S_0
member_types		MULTI_TEXT	True		STORAGE_CLUSTER,COMPUTE_CLUSTER,GROUP,K8S_0
origin		TEXT	False		STORAGE_CLUSTER,COMPUTE_CLUSTER,GROUP,K8S_0
tags		TEXT_MULTIMAP (Embedded Reporting) or List (Data Exporter)	False		GROUP,RESOURCE_GROUP,COMPUTE_CLUSTER,K8S_C
targets		Target (on page 1301)	False	Target (on page 1301)	GROUP,RESOURCE_GROUP,COMPUTE_CLUSTER,K8S_C

ImpactedMetric JSON

For a metric on an entity that is affected by an action, a description of the impacted metric.



Data Object	Description	Туре	Reference
afterActions	A description of what the metric utilization will be after the action executes.	ActionCommodity (on page 1295)	ActionCommodity (on page 1295)
beforeActions	A description of the current utilization, before the action executes.	ActionCommodity (on page 1295)	ActionCommodity (on page 1295)

MoveChange JSON

For a vMotion action, the changed placement of the affected entity.

Data Object	Description	Туре	Repeated	Reference
from	Where the entity will move from.	ActionImpactedEntity (on page 1296)	False	ActionImpactedEntity (on page 1296)
resource		ActionEntity (on page 1295)	True	ActionEntity (on page 1295)
to	Where the entity will move to.	ActionImpactedEntity (on page 1296)	False	ActionImpactedEntity (on page 1296)

Target JSON

Data Object	Description	Туре
category		String
entityVendorld		String
name		String
oid		Long
type		String

action.attrs JSON

Extra data that pertains to a given action.

JSON Object	Description	Туре	MapKeyType	Reference
buyRiInfo	For an action to buy Rls, additional information about the Rls.	BuyRiInfo (on page 1297)		BuyRilnfo (on page 1297)
deleteInfo	For an action to delete a file, a description of that file.	DeleteInfo (on page 1298)		DeleteInfo (on page 1298)
moveInfo	For a move action, a description of from and to for the move.	MoveChange (on page 1301)	entity_type (on page 1304)	MoveChange (on page 1301)



JSON Object	Description	Туре	MapKeyType	Reference
resizeInfo	For a resize action, a description of the commodity changes.	CommodityChange (on page 1297)	metric_type (on page 1307)	CommodityChange (on page 1297)
scaleInfo	For scaling a cloud VM, a description of the from and to for the VM move.	MoveChange (on page 1301)	entity_type (on page 1304)	MoveChange (on page 1301)
target	Extra information about the entity this action impacts.	ActionImpactedEntity (on page 1296)		ActionImpactedEntity (on page 1296)

Enums

These enums specify values for certain states or types.

AttachmentState Enum

Whether a given is attached or unattached.

- ATTACHED:
- UNATTACHED:

OSType Enum

The OS types that Workload Optimization Manager discovers on hosts and VMs.

- LINUX:
- LINUX_WITH_SQL_ENTERPRISE:
- LINUX_WITH_SQL_STANDARD:
- LINUX_WITH_SQL_WEB:
- RHEL:
- SUSE:
- UBUNTU_PRO:
- UNKNOWN_OS:
- WINDOWS:
- WINDOWS_BYOL:
- WINDOWS_WITH_SQL_ENTERPRISE:
- WINDOWS_WITH_SQL_STANDARD:
- WINDOWS_WITH_SQL_WEB:

action_category Enum

The different categories for a given action.

- COMPLIANCE:
- EFFICIENCY_IMPROVEMENT:
- PERFORMANCE_ASSURANCE:
- PREVENTION:



- UNKNOWN:
- SAVING:

action_mode Enum

The different modes for an action, such as automated or manual.

- AUTOMATIC:
- DISABLED:
- EXTERNAL_APPROVAL:
- MANUAL:
- RECOMMEND:

action_state Enum

The different states for an action, such as completed or pending.

- ACCEPTED:
- CLEARED:
- FAILED:
- FAILING:
- IN_PROGRESS:
- POST_IN_PROGRESS:
- PRE_IN_PROGRESS:
- QUEUED:
- READY:
- REJECTED:
- SUCCEEDED:
- BEFORE_EXEC:
- IN_PROGRESS_NON_CRITICAL:

action_type Enum

The different types of action.

- ACTIVATE:
- ALLOCATE:
- BUY_RI:
- DEACTIVATE:
- DELETE:
- MOVE:
- NONE:
- PROVISION:
- RECONFIGURE:
- RESIZE:
- SCALE:
- START:
- SUSPEND:



attr_type Enum

The supported types of attributes. For each type, you can find different data stored in the attribute.

- ENTITY_STATE:
- NUM_VCPU:
- VOLUME_ATTACHED:

cost_category Enum

For different cost data, the service or category that the cost pertains to.

- IP:
- ON_DEMAND_COMPUTE:
- ON_DEMAND_LICENSE:
- RESERVED_LICENSE:
- RI COMPUTE:
- SPOT:
- STORAGE:
- TOTAL:
- CLOUD_COMMITMENT_USAGE:

cost_source Enum

The type of billing agreement that is the source of the given cost data.

- BUY_RI_DISCOUNT:
- ENTITY_UPTIME_DISCOUNT:
- ON_DEMAND_RATE:
- RI_INVENTORY_DISCOUNT:
- TOTAL:
- UNCLASSIFIED:
- CLOUD_COMMITMENT_DISCOUNT:

entity_state Enum

The running state for an entity, such as powered off, suspended, or running.

- FAILOVER:
- MAINTENANCE:
- POWERED_OFF:
- POWERED_ON:
- SUSPENDED:
- UNKNOWN:

entity_type Enum

The set of supported entities that Workload Optimization Manager manages.

- ACTION_MANAGER:
- APPLICATION:
- APPLICATION_COMPONENT:



- APPLICATION_COMPONENT_SPEC:
- APPLICATION_SERVER:
- AVAILABILITY_ZONE:
- BILLING_FAMILY:
- BUSINESS:
- BUSINESS_ACCOUNT:
- BUSINESS_APPLICATION:
- BUSINESS_ENTITY:
- BUSINESS_TRANSACTION:
- BUSINESS_USER:
- CHASSIS:
- CLOUD_COMMITMENT:
- CLOUD_SERVICE:
- COMPUTE CLUSTER:
- COMPUTE_RESOURCE:
- COMPUTE TIER:
- CONTAINER:
- CONTAINER_PLATFORM_CLUSTER:
- CONTAINER_POD:
- CONTAINER_SPEC:
- DATABASE:
- DATABASE_SERVER:
- DATABASE_SERVER_TIER:
- DATABASE TIER:
- DATACENTER:
- DESIRED_RESERVED_INSTANCE:
- DESKTOP_POOL:
- DISK_ARRAY:
- DISTRIBUTED_VIRTUAL_PORTGROUP:
- DOCUMENT_COLLECTION:
- DPOD:
- GROUP:
- HCI_PHYSICAL_MACHINE:
- HYPERVISOR_SERVER:
- INFRASTRUCTURE:
- INTERNET:
- IO_MODULE:
- TP
- K8S_CLUSTER:
- LICENSING_SERVICE:
- LOAD_BALANCER:
- LOGICAL POOL:
- MAC:
- MOVER:
- NAMESPACE:
- NETWORK:
- NETWORKING_ENDPOINT:
- NODE_POOL:
- OPERATOR:
- PHYSICAL_MACHINE:



- PORT:
- PROCESSOR_POOL:
- REGION:
- RESERVED_INSTANCE:
- RESERVED_INSTANCE_SPECIFICATION:
- RESOURCE_GROUP:
- RIGHT_SIZER:
- SAVINGS:
- SERVICE:
- SERVICE_ENTITY_TEMPLATE:
- SERVICE_PROVIDER:
- STORAGE:
- STORAGE_CLUSTER:
- STORAGE CONTROLLER:
- STORAGE_TIER:
- STORAGE VOLUME:
- SWITCH:
- TARGET:
- THIS_ENTITY:
- THREE_TIER_APPLICATION:
- VIEW_POD:
- VIRTUAL_APPLICATION:
- VIRTUAL_DATACENTER:
- VIRTUAL_MACHINE:
- VIRTUAL_MACHINE_SPEC:
- VIRTUAL_VOLUME:
- VLAN:
- VM_SPEC:
- VPOD:
- WEB_SERVER:
- WORKLOAD_CONTROLLER:
- _NONE_:

environment_type Enum

Whether the environment is cloud, on-prem, or hybrid.

- CLOUD:
- HYBRID:
- ON PREM:
- UNKNOWN_ENV:

file_type Enum

Different types of file, such as configuration file or ISO image.

- CONFIGURATION:
- DISK:
- ESXCONSOLE:
- ISO:
- LOG:



- MEMORY:
- SNAPSHOT:
- SWAP:

metric_type Enum

The different types of metrics that Workload Optimization Manager discovers for entities.

■ ACTIVE_SESSIONS:

Count of the number of actively logged in sessions

Units: Count
BALLOONING:

Number of kb the host is dedicated for ballooning

Units: kilobytes

■ BUFFER_COMMODITY:

Utilization of a port buffer (fabric, UCS specific)

Units: megabytes

■ CARBON:

Carbon dioxide equivalent (CO2e) emissions for a given entity

Units: grams
CONNECTION:

Number of connections onto the application

Units: Count COOLING:

acceptable temperature range that is utilized by an entity

Units: percentage

■ CPU:

CPU used by host (current column) or host CPU consumed by VMs (consumed column).

Units: MHz

■ CPU_ALLOCATION:

For VMs (consumed column) - VM buys from VDC or from desktop pool (VDI). For hosts - PMs sells to VDCs.

Units: MHz

■ CPU_HEADROOM:

Number of VMs that can fit in all of the available CPU (on a cluster)

Units: Count

■ CPU_PROVISIONED:

Capacity is based on the over-provisioned value in policy

Units: MHz
CPU_READY:
Ready queue

Units: ms

■ DB_CACHE_HIT_RATE:

The percentage of accesses that result in cache hits.

Units: Percentage

■ DB_MEM:

DB mem utilization or DM capacity



Units: kilobytes

■ DTU:

Capacity defined in the cloud

Units: Count ENERGY:

Electricity consumed by a given entity over a period of time

Units: watt-hours

■ EXTENT:

Internal
Units: NA
FLOW:

Amount of network traffic per second between two nodes

Units: kilobytes/sec FLOW_ALLOCATION:

Units: bytes

■ HEAP:

Amount of heap configured for an application

Units: kilobytes IMAGE_CPU:

For VDI, usage of the business user

Units: MHz
IMAGE_MEM:

For VDI, usage of the business user

Units: kilobytes
IMAGE_STORAGE:

For VDI, usage of the business user

Units: megabytes
■ IO_THROUGHPUT:

Amount of traffic through the IO adapter

Units: kilobytes/sec

■ MEM:

Physical machine - usage of memory. VM - consumed memory.

Units: kilobytes

■ MEM_ALLOCATION:

Physical machine - what the host provides to VDCs. VM (consumed column) - what the VM buys from VDC or desktop pool.

Units: kilobytes
MEM_HEADROOM:

Number of VMs that can fit in the available memory on the cluster

Units: Count

■ MEM PROVISIONED:

Capacity, based on the over-provisioned value in policy

Units: kilobytes

■ NET_THROUGHPUT:

Amount of traffic through the Network adapter



Units: kilobytes/sec

■ POOL_CPU:

For VDI, usage of the desktop pool

Units: MHz
■ POOL_MEM:

For VDI, usage of the desktop pool

Units: kilobytes
POOL_STORAGE:

For VDI, usage of the desktop pool

Units: megabytes PORT CHANEL:

Traffic on ports for UCS Mgr/HPE1

Units: kilobytes/sec

■ POWER:

Electricity consumed by a given entity

Units: watts

■ PROCESSING UNITS:

unit of measure for shared processing power across one or more virtual processors

Units: PU Q16 VCPU:

VM - Sum of the Ready Queue usage of all of the CPU on the VM. To normalize the value, divide it by the number of vCPU. Host - Average of the underlying Ready Queue values from all of the corresponding VMs with the same number of vCPUs.

Units: ms

■ 01 VCPU:

VM - Sum of the Ready Queue usage of all of the CPU on the VM. To normalize the value, divide it by the number of vCPU. Host - Average of the underlying Ready Queue values from all of the corresponding VMs with the same number of vCPUs.

Units: ms

■ Q2 VCPU:

VM - Sum of the Ready Queue usage of all of the CPU on the VM. To normalize the value, divide it by the number of vCPU. Host - Average of the underlying Ready Queue values from all of the corresponding VMs with the same number of vCPUs.

Units: ms

■ Q32_VCPU:

VM - Sum of the Ready Queue usage of all of the CPU on the VM. To normalize the value, divide it by the number of vCPU. Host - Average of the underlying Ready Queue values from all of the corresponding VMs with the same number of vCPUs.

Units: ms

■ Q3_VCPU:

VM - Sum of the Ready Queue usage of all of the CPU on the VM. To normalize the value, divide it by the number of vCPU. Host - Average of the underlying Ready Queue values from all of the corresponding VMs with the same number of vCPUs.

Units: ms

■ Q4_VCPU:

VM - Sum of the Ready Queue usage of all of the CPU on the VM. To normalize the value, divide it by the number of vCPU. Host - Average of the underlying Ready Queue values from all of the corresponding VMs with the same number of vCPUs.

Units: ms

■ Q5_VCPU:

VM - Sum of the Ready Queue usage of all of the CPU on the VM. To normalize the value, divide it by the number of vCPU. Host - Average of the underlying Ready Queue values from all of the corresponding VMs with the same number of vCPUs.



Units: ms

■ Q64_VCPU:

VM - Sum of the Ready Queue usage of all of the CPU on the VM. To normalize the value, divide it by the number of vCPU. Host - Average of the underlying Ready Queue values from all of the corresponding VMs with the same number of vCPUs.

Units: ms

■ Q6_VCPU:

VM - Sum of the Ready Queue usage of all of the CPU on the VM. To normalize the value, divide it by the number of vCPU. Host - Average of the underlying Ready Queue values from all of the corresponding VMs with the same number of vCPUs.

Units: ms

■ Q7_VCPU:

VM - Sum of the Ready Queue usage of all of the CPU on the VM. To normalize the value, divide it by the number of vCPU. Host - Average of the underlying Ready Queue values from all of the corresponding VMs with the same number of vCPUs.

Units: ms

■ Q8_VCPU:

VM - Sum of the Ready Queue usage of all of the CPU on the VM. To normalize the value, divide it by the number of vCPU. Host - Average of the underlying Ready Queue values from all of the corresponding VMs with the same number of vCPUs.

Units: ms

■ QN VCPU:

VM - Sum of the Ready Queue usage of all of the CPU on the VM. To normalize the value, divide it by the number of vCPU. Host - Average of the underlying Ready Queue values from all of the corresponding VMs with the same number of vCPUs.

Units: ms

■ REMAINING_GC_CAPACITY:

Percentage of time not spent on garbage collection

Units: Percentage

RESPONSE_TIME:

Application response

Units: ms

■ SLA COMMODITY:

User-defined value

Units: Number

■ STORAGE ACCESS:

Number of I/O (read + write) within two discovery cycles

Units: count

■ STORAGE_ALLOCATION:

Allocated storage

Units: megabytes

■ STORAGE_AMOUNT:

Used storage

Units: megabytes

STORAGE_HEADROOM:

Count of VM that can fit for the storage in a cluster in terms of storage

Units: Count

STORAGE_LATENCY:

Acceptable latency. User can set capacity for most storage, is discovered for NetApp.

Units: ms

STORAGE_PROVISIONED:



Capacity, based on the over-provisioned value in policy

Units: megabytes

■ SWAPPING:

Memory swapping

Units: bytes/sec

■ THREADS:

Threads in use Units: Count

■ TOTAL_HEADROOM:

Min value of CPU, Mem, IO, of the headrooms

Units: Count

■ TOTAL_SESSIONS:

Total number of possible sessions

Units: Count
TRANSACTION:

Transactions for the application

Units: transactions/sec TRANSACTION LOG:

Size of the transaction log

Units: megabytes

VCPU:

CPU in use Units: MHz

VCPU_LIMIT_QUOTA:

Amount of virtual CPU limit a pod has allocated against the namespace quota

Units: millicores
VCPU_REQUEST:

Virtual CPU request allocated by a pod against the node allocatable capacity

Units: millicores

■ VCPU REQUEST QUOTA:

Amount of virtual CPU request a pod has allocated against the namespace quota

Units: millicores

■ VCPU_THROTTLING:

Throttling of container virtual CPU that could impact response time

Units: percentage

■ VIRTUAL_PROCESSORS:

Guest OS representation of the capacity of the VM

Units: VP VMEM:

Memory sold by a VM. Memory sold and bought for a container

Units: kilobytes

■ VMEM_LIMIT_QUOTA:

Total amount of virtual memory limit for all pods allocated to the namespace against the namespace quota

Units: kilobytes
VMEM_REQUEST:



Virtual memory request allocated by a pod against the node allocatable capacity

Units: kilobytes

■ VMEM_REQUEST_QUOTA:

Amount of virtual memory request a pod has allocated against the namespace quota

Units: kilobytes VSTORAGE:

Storage utilized by an entity

Units: megabytes

savings_type Enum

The different types of savings that Workload Optimization Manager actions can give.

■ MISSED_INVESTMENTS:

Actions you could have taken that would inscrease your investment to provide more resources to your applications.

■ MISSED_SAVINGS:

Actions you could have taken that could have reduced your costs.

■ REALIZED INVESTMENTS:

Actions you have taken that inscrease your investment to provide more resources to your applications.

■ REALIZED_SAVINGS:

Actions you have taken that have reduced your costs.

severity Enum

For a given action, the severity of the issue that it addresses.

- CRITICAL:
- MAJOR:
- MINOR:
- NORMAL:

terminal_state Enum

The ultimate state of an action.

- FAILED:
- SUCCEEDED:

Configuring an External TimescaleDB

You can configure External Reports to use an external deployment of TimescaleDB. To enable an external deployment, you will:

- Deploy or access the external TimescaleDB instance that you will use This is a PostgreSQL server with the TimescaleDB extension. The DB server must be deployed in a way that is accessible to your installation of Workload Optimization Manager. It can be deployed on the cloud or in an on-prem VM. The Embedded Reports feature currently supports PostgreSQL 12.x and TimescaleDB 2.0.1. For more information, see:
 - Creating an External TimescaleDB (on page 1313)
 - See the article, https://docs.timescale.com/v2.0/getting-started/installation



- Provision users, databases, and schemas on the TimescaleDB instance To provision these database objects you can manually provision or enable Workload Optimization Manager to automatically provision. For more information, see:
 - Manual Provisioning of Users and Databases (on page 1313)
 - Automatic Provisioning of Users and Databases (on page 1317)
- Edit properties in the Workload Optimization Manager cr.yaml file. Note that the location of the cr.yaml file is different, depending on whether you are configuring an OVA installation or a Kubernetes Node installation of Workload Optimization Manager.
- Optionally, enable secure connections between Workload Optimization Manager and the Timescale DB instance For information about enabling TLS/SSL for database connections, see the PostgreSQL documentation here.
 - We have verified that the steps to create a self-signed certificate, as outlined in that document, produce a server that functions properly with all components of Embedded Reporting. However, we do not recommend using self-signed certificates in production instances.

To configure External Reports to use an external deployment of TimescaleDB, you must edit the Workload Optimization Manager cr.yaml file. .

Creating an External TimescaleDB

You can create an external TimescaleDB service that you host in your environment, or you can use an existing TimescaleDB service that has been deployed on the cloud or in your enterprise by the DB Management team.

The TimescaleDB service that Workload Optimization Manager uses must satisfy these conditions:

- DeploymentWorkload Optimization ManagerThe TimescaleDB is a PostgreSQL server with the TimescaleDB extension. It
 must be deployed in a way that is accessible to your installation of Turbonomic. It can be deployed on the cloud or in an
 on-prem VM.
 - For information about installing Timescale, see the article: https://docs.timescale.com/v2.0/getting-started/installation.
- Supported VersionWorkload Optimization ManagerThe Embedded Reports feature currently supports PostgreSQL 12.x and TimescaleDB 2.0.1.
- An account with global R/W privileges on the TimescaleDB instanceWorkload Optimization ManagerThe Embedded Reports feature requires a specific set of databases to be created on the TimescaleDB. It is typical practice for an administrator to manually create the necessary databases. Alternatively, you can create a global R/W user account for the Workload Optimization Manager platform so it can create the databases automatically.
- Entry PointWorkload Optimization ManagerThe TimescaleDB must provide an entry point via DNS Name or IP Address that
 you can access from Workload Optimization Manager. You will configure this access in the Workload Optimization Manager
 cr.vaml file.

To create the TimescaleDB:

- 1. Install the DB package. Workload Optimization ManagerFor information about installing Timescale, see the articls: https://docs.timescale.com/v2.0/getting-started/installation.
- 2. Create a global R/W user account that can be used to create databases on the DB service. Workload Optimization ManagerLaunch the DB service and open a command session. Then create the global R/W account. Workload Optimization ManagerYou can alternatively set credentials to this account in the Workload Optimization Manager cr.yaml file. You can enter them as cleartext, or you can manage the credentials via Kubernetes Secrets. If you set the account credentials in cr.yaml, {{ site.data.vars.Product_Short }} can create the databases that the Embedded Reports feature needs.
- (OPTIONAL) Manually create the users and databases that Embedded Reports will use. Workload Optimization ManagerIf
 you cannot grant Workload Optimization Manager global R/W access to the DB, you must manually create the databases
 and users for Embedded Reports.

For information about manually creating databases and users, see <u>Manual Provisioning of Users and Databases (on page 1313)</u>.

For information about automatically creating databases and users via R/W access, see <u>Automatic Provisioning of Users and Databases (on page 1317)</u>.

Manual Provisioning of Users and Databases

woof



For Workload Optimization Manager to automatically create the required databases for Embedded Reports, the Workload Optimization Manager cr.yaml file must specify credentials for a user account that has global R/W access to the DB service. To do this you can Store the credentials in cleartext in the cr.yaml file.

If Automatic Provisioning is appropriate for your environment, then you can skip this section and go directly to <u>Automatic Provisioning of Users and Databases (on page 1317)</u>. That is where you will specify the global R/W account that Embedded Reports can use to access your TimescaleDB.

If Automatic Provisioning is not appropriate for your environment, then you must access the DB service with a R/W account and manually add the databases and user accounts that Embedded Reports can use. Then, after you have added the databases to your TimescaleDB, you will edit the Workload Optimization Manager cr.yaml file to make use of these databases.

Manually Provisioning Databases and Users on the TimescaleDB

The following steps will properly provision the database objects that Embedded Reporting requires. Note that these examples use default names for illustration. You can substitute your own names for databases and users. You must remember the names you use, because you must match that naming as you edit the Workload Optimization Manager cr.yaml file.

To provision the databases and users, open a command session on the TimescaleDB, and execute the following commands:

 Create two databases - one for extractor data, one for grafana data: The extractor database manages the Workload Optimization Manager data stream, and the grafana database manages data for reporting within Grafana.

Execute the following commands, where you can provide your own database names instead of extractor and grafana:

```
CREATE DATABASE extractor;
CREATE DATABASE grafana;
```

Create database users: For the extractor database, you will create a R/W user, a read-only group, and read-only user. You will also create a R/W user for the grafana database.

Execute the following commands, where you can provide your own names for instances of USER or ROLE:

```
-\- main read/write user for extractor data

CREATE USER extractor PASSWORD '<password>';

-\- group for users with read-only access to extractor data

CREATE ROLE readers_extractor_extractor;

-\- read-only user for extractor data as a member of that group

CREATE USER query PASSWORD '<password>';

GRANT CONNECT ON DATABASE extractor TO readers_extractor_extractor;

GRANT readers_extractor_extractor TO query;

-\- read-write user for grafana data

CREATE USER grafana_backend PASSWORD '<password>';
```

Create and prepare the schema for extractor data Connect to the extractor database and execute these commands, where you can provide your own name for the SCHEMA, and you grant privileges to the users and roles you created above:

```
CREATE SCHEMA extractor;
-\- read/write user has full access

GRANT ALL PRIVILEGES ON SCHEMA extractor TO extractor;
-\- all users in readers group have read-only access

GRANT USAGE on SCHEMA extractor TO readers_extractor_extractor;

GRANT SELECT ON ALL TABLES IN SCHEMA extractor TO readers_extractor_extractor;
-\- make sure readers get access to any tables added in the future

ALTER DEFAULT PRIVILEGES IN SCHEMA extractor GRANT SELECT ON TABLES TO readers_extractor_extractor;
-\- make the extractor and query users use the extractor schema by default

ALTER ROLE extractor SET search_path TO `extractor`;

ALTER ROLE query SET search_path TO `extractor`;
-\- install the timescaledb plugin into the extractor database using the extractor schema

CREATE EXTENSION timescaledb SCHEMA extractor;
```



Create and prepare the schema for grafana data Connect to the grafana database and execute these commands, where you can provide your own name for the SCHEMA, and you grant privileges to the users and roles you created above:

```
CREATE SCHEMA grafana;
-\- read/write user has full access
GRANT ALL PRIVILEGES ON SCHEMA grafana TO grafana_backend;
-\- make sure the grafana user uses the grafana schema by default
ALTER ROLE grafana_backend SET search_path TO 'grafana';
```

The above commands provision the required databases and users. Your provisioning must be complete and correct for Embedded Reports to properly collect data and display it in Grafana reports and dashboards.

Editing the CR File for Manually Created Databases

After you have provisioned the required database objects, you should edit the Workload Optimization Manager cr.yaml file to make use of these databases.

To edit the cr.yaml file:

Open the .cr file for editing.

The location of the file depends on the type of Turbonomic installation you are configuring:

■ For an OVA installation of Turbonomic:

Open a SSH terminal session on your Turbonomic instance.

Log in with the System Administrator that you set up when you installed Turbonomic:

```
    Username: turbo
```

- Password: <your_private_password>

Then edit the file:

/opt/turbonomic/kubernetes/operator/deploy/crds/charts_vlalphal_xl_cr.yaml

Turbonomic on a Kubernetes node or node cluster:

Open the following file for editing:

```
deploy/crds/charts_vlalpha1_xl_cr.yaml
```

2. Specify the endpoint for connecting to the external database.

You can use the database service DNS, or you can use an IP address.

Add the endpoint as the external Timescale DBIP property in the spec: global: section of the .cr file:

```
spec:
  global:
    externalTimescaleDBIP: <host-or-IP>
```

Specify Workload Optimization Manager access the databases you provisioned.

As you specify users and databases, be sure to match the names you used above to provision users, databases, and schema. These instructions use the default naming that you can see above.

You will specify:

- Global read-only access to the extractor database /spec/properties/global/dbs This grants the extractor and the api components read-only access to the extractor database that you provisioned above. Those components will use the guery user account.
- Read/write access to the extractor and grafana databases /spec/properties/extractor/dbs This grants the extractor component read/write access to the extractor and grafana databases that you provisioned above.
- Read/write access for Grafana to access the grafana database /spec/grafana/grafana.ini/database Edit the cr.yaml file to add the following entries:

```
spec:
  properties:
```



```
global:
    dbs:
      extractor:
        databaseName: extractor
        schemaName: extractor
        querv:
          userName: query
          password: <defaault-password>
  extractor:
    dbs:
      extractor:
        userName: extractor
        password: <default-password>
      grafana:
        scehamName: grafana
grafana:
  grafana.ini:
    database:
      name: grafana
      user: grafana_backend
      password: <default-password>
```

4. (Recommended) Block automatic provisioning by Workload Optimization Manager on the TimescaleDB.

If you have manually provisioned the Embedded Reports objects on the TimescaleDB instance, then you should disable the options for Workload Optimization Manager to automatically execute provisioning on the TimescaleDB instance.

66

NOTE: that Workload Optimization Manager cannot provision on the TimescaleDB instance if you do not specify a global user account. If you performed these configuration steps, then you should not have done so. But we still recommend that you disable the options to execute provisioning.

"

Set the following properties to false:

- shouldProvisionDatabase: spec/properties/global/dbs/postgresDefault/ shouldProvisionDatabase Determintes whether Workload Optimization Manager will attempt to provision any database in scope of the the definition.
- shouldProvisionUser: spec/properties/global/dbs/postgresDefault/shouldProvisionUser
 Determines whether Workload Optimization Manager will attempt to provision any logins in scope of the definition.
- destructiveProvisioningEnabled: spec/properties/global/dbs/postgresDefault/ destructiveProvisioningEnabled Determines whether, during its provisioning operations, Workload Optimization Manager can perform destructive operations like dropping databases, schemas or users that are found to be mis-configured. In the default installation scenario, the public schema that is created by PostgreSQL in any new database is dropped, to reduce the complexity of the overall model. Because this is considered a destructive operation, this option is true by default.

Edit the cr.yaml file to add the following properties:

```
spec:
  properties:
  global:
    dbs:
    postgresDefault:
       shouldProvisionDatabase: false
       shouldProvisionUser: false
       destructiveProvisioningEnabled: false
```



Placing these settings in the /spec/properties/global/dbs/postgresDefault block ensures that they will apply to all PostgreSQL databases and users used by any Turbonomic component. If your pre-provisioning is more selective than that, you can move the settings to more narrowly targeted property blocks like /spec/properties/extractor/dbs/grafana or /spec/properties/global/dbs/extractor.

Automatic Provisioning of Users and Databases

For Workload Optimization Manager to automatically create the required databases for Embedded Reports, the Workload Optimization Manager cr.yaml file must specify credentials for a user account that has global R/W access to the DB service. To do this you can Store the credentials in cleartext in the cr.yaml file.

If Automatic Provisioning is not appropriate for your environment, then you must access the DB service with a R/W account and manually add the databases and user accounts that Embedded Reports can use. See <u>Manual Provisioning of Users and Databases (on page 1313)</u>.

To enable an external TimescaleDB for Embedded Reports, you must edit the Workload Optimization Manager charts_v1alpha1_xl_cr.yaml file.

1. Open the .cr file for editing.

The location of the file depends on the type of Turbonomic installation you are configuring:

■ For an OVA installation of Turbonomic:

Open a SSH terminal session on your Turbonomic instance.

Log in with the System Administrator that you set up when you installed Turbonomic:

- Username: turbo
- Password: <your_private_password>

Then edit the file:

/opt/turbonomic/kubernetes/operator/deploy/crds/charts vlalphal xl cr.yaml

Turbonomic on a Kubernetes node or node cluster:

Open the following file for editing:

```
deploy/crds/charts_vlalpha1_xl_cr.yaml
```

2. Specify the endpoint for connecting to the external database.

For the connection endpoint, provide either the fully-qualified domain name of the external server or its IP address.

Add the endpoint to the spec/global/externalTimescaleDBIP property in the cr.yaml file:

```
spec:
...
global:
   externalTimescaleDBIP: <host-or-IP>
```

3. Specify the global R/W account that Workload Optimization Manager will use to log into the TimescaleDB service.

This enables Workload Optimization Manager to automatically create the databases, schemas, and uers that Embedded Reports requires.

NOTE: You should only do this if you want to enable global RW access to the TimescaleDB service in the cr.yaml file. You will specify the account credentials in clear text.

If you choose not to specify the global account here, then you must manually provision the database objects that Embedded Reports requires. See <u>Manual Provisioning of Users and Databases</u> (on page 1313).

"

To grant the access Workload Optimization Manager needs, specify the username and password for an account that has global R/W privileges on the TimescaleDB instance. Add these credentials in the /spec/properties/global/dbs/postgresDefault block of the cr.yaml file, as follows:



```
spec:
  properties:
  global:
   dbs:
    postgresDefault:
    rootUserName: <root-user>
    rootPassword: <root-password>
```

Reference: Working with YAML Files

YAML is the primary file format to create and configure resources on kubernetes, including everything to do with the Workload Optimization Manager platform. The Custom Resource YAML provides a convenient, single place to define the majority of configuration details for Workload Optimization Manager. When editing YAML files, you must be careful to respect the file syntax, including indents in the file. General rules for edits include:

- Always uses spaces, not tabs, for all indentation. Since spacing and indentations matter, and can yield an invalid result or a parameter completely skipped over, you should work with YAML files with an editor that supports using vertical lines associated with indentations to visually spot a misalignment. If your editor of choice makes this difficult, you can use the linux expand utility when you're done, to convert tabs to equivalent spaces.
- Indention uses two spaces per level.
- Be careful to keep the same indentation for all properties in a given section.
- Never use the same property name twice in the same section. Doing this will render the YAML file invalid, though you will likely not see any notification of a problem. Rather, all but one of the property definitions will be silently ignored.

Spacing matters

For the Workload Optimization Manager Custom Resource, indentation defines where parameters are applied (globally or to specific components), so ensure you line up the text appropriately. The following example shows examples of specifications that are applied at a global level ($\{ "spec" : \{ "global" : [\{ "tag" : "8.6.4" \}] \} \}$) which sets the container image tag for all instances. Then indented we see properties that are global for the remote database ($\{ "spec" : \{ "properties" : \{ "global" : [\{ "dbPort" : "6033" \}] \} \} \}$) describes a property of dbPort that would be set for remote DB connections.

Each line is indented two spaces from the higher level.

```
spec:
  global:
    repository: turbonomic
    tag: 8.6.4
  properties:
    global:
       dbPort: 6033
  kubeturbo:
    enabled: true
  aws:
    enabled: true
```

Combine properties correctly

A YAML file is read top down, and if there are different parameters that apply to the same component, they need to be combined. The following example shows a YAML where properties for the ui component of image tag and memory limit resources.

```
spec:
   global:
   repository: turbonomic
```



```
tag: 8.6.4
ui:
    image:
        tag: 8.0.5
properties:
    global:
        dbPort: 6033
kubeturbo:
    enabled: true
aws:
    enabled: true
ui:
    resources:
    limits:
        memory: 4Gi
```

This YAML will not set both image tag and memory limit resources for the ui component because they are set in two different sections. The memory limits would be applied since that is the last section to be read, and it would overwrite the first set of properties with the image tag. The following YAML will set both image tag and memory limit resources for the ui component:

```
global:
  repository: turbonomic
  tag: 8.6.4
ui:
  image:
    tag: 8.0.5
  resources:
    limits:
      memory: 4Gi
properties:
  global:
    dbPort: 6033
kubeturbo:
  enabled: true
aws:
  enabled: true
```

To avoid having the same property name twice in the same section, search for an existing instance of the key you want to add. With the complex embedded structure in many k8s resources, this can be quite challenging; however, you can use an online validator that does not accept duplicate keys to check your entire CR file (such as YAML Validator).

Finding a property

In this documentation we refer to specific properties in the CR file using a "path" expression. For example, assume the path /spec/global/repository to designate a repository property in the file. You can find the property in the file as follows:

- 1. Find a line that says spec: with no indentation at all.
- 2. Between that line and the next unindented line (not counting comments, which start with #), find a line that says global: and is at the next level of indentation.
- 3. Between that line and the next line with the same indentation, find a line that starts with repository:. That line is where the addressed property is defined.

In this example, find the repository property specified by /spec/global/repository:

```
apiVersion: charts.helm.k8s.io/vlalpha1
kind: Xl
```



```
metadata:
  name: xl-release
spec:
  properties:
    global:
    repository:  # This is NOT the correct property
    ...
# Global settings
global:
  repository:  # This is the one we're after
```

The first repository property is not at /spec/global/repository, but at /spec/properties/global/repository.