

## **Enabling PPPoE Relay Discovery and Service Selection Functionality**

#### Last Updated: December 4, 2011

The PPPoE Relay feature enables an L2TP access concentrator (LAC) to relay active discovery and service selection functionality for PPP over Ethernet (PPPoE), over a Layer 2 Tunneling Protocol (L2TP) control channel, to an L2TP network server (LNS) or tunnel switch (multihop node). The relay functionality of this feature allows the LNS or tunnel switch to advertise the services it offers to the client, thereby providing end-to-end control of services between the LNS and a PPPoE client.

- Finding Feature Information, page 1
- Prerequisites for Enabling PPPoE Relay Discovery and Service Selection Functionality, page 2
- Information About Enabling PPPoE Relay Discovery and Service Selection Functionality, page 2
- How to Enable PPPoE Relay Discovery and Service Selection Functionality, page 2
- Configuration Examples for Enabling PPPoE Relay Discovery and Service Selection Functionality, page 7
- Additional References, page 12
- Feature Information for Enabling PPPoE Relay Discovery and Service Selection Functionality, page

## **Finding Feature Information**

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.



# Prerequisites for Enabling PPPoE Relay Discovery and Service Selection Functionality

- You must understand the concepts described in the "Preparing for Broadband Access Aggregation" module.
- PPPoE sessions must be established using the procedures in the "Providing Protocol Support for Broadband Access Aggregation of PPPoE Sessions" module.
- This document assumes you understand how to configure a virtual private dialup network (VPDN) tunnel and a tunnel switch. See the Prerequisites for Enabling PPPoE Relay Discovery and Service Selection Functionality, page 2 for more information about these features.

# Information About Enabling PPPoE Relay Discovery and Service Selection Functionality

• L2TP Active Discovery Relay for PPPoE, page 2

### **L2TP Active Discovery Relay for PPPoE**

The PPPoE protocol described in RFC 2516 defines a method for active discovery and service selection of devices in the network by an LAC. A PPPoE client uses these methods to discover an access concentrator in the network, and the access concentrator uses these methods to advertise the services it offers.

The PPPoE Relay feature allows the active discovery and service selection functionality to be offered by the LNS, rather than just by the LAC. The PPPoE Relay feature implements the Network Working Group Internet-Draft titled *L2TP Active Discovery Relay for PPPoE*. The Internet-Draft describes how to relay PPPoE Active Discovery (PAD) and Service Relay Request (SRRQ) messages over an L2TP control channel (the tunnel). (See the L2TP Active Discovery Relay for PPPoE, page 2 for information on how to access Network Working Group Internet-Drafts.)

The key benefit of the PPPoE Relay feature is end-to-end control of services between the LNS and a PPPoE client.

## How to Enable PPPoE Relay Discovery and Service Selection Functionality

- Configuring the LAC and Tunnel Switch for PPPoE Relay, page 3
- Configuring the LNS (or Multihop Node) to Respond to Relayed PAD Messages, page 4
- Monitoring PPPoE Relay, page 6

## **Configuring the LAC and Tunnel Switch for PPPoE Relay**

Perform this task to configure the LAC and tunnel switch for PPPoE Relay, which configures a subscriber profile that directs PAD messages to be relayed on an L2TP tunnel. The subscriber profile also will contain an authorization key for the outgoing L2TP tunnel.

#### **SUMMARY STEPS**

- 1. enable
- 2. configure terminal
- **3. subscriber profile** *profile-name*
- 4. service relay pppoe vpdn group vpdn-group-name
- 5. exit

#### **DETAILED STEPS**

	Command or Action	Purpose
Step 1	enable	Enables privileged EXEC mode.
		Enter your password if prompted.
	Example:	
	Router> enable	
Step 2	configure terminal	Enters global configuration mode.
	Example:	
	Router# configure terminal	
Step 3	subscriber profile profile-name	Configures the subscriber profile name and enters subscriber profile configuration mode.
	Example:	profile-nameIs referenced from a PPPoE profile configured by the     bba-group pppoe global configuration command, so that all the
	Router(config)# subscriber profile profile-1	PPPoE sessions using the PPPoE profile defined by the <b>bba-group pppoe</b> command will be treated according to the defined subscriber profile.
Step 4	service relay pppoe vpdn group vpdn-group-name	Provides PPPoE relay service using a VPDN L2TP tunnel for the relay. The VPDN group name specified is used to obtain outgoing L2TP tunnel information.
	Example:	See the What to Do Next, page 4 section for the equivalent RADIUS profile entry.
	Router(config-sss-profile)# service relay pppoe vpdn group Group-A	

	Command or Action	Purpose
Step 5	exit	(Optional) Ends the configuration session and returns to privileged EXEC mode.
	Example:	
	Router(config-sss-profile)# exit	

• What to Do Next, page 4

#### What to Do Next

Configure the LNS side of the configuration by performing the tasks described in the next section.

## Configuring the LNS (or Multihop Node) to Respond to Relayed PAD Messages

On the router that responds to relayed PAD messages, perform this task to configure a PPPoE group and attach it to a VPDN group that accepts dial-in calls for L2TP. The relayed PAD messages will be passed from the VPDN L2TP tunnel and session to the PPPoE broadband group for receiving the PAD responses.

#### **SUMMARY STEPS**

- 1. enable
- 2. configure terminal
- 3. vpdn-group vpdn-group-name
- 4. accept-dialin
- 5. protocol l2tp
- **6. virtual-template** *template-number*
- 7. exit
- 8. terminate-from hostname host-name
- **9. relay pppoe bba-group** *pppoe-bba-group-name*

10. exit

#### **DETAILED STEPS**

	Command or Action	Purpose
Step 1enableEnables privileged EXEC mode.		Enables privileged EXEC mode.
		Enter your password if prompted.
	Example:	
	Router> enable	

	Command or Action	Purpose
Step 2	configure terminal	Enters global configuration mode.
	Example:	
	Router# configure terminal	
Step 3	vpdn-group vpdn-group-name	Creates a VPDN group and enters VPDN group configuration mode.
	Example:	
	Router(config)# vpdn-group Group-A	
Step 4	accept-dialin	Configures the LNS to accept tunneled PPP connections from an LAC and creates an accept-dialin VPDN subgroup.
	Example:	
	Router(config-vpdn)# accept-dialin	
Step 5	protocol l2tp	Specifies the L2TP tunneling protocol.
	Example:	
	Router(config-vpdn-req-in)# protocol 12tp	
Step 6	virtual-template template-number	Specifies which virtual template will be used to clone virtual access interfaces.
	Example:	
	Router(config-vpdn-req-in)# virtual-template 2	
Step 7	exit	Exits to VPDN group configuration mode.
	Example:	
	Router(config-vpdn-req-in)# exit	
Step 8	terminate-from hostname host-name	Specifies the LAC hostname that will be required when the VPDN tunnel is accepted.
	Example:	
	Router(config-vpdn)# terminate-from hostname LAC-1	

	Command or Action	Purpose	
		Specifies the PPPoE BBA group that will respond to the PAD messages.	
	<pre>Example: Router(config-vpdn)# relay pppoe bba-group group-2</pre>	<ul> <li>The PPPoE BBA group name is defined with the bbagroup pppoe group-name global configuration command.</li> <li>See the Configuring the LNS (or Multihop Node) to Respond to Relayed PAD Messages, page 4 section for the equivalent RADIUS profile entry.</li> </ul>	
Step 10	exit	Exits to global configuration mode.	
	Example:		
	Router(config-vpdn)# exit		

## **Monitoring PPPoE Relay**

Perform this task to monitor PPPoE Relay.

#### **SUMMARY STEPS**

- 1. enable
- 2. show pppoe session
- 3. show pppoe relay context all
- 4. clear pppoe relay context

#### **DETAILED STEPS**

#### Step 1 enable

Enables privileged EXEC mode.

• Enter your password if prompted.

#### **Example:**

Router> enable

#### Step 2 show pppoe session

Displays information about currently active PPPoE sessions.

#### Example:

## Router# show pppoe session 1 session in FORWARDED (FWDED) State 1 session total Uniq ID PPPOE RemMAC Port SID LocMAC

DE RemMAC Port VT VA State
D LocMAC VA-st

#### Step 3 show pppoe relay context all

Displays the PPPoE relay context created for relaying PAD messages.

#### **Example:**

```
Router# show pppoe relay context all
Total PPPoE relay contexts 1
UID ID Subscriber-profile State
25 18 cisco.com RELAYED
```

#### **Example:**

#### Step 4 clear pppoe relay context

This command clears the PPPoE relay context created for relaying PAD messages.

#### **Example:**

Router(config)# clear pppoe relay context

• Troubleshooting Tips, page 7

### **Troubleshooting Tips**

Use the following commands in privileged EXEC mode to help you troubleshoot the PPPoE Relay feature:

- · debug ppp forwarding
- · debug ppp negotiation
- debug pppoe events
- · debug pppoe packets
- debug vpdn l2x-events
- debug vpdn l2x-packets

# Configuration Examples for Enabling PPPoE Relay Discovery and Service Selection Functionality

- PPPoE Relay on LAC Configuration Example, page 8
- Basic LNS Configured for PPPoE Relay Example, page 8
- Tunnel Switch (or Multihop Node) Configured to Respond to PAD Messages Example, page 10
- Tunnel Switch Configured to Relay PAD Messages Example, page 11
- RADIUS Subscriber Profile Entry for the LAC Example, page 11
- RADIUS VPDN Group User Profile Entry for the LNS Example, page 12

### **PPPoE Relay on LAC Configuration Example**

The following is an example of a standard LAC configuration with the commands to enable PPPoE relay added:

```
hostname User2
username User1 password 0 field
username User2 password 0 field
username user-group password 0 field
username User5 password 0 field username User2-lac-domain password 0 field
username User1-client-domain@cisco.net password 0 field
username User3-lns-domain password 0 field
ip domain-name cisco.com
vpdn enable
vpdn source-ip 10.0.195.151
vpdn-group User2-vpdn-group-domain
request-dialin
 protocol 12tp
  domain cisco.net
 initiate-to ip 10.0.195.133
local name User2-lac-domain
interface Loopback123
ip address 10.22.2.2 255.255.255.0
interface Ethernet0/0
ip address 10.0.195.151 255.255.255.0
no keepalive
half-duplex
pppoe enable group group-1
no cdp enable
interface Virtual-Template1
mtu 1492
 ip unnumbered Loopback123
ppp authentication chap
ppp chap hostname User2-lac-domain
ip route 0.0.0.0 0.0.0.0 10.0.195.1
subscriber profile Profile1
service relay pppoe vpdn group User2-vpdn-group-domain
bba-group pppoe group-1
virtual-template 1
service profile Profile1
```

### **Basic LNS Configured for PPPoE Relay Example**

The following example shows the basic configuration for an LNS with commands added for PPPoE relay:

```
hostname User5
!
!
username User5 password 0 field
username user-group password 0 field
username User1 password 0 field
username User2 password 0 field
username User3 password 0 field
username User3-dialout password 0 cisco
```

```
username User2-dialout password 0 cisco
username abc password 0 cisco
username dial-7206a password 0 field
username mysgbpgroup password 0 cisco
username User3-lns-domain password 0 field
username User2-lac-domain password 0 field
username Userl-client-domain@cisco.net password 0 field
username User5-mh password 0 field
{\tt username} \ {\tt Userl@domain.net} \ {\tt password} \ {\tt 0} \ {\tt field}
ip subnet-zero
ip domain-name cisco.com
vpdn enable
vpdn multihop
vpdn source-ip 10.0.195.133
vpdn-group 1
request-dialin
 protocol 12tp
vpdn-group 2
! Default L2TP VPDN group
 accept-dialin
 protocol 12tp
vpdn-group User5-mh
 request-dialin
 protocol 12tp
  domain cisco.net
 initiate-to ip 10.0.195.143
local name User5-mh
vpdn-group User3-vpdn-group-domain
 accept-dialin
  protocol 12tp
  virtual-template 2
 terminate-from hostname User2-lac-domain
 local name User3-lns-domain
 relay pppoe group group-1
interface Loopback0
no ip address
interface Loopback123
 ip address 10.23.3.2 255.255.255.0
interface FastEthernet0/0
 ip address 10.0.195.133 255.255.255.0
 duplex auto
speed auto
no cdp enable
interface Virtual-Template2
mtu 1492
 ip unnumbered Loopback123
 ip access-group virtual-access3#234 in
ppp mtu adaptive
ppp authentication chap
ppp chap hostname User3-lns-domain
ip default-gateway 10.0.195.1
ip classless
ip route 0.0.0.0 0.0.0.0 10.0.195.1
bba-group pppoe group-1
```

```
virtual-template 2
```

## Tunnel Switch (or Multihop Node) Configured to Respond to PAD Messages Example

The following is an example of a standard tunnel switch configuration with the commands to enable response to PPPoE relay messages added:

```
hostname User3
username Userl password 0 rooml
username User2 password 0 room1
username User3 password 0 room1
username Userl@domain.net password 0 room1
username User3-lns-dnis password 0 cisco
username User3-lns-domain password 0 room1
username User2-lac-dnis password 0 cisco
username User2-lac-domain password 0 room1
username User5 password 0 room1
username User5-mh password 0 room1
username user-group password 0 room1
username User3-dialout password 0 cisco
username User2-dialout password 0 cisco
username abc password 0 cisco
username dial-7206a password 0 room1
username mysgbpgroup password 0 cisco
username Userl-client-domain@cisco.net password 0 room1
username User4-lns-domain password 0 room1
ip domain-name cisco.com
vpdn enable
vpdn-group User3-mh
accept-dialin
 protocol 12tp
  virtual-template 1
 terminate-from hostname User5-mh
relay pppoe bba-group group-1
interface Loopback0
 ip address 10.4.4.2 255.255.255.0
interface Loopback1
ip address 10.3.2.2 255.255.255.0
interface Ethernet2/0
 ip address 10.0.195.143 255.255.0.0
half-duplex
no cdp enable
interface Virtual-Template1
mtu 1492
 ip unnumbered Loopback0
no keepalive
ppp mtu adaptive
ppp authentication chap
ppp chap hostname User3-lns-domain
ip default-gateway 10.0.195.1
ip route 0.0.0.0 0.0.0.0 10.0.195.1
bba-group pppoe group-1
virtual-template 1
```

### **Tunnel Switch Configured to Relay PAD Messages Example**

The following partial example shows a configuration that allows the tunnel switch to relay PAD messages:

```
subscriber profile profile-1
! Configure profile for PPPoE Relay
service relay pppoe vpdn group Example1.net
vpdn-group Example2.net
! Configure L2TP tunnel for PPPoE Relay
 accept-dialin
 protocol 12tp
 terminate-from host Host1
relay pppoe bba-group group-1
vpdn-group Example1.net
! Configure L2TP tunnel for PPPoE Relay
 request-dialin
 protocol 12tp
 initiate-to ip 10.17.1.3
! PPPoE-group configured for relay
bba-group pppoe group-1
service profile profile-1
```

### RADIUS Subscriber Profile Entry for the LAC Example

The following example shows how to enter Subscriber Service Switch subscriber service attributes in a AAA RADIUS server profile.

```
profile-1 = profile-name.
.
```

Cisco:Cisco-Avpair = "sss:sss-service=relay-pppoe"

The following is an example of a typical RADIUS subscriber profile entry for an LAC:

```
cisco.com Password = "password"
   Cisco:Cisco-Avpair = "sss:sss-service=relay-pppoe",
   Tunnel-Type = L2TP,
   Tunnel-Server-Endpoint = ....,
   Tunnel-Client-Auth-ID = "client-id",
   Tunnel-Server-Auth-ID = "server-id",
   Cisco:Cisco-Avpair = "vpdn:12tp-tunnel-password=password",
   Cisco:Cisco-Avpair = "vpdn:12tp-nosession-timeout=never",
   Tunnel-Assignment-Id = assignment-id
```

### **RADIUS VPDN Group User Profile Entry for the LNS Example**

The following example shows how to enter the VPDN group attributes in a AAA RADIUS server profile.

```
profile-1 = profile-name.
.
. Cisco:Cisco-Avpair = "vpdn:relay-pppoe-bba-group=group-name"
```

The following is an example of a typical RADIUS subscriber profile entry for an LNS:

```
cisco.com Password = "password"
   Tunnel-Type = L2TP,
   Tunnel-Server-Endpoint = ....,
   Tunnel-Client-Auth-ID = "client-id",
   Tunnel-Server-Auth-ID = "server-id",
   Cisco:Cisco-Avpair = "vpdn:12tp-tunnel-password=password",
   Cisco:Cisco-Avpair = "vpdn:12tp-nosession-timeout=never",
   Cisco:Cisco-Avpair = "vpdn:relay-pppoe-bba-group=group-name"
   Tunnel-Assignment-Id = assignment-id
```

### **Additional References**

The following sections provide referenced related to the PPPoE Relay feature.

#### **Related Documents**

Related Topic	Document Title
VPDN tunnels	Cisco IOS XE Dial Technologies Configuration Guide
VPDN tunnel commands	Cisco IOS XE Dial Technologies Configuration Guide
Tunnel switching	L2TP Tunnel Switching feature module
PPPoE broadband groups	Cisco IOS XE Broadband Access Aggregation and DSL Configuration Guide
PPPoE broadband commands	Cisco IOS XE Broadband Access Aggregation and DSL Command Reference
Broadband access aggregation concepts	Cisco IOS XE Broadband Access Aggregation and DSL Configuration Guide
Tasks for preparing for broadband access aggregation	Cisco IOS XE Broadband Access Aggregation and DSL Configuration Guide

#### **Standards**

Standards	Title
None	

#### **MIBs**

ocate and download MIBs for selected forms, Cisco IOS XE software releases, and are sets, use Cisco MIB Locator found at the
owing URL:
//www.cisco.com/go/mibs

#### RFCs

RFCs	Title
RFC 2516	Method for Transmitting PPP Over Ethernet (PPPoE)
RFC 3817	<ul> <li>L2TP Active Discovery Relay for PPPoE</li> <li>Network Working Group Internet-Draft, L2TP         Active Discovery Relay for PPPoE, which can         be seen at http://tools.ietf.org/html/draft-         dasilva-l2tp-relaysvc-06</li> </ul>

#### **Technical Assistance**

Description	Link
The Cisco Support website provides extensive online resources, including documentation and tools for troubleshooting and resolving technical issues with Cisco products and technologies.	http://www.cisco.com/techsupport
To receive security and technical information about your products, you can subscribe to various services, such as the Product Alert Tool (accessed from Field Notices), the Cisco Technical Services Newsletter, and Really Simple Syndication (RSS) Feeds.	
Access to most tools on the Cisco Support website requires a Cisco.com user ID and password.	

## Feature Information for Enabling PPPoE Relay Discovery and **Service Selection Functionality**

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to <a href="https://www.cisco.com/go/cfn">www.cisco.com/go/cfn</a>. An account on Cisco.com is not required.

Table 1 Feature Information for Enabling PPPoE Relay Discovery and Service Selection Functionality

Feature Name	Releases	Feature Configuration Information
PPPoE Relay	Cisco IOS XE Release 2.1	The PPPoE Relay feature enables an L2TP access concentrator (LAC) to relay active discovery and service selection functionality for PPP over Ethernet (PPPoE), over a Layer 2 Tunneling Protocol (L2TP) control channel, to an L2TP network server (LNS) or tunnel switch (multihop node). This feature was integrated into Cisco IOS XE Release 2.1.
PPPoE Service Selection	Cisco IOS XE Release 2.4	This feature was integrated into Cisco IOS XE Release 2.4.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

© 2011 Cisco Systems, Inc. All rights reserved.