



Configuring OSPF

Last Updated: November 1, 2011

This module describes how to configure Open Shortest Path First (OSPF). OSPF is an Interior Gateway Protocol (IGP) developed by the OSPF working group of the Internet Engineering Task Force (IETF). OSPF was designed expressly for IP networks and it supports IP subnetting and tagging of externally derived routing information. OSPF also allows packet authentication and uses IP multicast when sending and receiving packets.

Cisco supports RFC 1253, *OSPF Version 2 Management Information Base*, August 1991. The OSPF MIB defines an IP routing protocol that provides management information related to OSPF and is supported by Cisco routers.

For protocol-independent features that work with OSPF, see the "Configuring IP Routing Protocol-Independent Features" module.

- [Finding Feature Information, page 1](#)
- [Information About OSPF, page 1](#)
- [How to Configure OSPF, page 9](#)
- [Configuration Examples for OSPF, page 43](#)
- [Additional References, page 62](#)
- [Feature Information for Configuring OSPF, page 64](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Information About OSPF

- [Cisco OSPF Implementation, page 2](#)



Americas Headquarters:
Cisco Systems, Inc., 170 West Tasman Drive, San Jose, CA 95134-1706 USA

- [Router Coordination for OSPF, page 2](#)
- [Route Distribution for OSPF, page 2](#)

Cisco OSPF Implementation

The Cisco implementation conforms to the OSPF Version 2 specifications detailed in the Internet RFC 2328. The list that follows outlines key features supported in the Cisco OSPF implementation:

- Stub areas--Definition of stub areas is supported.
- Route redistribution--Routes learned via any IP routing protocol can be redistributed into any other IP routing protocol. At the intradomain level, OSPF can import routes learned via Interior Gateway Routing Protocol (IGRP), Routing Information Protocol (RIP), and Intermediate System-to-Intermediate System (IS-IS). OSPF routes can also be exported into IGRP, RIP, and IS-IS. At the interdomain level, OSPF can import routes learned via Exterior Gateway Protocol (EGP) and Border Gateway Protocol (BGP). OSPF routes can be exported into BGP and EGP.
- Authentication--Plain text and message-digest algorithm 5 (MD5) authentication among neighboring routers within an area is supported.
- Routing interface parameters--Configurable parameters supported include interface output cost, retransmission interval, interface transmit delay, router priority, router "dead" and hello intervals, and authentication key.
- Virtual links--Virtual links are supported.
- Not-so-stubby area (NSSA)--RFC 3101. In Cisco IOS Release 15.1(2)S and later releases, RFC 3101 replaces RFC 1587.
- OSPF over demand circuit--RFC 1793.

Router Coordination for OSPF

OSPF typically requires coordination among many internal routers: Area Border Routers (ABRs), which are routers connected to multiple areas, and Autonomous System Boundary Routers (ASBRs). At a minimum, OSPF-based routers or access servers can be configured with all default parameter values, no authentication, and interfaces assigned to areas. If you intend to customize your environment, you must ensure coordinated configurations of all routers.

Route Distribution for OSPF

You can specify route redistribution; see the task "Redistribute Routing Information" in the Network Protocols Configuration Guide, Part 1 for information on how to configure route redistribution.

The Cisco OSPF implementation allows you to alter certain interface-specific OSPF parameters, as needed. You are not required to alter any of these parameters, but some interface parameters must be consistent across all routers in an attached network. Those parameters are controlled by the **ip ospf hello-interval**, **ip ospf dead-interval**, and **ip ospf authentication-key** interface configuration commands. Therefore, be sure that if you do configure any of these parameters, the configurations for all routers on your network have compatible values.

OSPF classifies different media into the following three types of networks by default:

- Broadcast networks (Ethernet, Token Ring, and FDDI)
- Nonbroadcast multiaccess (NBMA) networks (Switched Multimegabit Data Service (SMDS), Frame Relay, and X.25)
- Point-to-point networks (High-Level Data Link Control [HDLC] and PPP)

You can configure your network as either a broadcast or an NBMA network.

X.25 and Frame Relay provide an optional broadcast capability that can be configured in the map to allow OSPF to run as a broadcast network. Refer to the **x25 map** and **frame-relay map** command descriptions in the *Cisco IOS Wide-Area Networking Command Reference* publication for more detail.

- [OSPF Network Types, page 3](#)
- [Original LSA Behavior, page 7](#)
- [LSA Group Pacing with Multiple Timers, page 7](#)

OSPF Network Types

You have the choice of configuring your OSPF network type as either broadcast or NBMA, regardless of the default media type. Using this feature, you can configure broadcast networks as NBMA networks when, for example, you have routers in your network that do not support multicast addressing. You also can configure NBMA networks (such as X.25, Frame Relay, and SMDs) as broadcast networks. This feature saves you from needing to configure neighbors, as described in the section "[Configuring OSPF for Nonbroadcast Networks, page 17](#)" later in this module.

Configuring NBMA networks as either broadcast or nonbroadcast assumes that there are virtual circuits (VCs) from every router to every router or fully meshed network. This is not true for some cases, for example, because of cost constraints, or when you have only a partially meshed network. In these cases, you can configure the OSPF network type as a point-to-multipoint network. Routing between two routers not directly connected will go through the router that has VCs to both routers. Note that you need not configure neighbors when using this feature.

An OSPF point-to-multipoint interface is defined as a numbered point-to-point interface having one or more neighbors. It creates multiple host routes. An OSPF point-to-multipoint network has the following benefits compared to NBMA and point-to-point networks:

- Point-to-multipoint is easier to configure because it requires no configuration of neighbor commands, it consumes only one IP subnet, and it requires no designated router election.
- It costs less because it does not require a fully meshed topology.
- It is more reliable because it maintains connectivity in the event of VC failure.

On point-to-multipoint, broadcast networks, there is no need to specify neighbors. However, you can specify neighbors with the **neighbor** router configuration command, in which case you should specify a cost to that neighbor.

Before the **point-to-multipoint** keyword was added to the **ip ospf network** interface configuration command, some OSPF point-to-multipoint protocol traffic was treated as multicast traffic. Therefore, the **neighbor** router configuration command was not needed for point-to-multipoint interfaces because multicast took care of the traffic. Hello, update, and acknowledgment messages were sent using multicast. In particular, multicast hello messages discovered all neighbors dynamically.

On any point-to-multipoint interface (broadcast or not), the Cisco IOS software assumed that the cost to each neighbor was equal. The cost was configured with the **ip ospf cost** interface configuration command. In reality, the bandwidth to each neighbor is different, so the cost should differ. With this feature, you can configure a separate cost to each neighbor. This feature applies to point-to-multipoint interfaces only.

Because many routers might be attached to an OSPF network, a *designated router* is selected for the network. Special configuration parameters are needed in the designated router selection if broadcast capability is not configured.

These parameters need only be configured in those devices that are themselves eligible to become the designated router or backup designated router (in other words, routers with a nonzero router priority value).

You can specify the following neighbor parameters, as required:

- Priority for a neighboring router
- Nonbroadcast poll interval

On point-to-multipoint, nonbroadcast networks, use the **neighbor** router configuration command to identify neighbors. Assigning a cost to a neighbor is optional.

Prior to Cisco IOS Release 12.0, some customers were using point-to-multipoint on nonbroadcast media (such as classic IP over ATM), so their routers could not dynamically discover their neighbors. This feature allows the **neighbor** router configuration command to be used on point-to-multipoint interfaces.

On any point-to-multipoint interface (broadcast or not), the Cisco IOS software assumed the cost to each neighbor was equal. The cost was configured with the **ip ospf cost** interface configuration command. In reality, the bandwidth to each neighbor is different, so the cost should differ. With this feature, you can configure a separate cost to each neighbor. This feature applies to point-to-multipoint interfaces only.

Our OSPF software allows you to configure several area parameters. These area parameters, shown in the following task table, include authentication, defining stub areas, and assigning specific costs to the default summary route. Authentication allows password-based protection against unauthorized access to an area.

Stub areas are areas into which information on external routes is not sent. Instead, there is a default external route generated by the ABR, into the stub area for destinations outside the autonomous system. To take advantage of the OSPF stub area support, *default routing* must be used in the stub area. To further reduce the number of LSAs sent into a stub area, you can configure the **no-summary** keyword of the **area stub** router configuration command on the ABR to prevent it from sending summary link advertisement (LSAs Type 3) into the stub area.

The OSPF NSSA feature is described by RFC 3101. In Cisco IOS Release 15.1(2)S and later releases, RFC 3101 replaces RFC 1587. RFC 3101 is backward compatible with RFC 1587. For a detailed list of differences between them, see Appendix F of RFC 3101. NSSA support was first integrated into Cisco IOS Release 11.2. OSPF NSSA is a nonproprietary extension of the existing OSPF stub area feature.

RFC 3101 support enhances both the Type 7 autonomous-system external routing calculation and the translation of Type 7 LSAs into Type 5 LSAs. For more information, see RFC 3101.

Use NSSA to simplify administration if you are an Internet service provider (ISP) or a network administrator that must connect a central site that is using OSPF to a remote site that is using a different routing protocol.

Prior to NSSA, the connection between the corporate site border router and the remote router could not be run as an OSPF stub area because routes for the remote site could not be redistributed into the stub area, and two routing protocols needed to be maintained. A simple protocol such as RIP was usually run and handled the redistribution. With NSSA, you can extend OSPF to cover the remote connection by defining the area between the corporate router and the remote router as an NSSA.

As with OSPF stub areas, NSSA areas cannot be injected with distributed routes via Type 5 LSAs. Route redistribution into an NSSA area is possible only with a special type of LSA that is known as Type 7 that can exist only in an NSSA area. An NSSA ASBR generates the Type 7 LSA so that the routes can be redistributed, and an NSSA ABR translates the Type 7 LSA into a Type 5 LSA, which can be flooded throughout the whole OSPF routing domain. Summarization and filtering are supported during the translation.


Cisco IOS Release 15.1(2)S and later releases support RFC 3101, which allows you to configure an NSSA ABR router as a forced NSSA LSA translator. This means that the NSSA ABR router will unconditionally assume the role of LSA translator, preempting the default behavior, which would only include it among the candidates to be elected as translator.

**Note**

Even a forced translator might not translate all LSAs; translation depends on the contents of each LSA.

The figure below shows a network diagram in which OSPF Area 1 is defined as the stub area. The Enhanced Interior Gateway Routing Protocol (EIGRP) routes cannot be propagated into the OSPF domain because routing redistribution is not allowed in the stub area. However, once OSPF Area 1 is defined as an NSSA, an NSSA ASBR can inject the EIGRP routes into the OSPF NSSA by creating Type 7 LSAs.

Figure 1 **OSPF NSSA**



The redistributed routes from the RIP router will not be allowed into OSPF Area 1 because NSSA is an extension to the stub area. The stub area characteristics will still exist, including the exclusion of Type 5 LSAs.

Route summarization is the consolidation of advertised addresses. This feature causes a single summary route to be advertised to other areas by an ABR. In OSPF, an ABR will advertise networks in one area into another area. If the network numbers in an area are assigned in a way such that they are contiguous, you can configure the ABR to advertise a summary route that covers all the individual networks within the area that fall into the specified range.

When routes from other protocols are redistributed into OSPF (as described in the module "Configuring IP Routing Protocol-Independent Features"), each route is advertised individually in an external LSA. However, you can configure the Cisco IOS software to advertise a single route for all the redistributed routes that are covered by a specified network address and mask. Doing so helps decrease the size of the OSPF link-state database.

In OSPF, all areas must be connected to a backbone area. If there is a break in backbone continuity, or the backbone is purposefully partitioned, you can establish a virtual link. The two endpoints of a virtual link are ABRs. The virtual link must be configured in both routers. The configuration information in each router consists of the other virtual endpoint (the other ABR) and the nonbackbone area that the two routers have in common (called the transit area). Note that virtual links cannot be configured through stub areas.

You can force an ASBR to generate a default route into an OSPF routing domain. Whenever you specifically configure redistribution of routes into an OSPF routing domain, the router automatically

becomes an ASBR. However, an ASBR does not, by default, generate a *default route* into the OSPF routing domain.

You can configure OSPF to look up Domain Naming System (DNS) names for use in all OSPF **show EXEC** command displays. You can use this feature to more easily identify a router, because the router is displayed by name rather than by its router ID or neighbor ID.

OSPF uses the largest IP address configured on the interfaces as its router ID. If the interface associated with this IP address is ever brought down, or if the address is removed, the OSPF process must recalculate a new router ID and resend all its routing information out its interfaces.

If a loopback interface is configured with an IP address, the Cisco IOS software will use this IP address as its router ID, even if other interfaces have larger IP addresses. Because loopback interfaces never go down, greater stability in the routing table is achieved.

OSPF automatically prefers a loopback interface over any other kind, and it chooses the highest IP address among all loopback interfaces. If no loopback interfaces are present, the highest IP address in the router is chosen. You cannot tell OSPF to use any particular interface.

In Cisco IOS Release 10.3 and later releases, by default OSPF calculates the OSPF metric for an interface according to the bandwidth of the interface. For example, a 64-kbps link gets a metric of 1562, and a T1 link gets a metric of 64.

The OSPF metric is calculated as the *ref-bw* value divided by the *bandwidth* value, with the *ref-bw* value equal to 108 by default, and the *bandwidth* value determined by the **bandwidth** interface configuration command. The calculation gives FDDI a metric of 1. If you have multiple links with high bandwidth, you might want to specify a larger number to differentiate the cost on those links.

An administrative distance is a rating of the trustworthiness of a routing information source, such as an individual router or a group of routers. Numerically, an administrative distance is an integer from 0 to 255. In general, the higher the value, the lower the trust rating. An administrative distance of 255 means the routing information source cannot be trusted at all and should be ignored.

OSPF uses three different administrative distances: intra-area, interarea, and external. Routes within an area are intra-area; routes to another area are interarea; and routes from another routing domain learned via redistribution are external. The default distance for each type of route is 110.

Because simplex interfaces between two devices on an Ethernet represent only one network segment, for OSPF you must configure the sending interface to be a passive interface. This configuration prevents OSPF from sending hello packets for the sending interface. Both devices are able to see each other via the hello packet generated for the receiving interface.

You can configure the delay time between when OSPF receives a topology change and when it starts a shortest path first (SPF) calculation. You can also configure the hold time between two consecutive SPF calculations.

The OSPF on-demand circuit is an enhancement to the OSPF protocol that allows efficient operation over on-demand circuits such as ISDN, X.25 switched virtual circuits (SVCs), and dialup lines. This feature supports RFC 1793, Extending OSPF to Support Demand Circuits.

Prior to this feature, OSPF periodic hello and LSA updates would be exchanged between routers that connected the on-demand link, even when no changes occurred in the hello or LSA information.

With this feature, periodic hellos are suppressed and the periodic refreshes of LSAs are not flooded over the demand circuit. These packets bring up the link only when they are exchanged for the first time, or when a change occurs in the information they contain. This operation allows the underlying data link layer to be closed when the network topology is stable.

This feature is useful when you want to connect telecommuters or branch offices to an OSPF backbone at a central site. In this case, OSPF for on-demand circuits allows the benefits of OSPF over the entire domain,

without excess connection costs. Periodic refreshes of hello updates, LSA updates, and other protocol overhead are prevented from enabling the on-demand circuit when there is no "real" data to send.

Overhead protocols such as hellos and LSAs are transferred over the on-demand circuit only upon initial setup and when they reflect a change in the topology. This means that critical changes to the topology that require new SPF calculations are sent in order to maintain network topology integrity. Periodic refreshes that do not include changes, however, are not sent across the link.

The OSPF LSA group pacing feature allows the router to group OSPF LSAs and pace the refreshing, checksumming, and aging functions. The group pacing results in more efficient use of the router.

The router groups OSPF LSAs and paces the refreshing, checksumming, and aging functions so that sudden increases in CPU usage and network resources are avoided. This feature is most beneficial to large OSPF networks.

OSPF LSA group pacing is enabled by default. For typical customers, the default group pacing interval for refreshing, checksumming, and aging is appropriate and you need not configure this feature.

Original LSA Behavior

Each OSPF LSA has an age, which indicates whether the LSA is still valid. Once the LSA reaches the maximum age (1 hour), it is discarded. During the aging process, the originating router sends a refresh packet every 30 minutes to refresh the LSA. Refresh packets are sent to keep the LSA from expiring, whether there has been a change in the network topology or not. Checksumming is performed on all LSAs every 10 minutes. The router keeps track of LSAs it generates and LSAs it receives from other routers. The router refreshes LSAs it generated; it ages the LSAs it received from other routers.

Prior to the LSA group pacing feature, the Cisco IOS software would perform refreshing on a single timer, and checksumming and aging on another timer. In the case of refreshing, for example, the software would scan the whole database every 30 minutes, refreshing every LSA the router generated, no matter how old it was. The figure below illustrates all the LSAs being refreshed at once. This process wasted CPU resources because only a small portion of the database needed to be refreshed. A large OSPF database (several thousand LSAs) could have thousands of LSAs with different ages. Refreshing on a single timer resulted in the age of all LSAs becoming synchronized, which resulted in much CPU processing at once. Furthermore, a large number of LSAs could cause a sudden increase of network traffic, consuming a large amount of network resources in a short period of time.

Figure 2 *OSPF LSAs on a Single Timer Without Group Pacing*

All LSAs refreshed, 120 external LSAs on Ethernet need three packets



LSA Group Pacing with Multiple Timers


Configuring each LSA to have its own timer avoids excessive CPU processing and sudden network-traffic increase. To again use the example of refreshing, each LSA gets refreshed when it is 30 minutes old, independent of other LSAs. So the CPU is used only when necessary. However, LSAs being refreshed at frequent, random intervals would require many packets for the few refreshed LSAs the router must send out, which would be inefficient use of bandwidth.

Therefore, the router delays the LSA refresh function for an interval of time instead of performing it when the individual timers are reached. The accumulated LSAs constitute a group, which is then refreshed and

sent out in one packet or more. Thus, the refresh packets are paced, as are the checksumming and aging. The pacing interval is configurable; it defaults to 4 minutes, which is randomized to further avoid synchronization.

The figure below illustrates the case of refresh packets. The first timeline illustrates individual LSA timers; the second timeline illustrates individual LSA timers with group pacing.

Figure 3 OSPF LSAs on Individual Timers with Group Pacing



The group pacing interval is inversely proportional to the number of LSAs the router is refreshing, checksumming, and aging. For example, if you have approximately 10,000 LSAs, decreasing the pacing interval would benefit you. If you have a very small database (40 to 100 LSAs), increasing the pacing interval to 10 to 20 minutes might benefit you slightly.

The default value of pacing between LSA groups is 240 seconds (4 minutes). The range is from 10 seconds to 1800 seconds (30 minutes).

By default, OSPF floods new LSAs over all interfaces in the same area, except the interface on which the LSA arrives. Some redundancy is desirable, because it ensures robust flooding. However, too much redundancy can waste bandwidth and might destabilize the network due to excessive link and CPU usage in certain topologies. An example would be a fully meshed topology.

You can block OSPF flooding of LSAs two ways, depending on the type of networks:

- On broadcast, nonbroadcast, and point-to-point networks, you can block flooding over specified OSPF interfaces.
- On point-to-multipoint networks, you can block flooding to a specified neighbor.

The growth of the Internet has increased the importance of scalability in IGP's such as OSPF. By design, OSPF requires LSAs to be refreshed as they expire after 3600 seconds. Some implementations have tried to improve the flooding by reducing the frequency to refresh from 30 minutes to about 50 minutes. This solution reduces the amount of refresh traffic but requires at least one refresh before the LSA expires. The OSPF flooding reduction solution works by reducing unnecessary refreshing and flooding of already known and unchanged information. To achieve this reduction, the LSAs are now flooded with the higher bit set. The LSAs are now set as "do not age."

Cisco routers do not support LSA Type 6 Multicast OSPF (MOSPF), and they generate syslog messages if they receive such packets. If the router is receiving many MOSPF packets, you might want to configure the router to ignore the packets and thus prevent a large number of syslog messages.

The former OSPF implementation for sending update packets needed to be more efficient. Some update packets were getting lost in cases where the link was slow, a neighbor could not receive the updates quickly enough, or the router was out of buffer space. For example, packets might be dropped if either of the following topologies existed:

- A fast router was connected to a slower router over a point-to-point link.
- During flooding, several neighbors sent updates to a single router at the same time.

OSPF update packets are now automatically paced so they are not sent less than 33 milliseconds apart. Pacing is also added between resends to increase efficiency and minimize lost retransmissions. Also, you can display the LSAs waiting to be sent out an interface. The benefit of the pacing is that OSPF update and retransmission packets are sent more efficiently. There are no configuration tasks for this feature; it occurs automatically.

You can display specific statistics such as the contents of IP routing tables, caches, and databases. Information provided can be used to determine resource utilization and solve network problems. You can also display information about node reachability and discover the routing path that your device packets are taking through the network

How to Configure OSPF

To configure OSPF, perform the tasks described in the following sections. The tasks in the Enabling OSPF section are required; the tasks in the remaining sections are optional, but might be required for your application. For information about the maximum number of interfaces, see the [Restrictions](#), page 43.

- [Enabling OSPF](#), page 10
- [Configuring OSPF Interface Parameters](#), page 11
- [Configuring OSPF NSSA](#), page 13
- [Configuring OSPF over Different Physical Networks](#), page 17
- [Configuring OSPF Area Parameters](#), page 18
- [Configuring OSPF NSSA Parameters](#), page 19
- [Configuring Route Summarization Between OSPF Areas](#), page 21
- [Configuring Route Summarization When Redistributing Routes into OSPF](#), page 22
- [Establishing Virtual Links](#), page 23
- [Generating a Default Route](#), page 24
- [Configuring Lookup of DNS Names](#), page 25
- [Forcing the Router ID Choice with a Loopback Interface](#), page 26
- [Controlling Default Metrics](#), page 27
- [Changing the OSPF Administrative Distances](#), page 28
- [Configuring OSPF on Simplex Ethernet Interfaces](#), page 29
- [Configuring Route Calculation Timers](#), page 30
- [Configuring OSPF over On-Demand Circuits](#), page 31
- [Logging Neighbors Going Up or Down](#), page 32
- [Changing the LSA Group Pacing Interval](#), page 33
- [Blocking OSPF LSA Flooding](#), page 34
- [Reducing LSA Flooding](#), page 35
- [Ignoring MOSPF LSA Packets](#), page 36
- [Displaying OSPF Update Packet Pacing](#), page 37
- [Monitoring and Maintaining OSPF](#), page 39

- [Restrictions, page 43](#)

Enabling OSPF

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **router ospf** *process-id*
4. **network** *ip-address wildcard-mask area area-id*
5. **end**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 router ospf <i>process-id</i> Example: Router(config)# router ospf 109	Enables OSPF routing, which places the router in router configuration mode.
Step 4 network <i>ip-address wildcard-mask area area-id</i> Example: Router(config-router)# network 192.168.129.16 0.0.0.3 area 20	Defines an interface on which OSPF runs and defines the area ID for that interface.
Step 5 end Example: Router(config-router)# end	Exits router configuration mode and returns to privileged EXEC mode.

Configuring OSPF Interface Parameters

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **interface** *type number*
4. **ip ospf cost** *cost*
5. **ip ospf retransmit-interval** *seconds*
6. **ip ospf transmit-delay** *seconds*
7. **ip ospf priority** *number-value*
8. **ip ospf hello-interval** *seconds*
9. **ip ospf dead-interval** *seconds*
10. **ip ospf authentication-key** *key*
11. **ip ospf message-digest-key** *key md5 key*
12. **ip ospf authentication** [**message-digest** | **null**]
13. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	interface <i>type number</i> Example: Router(config)# interface GigabitEthernet 0/0	Configures an interface type and enters interface configuration mode.
Step 4	ip ospf cost <i>cost</i> Example: Router(config-if)# ip ospf cost 65	Explicitly specifies the cost of sending a packet on an OSPF interface.

Command or Action	Purpose
<p>Step 5 <code>ip ospf retransmit-interval seconds</code></p> <p>Example:</p> <pre>Router(config-if)# ip ospf retransmit-interval 1</pre>	<p>Specifies the number of seconds between link-state advertisement (LSA) retransmissions for adjacencies belonging to an OSPF interface.</p>
<p>Step 6 <code>ip ospf transmit-delay seconds</code></p> <p>Example:</p> <pre>Router(config-if)# ip ospf transmit delay 1</pre>	<p>Sets the estimated number of seconds required to send a link-state update packet on an OSPF interface.</p>
<p>Step 7 <code>ip ospf priority number-value</code></p> <p>Example:</p> <pre>Router(config-if)# ip ospf priority 1</pre>	<p>Sets priority to help determine the OSPF designated router for a network.</p>
<p>Step 8 <code>ip ospf hello-interval seconds</code></p> <p>Example:</p> <pre>Router(config-if)# ip ospf hello-interval 1</pre>	<p>Specifies the length of time between the hello packets that the Cisco IOS software sends on an OSPF interface.</p>
<p>Step 9 <code>ip ospf dead-interval seconds</code></p> <p>Example:</p> <pre>Router(config-if)# ip ospf dead-interval 1</pre>	<p>Sets the number of seconds that a device must wait before it declares a neighbor OSPF router down because it has not received a hello packet.</p>
<p>Step 10 <code>ip ospf authentication-key key</code></p> <p>Example:</p> <pre>Router(config-if)# ip ospf authentication-key 1</pre>	<p>Assigns a password to be used by neighboring OSPF routers on a network segment that is using the OSPF simple password authentication.</p>
<p>Step 11 <code>ip ospf message-digest-key key md5 key</code></p> <p>Example:</p> <pre>Router(config-if)# ip ospf message-digest-key 1 md5 23456789</pre>	<p>Enables OSPF MD5 authentication. The values for the key-id and keyarguments must match values specified for other neighbors on a network segment.</p>

Command or Action	Purpose
Step 12 <code>ip ospf authentication [message-digest null]</code> Example: <pre>Router(config-if)# ip ospf authentication message-digest</pre>	Specifies the authentication type for an interface.
Step 13 <code>end</code> Example: <pre>Router(config-if)# end</pre>	Exits interface configuration mode and returns to privileged EXEC mode.

Configuring OSPF NSSA

- [Configuring an OSPF NSSA Area and Its Parameters, page 13](#)
- [Configuring an NSSA ABR as a Forced NSSA LSA Translator, page 14](#)
- [Disabling RFC 3101 Compatibility and Enabling RFC 1587 Compatibility, page 16](#)

Configuring an OSPF NSSA Area and Its Parameters

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `router ospf process-id`
4. `redistribute protocol [process-id] {level-1 | level-1-2 | level-2} [autonomous-system-number] [metric {metric-value | transparent}] [metric-type type-value] [match {internal | external 1 | external 2}] [tag tag-value] [route-map map-tag] [subnets] [nssa-only]`
5. `network ip-address wildcard-mask area area-id`
6. `area area-id nssa [no-redistribution] [default-information-originate [metric] [metric-type]] [no-summary] [nssa-only]`
7. `end`

DETAILED STEPS

Command or Action	Purpose
Step 1 <code>enable</code> Example: <pre>Router> enable</pre>	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.

Command or Action	Purpose
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	Enters global configuration mode.
<p>Step 3 <code>router ospf process-id</code></p> <p>Example:</p> <pre>Router(config)# router ospf 10</pre>	<p>Enables OSPF routing and enters router configuration mode.</p> <ul style="list-style-type: none"> The process-id argument identifies the OSPF process. In this example the number of the routing process is 10.
<p>Step 4 <code>redistribute protocol [process-id] {level-1 level-1-2 level-2} [autonomous-system-number] [metric {metric-value transparent}] [metric-type type-value] [match {internal external 1 external 2}] [tag tag-value] [route-map map-tag] [subnets] [nssa-only]</code></p> <p>Example:</p> <pre>Router(config-router)# redistribute rip subnets</pre>	<p>Redistributes routes from one routing domain into another routing domain.</p> <ul style="list-style-type: none"> The example causes RIP subnets to be redistributed into the OSPF domain.
<p>Step 5 <code>network ip-address wildcard-mask area area-id</code></p> <p>Example:</p> <pre>Router(config-router)# network 172.19.92.0 0.0.0.255 area 1</pre>	<p>Defines the interfaces on which OSPF runs and defines the area ID for those interfaces.</p> <ul style="list-style-type: none"> The example defines 172.19.92.0/0.0.0.255 interfaces for OSPF area 1 for OSPF routing process 10.
<p>Step 6 <code>area area-id nssa [no-redistribution] [default-information-originate] [metric] [metric-type]] [no-summary] [nssa-only]</code></p> <p>Example:</p> <pre>Router(config-router)# area 1 nssa</pre>	<p>Configures an NSSA area.</p> <ul style="list-style-type: none"> In the example, area 1 is configured as an NSSA area.
<p>Step 7 <code>end</code></p> <p>Example:</p> <pre>Router(config-router)# end</pre>	Exits router configuration mode and returns to privileged EXEC mode.

Configuring an NSSA ABR as a Forced NSSA LSA Translator

**Note**

In Cisco IOS Release 15.1(2)S and later releases, the output of the **show ip ospf** command shows whether the NSSA ABR is configured as a forced translator, and whether the router is running as RFC 3101 or RFC 1587 compatible.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **router ospf** *process-id*
4. **area** *area-id* **nssa translate type7 always**
5. **end**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 router ospf <i>process-id</i> Example: Router(config)# router ospf 1	Enables OSPF routing and enters router configuration mode. <ul style="list-style-type: none"> • The <i>process-id</i> argument identifies the OSPF process.
Step 4 area <i>area-id</i> nssa translate type7 always Example: Router(config-router)# area 10 nssa translate type7 always	Configures an NSSA ABR router as a forced NSSA LSA translator. Note In Cisco IOS Release 15.1(2)S and later releases, RFC 3101 replaces RFC 1587, and you can use the always keyword in the area nssa translate command to configure an NSSA ABR router as a forced NSSA LSA translator. This command will work if RFC 3101 is disabled and RFC 1587 is being used.
Step 5 end Example: Router(config-router)# end	Exits router configuration mode and returns to privileged EXEC mode.

Disabling RFC 3101 Compatibility and Enabling RFC 1587 Compatibility



Note

In Cisco IOS Release 15.1(2)S and later releases, the output of the **show ip ospf** command will indicate if the NSSA ABR is configured as RFC 3101 or RFC 1587 compatible.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **router ospf *process-id***
4. **compatible rfc1587**
5. **end**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 router ospf <i>process-id</i> Example: Router(config)# router ospf 1	Enables OSPF routing and enters router configuration mode. <ul style="list-style-type: none"> • The process-id argument identifies the OSPF process.
Step 4 compatible rfc1587 Example: Router(config-router)# compatible rfc1587	Changes the method used to perform route selection to RFC 1587 compatibility and disables RFC 3101.

Command or Action	Purpose
Step 5 <code>end</code> Example: <code>Router(config-router)# end</code>	Exits router configuration mode and returns to privileged EXEC mode.

Configuring OSPF over Different Physical Networks

- [Configuring Point-to-Multipoint Broadcast Networks, page 17](#)
- [Configuring OSPF for Nonbroadcast Networks, page 17](#)

Configuring Point-to-Multipoint Broadcast Networks

SUMMARY STEPS

1. `ip ospf network point-to-multipoint`
2. `exit`
3. `router ospf process-id`
4. `neighbor ip-address cost number`

DETAILED STEPS

Command or Action	Purpose
Step 1 <code>ip ospf network point-to-multipoint</code>	Configures an interface as point-to-multipoint for broadcast media.
Step 2 <code>exit</code>	Enters global configuration mode.
Step 3 <code>router ospf process-id</code>	Configures an OSPF routing process and enters router configuration mode.
Step 4 <code>neighbor ip-address cost number</code>	Specifies a neighbor and assigns a cost to the neighbor. Note Repeat this step for each neighbor if you want to specify a cost. Otherwise, neighbors will assume the cost of the interface, based on the <code>ip ospf cost</code> interface configuration command.

Configuring OSPF for Nonbroadcast Networks

SUMMARY STEPS

1. `ip ospf network point-to-multipoint non-broadcast`
2. `exit`
3. `router ospf process-id`
4. `neighbor ip-address [cost number]`

DETAILED STEPS

Command or Action	Purpose
Step 1 <code>ip ospf network point-to-multipoint non-broadcast</code>	Configures an interface as point-to-multipoint for nonbroadcast media.
Step 2 <code>exit</code>	Enters global configuration mode.
Step 3 <code>router ospf process-id</code>	Configures an OSPF routing process and enters router configuration mode.
Step 4 <code>neighbor ip-address [cost number]</code>	Specifies a neighbor and assigns a cost to the neighbor. Note Repeat this step for each neighbor if you want to specify a cost. Otherwise, neighbors will assume the cost of the interface, based on the <code>ip ospf cost</code> interface configuration command.

Configuring OSPF Area Parameters

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `router ospf process-id`
4. `area area-id authentication`
5. `area area-id stub [no summary]`
6. `area area-id stub default-cost cost`
7. `end`

DETAILED STEPS

Command or Action	Purpose
Step 1 <code>enable</code> Example: Router> <code>enable</code>	Enables privileged EXEC mode. <ul style="list-style-type: none">• Enter your password if prompted.
Step 2 <code>configure terminal</code> Example: Router# <code>configure terminal</code>	Enters global configuration mode.

Command or Action	Purpose
Step 3 <code>router ospf process-id</code> Example: <code>Router(config)# router ospf 10</code>	Enables OSPF routing and enters router configuration mode.
Step 4 <code>area area-id authentication</code> Example: <code>Router(config-router)# area 10.0.0.0 authentication</code>	Enables authentication for an OSPF area.
Step 5 <code>area area-id stub [no summary]</code> Example: <code>Router(config-router)# area 10.0.0.0 stub no-summary</code>	Defines an area to be a stub area.
Step 6 <code>area area-id stub default-cost cost</code> Example: <code>Router(config-router)# area 10.0.0.0 default-cost 1</code>	Assigns a specific cost to the default summary route used for the stub area.
Step 7 <code>end</code> Example: <code>Router(config-router)# end</code>	Exits router configuration mode and returns to privileged EXEC mode.

Configuring OSPF NSSA Parameters

- [Prerequisites, page 19](#)

Prerequisites

Evaluate the following considerations before you implement this feature:

- You can set a Type 7 default route that can be used to reach external destinations. When configured, the router generates a Type 7 default into the NSSA or the NSSA ABR.
- Every router within the same area must agree that the area is NSSA; otherwise, the routers will not be able to communicate.
- [Configuring OSPF NSSA Area Parameters, page 20](#)

Configuring OSPF NSSA Area Parameters

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **router ospf** *process-id*
4. **area** *area-id* **nssa** [**no-redistribution**] [**default-information-originate**]
5. **summary-address** *prefix mask* [**not-advertise**] [**tag tag**] [**nssa-only**]
6. **end**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 router ospf <i>process-id</i> Example: Router(config)# router ospf 109	Enables OSPF routing, which places the router in router configuration mode.
Step 4 area <i>area-id</i> nssa [no-redistribution] [default-information-originate] Example: Router(config-router)# area 10 nssa no-redistribution	Defines an area to be an NSSA.
Step 5 summary-address <i>prefix mask</i> [not-advertise] [tag tag] [nssa-only] Example: Router(config-router)# summary-address 10.1.0.0 255.255.0.0 not-advertise	Controls the summarization and filtering during the translation and limits the summary to NSSA areas.

Command or Action	Purpose
Step 6 <code>end</code> Example: <code>Router(config-router)# end</code>	Exits router configuration mode and returns to privileged EXEC mode.

Configuring Route Summarization Between OSPF Areas

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `router ospf process-id`
4. `area area-id range ip-address mask [advertise | not-advertise] [cost cost]`
5. `end`

DETAILED STEPS

Command or Action	Purpose
Step 1 <code>enable</code> Example: <code>Router> enable</code>	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 <code>configure terminal</code> Example: <code>Router# configure terminal</code>	Enters global configuration mode.
Step 3 <code>router ospf process-id</code> Example: <code>Router(config)# router ospf 109</code>	Enables OSPF routing, which places the router in router configuration mode.

Command or Action	Purpose
<p>Step 4 <code>area area-id range ip-address mask [advertise not-advertise] [cost cost]</code></p> <p>Example:</p> <pre>Router(config-router)# area 0 range 192.168.110.0 255.255.0.0</pre>	Specifies an address range for which a single route will be advertised.
<p>Step 5 <code>end</code></p> <p>Example:</p> <pre>Router(config-router)# end</pre>	Exits router configuration mode and returns to privileged EXEC mode.

Configuring Route Summarization When Redistributing Routes into OSPF

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `router ospf process-id`
4. `area area-id nssa [no-redistribution] [default-information-originate]`
5. `summary-address {ip-address mask | prefix mask } [not-advertise] [tag tag]`
6. `end`

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 <code>enable</code></p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> • Enter your password if prompted.
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	Enters global configuration mode.

Command or Action	Purpose
<p>Step 3 <code>router ospf <i>process-id</i></code></p> <p>Example:</p> <pre>Router(config)# router ospf 109</pre>	<p>Enables OSPF routing, which places the router in router configuration mode.</p>
<p>Step 4 <code>area <i>area-id</i> nssa [no-redistribution] [default-information-originate]</code></p> <p>Example:</p> <pre>Router(config-router)# area 10 nssa no-redistribution</pre>	<p>Defines an area to be an NSSA.</p>
<p>Step 5 <code>summary-address {<i>ip-address mask</i> <i>prefix mask</i> } [not-advertise] [tag <i>tag</i>]</code></p> <p>Example:</p> <pre>Router(config-router)# summary-address 10.1.0.0 255.255.0.0 not-advertise</pre>	<p>Specifies an address and mask that covers redistributed routes, so only one summary route is advertised. Use the optional not-advertise keyword to filter out a set of routes the summarization and filtering during the translation and limits the summary to NSSA areas.</p>
<p>Step 6 <code>end</code></p> <p>Example:</p> <pre>Router(config-router)# end</pre>	<p>Exits router configuration mode and returns to privileged EXEC mode.</p>

Establishing Virtual Links

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `router ospf process-id`
4. `area area-id virtual-link router-id [authentication] [message-digest | null] [hello-interval seconds] [retransmit-interval seconds][transmit-delay seconds][dead-interval seconds][authentication-key key][message-digest-key key][md5 key]`
5. `end`

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 <code>enable</code></p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> Enter your password if prompted.
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 <code>router ospf process-id</code></p> <p>Example:</p> <pre>Router> router ospf 109</pre>	<p>Enables OSPF routing, which places the router in router configuration mode.</p>
<p>Step 4 <code>area area-id virtual-link router-id [authentication] [message-digest null] [hello-interval seconds][retransmit-interval seconds][transmit-delay seconds][dead-interval seconds][authentication-key key] [message-digest-key key][md5 key]</code></p> <p>Example:</p> <pre>Router(config-router)# area 10 virtual link 1</pre>	<p>Establishes a virtual link.</p>
<p>Step 5 <code>end</code></p> <p>Example:</p> <pre>Router(config-router)# end</pre>	<p>Exits router configuration mode and returns to privileged EXEC mode.</p>

Generating a Default Route

SUMMARY STEPS

- `enable`
- `configure terminal`
- `router ospf process-id`
- `default-information originate [always][metric metric-value] [metric-type type-value][route-map map-name]`
- `end`

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 <code>enable</code></p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> • Enter your password if prompted.
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 <code>router ospf <i>process-id</i></code></p> <p>Example:</p> <pre>Router(config)# router ospf 109</pre>	<p>Enables OSPF routing, which places the router in router configuration mode.</p>
<p>Step 4 <code>default-information originate [always][metric <i>metric-value</i>] [metric-type <i>type-value</i>][route-map <i>map-name</i>]</code></p> <p>Example:</p> <pre>Router(config-router)# default-information originate always</pre>	<p>Forces the ASBR to generate a default route into the OSPF routing domain.</p> <p>Note The always keyword includes the following exception when the route map is used. When a route map is used, the origination of the default route by OSPF is not bound to the existence of a default route in the routing table.</p>
<p>Step 5 <code>end</code></p> <p>Example:</p> <pre>Router(config-router)# end</pre>	<p>Exits router configuration mode and returns to privileged EXEC mode.</p>

Configuring Lookup of DNS Names

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `ip ospf name-lookup`
4. `end`

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	ip ospf name-lookup Example: Router# ip ospf name-lookup	Enables OSPF routing, which places the router in router configuration mode.
Step 4	end Example: Router(config)# end	Exits global configuration mode and returns to privileged EXEC mode.

Forcing the Router ID Choice with a Loopback Interface

SUMMARY STEPS

1. **interface loopback 0**
2. **ip address** *ip-address mask*

DETAILED STEPS

	Command or Action	Purpose
Step 1	interface loopback 0	Creates a loopback interface, which places the router in interface configuration mode.
Step 2	ip address <i>ip-address mask</i>	Assigns an IP address to this interface.

Controlling Default Metrics

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **router ospf** *process-id*
4. **auto-cost reference-bandwidth** *ref-bw*
5. **end**

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 enable</p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> • Enter your password if prompted.
<p>Step 2 configure terminal</p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 router ospf <i>process-id</i></p> <p>Example:</p> <pre>Router# router ospf 109</pre>	<p>Enables OSPF routing, which places the router in router configuration mode.</p>
<p>Step 4 auto-cost reference-bandwidth <i>ref-bw</i></p> <p>Example:</p> <pre>Router(config-router)# auto cost reference-bandwidth 101</pre>	<p>Differentiates high -bandwidth links.</p>
<p>Step 5 end</p> <p>Example:</p> <pre>Router(config-router)# end</pre>	<p>Exits router configuration mode and returns to privileged EXEC mode.</p>

Changing the OSPF Administrative Distances

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **router ospf** *process-id*
4. **distance ospf** {intra-area | inter-area | external} *dist*
5. **end**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 router ospf <i>process-id</i> Example: Router(config)# router ospf 109	Enables OSPF routing, which places the router in router configuration mode.
Step 4 distance ospf {intra-area inter-area external} <i>dist</i> Example: Router(config-router)# distance ospf external 200	Changes the OSPF distance values.
Step 5 end Example: Router(config-router)# end	Exits router configuration mode and returns to privileged EXEC mode.

Configuring OSPF on Simplex Ethernet Interfaces

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **router ospf** *process-id*
4. **passive-interface** *interface-type interface-number*
5. **end**

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 enable</p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> • Enter your password if prompted.
<p>Step 2 configure terminal</p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 router ospf <i>process-id</i></p> <p>Example:</p> <pre>Router(config)# router ospf 109</pre>	<p>Enables OSPF routing, which places the router in router configuration mode.</p>
<p>Step 4 passive-interface <i>interface-type interface-number</i></p> <p>Example:</p> <pre>Router(config-router)# passive-interface GigabitEthernet 1/0</pre>	<p>Suppresses the sending of hello packets through the specified interface.</p>
<p>Step 5 end</p> <p>Example:</p> <pre>Router(config-router)# end</pre>	<p>Exits router configuration mode and returns to privileged EXEC mode.</p>

Configuring Route Calculation Timers

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **router ospf** *process-id*
4. **timers throttle spf** *spf-start spf-hold spf-max-wait*
5. **end**

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 enable</p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> • Enter your password if prompted.
<p>Step 2 configure terminal</p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 router ospf <i>process-id</i></p> <p>Example:</p> <pre>Router(config)# router ospf 109</pre>	<p>Enables OSPF routing, which places the router in router configuration mode.</p>
<p>Step 4 timers throttle spf <i>spf-start spf-hold spf-max-wait</i></p> <p>Example:</p> <pre>Router(config-router)# timers throttle spf 5 1000 9000</pre>	<p>Configures route calculation timers.</p>
<p>Step 5 end</p> <p>Example:</p> <pre>Router(config-router)# end</pre>	<p>Exits router configuration mode and returns to privileged EXEC mode.</p>

Configuring OSPF over On-Demand Circuits

SUMMARY STEPS

1. `router ospf process-id`
2. `interface type number`
3. `ip ospf demand-circuit`

DETAILED STEPS

	Command or Action	Purpose
Step 1	<code>router ospf process-id</code>	Enables OSPF operation.
Step 2	<code>interface type number</code>	Enters interface configuration mode.
Step 3	<code>ip ospf demand-circuit</code>	Configures OSPF over an on-demand circuit.



Note

You can prevent an interface from accepting demand-circuit requests from other routers to by specifying the **ignore** keyword in the `ip ospf demand-circuit` command.

- [Prerequisites, page 31](#)

Prerequisites

Evaluate the following considerations before implementing the On-Demand Circuits feature:

- Because LSAs that include topology changes are flooded over an on-demand circuit, we recommend that you put demand circuits within OSPF stub areas or within NSSAs to isolate the demand circuits from as many topology changes as possible.
- Every router within a stub area or NSSA must have this feature loaded in order to take advantage of the on-demand circuit functionality. If this feature is deployed within a regular area, all other regular areas must also support this feature before the demand circuit functionality can take effect because Type 5 external LSAs are flooded throughout all areas.
- Hub-and-spoke network topologies that have a point-to-multipoint (P2MP) OSPF interface type on a hub might not revert to nondemand circuit mode when needed. You must simultaneously reconfigure OSPF on all interfaces on the P2MPsegment when reverting them from demand circuit mode to nondemand circuit mode.
- Do not implement this feature on a broadcast-based network topology because the overhead protocols (such as hello and LSA packets) cannot be successfully suppressed, which means the link will remain up.
- Configuring the router for an OSPF on-demand circuit with an asynchronous interface is not a supported configuration. The supported configuration is to use dialer interfaces on both ends of the circuit. For more information, refer to [Why OSPF Demand Circuit Keeps Bringing Up the Link](#).

Logging Neighbors Going Up or Down

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **router ospf** *process-id*
4. **log-adjacency-changes** [**detail**]
5. **end**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 router ospf <i>process-id</i> Example: Router(config)# router ospf 109	Enables OSPF routing, which places the router in router configuration mode.
Step 4 log-adjacency-changes [detail] Example: Router(config-router)# timers pacing lsa-group 60	Changes the group pacing of LSAs.
Step 5 end Example: Router(config-router)# end	Exits router configuration mode and returns to privileged EXEC mode.

Changing the LSA Group Pacing Interval

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **router ospf *process-id***
4. **timers pacing lsa-group *seconds***
5. **end**

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 enable</p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> • Enter your password if prompted.
<p>Step 2 configure terminal</p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 router ospf <i>process-id</i></p> <p>Example:</p> <pre>Router(config)# router ospf 109</pre>	<p>Enables OSPF routing, which places the router in router configuration mode.</p>
<p>Step 4 timers pacing lsa-group <i>seconds</i></p> <p>Example:</p> <pre>Router(config-router)# timers pacing lsa-group 60</pre>	<p>Changes the group pacing of LSAs.</p>
<p>Step 5 end</p> <p>Example:</p> <pre>Router(config-router)# end</pre>	<p>Exits router configuration mode and returns to privileged EXEC mode.</p>

Blocking OSPF LSA Flooding

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **interface** *typenumber*
4. **ip ospf database-filter all out**
5. **end**
6. **configure terminal**
7. **router ospf** *process-id*
8. **neighbor** *ip-address* **database-filter all out**
9. **end**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 interface <i>typenumber</i> Example: Router(config)# interface GigabitEthernet 0/0	Configures an interface type and enters interface configuration mode.
Step 4 ip ospf database-filter all out Example: Router(config-if)# ip ospf database-filter all out	Blocks the flooding of OSPF LSA packets to the interface.

Command or Action	Purpose
<p>Step 5 <code>end</code></p> <p>Example:</p> <pre>Router(config-interface)# end</pre>	<p>Exits interface configuration mode and returns to privileged EXEC mode.</p>
<p>Step 6 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 7 <code>router ospf <i>process-id</i></code></p> <p>Example:</p> <pre>Router(config)# router ospf 109</pre>	<p>Enables OSPF routing, which places the router in router configuration mode.</p>
<p>Step 8 <code>neighbor <i>ip-address</i> database-filter all out</code></p> <p>Example:</p> <pre>Router(config-router)# neighbor 10.2.3.4 database-filter all out</pre>	<p>On point-to-multipoint networks, this command blocks the flooding of OSPF LSA packets to the specified neighbor.</p>
<p>Step 9 <code>end</code></p> <p>Example:</p> <pre>Router(config-router)# end</pre>	<p>Exits router configuration mode and returns to privileged EXEC mode.</p>

Reducing LSA Flooding

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `interface type number`
4. `ip ospf flood-reduction`
5. `end`

DETAILED STEPS

Command or Action	Purpose
Step 1 <code>enable</code> Example: <pre>Router> enable</pre>	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 <code>configure terminal</code> Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 3 <code>interface type number</code> Example: <pre>Router(config)# interface GigabitEthernet 0/0</pre>	Configures an interface type and enters interface configuration mode.
Step 4 <code>ip ospf flood-reduction</code> Example: <pre>Router(config-if)# ip ospf flood-reduction</pre>	Suppresses the unnecessary flooding of LSAs in stable topologies.
Step 5 <code>end</code> Example: <pre>Router(config-interface)# end</pre>	Exits interface configuration mode and returns to privileged EXEC mode.

Ignoring MOSPF LSA Packets

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `router ospf process-id`
4. `ignore sla mospf`
5. `end`

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 router ospf <i>process-id</i> Example: Router(config)# router ospf 109	Enables OSPF routing, which places the router in router configuration mode.
Step 4 ignore sla mospf Example: Router(config-router)# ignore sla mospf	Prevents the router from generating syslog messages when it receives MOSPF LSA packets.
Step 5 end Example: Router(config-router)# end	Exits router configuration mode and returns to privileged EXEC mode.

Displaying OSPF Update Packet Pacing

SUMMARY STEPS

- enable
- show ip ospf flood-list *interface-type interface-number*

DETAILED STEPS

Command or Action	Purpose
Step 1 <code>enable</code> Example: <code>Router> enable</code>	Enables privileged EXEC mode. <ul style="list-style-type: none">• Enter your password if prompted.
Step 2 <code>show ip ospf flood-list interface-type interface-number</code> Example: <code>Router# show ip ospf flood-list ethernet 1</code>	Displays a list of LSAs waiting to be flooded over an interface.

Monitoring and Maintaining OSPF

SUMMARY STEPS

1. enable
2. show ip ospf [*process-id*]
3. show ip ospf border-routers
4. show ip ospf [*process-id* [*area-id*]] database
5. show ip ospf [*process-id* [*area-id*]] database [database-summary]
6. show ip ospf [*process-id* [*area-id*]] database [router][self-originate]
7. show ip ospf [*process-id* [*area-id*]] database [router][adv-router [*ip address*]]
8. show ip ospf [*process-id* [*area-id*]] database [router] [*link-state-id*]
9. show ip ospf [*process-id* [*area-id*]] database [network] [*link-state-id*]
10. show ip ospf [*process-id* [*area-id*]] database [summary] [*link-state-id*]
11. show ip ospf [*process-id* [*area-id*]] database [absr-summary][*link-state-id*]
12. show ip ospf [*process-id* [*area-id*]] database [external][*link-state-id*]
13. show ip ospf [*process-id* [*area-id*]] database [nssa-external][*link-state-id*]
14. show ip ospf [*process-id* [*area-id*]] database [opaque-link][*link-state-id*]
15. show ip ospf [*process-id* [*area-id*]] database [opaque-area][*link-state-id*]
16. show ip ospf [*process-id* [*area-id*]] database [opaque-as][*link-state-id*]
17. show ip ospf flood-list interface -type interface-number
18. show ip ospf flood-list interface -type interface-number
19. show ip ospf interface interface -type interface-number
20. show ip ospf neighbor [interface -type interface-number][neighbor-id][detail]
21. show ip ospf request-list [neighbor][interface][interface-neighbor]
22. show ip ospf retransmission-list [neighbor][interface][interface-neighbor]
23. show ip ospf process-id summary-address [neighbor][interface][interface-neighbor]
24. show ip ospf virtual-links
25. clear ip ospf [*process-id* {process | redistribution | counters [neighbor[neighbor-interface][neighbor-id]]}]

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable	Enables privileged EXEC mode.
	<p>Example:</p> <pre>Router> enable</pre>	<ul style="list-style-type: none"> • Enter your password if prompted.

Command or Action	Purpose
Step 2 <code>show ip ospf [process-id]</code> Example: <pre>Router> show ip ospf 1</pre>	Displays general information about OSPF routing processes.
Step 3 <code>show ip ospf border-routers</code> Example: <pre>Router> show ip ospf border-routers</pre>	Displays the internal OSPF routing table entries to the ABR and ASBR.
Step 4 <code>show ip ospf [process-id [area-id]] database</code> Example: <pre>Router> show ip ospf 1 1 database</pre>	Displays lists of information related to the OSPF database.
Step 5 <code>show ip ospf [process-id [area-id]] database [database-summary]</code> Example: <pre>Router> show ip ospf 1 1 database database-summary</pre>	Displays lists of information related to the OSPF database.
Step 6 <code>show ip ospf [process-id[area-id]] database [router][self-originate]</code> Example: <pre>Router> show ip ospf 1 1 database router self-originate</pre>	Displays lists of information related to the OSPF database.
Step 7 <code>show ip ospf [process-id[area-id]] database [router][adv-router [ip address]]</code> Example: <pre>Router> show ip ospf 1 1 database router adv-router</pre>	Displays lists of information related to the OSPF database.
Step 8 <code>show ip ospf [process-id [area-id]] database [router] [link-state-id]</code> Example: <pre>Router> show ip ospf 1 1 database router 172.16.240.0</pre>	Displays lists of information related to the OSPF database.

	Command or Action	Purpose
Step 9	<p>show ip ospf [<i>process-id</i> [<i>area-id</i>]] database [network] [<i>link-state-id</i>]</p> <p>Example:</p> <pre>Router> show ip ospf 1 1 database network 172.16.240.0</pre>	Displays lists of information related to the OSPF database.
Step 10	<p>show ip ospf [<i>process-id</i>[<i>area-id</i>]] database [summary] [<i>link-state-id</i>]</p> <p>Example:</p> <pre>Router> show ip ospf 1 1 database summary 172.16.240.0</pre>	Displays lists of information related to the OSPF database.
Step 11	<p>show ip ospf [<i>process-id</i> [<i>area-id</i>]] database [absr-summary][<i>link-state-id</i>]</p> <p>Example:</p> <pre>Router> show ip ospf 1 1 database absr-summary 172.16.240.0</pre>	Displays lists of information related to the OSPF database.
Step 12	<p>show ip ospf [<i>process-id</i> [<i>area-id</i>]] database [external][<i>link-state-id</i>]</p> <p>Example:</p> <pre>Router> show ip ospf 1 1 database external 172.16.240.0</pre>	Displays lists of information related to the OSPF database.
Step 13	<p>show ip ospf [<i>process-id</i> [<i>area-id</i>]] database [nssa-external][<i>link-state-id</i>]</p> <p>Example:</p> <pre>Router> show ip ospf 1 1 database nssa-external 172.16.240.0</pre>	Displays lists of information related to the OSPF database.
Step 14	<p>show ip ospf [<i>process-id</i> [<i>area-id</i>]] database [opaque-link][<i>link-state-id</i>]</p> <p>Example:</p> <pre>Router> show ip ospf 1 1 database opaque-link 172.16.240.0</pre>	Displays lists of information related to the OSPF database.
Step 15	<p>show ip ospf [<i>process-id</i> [<i>area-id</i>]] database [opaque-area][<i>link-state-id</i>]</p> <p>Example:</p> <pre>Router> show ip ospf 1 1 database opaque-area 172.16.240.0</pre>	Displays lists of information related to the OSPF database.

Command or Action	Purpose
<p>Step 16 <code>show ip ospf [process-id [area-id]] database [opaque-as][link-state-id]</code></p> <p>Example:</p> <pre>Router> show ip ospf 1 1 database opaque-as 172.16.240.0</pre>	<p>Displays lists of information related to the OSPF database.</p>
<p>Step 17 <code>show ip ospf flood-list interface -type interface-number</code></p> <p>Example:</p> <pre>Router> show ip ospf 1 1 flood-list GigabitEthernet 1/0</pre>	<p>Displays lists of information related to the OSPF database.</p>
<p>Step 18 <code>show ip ospf flood-list interface -type interface-number</code></p> <p>Example:</p> <pre>Router> show ip ospf flood-list GigabitEthernet 1/0</pre>	<p>Displays a list of LSAs waiting to be flooded over an interface (to observe OSPF packet pacing).</p>
<p>Step 19 <code>show ip ospfinterface interface -type interface-number</code></p> <p>Example:</p> <pre>Router> show ip ospf interface GigabitEthernet 0/0</pre>	<p>Displays OSPF-related interface information.</p>
<p>Step 20 <code>show ip ospf neighbor [interface -type interface-number][neighbor-id] [detail]</code></p> <p>Example:</p> <pre>Router> show ip ospf neighbor</pre>	<p>Displays OSPF neighbor information on a per-interface basis.</p>
<p>Step 21 <code>show ip ospf request-list [neighbor][interface][interface-neighbor]</code></p> <p>Example:</p> <pre>Router> show ip ospf request-list</pre>	<p>Displays a list of all LSAs requested by a router.</p>
<p>Step 22 <code>show ip ospf retransmission-list [neighbor][interface][interface-neighbor]</code></p> <p>Example:</p> <pre>Router> show ip ospf retransmission-list</pre>	<p>Displays a list of all LSAs waiting to be re-sent.</p>

Command or Action	Purpose
<p>Step 23 <code>show ip ospf process-id summary-address [neighbor][interface] [interface-neighbor]</code></p> <p>Example:</p> <pre>Router> show ip ospf summary-address</pre>	<p>Displays a list of all summary address redistribution information configured under an OSPF process.</p>
<p>Step 24 <code>show ip ospf virtual-links</code></p> <p>Example:</p> <pre>Router> show ip ospf virtual-links</pre>	<p>Displays OSPF-related virtual links information.</p>
<p>Step 25 <code>clear ip ospf [process-id {process redistribution counters [neighbor[neighbor-interface][neighbor-id]]}</code></p> <p>Example:</p> <pre>Router> clear ip ospf process</pre>	<p>Clears redistribution based on the OSPF routing process ID. If the pid option is not specified, all OSPF processes are cleared.</p>

Restrictions

On systems with a large number of interfaces, it may be possible to configure OSPF such that the number of links advertised in the router LSA causes the link state update packet to exceed the size of a "huge" Cisco IOS buffer. To resolve this problem, reduce the number of OSPF links or increase the huge buffer size by entering the `buffers huge size size` command.

A link state update packet containing a router LSA typically has a fixed overhead of 196 bytes, and an additional 12 bytes are required for each link description. With a huge buffer size of 18024 bytes there can be a maximum of 1485 link descriptions.

Because the maximum size of an IP packet is 65,535 bytes, there is still an upper bound on the number of links possible on a router.

Configuration Examples for OSPF


- [Example: OSPF Point-to-Multipoint, page 44](#)
- [Example: OSPF Point-to-Multipoint with Broadcast, page 45](#)
- [Example: OSPF Point-to-Multipoint with Nonbroadcast, page 46](#)
- [Example: Variable-Length Subnet Masks, page 47](#)
- [Example: OSPF NSSA, page 47](#)
- [Example: OSPF NSSA Area with RFC 3101 Disabled and RFC 1587 Active, page 52](#)
- [Example: OSPF Routing and Route Redistribution, page 53](#)
- [Examples: Route Map, page 58](#)
- [Example: Changing OSPF Administrative Distance, page 60](#)

- [Example: OSPF over On-Demand Routing, page 61](#)
- [Example: LSA Group Pacing, page 62](#)
- [Example: Block LSA Flooding, page 62](#)
- [Example: Ignore MOSPF LSA Packets, page 62](#)

Example: OSPF Point-to-Multipoint

In the figure below, the router named Router 1 uses data-link connection identifier (DLCI) 201 to communicate with the router named Router 2, DLCI 202 to the router named Router 4, and DLCI 203 to the router named Router 3. Router 2 uses DLCI 101 to communicate with Router 1 and DLCI 102 to the router named Router 3. Router 3 communicates with Router 2 (DLCI 401) and Router 1 (DLCI 402). Router 4 communicates with Router 1 (DLCI 301). Configuration examples follow the figure.

Figure 4 OSPF Point-to-Multipoint Example



Router 1 Configuration

```
hostname Router 1
!
interface serial 1
 ip address 10.0.0.2 255.0.0.0
 ip ospf network point-to-multipoint
 encapsulation frame-relay
 frame-relay map ip 10.0.0.1 201 broadcast
 frame-relay map ip 10.0.0.3 202 broadcast
 frame-relay map ip 10.0.0.4 203 broadcast
!
router ospf 1
 network 10.0.0.0 0.0.0.255 area 0
```

Router 2 Configuration

```
hostname Router 2
!
interface serial 0
 ip address 10.0.0.1 255.0.0.0
 ip ospf network point-to-multipoint
 encapsulation frame-relay
 frame-relay map ip 10.0.0.2 101 broadcast
 frame-relay map ip 10.0.0.4 102 broadcast
!
router ospf 1
 network 10.0.0.0 0.0.0.255 area 0
```

Router 3 Configuration

```

hostname Router 3
!
interface serial 3
 ip address 10.0.0.4 255.0.0.0
 ip ospf network point-to-multipoint
 encapsulation frame-relay
 clock rate 1000000
 frame-relay map ip 10.0.0.1 401 broadcast
 frame-relay map ip 10.0.0.2 402 broadcast
!
router ospf 1
 network 10.0.0.0 0.0.0.255 area 0

```

Router 4 Configuration

```

hostname Router 4
!
interface serial 2
 ip address 10.0.0.3 255.0.0.0
 ip ospf network point-to-multipoint
 encapsulation frame-relay
 clock rate 2000000
 frame-relay map ip 10.0.0.2 301 broadcast
!
router ospf 1
 network 10.0.0.0 0.0.0.255 area 0

```

Example: OSPF Point-to-Multipoint with Broadcast

The following example illustrates a point-to-multipoint network with broadcast:

```

interface Serial0
 ip address 10.0.1.1 255.255.255.0
 encapsulation frame-relay
 ip ospf cost 100
 ip ospf network point-to-multipoint
 frame-relay map ip 10.0.1.3 202 broadcast
 frame-relay map ip 10.0.1.4 203 broadcast
 frame-relay map ip 10.0.1.5 204 broadcast
 frame-relay local-dlci 200
!
router ospf 1
 network 10.0.1.0 0.0.0.255 area 0
 neighbor 10.0.1.5 cost 5
 neighbor 10.0.1.4 cost 10

```

The following example shows the configuration of the neighbor at 10.0.1.3:

```

interface serial 0
 ip address 10.0.1.3 255.255.255.0
 ip ospf network point-to-multipoint
 encapsulation frame-relay
 frame-relay local-dlci 301
 frame-relay map ip 10.0.1.1 300 broadcast
 no shutdown
!
router ospf 1
 network 10.0.1.0 0.0.0.255 area 0

```

The output shown for neighbors in the first configuration is as follows:

```

Router# show ip ospf neighbor
Neighbor ID      Pri   State           Dead Time   Address      Interface
172.16.1.1       1     FULL/ -         00:01:50   10.0.1.5    Serial0

```

```

172.16.1.4      1  FULL/  -      00:01:47  10.0.1.4   Serial0
172.16.1.8      1  FULL/  -      00:01:45  10.0.1.3   Serial0

```

The route information in the first configuration is as follows:

```

Router# show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, * - candidate default
       U - per-user static route, o - ODR
Gateway of last resort is not set
C     1.0.0.0/8 is directly connected, Loopback0
O     10.0.0.0/8 is variably subnetted, 4 subnets, 2 masks
O     10.0.1.3/32 [110/100] via 10.0.1.3, 00:39:08, Serial0
C     10.0.1.0/24 is directly connected, Serial0
O     10.0.1.5/32 [110/5] via 10.0.1.5, 00:39:08, Serial0
O     10.0.1.4/32 [110/10] via 10.0.1.4, 00:39:08, Serial0

```

Example: OSPF Point-to-Multipoint with Nonbroadcast

The following example illustrates a point-to-multipoint network with nonbroadcast:

```

interface Serial0
ip address 10.0.1.1 255.255.255.0
ip ospf network point-to-multipoint non-broadcast
encapsulation frame-relay
no keepalive
frame-relay local-dlci 200
frame-relay map ip 10.0.1.3 202
frame-relay map ip 10.0.1.4 203
frame-relay map ip 10.0.1.5 204
no shutdown
!
router ospf 1
network 10.0.1.0 0.0.0.255 area 0
neighbor 10.0.1.3 cost 5
neighbor 10.0.1.4 cost 10
neighbor 10.0.1.5 cost 15

```

The following example is the configuration for the router on the other side:

```

interface Serial9/2
ip address 10.0.1.3 255.255.255.0
encapsulation frame-relay
ip ospf network point-to-multipoint non-broadcast
no ip mroute-cache
no keepalive
no fair-queue
frame-relay local-dlci 301
frame-relay map ip 10.0.1.1 300
no shutdown
!
router ospf 1
network 10.0.1.0 0.0.0.255 area 0

```

The output shown for neighbors in the first configuration is as follows:

```

Router# show ip ospf neighbor
Neighbor ID      Pri   State           Dead Time   Address        Interface
172.16.1.1       1     FULL/  -         00:01:52   10.0.1.5       Serial0
172.16.1.4       1     FULL/  -         00:01:52   10.0.1.4       Serial0
172.16.1.8       1     FULL/  -         00:01:52   10.0.1.3       Serial0

```

Example: Variable-Length Subnet Masks

OSPF, static routes, and IS-IS support variable-length subnet masks (VLSMs). With VLSMs, you can use different masks for the same network number on different interfaces, which allows you to conserve IP addresses and more efficiently use available address space.

In the following example, a 30-bit subnet mask is used, leaving two bits of address space reserved for serial line host addresses. There is sufficient host address space for two host endpoints on a point-to-point serial link.

```
interface ethernet 0
 ip address 172.16.10.1 255.255.255.0
 ! 8 bits of host address space reserved for ethernet
interface serial 0
 ip address 172.16.20.1 255.255.255.252
 ! 2 bits of address space reserved for serial lines
 ! Router is configured for OSPF and assigned AS 107
router ospf 107
 ! Specifies network directly connected to the router
 network 172.16.0.0 0.0.255.255 area 0.0.0.0
```

Example: OSPF NSSA

In the following example, an OSPF stub network is configured to include OSPF Area 0 and OSPF Area 1, using five routers. OSPF Area 1 is defined as an NSSA, with Router 3 configured to be the NSSA ASBR and Router 2 configured to be the NSSA ABR. Following is the configuration output for the five routers.

Router 1

```
hostname Router1
!
interface Loopback1
 ip address 10.1.0.1 255.255.255.255
!
interface Ethernet0/0
 ip address 192.168.0.1 255.255.255.0
 ip ospf 1 area 0
 no cdp enable
!
interface Serial10/0
 description Router2 interface s11/0
 ip address 192.168.10.1 255.255.255.0
 ip ospf 1 area 1
 serial restart-delay 0
 no cdp enable
!
router ospf 1
 area 1 nssa
!
end
```

Router 2

```
hostname Router2
!
!
interface Loopback1
 ip address 10.1.0.2 255.255.255.255
!
interface Serial10/0
 description Router1 interface s11/0
 no ip address
```

```

shutdown
serial restart-delay 0
no cdp enable
!
interface Serial11/0
description Router1 interface s10/0
ip address 192.168.10.2 255.255.255.0
ip ospf 1 area 1
serial restart-delay 0
no cdp enable
!
interface Serial14/0
description Router3 interface s13/0
ip address 192.168.14.2 255.255.255.0
ip ospf 1 area 1
serial restart-delay 0
no cdp enable
!
router ospf 1
area 1 nssa
!
end

```

Router 3

```

hostname Router3
!
interface Loopback1
ip address 10.1.0.3 255.255.255.255
!
interface Ethernet3/0
ip address 192.168.3.3 255.255.255.0
no cdp enable
!
interface Serial13/0
description Router2 interface s14/0
ip address 192.168.14.3 255.255.255.0
ip ospf 1 area 1
serial restart-delay 0
no cdp enable
!
router ospf 1
log-adjacency-changes
area 1 nssa
redistribute rip subnets
!
router rip
version 2
redistribute ospf 1 metric 15
network 192.168.3.0
end

```

Router 4

```

hostname Router4
!
interface Loopback1
ip address 10.1.0.4 255.255.255.255
!
interface Ethernet3/0
ip address 192.168.3.4 255.255.255.0
no cdp enable
!
interface Ethernet4/1
ip address 192.168.41.4 255.255.255.0
!
router rip
version 2
network 192.168.3.0
network 192.168.41.0

```




```
!
end
```

Router 5

```
hostname Router5
!
interface Loopback1
 ip address 10.1.0.5 255.255.255.255
!
interface Ethernet0/0
 ip address 192.168.0.10 255.255.255.0
 ip ospf 1 area 0
 no cdp enable
!
interface Ethernet1/1
 ip address 192.168.11.10 255.255.255.0
 ip ospf 1 area 0
!
router ospf 1
!
end
```

The figure below shows the OSPF stub network with NSSA Area 1. The redistributed routes that Router 4 is propagating from the two RIP networks will be translated into Type 7 LSAs by NSSA ASBR Router 3. Router 2, which is configured to be the NSSA ABR, will translate the Type 7 LSAs back to Type 5 so that they can be flooded through the rest of the OSPF stub network within OSPF Area 0.

Figure 5 OSPF NSSA Network with NSSA ABR and ASBR Routers



When the **show ip ospf** command is entered on Router 2, the output confirms that OSPF Area 1 is an NSSA area:

```
Router2# show ip ospf
Routing Process "ospf 1" with ID 10.1.0.2
Start time: 00:00:01.392, Time elapsed: 12:03:09.480
Supports only single TOS(TOS0) routes
Supports opaque LSA
Supports Link-local Signaling (LLS)
```

```

Supports area transit capability
Router is not originating router-LSAs with maximum metric
Initial SPF schedule delay 5000 msecs
Minimum hold time between two consecutive SPF's 10000 msecs
Maximum wait time between two consecutive SPF's 10000 msecs
Incremental-SPF disabled
Minimum LSA interval 5 secs
Minimum LSA arrival 1000 msecs
LSA group pacing timer 240 secs
Interface flood pacing timer 33 msecs
Retransmission pacing timer 66 msecs
Number of external LSA 0. Checksum Sum 0x000000
Number of opaque AS LSA 0. Checksum Sum 0x000000
Number of DCbitless external and opaque AS LSA 0
Number of DoNotAge external and opaque AS LSA 0
Number of areas in this router is 1. 0 normal 0 stub 1 nssa
Number of areas transit capable is 0
External flood list length 0
  Area 1
    Number of interfaces in this area is 2
! It is a NSSA area
  Area has no authentication
  SPF algorithm last executed 11:37:58.836 ago
  SPF algorithm executed 3 times
  Area ranges are
    Number of LSA 7. Checksum Sum 0x045598
    Number of opaque link LSA 0. Checksum Sum 0x000000
    Number of DCbitless LSA 0
    Number of indication LSA 0
    Number of DoNotAge LSA 0
    Flood list length 0

```

```

Router2# show ip ospf data
      OSPF Router with ID (10.1.0.2) (Process ID 1)
        Router Link States (Area 1)
Link ID          ADV Router      Age           Seq#           Checksum Link count
10.1.0.1         10.1.0.1        1990         0x80000016    0x00CBCB 2
10.1.0.2         10.1.0.2        1753         0x80000016    0x009371 4
10.1.0.3         10.1.0.3        1903         0x80000016    0x004149 2
        Summary Net Link States (Area 1)
Link ID          ADV Router      Age           Seq#           Checksum
192.168.0.0     10.1.0.1        1990         0x80000017    0x00A605
192.168.11.0    10.1.0.1        1990         0x80000015    0x009503
        Type-7 AS External Link States (Area 1)
Link ID          ADV Router      Age           Seq#           Checksum Tag
192.168.3.0     10.1.0.3        1903         0x80000015    0x00484F 0
192.168.41.0    10.1.0.3        1903         0x80000015    0x00A4CC 0

```

Entering the **show ip ospf database data** command displays additional information about redistribution between Type 5 and Type 7 LSAs for routes that have been injected into the NSSA area and then flooded through the OSPF network.

```

Router2# show ip ospf database data
      OSPF Router with ID (10.1.0.2) (Process ID 1)
Area 1 database summary
  LSA Type      Count   Delete   Maxage
  Router        3       0        0
  Network       0       0        0
  Summary Net   2       0        0
  Summary ASBR  0       0        0
  Type-7 Ext    2       0        0
    Prefixes redistributed in Type-7  0
  Opaque Link   0       0        0
  Opaque Area   0       0        0
  Subtotal      7       0        0
Process 1 database summary
  LSA Type      Count   Delete   Maxage
  Router        3       0        0
  Network       0       0        0
  Summary Net   2       0        0
  Summary ASBR  0       0        0
  Type-7 Ext    2       0        0

```

```

Opaque Link      0      0      0
Opaque Area      0      0      0
Type-5 Ext       0      0      0
  Prefixes redistributed in Type-5  0
Opaque AS        0      0      0
Total            7      0      0

```

Entering the **show ip ospf database nssa** command also displays detailed information for Type 7 to Type 5 translations:

```

Router2# show ip ospf database nssa
      OSPF Router with ID (10.1.0.2) (Process ID 1)
      Type-7 AS External Link States (Area 1)
      Routing Bit Set on this LSA
      LS age: 1903
      Options: (No TOS-capability, Type 7/5 translation, DC)
      LS Type: AS External Link
      Link State ID: 192.168.3.0 (External Network Number )
      Advertising Router: 10.1.0.3
      LS Seq Number: 80000015
      Checksum: 0x484F
      Length: 36
      Network Mask: /24
      Metric Type: 2 (Larger than any link state path)
      TOS: 0
      Metric: 20
      Forward Address: 192.168.14.3
      External Route Tag: 0
      Routing Bit Set on this LSA
      LS age: 1903
      Options: (No TOS-capability, Type 7/5 translation, DC)
      LS Type: AS External Link
      Link State ID: 192.168.41.0 (External Network Number )
      Advertising Router: 10.1.0.3
      LS Seq Number: 80000015
      Checksum: 0xA4CC
      Length: 36
      Network Mask: /24
      Metric Type: 2 (Larger than any link state path)
      TOS: 0
      Metric: 20
      Forward Address: 192.168.14.3
      External Route Tag: 0

```

Router 3

Entering the **show ip ospf** command on Router 3 displays the information to confirm that Router 3 is acting as an ASBR and that OSPF Area 1 has been configured to be an NSSA area:

```

Router3# show ip ospf
Routing Process "ospf 1" with ID 10.1.0.3
Start time: 00:00:01.392, Time elapsed: 12:02:34.572
Supports only single TOS(TOS0) routes
Supports opaque LSA
Supports Link-local Signaling (LLS)
Supports area transit capability
!It is an autonomous system boundary router
Redistributing External Routes from,
  rip, includes subnets in redistribution
Router is not originating router-LSAs with maximum metric
Initial SPF schedule delay 5000 msecs
Minimum hold time between two consecutive SPF's 10000 msecs
Maximum wait time between two consecutive SPF's 10000 msecs
Incremental-SPF disabled
Minimum LSA interval 5 secs
Minimum LSA arrival 1000 msecs
LSA group pacing timer 240 secs
Interface flood pacing timer 33 msecs
Retransmission pacing timer 66 msecs
Number of external LSA 0. Checksum Sum 0x000000
Number of opaque AS LSA 0. Checksum Sum 0x000000

```

```

Number of DCbitless external and opaque AS LSA 0
Number of DoNotAge external and opaque AS LSA 0
Number of areas in this router is 1. 0 normal 0 stub 1 nssa
Number of areas transit capable is 0
External flood list length 0
  Area 1
    Number of interfaces in this area is 1
! It is a NSSA area
    Area has no authentication
    SPF algorithm last executed 11:38:13.368 ago
    SPF algorithm executed 3 times
    Area ranges are
    Number of LSA 7. Checksum Sum 0x050CF7
    Number of opaque link LSA 0. Checksum Sum 0x000000
    Number of DCbitless LSA 0
    Number of indication LSA 0
    Number of DoNotAge LSA 0
    Flood list length 0

```

Example: OSPF NSSA Area with RFC 3101 Disabled and RFC 1587 Active

In the following example, the output for the **show ip ospf** and **show ip ospf database nssa** commands is for an OSPF NSSA area where RFC 3101 is disabled, RFC 1587 is active, and an NSSA ABR router is configured as a forced NSSA LSA translator. As described in the "Configuring OSPF NSSA", if RFC 3101 is disabled, the forced NSSA LSA translator remains inactive. The command output demonstrates this.

```

Router# show ip ospf
Routing Process "ospf 1" with ID 10.0.2.1
Start time: 00:00:25.512, Time elapsed: 00:01:02.200
Supports only single TOS(TOS0) routes
Supports opaque LSA
Supports Link-local Signaling (LLS)
Supports area transit capability
Supports NSSA (compatible with RFC 1587)
Event-log enabled, Maximum number of events: 1000, Mode: cyclic
Router is not originating router-LSAs with maximum metric
Initial SPF schedule delay 5000 msec
Minimum hold time between two consecutive SPF's 10000 msec
Maximum wait time between two consecutive SPF's 10000 msec
Incremental-SPF disabled
Minimum LSA interval 5 secs
Minimum LSA arrival 1000 msec
LSA group pacing timer 240 secs
Interface flood pacing timer 33 msec
Retransmission pacing timer 66 msec
Number of external LSA 0. Checksum Sum 0x000000
Number of opaque AS LSA 0. Checksum Sum 0x000000
Number of DCbitless external and opaque AS LSA 0
Number of DoNotAge external and opaque AS LSA 0
Number of areas in this router is 1. 0 normal 0 stub 1 nssa
Number of areas transit capable is 0
External flood list length 0
IETF NSF helper support enabled
Cisco NSF helper support enabled
Reference bandwidth unit is 100 mbps
  Area 1
    Number of interfaces in this area is 1
    It is a NSSA area
    Configured to translate Type-7 LSAs, inactive (RFC3101 support
    disabled)
    Area has no authentication
    SPF algorithm last executed 00:00:07.160 ago
    SPF algorithm executed 3 times
    Area ranges are
    Number of LSA 3. Checksum Sum 0x0245F0
    Number of opaque link LSA 0. Checksum Sum 0x000000
    Number of DCbitless LSA 0
    Number of indication LSA 0
    Number of DoNotAge LSA 0
    Flood list length 0

```

The "Supports NSSA (compatible with RFC 1587)" line in the output indicates that RFC 1587 is active or that the OSPF NSSA area is RFC 1587 compatible.

The "Configured to translate Type-7 LSAs, inactive (RFC3101 support disabled)" line indicates that the OSPF NSSA area has an ABR router configured to act as a forced translator of Type 7 LSAs, but it is inactive because RFC 3101 is disabled.

```
Router2# show ip ospf database nssa
Router Link States (Area 1)
LS age: 28
Options: (No TOS-capability, DC)
LS Type: Router Links
Link State ID: 10.0.2.1
Advertising Router: 10.0.2.1
LS Seq Number: 80000004
Checksum: 0x5CA2
Length: 36
Area Border Router
AS Boundary Router
Unconditional NSSA translator
Number of Links: 1
Link connected to: a Stub Network
(Link ID) Network/subnet number: 192.0.2.5
(Link Data) Network Mask: 255.255.255.0
Number of MTID metrics: 0
TOS 0 Metrics: 10
```

The "Unconditional NSSA translator" line indicates that the status of the NSSA ASBR router is as a forced NSSA LSA translator.

Example: OSPF Routing and Route Redistribution

OSPF typically requires coordination among many internal routers, ABRs, and ASBRs. At a minimum, OSPF-based routers can be configured with all default parameter values, with no authentication, and with interfaces assigned to areas.

Three types of examples follow:

- The first is a simple configuration illustrating basic OSPF commands.
- The second example illustrates a configuration for an internal router, ABR, and ASBRs within a single, arbitrarily assigned, OSPF autonomous system.
- The third example illustrates a more complex configuration and the application of various tools available for controlling OSPF-based routing environments.
- [Example: Basic OSPF Configuration, page 53](#)
- [Example: Basic OSPF Configuration for Internal Router ABR and ASBRs, page 54](#)
- [Example: Complex Internal Router with ABR and ASBR, page 54](#)
- [Example: Complex OSPF Configuration for ABR, page 57](#)

Example: Basic OSPF Configuration

The following example illustrates a simple OSPF configuration that enables OSPF routing process 9000, attaches Ethernet interface 0 to area 0.0.0.0, and redistributes RIP into OSPF, and OSPF into RIP:

```
interface ethernet 0
 ip address 10.93.1.1 255.255.255.0
 ip ospf cost 1
!
interface ethernet 1
 ip address 10.94.1.1 255.255.255.0
```

```

!
router ospf 9000
 network 10.93.0.0 0.0.255.255 area 0.0.0.0
 redistribute rip metric 1 subnets
!
router rip
 network 10.94.0.0
 redistribute ospf 9000
 default-metric 1

```

Example: Basic OSPF Configuration for Internal Router ABR and ASBRs

The following example illustrates the assignment of four area IDs to four IP address ranges. In the example, OSPF routing process 109 is initialized, and four OSPF areas are defined: 10.9.50.0, 2, 3, and 0. Areas 10.9.50.0, 2, and 3 mask specific address ranges, and area 0 enables OSPF for *all other* networks.

```

router ospf 109
 network 192.168.10.0 0.0.0.255 area 10.9.50.0
 network 192.168.20.0 0.0.255.255 area 2
 network 192.168.30.0 0.0.0.255 area 3
 network 192.168.40.0 255.255.255.255 area 0
!
! Interface Ethernet0 is in area 10.9.50.0:
interface ethernet 0
 ip address 192.168.10.5 255.255.255.0
!
! Interface Ethernet1 is in area 2:
interface ethernet 1
 ip address 192.168.20.5 255.255.255.0
!
! Interface Ethernet2 is in area 2:
interface ethernet 2
 ip address 192.168.20.7 255.255.255.0
!
! Interface Ethernet3 is in area 3:
interface ethernet 3
 ip address 192.169.30.5 255.255.255.0
!
! Interface Ethernet4 is in area 0:
interface ethernet 4
 ip address 192.168.40.1 255.255.255.0
!
! Interface Ethernet5 is in area 0:
interface ethernet 5
 ip address 192.168.40.12 255.255.0.0

```

Each **network area** router configuration command is evaluated sequentially, so the order of these commands in the configuration is important. The Cisco IOS software sequentially evaluates the address/wildcard-mask pair for each interface. See the **network area** command in the *Cisco IOS IP Routing: OSPF Command Reference* for more information.

Consider the first **network area** command. Area ID 10.9.50.0 is configured for the interface on which subnet 192.168.10.0 is located. Assume that a match is determined for Ethernet interface 0. Ethernet interface 0 is attached to area 10.9.50.0 only.


The second **network area** command is evaluated next. For area 2, the same process is then applied to all interfaces (except Ethernet interface 0). Assume that a match is determined for interface Ethernet 1. OSPF is then enabled for that interface and Ethernet interface 1 is attached to area 2.

This process of attaching interfaces to OSPF areas continues for all **network area** commands. Note that the last **network area** command in this example is a special case. With this command, all available interfaces (not explicitly attached to another area) are attached to area 0.

Example: Complex Internal Router with ABR and ASBR

The following example outlines a configuration for several routers within a single OSPF autonomous system. The figure below provides a general network map that illustrates this example configuration.

Figure 6 Sample OSPF Autonomous System Network Map



In this configuration, five routers are configured with OSPF:

- Router A and Router B are both internal routers within area 1.
- Router C is an OSPF ABR. Note that for Router C, Area 1 is assigned to E3 and area 0 is assigned to S0.
- Router D is an internal router in area 0 (backbone area). In this case, both **network** router configuration commands specify the same area (area 0, or the backbone area).
- Router E is an OSPF ASBR. Note that BGP routes are redistributed into OSPF and that these routes are advertised by OSPF.

**Note**

You do not need to include definitions of all areas in an OSPF autonomous system in the configuration of all routers in the autonomous system. Only the *directly* connected areas must be defined. In the example that follows, routes in area 0 are learned by the routers in area 1 (Router A and Router B) when the ABR (Router C) injects summary LSAs into area 1.

The OSPF domain in BGP autonomous system 109 is connected to the outside world via the BGP link to the external peer at IP address 10.0.0.6. Example configurations follow.

Following is the sample configuration for the general network map shown in the figure above.

Router A Configuration--Internal Router

```
interface ethernet 1
 ip address 192.168.1.1 255.255.255.0
router ospf 1
 network 192.168.0.0 0.0.255.255 area 1
```

Router B Configuration--Internal Router

```
interface ethernet 2
 ip address 192.168.1.2 255.255.255.0
router ospf 202
 network 192.168.0.0 0.0.255.255 area 1
```

Router C Configuration--ABR

```
interface ethernet 3
 ip address 192.168.1.3 255.255.255.0
interface serial 0
 ip address 192.168.2.3 255.255.255.0
router ospf 999
 network 192.168.1.0 0.0.0.255 area 1
 network 192.168.2.0 0.0.0.255 area 0
```

Router D Configuration--Internal Router

```
interface ethernet 4
 ip address 10.0.0.4 255.0.0.0
interface serial 1
 ip address 192.168.2.4 255.255.255.0
router ospf 50
 network 192.168.2.0 0.0.0.255 area 0
 network 10.0.0.0 0.255.255.255 area 0
```

Router E Configuration--ASBR

```
interface ethernet 5
 ip address 10.0.0.5 255.0.0.0
interface serial 2
 ip address 172.16.1.5 255.255.255.0
router ospf 65001
 network 10.0.0.0 0.255.255.255 area 0
 redistribute bgp 109 metric 1 metric-type 1
router bgp 109
 network 192.168.0.0
 network 10.0.0.0
 neighbor 172.16.1.6 remote-as 110
```



Example: Complex OSPF Configuration for ABR

The following example configuration accomplishes several tasks in setting up an ABR. These tasks can be split into two general categories:

- Basic OSPF configuration
- Route redistribution

The specific tasks outlined in this configuration are detailed briefly in the following descriptions. The figure below illustrates the network address ranges and area assignments for the interfaces.

Figure 7 Interface and Area Specifications for OSPF Example Configuration



The basic configuration tasks in this example are as follows:

- Configure address ranges for Ethernet interface 0 through Ethernet interface 3.
- Enable OSPF on each interface.
- Set up an OSPF authentication password for each area and network.
- Assign link-state metrics and other OSPF interface configuration options.
- Create a *stub area* with area ID 36.0.0.0. (Note that the **authentication** and **stub** options of the **area** router configuration command are specified with separate **area** command entries, but can be merged into a single **area** command.)
- Specify the backbone area (area 0).

Configuration tasks associated with redistribution are as follows:

- Redistribute IGRP and RIP into OSPF with various options set (including including **metric-type**, **metric**, **tag**, and **subnet**).
- Redistribute IGRP and OSPF into RIP.

The following is an example OSPF configuration:

```
interface ethernet 0
 ip address 192.42.110.201 255.255.255.0
 ip ospf authentication-key abcdefgh
 ip ospf cost 10
!
```

```

interface ethernet 1
 ip address 172.19.251.202 255.255.255.0
 ip ospf authentication-key ijklmnop
 ip ospf cost 20
 ip ospf retransmit-interval 10
 ip ospf transmit-delay 2
 ip ospf priority 4
!
interface ethernet 2
 ip address 172.19.254.2 255.255.255.0
 ip ospf authentication-key abcdefgh
 ip ospf cost 10
!
interface ethernet 3
 ip address 10.56.0.0 255.255.0.0
 ip ospf authentication-key ijklmnop
 ip ospf cost 20
 ip ospf dead-interval 80

```

In the following configuration OSPF is on network 172.16.0.0:

```

router ospf 201
 network 10.10.0.0 0.255.255.255 area 10.10.0.0
 network 192.42.110.0 0.0.0.255 area 192.42.110.0
 network 172.16.0.0 0.0.255.255 area 0
 area 0 authentication
 area 10.10.0.0 stub
 area 10.10.0.0 authentication
 area 10.10.0.0 default-cost 20
 area 192.42.110.0 authentication
 area 10.10.0.0 range 10.10.0.0 255.0.0.0
 area 192.42.110.0 range 192.42.110.0 255.255.255.0
 area 0 range 172.16.251.0 255.255.255.0
 area 0 range 172.16.254.0 255.255.255.0
 redistribute igrp 200 metric-type 2 metric 1 tag 200 subnets
 redistribute rip metric-type 2 metric 1 tag 200

```

In the following configuration, IGRP autonomous system 200 is on 192.0.2.1:

```

router igrp 200
 network 172.31.0.0
!
! RIP for 192.168.110
!
router rip
 network 192.168.110.0
 redistribute igrp 200 metric 1
 redistribute ospf 201 metric 1

```

Examples: Route Map

The examples in this section illustrate the use of redistribution, with and without route maps. Examples from both the IP and Connectionless Network Service (CLNS) routing protocols are given.

The following example redistributes all OSPF routes into IGRP:

```

router igrp 109
 redistribute ospf 110

```

The following example redistributes RIP routes with a hop count equal to 1 into OSPF. These routes will be redistributed into OSPF as external LSAs with a metric of 5, a metric type of Type 1, and a tag equal to 1.

```

router ospf 109
 redistribute rip route-map rip-to-ospf
!
route-map rip-to-ospf permit
 match metric 1
 set metric 5

```

```

set metric-type type1
set tag 1

```

The following example redistributes OSPF learned routes with tag 7 as a RIP metric of 15:

```

router rip
 redistribute ospf 109 route-map 5
!
route-map 5 permit
 match tag 7
 set metric 15

```

The following example redistributes OSPF intra-area and interarea routes with next hop routers on serial interface 0 into BGP with an INTER_AS metric of 5:

```

router bgp 109
 redistribute ospf 109 route-map 10
!
route-map 10 permit
 match route-type internal
 match interface serial 0
 set metric 5

```

The following example redistributes two types of routes into the integrated IS-IS routing table (supporting both IP and CLNS). The first type is OSPF external IP routes with tag 5; these routes are inserted into Level 2 IS-IS link state packets (LSPs) with a metric of 5. The second type is ISO-IGRP derived CLNS prefix routes that match CLNS access list 2000; these routes will be redistributed into IS-IS as Level 2 LSPs with a metric of 30.

```

router isis
 redistribute ospf 109 route-map 2
 redistribute iso-igrp nsfnet route-map 3
!
route-map 2 permit
 match route-type external
 match tag 5
 set metric 5
 set level level-2
!
route-map 3 permit
 match address 2000
 set metric 30

```

With the following configuration, OSPF external routes with tags 1, 2, 3, and 5 are redistributed into RIP with metrics of 1, 1, 5, and 5, respectively. The OSPF routes with a tag of 4 are not redistributed.

```

router rip
 redistribute ospf 109 route-map 1
!
route-map 1 permit
 match tag 1 2
 set metric 1
!
route-map 1 permit
 match tag 3
 set metric 5
!
route-map 1 deny
 match tag 4
!
route map 1 permit
 match tag 5
 set metric 5

```

In the following configuration, a RIP learned route for network 160.89.0.0 and an ISO-IGRP learned route with prefix 49.0001.0002 will be redistributed into an IS-IS Level 2 LSP with a metric of 5:

```

router isis

```

```

redistribute rip route-map 1
redistribute iso-igrp remote route-map 1
!
route-map 1 permit
match ip address 1
match cpls address 2
set metric 5
set level level-2
!
access-list 1 permit 192.168.0.0 0.0.255.255
cpls filter-set 2 permit 49.0001.0002...

```

The following configuration example illustrates how a route map is referenced by the **default-information** router configuration command. This type of reference is called *conditional default origination*. OSPF will originate the default route (network 0.0.0.0) with a Type 2 metric of 5 if 140.222.0.0 is in the routing table.

**Note**

Only routes external to the OSPF process can be used for tracking, such as non-OSPF routes or OSPF routes from a separate OSPF process.

```


route-map ospf-default permit
match ip address 1
set metric 5
set metric-type type-2
!
access-list 1 permit 172.16.0.0 0.0.255.255
!
router ospf 109
default-information originate route-map ospf-default

```

Example: Changing OSPF Administrative Distance

The following configuration changes the external distance to 200, making it less trustworthy. The figure below illustrates the example.

Figure 8 OSPF Administrative Distance



Router A Configuration

```
router ospf 1
 redistribute ospf 2 subnet
 distance ospf external 200
!
router ospf 2
 redistribute ospf 1 subnet
 distance ospf external 200
```


Router B Configuration

```
router ospf 1
 redistribute ospf 2 subnet
 distance ospf external 200
!
router ospf 2
 redistribute ospf 1 subnet
 distance ospf external 200
```

Example: OSPF over On-Demand Routing

The following configuration allows OSPF over an on-demand circuit, as shown in the figure below. Note that the on-demand circuit is defined on one side only (BRI 0 on Router A); it is not required to be configured on both sides.

Figure 9 *OSPF over On-Demand Circuit*

**Router A Configuration**

```
username RouterB password 7 060C1A2F47
 isdn switch-type basic-5ess
 ip routing
!
interface TokenRing0
 ip address 192.168.50.5 255.255.255.0
 no shutdown
!
interface BRI0
 no cdp enable
 description connected PBX 1485
 ip address 192.168.45.30 255.255.255.0
 encapsulation ppp
 ip ospf demand-circuit
 dialer map ip 140.10.10.6 name RouterB broadcast 61484
 dialer-group 1
 ppp authentication chap
 no shutdown
!
router ospf 100
 network 192.168.45.0 0.0.0.255 area 0
 network 192.168.45.50 0.0.0.255 area 0
!
dialer-list 1 protocol ip permit
```

Router B Configuration

```

username RouterA password 7 04511E0804
isdn switch-type basic-5ess
ip routing
!
interface Ethernet0
 ip address 192.168.50.16 255.255.255.0
 no shutdown
!
interface BRI0
 no cdp enable
 description connected PBX 1484
 ip address 192.168.45.17 255.255.255.0
 encapsulation ppp
 dialer map ip 192.168.45.19 name RouterA broadcast 61485
 dialer-group 1
 ppp authentication chap
 no shutdown
!
router ospf 100
 network 192.168.45.0 0.0.0.255 area 0
 network 192.168.45.50 0.0.0.255 area 0
!
dialer-list 1 protocol ip permit

```

Example: LSA Group Pacing

The following example changes the OSPF pacing between LSA groups to 60 seconds:

```

router ospf
 timers pacing lsa-group 60

```

Example: Block LSA Flooding

The following example prevents flooding of OSPF LSAs to broadcast, nonbroadcast, or point-to-point networks reachable through Ethernet interface 0:

```

interface ethernet 0
 ip ospf database-filter all out

```

The following example prevents flooding of OSPF LSAs to point-to-multipoint networks to the neighbor at IP address 10.10.10.45:

```

router ospf 109
 neighbor 10.10.10.45 database-filter all out

```

Example: Ignore MOSPF LSA Packets

The following example configures the router to suppress the sending of syslog messages when it receives MOSPF packets:

```

router ospf 109
 ignore lsa mospf

```

Additional References

Related Documents

Related Topic	Document Title
Cisco IOS commands	Cisco IOS Master Commands List, All Releases
OSPF commands	<i>Cisco IOS IP Routing: OSPF Command Reference</i>
Protocol-independent features that work with OSPF	"Configuring IP Routing Protocol-Independent Features"

Standards

Standard	Title
No new or modified standards are supported, and support for existing standards has not been modified.	--

MIBs

MIB	MIBs Link
No new or modified MIBs are supported, and support for existing MIBs has not been modified.	To locate and download MIBs for selected platforms, Cisco software releases, and feature sets, use Cisco MIB Locator found at the following URL: http://www.cisco.com/go/mibs

RFCs

RFC	Title
RFC 1253	OSPF Version 2 Management Information Base , August 1991.
RFC 1587	The OSPF NSSA Option , March 1994
RFC 1793	Extending OSPF to Support Demand Circuits , April 1995
RFC 2328	OSPF Version 2 , April 1998
RFC 3101	The OSPF NSSA Option , January 2003

Technical Assistance

Description	Link
The Cisco Support and Documentation website provides online resources to download documentation, software, and tools. Use these resources to install and configure the software and to troubleshoot and resolve technical issues with Cisco products and technologies. Access to most tools on the Cisco Support and Documentation website requires a Cisco.com user ID and password.	http://www.cisco.com/cisco/web/support/index.html

Feature Information for Configuring OSPF

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Table 1 *Feature Information for OSPF*

Feature Name	Releases	Feature Information
OSPF	11.2.1	OSPF is an IGP developed by the OSPF working group of the IETF. Designed expressly for IP networks, OSPF supports IP subnetting and tagging of externally derived routing information. OSPF also allows packet authentication and uses IP multicast when sending and receiving packets.
OSPF Flooding Reduction	12.1(2)T	The OSPF flooding reduction solution works by reducing unnecessary refreshing and flooding of already known and unchanged information. This feature is documented in the following section:

Feature Name	Releases	Feature Information
OSPF Not-So-Stubby Areas	11.2.1	OSPF NSSA is a nonproprietary extension of the existing OSPF stub area feature. This feature is documented in the following sections:
OSPF Packet Pacing	12.0(1)T	OSPF update packets are automatically paced so they are not sent less than 33 milliseconds apart. This feature is documented in the following section:
OSPF Support for NSSA RFC 3101	15.1(2)S 15.0(1)SY 15.2(2)T	This feature adds support for the OSPF NSSA specification described by RFC 3101. RFC3101 replaced RFC 1587 and is backward compatible with RFC1587. The following commands were introduced or modified: area nssa translate, compatible rfc1587.
OSPF - Demand Circuit Disable	15.0(1)SY	The ignore keyword was added to the ip ospf demand-circuit command, allowing you to prevent an interface from accepting demand-circuit requests from other routers.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

© 2011 Cisco Systems, Inc. All rights reserved.