



Access Remote WAE Automation Server

From the WAE Design GUI, you can open plan files residing on a remote WAE Automation server to make modifications before deploying LSPs or saving the plan file back to the server.

To work with files being deployed to the network or saved to the WAE Automation server, you need to understand these two terms.

- The *working plan file* represents the current state of the network.
- A *staging area* is an area in which you can work on plan files without deploying them. There is only one working plan file area, but there can be multiple staging areas.

Prerequisites

For information on deployment prerequisites, see the *WAE Platform Configuration Guide*.

- You must know the username and password of the WAE Automation server, or its authentication must be disabled.
- If using the staging area, it must already exist on the server, and you must know the stage ID.
- The WAE Automation server must be configured for the type of deployment you are using, and there are further prerequisites for this server.

Open Remote Plan File

-
- Step 1** Select the File->Open from->WAE menu.
 - Step 2** Identify the remote server using the steps outlined in the [Identify Server Location](#) section.
 - Step 3** If opening a plan file from a staging area, enter the stage ID. If left blank, the working plan file is opened.
-

Deploy to the Network

You have two options for deploying LSPs to the network. One is using a patch file, and the other is using a plan file.

**Note**

It is strongly recommended that you verify a patch file or plan file before deploying LSPs to the network. The patch file can be verified via the View Dry Run option. Verification of the plan file is a manual process.

Deploy Patch Files

When deploying a patch file, it is applied to the working plan file that currently resides on the server, and the working plan file is then deployed to the network.

For general descriptions of patch files and plan files, see the “Plan Files and Patch Files” chapter in the *WAE Design User Guide*. To create patch files, use the Compare Plans report tool; for information, see the “Reports” chapter in the *WAE Design User Guide*.

**Note**

You can only deploy new, modified, and deleted LSPs.

WAE Design Patch Workflow

When deploying patch files, one potential workflow is the following.


1. Open a plan file from a WAE Automation server.
2. Duplicate the plan file by saving it as a different name.
3. Make LSP modifications as needed in the duplicated plan file.
4. Open both plan files, and create a comparison report of the two using the option to create a patch file.
5. Deploy this patch file to the network.

Patch Deployment

-
- Step 1** Select the File->Save to->WAE menu.
- Step 2** Identify the remote server using the steps outlined in the [Identify Server Location](#) section.
- Step 3** Select Deploy Patch.

If deploying a patch file, you can browse to or enter its full path. Best practice is to select View Dry Run to verify the patch file can be successfully applied to the working plan file on the server. If you choose this option, a dialog box appears showing the results as successful or failed on a per-LSP basis. To see more details, which can be helpful in troubleshooting issues before deploying, click the Show Details button. Once you have verified the information, click OK to close it.

- Step 4** Click OK. A Deployment Status window opens, providing information as to the success or failure of the deployment to the network. Click the Show Details button for more information on a per-LSP basis.



Deploy Plans

When deploying a plan file, it is compared to the working plan file that currently resides on the server, and then the LSP differences are deployed directly to the network. A copy of it is also saved to the working plan file area.

- Step 1** Select the File->Save to->WAE menu.
- Step 2** Identify the remote server using the steps outlined in the [Identify Server Location](#) section.
- Step 3** Select Deploy Plan.
- Step 4** Click OK.

Save to the WAE Automation Server

You can save plan files to either the working plan file area or staging area. You can optionally “process” the plan so that upon querying a demand, worst-case analysis is automatically performed on interfaces, circuits, and SRLGs. Note that these plan files are not stored with the plan files generated by WAE Collector.

Saving the plan file to the working area overwrites the existing plan file. This means that any newly discovered or recently modified plan files are overwritten. For this reason, if you are not deploying a patch file or plan file, it is a best practice to save plan files to a staging area.

- Step 1** Select the File->Save to->WAE menu.
- Step 2** Identify the remote server using the steps outlined in the [Identify Server Location](#) section.

Step 3 Select the Save Plan option.

Save plan
Stage ID: 7
 Process plan

Step 4 If using a staging area for this access, enter the stage ID number. If this field is left empty, the plan file is saved to the working plan area.

Step 5 (Optional) to simulate failure scenarios such that upon querying a demand, worst-case analysis is automatically performed on interfaces, circuits, and SRLGs, select the Process Plan option.

Step 6 Click OK.

Identify Server Location

Step 1 After opening the dialog box, enter or select the hostname or IP address of the server.

Step 2 Identify how to connect to the server by selecting the appropriate protocol and by entering or selecting the port number (for example, HTTP 7777).

Step 3 If the authentication is enabled, enter the same username and password. If the authentication is disabled, the username and password fields must be empty.

Location
Server: 198.18.134.26
Protocol: HTTP
Port: 7777
Username: obidusan
Password: ●●●●●●●●●●
 Save Settings
 Save Password
Clear Settings

Save and Clear Settings

- To save all settings for use the next time you open the remote access dialog box, click Save Settings. This saves all settings whether the fields and all entries in the drop-down lists are empty or not. You can optionally save the authentication password.
- To clear all current user-specified settings from the fields and from the drop-down lists, click Clear Settings. Note that this does not clear the default Protocol, Port, and Stage ID values, though manual entries in these fields are cleared.
- To delete all user-specific settings so the next time you open the remote access dialog box all fields and all drop-down lists are empty (except for the default Protocol, Port, and Stage ID values), follow these steps.

Click Clear Settings.

Ensure Save Settings is enabled.

Click OK to exit. Upon being prompted for whether to continue, click Yes.

Related Topics

- *WAE Platform Configuration Guide*
- *WAE Design User Guide*

