

RADIUS Logical Line ID

The RADIUS Logical Line ID feature, also known as the Logical Line Identification (LLID) Blocking feature enables administrators to track their customers on the basis of the physical lines on which customer calls originate. Administrators use a virtual port that does not change as customers move from one physical line to another. This virtual port facilitates the maintenance of the administrator's customer profile database and allows the administrator to do additional security checks on customers.

- Finding Feature Information, page 1
- Prerequisites for RADIUS Logical Line ID, page 1
- Restrictions for RADIUS Logical Line ID, page 2
- Information About RADIUS Logical Line ID, page 2
- How to Configure RADIUS Logical Line ID, page 3
- Configuration Examples for RADIUS Logical Line ID, page 5
- Additional References, page 6
- Feature Information for RADIUS Logical Line ID, page 8
- Glossary, page 8

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest caveats and feature information, see Bug Search Tool and the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the feature information table.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for RADIUS Logical Line ID

Although this feature can be used with any RADIUS server, some RADIUS servers may require modifications to their dictionary files to allow the Calling-Station-ID attribute to be returned in Access-Accept messages.

For example, the Merit RADIUS server does not support LLID downloading unless you modify its dictionary as follows: "ATTRIBUTE Calling-Station-Id 31 string (*, *)"

Restrictions for RADIUS Logical Line ID

The RADIUS Logical Line ID feature supports RADIUS only. TACACS+ is not supported.

This feature can be applied only toward PPP over Ethernet over ATM (PPPoEoATM) and PPP over Ethernet over VLAN (PPPoEoVLAN) (Dot1Q) calls; no other calls, such as ISDN, can be used.

Information About RADIUS Logical Line ID

Preauthorization

LLID is an alphanumeric string (which must be a minimum of one character and a maximum of 253 characters) that is a logical identification of a subscriber line. LLID is maintained in a customer profile database on a RADIUS server. When the customer profile database receives a preauthorization request from the access router, the RADIUS server sends the LLID to the router as the Calling-Station-ID attribute (attribute 31).

The Layer 2 Tunneling Protocol (L2TP) access concentrator (LAC) sends a preauthorization request to the customer profile database when the LAC is configured for preauthorization. Configure the LAC for preauthorization using the **subscriber access** command.



Downloading the LLID is referred to as "preauthorization" because it occurs before either service (domain) authorization or user authentication and authorization occur.

The customer profile database on the RADIUS server consists of user profiles for each physical network access server (NAS) port that is connected to the router. Each user profile contains a profile matched to a username (attribute 1) representing the physical port on the router. When the router is configured for preauthorization, it queries the customer profile database using a username representative of the physical NAS port making the connection to the router. When a match is found in the customer profile database, the customer profile database returns an Access-Accept message containing the LLID in the user profile. The LLID is defined in the Access-Accept record as the Calling-Station-ID attribute.

The preauthorization process can also provide the real username being used for authentication to the RADIUS server. Because the physical NAS port information is being used as the username (attribute 1), RADIUS attribute 77 (Connect-Info) can be configured to contain the authentication username. This configuration allows the RADIUS server to provide additional validation on the authorization request if it chooses, such as analyzing the username for privacy rules, before returning an LLID back to the router.

How to Configure RADIUS Logical Line ID

Configuring Preauthorization

To download the LLID and configure the LAC for preauthorization, perform the following steps.

SUMMARY STEPS

- 1. enable
- 2. configure terminal
- 3. ip radius source-interface interface-name
- 4. subscriber access {pppoe | pppoa} pre-authorize nas-port-id [default | list-name] [send username]

DETAILED STEPS

enable Example: Router> enable configure terminal Example: Router# configure terminal ip radius source-interface interface-name Example:	Enables privileged EXEC mode. • Enter your password if prompted. Enters global configuration mode. Specifies the IP address portion of the username for the preauthorization request.
Router> enable configure terminal Example: Router# configure terminal ip radius source-interface interface-name	Enters global configuration mode. Specifies the IP address portion of the username for the
configure terminal Example: Router# configure terminal ip radius source-interface interface-name	Specifies the IP address portion of the username for the
Example: Router# configure terminal ip radius source-interface interface-name	Specifies the IP address portion of the username for the
Router# configure terminal ip radius source-interface interface-name	
ip radius source-interface interface-name	
Example:	
Example:	
Router (config)# ip radius source-interface Loopback1	
subscriber access {pppoe pppoa} pre-authorize nas-port-id [default <i>list-name</i>] [send username]	Enables the LLID to be downloaded so the router can be configured for preauthorization.
Example:	The send username option specifies that you include the authentication username of the session inside the Connect-Info (attribute 77) in the Access-Request message
	Router (config) # ip radius source-interface Loopback1 subscriber access {pppoe pppoa} pre-authorize nas-port-id [default list-name] [send username]

Command or Action	Purpose
Example:	
Router (config) # subscriber access pppoe pre-authorize nas-port-id mlist_llid send username	

Configuring the LLID in a RADIUS User Profile

To configure the user profile for preauthorization, add a NAS port user to the customer profile database and add RADIUS Internet Engineering Task Force (IETF) attribute 31 (Calling-Station-ID) to the user profile.

SUMMARY STEPS

- 1. UserName=nas_port: ip-address:slot/module/port/vpi.vci
- 2. User-Name=nas-port: ip-address:slot/module/port/vlan-id
- **3.** Calling-Station-Id = "string (*,*)"

DETAILED STEPS

	Command or Action	Purpose
Step 1	UserName=nas_port: ip-address:slot/module/port/vpi.vci	(Optional) Adds a PPPoE over ATM NAS port user.
Step 2	User-Name=nas-port: ip-address:slot/module/port/vlan-id	(Optional) Adds a PPPoE over VLAN NAS port user.
Step 3	Calling-Station-Id = "string (*,*)"	Adds attribute 31 to the user profile. • StringOne or more octets, containing the phone number from which the user placed the call.

Verifying Logical Line ID

To verify feature functionality, perform the following steps.

SUMMARY STEPS

- 1. enable
- 2. debug radius

DETAILED STEPS

	Command or Action	Purpose	
Step 1	enable	Enables privileged EXEC mode.	
	Example:	• Enter your password if prompted.	
	Router> enable		
Step 2	debug radius	Checks to see that RADIUS attribute 31 is the LLID in the Accounting-Request on LAC and in the Access-Request and	
	Example:	Accounting-Request on the LNS.	
	Router# debug radius		

Configuration Examples for RADIUS Logical Line ID

LAC for Preauthorization Configuration Example

The following example shows how to configure your LAC for preauthorization by downloading the LLID:

```
aaa new-model
aaa group server radius sg_llid
 server 172.31.164.106 aut\overline{h}-port 1645 acct-port 1646
aaa group server radius sg water
server 172.31.164.106 auth-port 1645 acct-port 1646
aaa authentication ppp default group radius
aaa authorization confg-commands
aaa authorization network default group sg water
aaa authorization network mlist llid group sg llid
aaa session-id common
username s7200 2 password 0 lab
username s5300 password 0 lab
username sg water password 0 lab
vpdn enable
vpdn-group 2
request-dialin
protocol 12tp
 domain example.com
 domain example.com#184
 initiate-to ip 10.1.1.1
 local name s7200 2
 12tp attribute clid mask-method right * 255 match #184
vpdn-group 3
accept dialin
 protocol pppoe
  virtual-template 1
Enable the LLID to be downloaded.
subscriber access pppoe pre-authorize nas-port-id mlist llid send username
```

```
interface Loopback0
 ip address 10.1.1.2 255.255.255.0
interface Loopback1
ip address 10.1.1.1 255.255.255.0
interface FastEthernet1/0/0
ip address 10.1.1.8 255.255.255.0 secondary
 ip address 10.0.58.111 255.255.255.0
no cdp enable
interface ATM4/0/0
no ip address
no atm ilmi-keepalive
interface ATM4/0/0.1 point-to-point
pvc 1/100
 encapsulation aa15snap
 protocol pppoe
interface virtual-template1
no ip unnumbered Loopback0
no peer default ip address
ppp authentication chap
radius-server host 172.31.164.120 auth-port 1645 acct-port 1646 key rad123
radius-server host 172.31.164.106 auth-port 1645 acct-port 1646 key rad123
ip radius source-interface Loopback1
```

RADIUS User Profile for LLID Example

The following example shows how to configure the user profile for LLID querying for PPPoEoVLAN and PPPoEoATM and how to add attribute 31:

```
pppoeovlan
-----
nas-port:10.1.0.3:6/0/0/0    Password = "password1",
        Service-Type = Outbound,
        Calling-Station-ID = "cat-example"

pppoeoa
------
nas-port:10.1.0.3:6/0/0/1.100    Password = "password1",
        Service-Type = Outbound,
        Calling-Station-ID = "cat-example"
```

Additional References

The following sections provide references related to RADIUS EAP Support feature.

Related Documents

Related Topic	Document Title
Configuring PPP Authentication Using AAA	"Configuring Authentication" module.
Configuring RADIUS	" Configuring RADIUS " module.
PPP Configuration	"Configuring Asynchronous SLIP and PPP" module.
Dial Technologies commands	Cisco IOS Dial Technologies Command Reference

Related Topic	Document Title
Security Commands	Cisco IOS Security Command Reference

Standards

Standard	Title
None	

MIBs

MIB	MIBs Link	
None	To locate and download MIBs for selected platforms, Cisco IOS releases, and feature sets, use Cisco MIB Locator found at the following URL: http://www.cisco.com/go/mibs	

RFCs

RFC	Title	
RFC 2284	PPP Extensible Authentication Protocol (EAP)	
RFC 1938	A One-Time Password System	
RFC 2869	RADIUS Extensions	

Technical Assistance

Description	Link
The Cisco Support website provides extensive online resources, including documentation and tools for troubleshooting and resolving technical issues with Cisco products and technologies.	http://www.cisco.com/techsupport
To receive security and technical information about your products, you can subscribe to various services, such as the Product Alert Tool (accessed from Field Notices), the Cisco Technical Services Newsletter, and Really Simple Syndication (RSS) Feeds.	
Access to most tools on the Cisco Support website requires a Cisco.com user ID and password.	

Feature Information for RADIUS Logical Line ID

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Table 1: Feature Information for RADIUS Logical Line ID

Feature Name	Releases	Feature Information
RADIUS Logical Line ID	Cisco IOS XE Release 2.1	The RADIUS Logical Line ID feature, also known as the Logical Line Identification (LLID) Blocking feature enables administrators to track their customers on the basis of the physical lines on which customer calls originate. In Cisco IOS XE Release 2.1, this
		feature was introduced on Cisco ASR 1000 Series Aggregation Services Routers.
		The following command was introduced or modified by this feature: subscriber access .
Calling Station ID Attribute 31	Cisco IOS XE Release 2.1	This feature was introduced on Cisco ASR 1000 Series Routers.
LLID Blocking	Cisco IOS XE Release 2.1	This feature was introduced on Cisco ASR 1000 Series Routers.

Glossary

attribute --A RADIUS Internet Engineering Task Force (IETF) attribute is one of the original set of 255 standard attributes that are used to communicate authentication, authorization, and accounting (AAA) information between a client and a server. Because IETF attributes are standard, the attribute data is predefined and well known; thus all clients and servers that exchange AAA information through IETF attributes must agree on attribute data such as the exact meaning of the attributes and the general bounds of the values for each attribute.

CHAP --Challenge Handshake Authentication Protocol. Security feature that is supported on lines using PPP encapsulation and prevents unauthorized access. CHAP does not itself prevent unauthorized access; it merely identifies the remote end. The router or access server then determines whether that user is allowed access.

EAP --Extensible Authentication Protocol. A PPP authentication protocol that supports multiple authentication mechanisms that are negotiated during the authentication phase (instead of the Link Control Protocol [LCP] phase). EAP allows a third-party authentication server to interact with the PPP implementation through a generic interface.

LCP --link control protocol. Protocol that establishes, configures, and tests data-link connections for use by PPP.

MD5 (**HMAC** variant) -- Message Digest 5. A hash algorithm used to authenticate packet data. HMAC is a key hashing for message authentication.

NAS --network access server. A device providing local network access to users across a remote access network such as the public switched telephone network (PSTN).

PAP --Password Authentication Protocol. Authentication protocol that allows PPP peers to authenticate one another. The remote router attempting to connect to the local router is required to send an authentication request. Unlike CHAP, PAP passes the password and host name or username in the clear (unencrypted). PAP does not itself prevent unauthorized access; it merely identifies the remote end. The router or access server then determines if that user is allowed access. PAP is supported only on PPP lines.

PPP --Point-to-Point Protocol. A protocol that encapsulates network layer protocol information over point-to-point links. PPP is defined in RFC 1661.

RADIUS --Remote Authentication Dial-In User Service. Database for authenticating modem and ISDN connections and for tracking connection time.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental. © 2001-2009 Cisco Systems, Inc. All rights reserved.

Glossary