



Monitor Configurations in Secure Workload

The **Monitoring** options available to you vary depending on your role.

- [Agent Monitoring](#), on page 1
- [Agent Monitoring Type](#), on page 1
- [Agent Status and Statistics](#), on page 3
- [Enforcement Status](#), on page 5
- [Enforcement Status for Cloud Connectors](#), on page 6
- [Pause Policy Updates](#), on page 7

Agent Monitoring

The page displays the count of all monitored agents in a cluster based on the currently selected root scope.




Note Total Inventory count is the summation of all inventory observed on the network after applying collection rules.

Agent Monitoring Type

To monitor agents, click **Manage > Agents** in the left navigation bar, then click the **Monitor** tab.

This page is only available for users that have **Site Admin** and **Customer Support** roles. **Scope owners** can see Inventory, Deep Visibility Agents, and Enforcement Agents.

Figure 1: Total Number of Installed Agents



The following table shows the differences between each agent type.

Agent Type	Description
Deep Visibility	Provides highest fidelity in terms of time series flow data, processes running on a host. Most Linux and Windows platforms are supported. See <code>sw_agents_deployment-label</code>
Enforcement	Provides all capabilities available in Deep Visibility Agents. In addition, Enforcement agents are capable of setting firewall rules on the installed host.

AnyConnect	Provides time series flow data on endpoints running AnyConnect Secure Mobility Agent with Network Visibility Module (NVM) without requiring any Cisco Secure Workload agent installation. IPFIX records generated by NVM are sent to Secure Workload AnyConnect Proxy connector. Windows, Mac, and certain smartphone platforms are supported.
ISE	Provides metadata about endpoints registered with Cisco ISE. Through ISE pxGrid, ISE connector collects the metadata, registers the ISE endpoints on Secure Workload as ISE agents pushes labels based on the attributes fetched from ISE appliance and LDAP attributes for the users logged in to the endpoints.
The following table provides a brief summary of various appliance agents provided by Cisco Secure Workload.	
Appliance Agents	Description
SPAN	Provides the flow analysis without requiring any per-host agent installation. It runs in the Secure Workload ERSPAN VM appliance. It consumes ERSPAN packets sourced by any Cisco switch.



Note Appliance agents such as NetFlow, NetScaler, F5, AWS, and AnyConnect Proxy are now supported as connectors. For more information on connectors, see [What are Connectors](#).


Any non-zero agent type button allows further drill-down into the distribution of each agent type.

Agent Status and Statistics

To view the charts described in this topic, choose **Manage > Agents**, then click the **Distribution** tab.

The following charts are available for both Deep Visibility and Enforcement Agent types.

Figure 2: Agents Distribution



For each agent type, this page provides an overview and the health of registered agents including overall CPU overhead, bandwidth overhead, missed packets, OS/version distribution and agent upgrade status.

CPU Overhead Chart

The CPU Overhead chart provides an aggregated view of CPU overhead per core from all agents. Per-agent CPU Overhead is provided as part of the [Workload Profile](#). This chart is only available for Deep Visibility and Enforcement Agent Types.

Bandwidth Overhead Chart

The Bandwidth Overhead chart provides aggregated stats of total bandwidth and bandwidth used by agents. Per-agent bandwidth overhead is provided as part of the [Workload Profile](#). This chart is only available for Deep Visibility and Enforcement Agent Types.

Agent Health Chart

The Agent Health chart provides the number of active or inactive agents. Active agents are the ones checking in with config server for upgrade on regular intervals. The checking interval is 30 minutes. If we see that an agent has missed more than two check-in periods from an agent, it would be declared as an inactive agent.

Software Agent Updates to Latest Revision Chart

Every time an agent checks in with the config server, the agent would also provide its current RPM version. If an agent is configured to a specific version and is not able to update after 2 check-in periods, the agent would be declared as not able to upgrade to the latest version.

Agent Packet Missed Chart

In rare occasions when the traffic volume traversing a host is greater than the rate at which the agent is able to inspect, some packets are skipped from being analyzed. The number of missed packets and the corresponding agent name are displayed in this chart.

Agent Software Version and OS Distribution Charts

These charts show the agent version distribution and parent OS platform of all agents registered with the Secure Workload cluster.

Enforcement Status

To view enforcement status, click **Defend > Enforcement Status** in the navigation bar at the left side of the window.

This page is available for site admin/customer support users and scope owners to get an overview of the current status of all the enforcement agents, including the cloud connectors that are enforcing a policy.

If any of the charts shows red or orange, see the applicable topic:

Table 1: Enforcement Status Charts

Chart	Result	Take Action
Agent Enforcement Enabled	Not Enabled	Make sure enforcement is enabled in the agent configuration. See Create an Agent Configuration Profile .
Agent Policy Config	Stale Policies	This situation is generally temporary and typically doesn't require any action. It occurs because a Secure Workload deployment based on labels updates inventory and policies dynamically. However, if this situation persists for any individual workloads, contact Cisco TAC.
Agent Concrete Policies	Skipped	This indicates that policies weren't pushed to some agents.



- Tip**
- To view status for individual scopes or for the entire tenant, use the **Filter by Scope** option at the top-left side of the page.
 - If the charts indicate a problem, identify which workloads have the problem by clicking the relevant part of a chart.
The table displays the affected workloads.
Alternatively, to see filtering options, click the (i) button in the **Filter** box below the charts.
 - To view a wealth of additional details, click the IP address link in the filtered list of workloads to display the Workload Profile page.

The following table describes the fields shown in the enforcement status table.

Field	Description
Host Name	Host name of the workload.
Address	IP addresses of all the interfaces on the workload.
Enforcement Enabled	Indicates whether enforcement is enabled or not on the agent.
Concrete Policies in Sync	This indicates whether the desired version of concrete policies are currently enforced on the agent.
Concrete Policies	If this value shows Skipped for any host, this means the limit on policies is reached for the agent on that host. (See Limits Related to Policies .)
Policy Count	The number of concrete policies on the agent.
Status	The status of the latest policy config enforcement. If the status is CONFIG_SUCCESS , it indicates that current version is enforced without any issue.

Enforcement Status for Cloud Connectors

If you have set up AWS or Azure cloud connectors:

All interfaces enforcement status are displayed on the enforcement status page. If the policies are applied successfully, the policies are in sync else the corresponding error messages are displayed.

Policy count in the enforcement status page is Secure Workload accounting but not AWS or Azure rule accounting.

(AWS only) The hostname field on this page is derived from public DNS. If the public DNS is not enabled on the given VPC, the hostname field is empty.

Pause Policy Updates



Caution This option pauses policy updates for ALL workloads in ALL scopes.

This feature requires site admin or customer support privileges.

To pause rule updates for all enforcement endpoints in all scopes:

1. From the navigation pane, choose **Defend > Enforcement**.
2. Click the status beside **Policy Updates**.
3. Read and accept the caution.

Figure 3: Firewall Rules are being Updated Continuously




Figure 4: Firewall Rule Updates are Paused

