




OpenAM Single Sign-On

- [Single Sign-On Setup Task List, on page 1](#)
- [Single Sign-On Setup Preparation, on page 3](#)
- [Single Sign-On Setup and Management Tasks, on page 5](#)

Single Sign-On Setup Task List

The following figure provides the sequence of tasks that are required to successfully configure SSO. Cisco recommends that you complete each task outlined in this flow in the order indicated.

Figure 1: Task Flow for Single Sign-On setup



The following table lists the tasks to configure Single Sign-On.

Table 1: Task List for Single Sign-On Setup

Item	Task
1	Provision a new user account for the OpenAM server to be used for Single Sign-On on the Active Directory (AD) server. Note Ensure the Windows Server 2008 supported tools are installed before proceeding.
2	Configure client browsers for Single Sign-On. See topics related to third-party software and system requirements for a list of web browsers and supported versions.
3	Configure Microsoft Windows Registry for Real-Time Monitoring Tool (RTMT).
4	Install Java Runtime Environment (JRE). Note A Java keystore and the associated security certificates are required for secure connections to the OpenAM server, which runs on an Apache Tomcat. The procedure to install Java are different depending if you use self-signed or Certificate Authority (CA) signed security certificates.
5	Import IM and Presence Service certificate into OpenAM. Do this for each IM and Presence Service node that is to use Single Sign-On.
6	Install the Apache Tomcat Web Container on the OpenAM Windows server.
7	Deploy OpenAM War on Apache Tomcat.
8	Set up OpenAM using the GUI Configurator. You access the OpenAM web-based administration interface using a web browser by entering the FQDN of the OpenAM server.
9	Set up policies on the OpenAM server. You must follow the policy rules that are defined in the procedure. Note You must use the FQDN of the IM and Presence Service node to access the Cisco Unified CM IM and Presence Administration/User interface. Do not use the hostname of the node.
10	Configure SSO module instance. A single module instance can be shared by multiple IM and Presence Service nodes for SSO if the same Active Directory domain is used throughout the deployment.
11	Configure J2EE agent profile on OpenAM. You must configure an associated J2EE Agent Profile on the OpenAM server for the J2EE Agent of each IM and Presence Service node using SSO.
12	Set the OpenAM session timeout to a value that is higher than the session timeout parameter setting for the IM and Presence Service node.
13	Import the OpenAM certificate into the tomcat-trust trust store for each IM and Presence Service node using SSO.

Item	Task
14	<p>Activate Single Sign-On.</p> <p>Enabling SSO affects service. Cisco highly recommends that you enable SSO during a maintenance window.</p>

You can perform these additional tasks that are not required to setup up Single Sign-On:

- Disable Single Sign-On
- Uninstall OpenAM on Windows
- Set the debug level
- Troubleshoot Single Sign-On

Related Topics

[Disable Single Sign-On](#), on page 31

[Uninstall OpenAM on Windows](#), on page 31

[Set Debug Level](#), on page 32

[Troubleshooting Single Sign-On](#)

Single Sign-On Setup Preparation

Third-Party Software and System Requirements for Single Sign-On

The Single Sign-On (SSO) feature makes use of a third-party application from ForgeRock called OpenAM. Support for the OpenAM application is available only from ForgeRock. The software requirements and configuration guidelines to enable the SSO feature to work with OpenAM are provided. The installation of OpenAM on a Windows Server is also outlined.

Advanced OpenAM configurations, such as deploying OpenAM behind load balancers or the use of session replication between OpenAM servers, have not been validated. For information about these advanced features, see http://www.cisco.com/en/us/docs/voice_ip_comm/cucm/miscellany/oam90-cucm8586-cuc86-ss0.pdf.

The SSO feature requires the following third-party applications:

- Microsoft Windows Server 2008 R2
- Microsoft Active Directory
- ForgeRock Open Access Manager (OpenAM) Version 9.0



Note The SSO feature uses Active Directory and OpenAM in combination to provide SSO access to web-based client applications.

These third-party products must meet the following configuration requirements:

- Active Directory must be deployed in a Windows domain-based network configuration, not just as an LDAP server.
- The OpenAM server must be accessible on the network to all client systems and the Active Directory server.
- The Active Directory (Domain Controller) server, Windows clients, IM and Presence Service nodes, and OpenAM server must be in the same domain.
- DNS must be enabled in the domain.
- The clocks of all the entities participating in SSO must be synchronized.

See the third-party product documentation for more information about those products.

The following table provides a list of the software applications and versions that were used and tested in the procedures that appear in this chapter. In order for you to receive Cisco support, Cisco recommends that you adhere to these suggested requirements during your configuration.

Table 2: Software Versions

Component	Version
Active Directory	Windows Server 2008 R2 Enterprise
Desktop Operating System for end user clients	Windows 7 Professional (SP1)
OpenAM	OpenAM Release 10.0 http://forgerock.org/openam-archive.html For more information: https://wikis.forgerock.org/confluence/display/openam/OpenAM+Release+Documentation
OpenAM underlying Operating System	Windows Server 2008 R2 Enterprise
Apache Tomcat on which OpenAM is loaded	Tomcat 6.0.2.0, Tomcat 7.0.29 http://archive.apache.org/dist/tomcat/tomcat-7/v7.0.29/bin
Java Development Kit (JDK) of OpenAM underlying Operating System	JDK 7 Update
Web browser	Internet Explorer 8, 9 and Mozilla Firefox 10, 11

Important Information Before Single Sign-On Setup



Note From Release 10.0(1) and later, Agent Flow SSO is not compatible with FIPS mode.

To help ensure that the configuration of SSO runs as smoothly as possible, Cisco recommends that you gather the following information before you configure SSO:

- Ensure that the installed base operating system (such as Windows server) for the OpenAM system is running.
- Make a note of the Fully Qualified Domain Name (FQDN) of the Windows Active Directory (AD) server to which the OpenAM will be integrating.
- Make a note of the FQDN of the Windows server on which OpenAM is to be installed.
- Ensure that the IM and Presence Web Application timeout is set consistently across all IM and Presence nodes in the cluster and make note of that timeout value. You can use the Cisco Unified CM IM and Presence Administration CLI to verify the timeout value by entering the following command: `show webapp session timeout`. For more information, see the *Command Line Interface Reference Guide for Cisco Unified Communications Solutions*.
- Ensure that Cisco Unified Communications Manager has been configured to sync users from Active Directory (AD) using “sAMAccountName” as the LDAP Attribute for User ID. For more information, see the “DirSync Service” section in the *Cisco Unified Communications Manager System Guide*.

Single Sign-On Setup and Management Tasks

Provision Active Directory for Single Sign-On

Before you begin

Ensure that you have Windows Server 2008 support tools installed. Support tools are installed on Windows Server 2008 by default.

Procedure

- Step 1** Log in to the Active Directory (AD) server.
- Step 2** From the **Start** menu, choose **Programs > Administration Tools** and choose **Active Directory Users and Computers**.
- Step 3** Right-click **Users** and choose **New > User**.
- Step 4** In the **User logon name** field, enter the OpenAM server hostname.
- Note** The OpenAM server hostname should not include the domain name.
- Step 5** Click **Next**.
- Step 6** Enter and confirm a password.
This password is required in Step 10.
- Step 7** Uncheck the **User must change password at next login** check box.
- Step 8** Click **Next**.
- Step 9** Click **Finish** to finish creating the new user account.
- Step 10** Create a keytab file on the AD server using the following command from the command prompt.

```
ktpass -princ HTTP/<hostname>.<domainname>@<DCDOMAIN> -pass <password> -mapuser <userName>
-out <hostname>.HTTP.keytab -ptype KRB5_NT_PRINCIPAL -target <DCDOMAIN>
```

Example:

```
ktpass -princ HTTP/server1.cisco.com@CISCO.COM -pass cisco!123 -mapuser server1 -out
server1.HTTP.keytab -ptype KRB5_NT_PRINCIPAL -target CISCO.COM
```

where:

Parameter	Description
hostname	The hostname (not the FQDN) of your OpenAM server. For example, server1
domainname	The AD domain name. For example, cisco.com.
DCDOMAIN	The AD domain name, entered in block capitals. In this example, CISCO.COM.
password	The password value that was specified when you created the user account for the OpenAM server earlier in this procedure.
userName	The AD account name entered in Step 4. This value should be the OpenAM server hostname. In this example, server1.

Note Record the *-princ* value for use in later procedures.

Step 11

After successful creation of the keytab file, copy the keytab file to a location on the OpenAM server; this path will later be specified in OpenAM configuration. Create a directory under `C:\>` and copy the above keytab file. For example, `C:/keytab/server1.HTTP.keytab`.

Client Browser Setup for Single Sign-On

To use SSO for a browser-based client application, you must configure the web browser. The following sections describe how to configure client browsers to use SSO.

Configure Internet Explorer for Single Sign-On

The SSO feature supports Windows clients running Internet Explorer. Perform the following procedure to configure Internet Explorer to use SSO.



Tip For information about supported web browsers, see topics related to third-party software and system requirements for Single Sign-On.

Procedure

- Step 1** Choose **Tools > Internet Options > Advanced** tab.
- Step 2** Click **Enable Integration Windows Authentication**.
- Step 3** Click **OK** to save the changes.

- Step 4** Restart Internet Explorer.
- Step 5** Choose **Tools > Internet Options > Security > Local Intranet** and click **Custom Level**.
- Step 6** Under **User Authentication**, check **Automatic Logon Only in Intranet Zone**.
- Step 7** Click **OK**.
- Step 8** Click **Sites**.
- Step 9** Check **Automatically detect intranet network**.
- Step 10** Click **Advanced**.
- Step 11** Fill in the **Add this web site to the zone** field with the FQDN of the OpenAM server using the following format: `https://OpenAM_FQDN`.
- Step 12** Click **Add**.
- Step 13** Click **Close**.
- Step 14** Click **OK**.
- Step 15** Uncheck **Enable Protected Mode**.
- Step 16** Click **Apply**.
- Step 17** Click **OK**.
- Step 18** Restart Internet Explorer.
- Step 19** Open the Windows Registry Editor. Perform one of the following actions:
- For Windows XP or Windows 2008, choose **Start > Run** and type *regedit*.
 - For Windows Vista and Windows 7.0, click **Start** and type *regedit*. For Windows Vista, you must click **Continue**.
- Step 20** Under registry key `HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\LSA`, right-click and choose **New > DWORD (32-bit) value** and rename it to be *SuppressExtendedProtection*.
Only an administrator can set the DWORD.
- Step 21** Set the following values:
- Base: hexadecimal
 - Value data: 002
- The newly created DWORD appears in the LSA directory list as follows:
- Name: SuppressExtendedProtection
 - Type: REG_DWORD
 - Value: 0x00000002 (2)

Related Topics

[Third-Party Software and System Requirements for Single Sign-On](#), on page 3

Configure Firefox for Single Sign-On

The SSO feature supports Windows clients running Firefox.



Tip For a list of supported web browsers, see topics related to third-party software and system requirements for Single Sign-On.

Procedure

- Step 1** Open Firefox and enter the following URL: **about:config**
- Step 2** Scroll down to **network.negotiate-auth.trusted-uris**, right-click that Preference Name, and choose **Modify**.
- Step 3** Set the string value to your domain (for example, cisco.com).
- Step 4** Click **OK**.

Related Topics

[Third-Party Software and System Requirements for Single Sign-On](#), on page 3

Configure Windows Registry for the Real-Time Monitoring Tool

Configuring SSO for the Real-Time Monitoring Tool (RTMT) is optional. To achieve this configuration, you must create a new registry key on your Desktop client (Windows XP or Windows 7).



Note An administrator must set the `allowtgtsessionkey` registry key entry for the Desktop client.

This new registry key should be stored at either of the locations below, depending on your Operating system:

Procedure

- Step 1** Go to either of the following locations, depending on your operating system:
 - Windows XP -
HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\Lsa\Kerberos
 - Windows Vista/Windows 7 -
HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\Lsa\Kerberos\Parameters
- Step 2** Right-click the folder, choose **New > DWORD (32-bit) Value**, and rename it to be `allowtgtsessionkey`.
- Step 3** Right-click the newly created registry key and choose **Modify**.
- Step 4** In the **Value data** field, enter `1`.

Install Java

OpenAM requires a Java Runtime Environment (JRE) to operate. The following procedure provides details for installing the JRE on your Windows server, forming the OpenAM base system.

Procedure

- Step 1** Go to <http://www.oracle.com/technetwork/java/archive-139210.html>.
- Step 2** Download the recommended version of the JDK installation file by choosing the executable file that corresponds to your server architecture (Windows x86 or Windows x64).
- Note** For a list of recommended software versions, see topics related to third-party software and system requirements for Single Sign-On.
- Step 3** Double-click the downloaded file to begin the installation of the JDK and accept the default values provided in the Installation wizard.
- Note** Make a note of the installation directory. This value indicates the location of the Java JRE and can be used to infer the JDK directory path. Example values may be as follows, depending on the JDK values that are used:
- `jre-path=C:\Program Files\Java\jre7`
 - `jdk-path=C:\Program Files\Java\jdk1.7.0_03`
- Step 4** A Java keystore and the associated security certificates are required to facilitate secure connections to the OpenAM server, which runs on Apache Tomcat. Perform one of the following actions:
- If you use a self-signed security certificate for OpenAM/Tomcat, proceed to Step 5.
 - If you use a Certificate Authority (CA) signed security certificate for OpenAM/Tomcat, proceed to Step 11.
- Step 5** Create the Java keystore by opening a Windows command prompt on the Windows Server, and executing the following command: `C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -genkey -alias tomcat -keyalg RSA -validity 1825 -keystore C:\keystore`
- This command creates the Java keystore file at the following location: `C:\keystore`. The keytool command is located in the `<jdk-path>/bin` directory, the exact path to the keytool command in the preceding command may vary depending on the JDK version used. For information about the keytool command, see <http://docs.oracle.com/javase/7/docs/technotes/tools/windows/keytool.html>.
- Step 6** When you are prompted for a keystore password, enter a valid keystore password. For example, "cisco!123". Make a note of the keystore password as it is required to access the keystore.
- Note** Do not use example values on the production server; Use a unique password value for the keystore. This password will be visible in plain text in the Apache Tomcat configuration files and utilities.
- Step 7** When you are prompted to enter the first name and last name, enter the FQDN (hostname.domainname) of the OpenAM server.
- You are also prompted to enter your organization unit name, organization name, city or locality, state or province, and two-letter country code.
- Step 8** When you are prompted for a Tomcat password, press RETURN to use the same keystore password value for the Tomcat private key. The Java keystore is created at the location specified in the keytool command. For example, `C:\keystore`.
- Step 9** You can view the Tomcat certificate in the keystore using the following command:

Example:

```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -list -v -alias tomcat -keystore C:\keystore
```

Step 10 *If you chose to use a self-signed security certificate for Tomcat, proceed to the end of this procedure and consider this task complete.*

Step 11 Create a Java keystore to store Certificate Authority (CA)-signed security certificates for OpenAM/Tomcat. Open a command prompt on the Windows Server and execute the following command:

Example:

```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -genkey -alias tomcat -keyalg RSA -validity 1825 -keystore C:\keystore
```

This command creates the Java keystore file at the following location: C:\keystore. The keytool command is located in the <jdk-path>/bin directory, the exact path to the keytool command in the example provided above may vary depending on the JDK version used. For information about the keytool command, see <http://docs.oracle.com/javase/7/docs/technotes/tools/windows/keytool.html>.

Step 12 When you are prompted for a keystore password, enter a valid keystore password. For example, "cisco!123". Make a note of the keystore password as it is required to access the keystore.

Do not use example values on the production server; Use a unique password value for the keystore. This password will be visible in plain text in the Apache Tomcat configuration files and utilities.

Step 13 When you are prompted to enter the first name and last name, enter the FQDN (hostname.domainname) of the OpenAM server.

You are also prompted to enter your organization unit name, organization name, city or locality, state or province, and two-letter country code.

Step 14 When you are prompted for a Tomcat password, press RETURN to use the same keystore password value for the Tomcat private key. The Java keystore is created at the location specified in the keytool command. For example, C:\keystore.

Step 15 You can view the Tomcat certificate in the keystore using the following command:

Example:

```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -list -v -alias tomcat -keystore C:\keystore
```

Step 16 Generate a certificate signing request (CSR) for this OpenAM/Tomcat instance. Open a command prompt on the Windows Server and execute the following command .

Example:

```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -certreq -keyalg RSA -alias tomcat -file certreq.csr -keystore C:\keystore
```

Step 17 Submit the CSR to your CA, request the CA to sign the CSR and create a certificate. Obtain and copy the following certificates to the Windows Server that is going to be the OpenAM server:

- CA signing or root certificate
- Intermediate signing certificates (if applicable)
- Newly signed OpenAM/Tomcat certificate

Note Refer to the CA documentation for instructions about completing these tasks.

Step 18 Import the CA signing or root certificate into the Java keystore that was created in Step 11. Open a command prompt on the Windows Server and execute the following command, answering “yes” to the prompt, “Trust this certificate?”:

Example:

```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -import -alias
root -trustcacerts -file <filename_of_the_CA_root_certificate> -keystore
C:\keystore
```

Step 19 You can view the CA signing certificate in the keystore using the following command:

Example:

```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -list -v -alias
root -keystore C:\keystore
```

Step 20 Import any other intermediate signing certificates (if applicable) into the Java keystore that was created in Step 11. Open a command prompt on the Windows Server and execute the following command, answering “yes” to the prompt, “Trust this certificate?”:

Example:

```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -import -alias
inter01 -trustcacerts -file
<filepath_of_the_intermediate_signing_certificate> -keystore C:\keystore
```

The -alias option must be updated with a value unique to the Java keystore, otherwise the import operation will result in an error similar to the following: “Certificate not imported, alias<inter01> already exists.”

Step 21 You can view any of the intermediate signing certificates in the keystore using the following command:

Example:

```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -list -v -alias
inter01 C:\keystore
```

The -alias option must be updated with the corresponding alias value for the intermediate certificates you wish to view. The above example uses a sample alias value of “inter01”.

Step 22 Import the newly signed certificate OpenAM/Tomcat certificate into the Java keystore that was created in Step 11. Open a command prompt on the Windows Server and execute the following command:

Example:

```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -import -alias
tomcat -file <new_certificate_filepath> -keystore C:\keystore
```

Step 23 You can view the new OpenAM/Tomcat certificate in the keystore using the following command:

Example:

```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -list -v -alias
tomcat -keystore C:\keystore
```

The issuer of this new Tomcat certificate is the CA or one of the intermediate CAs (if applicable).

Related Topics

[Third-Party Software and System Requirements for Single Sign-On](#), on page 3

[Import OpenAM Certificate Into IM and Presence Service](#), on page 24

Import IM and Presence Certificates Into OpenAM

OpenAM must communicate with a J2EE Agent component that exists on each IM and Presence Service node for which SSO is enabled. This communication is over an encrypted channel and therefore the necessary security certificates must be imported onto OpenAM.

The OpenAM server must trust the security certificate presented by each IM and Presence Service node for the encrypted communication channel to be established. OpenAM trusts a security certificate by importing the required security certificates into the OpenAM keystore. A given IM and Presence Service node can present one of two types of security certificate:

- Self-signed certificate
- CA-signed certificate



Note The IM and Presence Service Tomcat certificate and tomcat-trust trust store contain the security certificates of interest for secure communication with OpenAM. The other IM and Presence Service certificates and associated trust stores are not relevant for SSO (for example, cup, cup-xmpp, cup-xmpp-s2s or ipsec).

If your SSO-enabled IM and Presence Service deployment is configured to use self-signed certificates, each of the self-signed certificates must be imported into OpenAM.

If your SSO-enabled IM and Presence Service deployment is configured to use CA-signed certificates, the CA root certificate and any associated intermediate certificates must be imported into OpenAM. If you are also using a CA-signed certificate for your OpenAM/Tomcat instance, the required CA root and intermediate certificates may already be imported into the OpenAM keystore.

This procedure provides the details on how to identify the type of security certificate being used by the IM and Presence Service node and how to import the certificates into the OpenAM keystore that was created when you installed Java.

Procedure

-
- Step 1** Sign in to Cisco Unified IM and Presence Operating System Administration for the IM and Presence Service node for which SSO is to be enabled.
- Step 2** Choose **Security > Certificate Management**.
- Step 3** Click **Find**.
- Step 4** Locate the entry with **Certificate Name** of **tomcat**.
- Step 5** Examine the Description column of the tomcat certificate.
- Step 6** If the description states that the tomcat certificate is **Self-signed certificate generated by system**, this indicates that the IM and Presence Service node is using a self-signed certificate. If this description is not present, a CA-signed certificate can be assumed.
- If the certificate is self-signed, proceed to Step 7.
 - If the certificate is CA-signed, proceed to Step 13.
- Step 7** Click the **tomcat.pem** link.
- Step 8** Click **Download** to download the tomcat.pem file.

- Step 9** Copy the **tomcat.pem** file to the OpenAM server.
- Step 10** Import the **tomcat.pem** file as a trusted certificate into the keystore that was created on the OpenAM server when you installed Java. Open a command prompt on the Windows server (OpenAM) and execute the following command, updating the command with the values for your keytool command path and keystore location as applicable for your environment, and answer **Yes** to the prompt “Trust this certificate?”: `C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -import -alias cup01 -trustcacerts -file <full_filepath_of_the_tomcat.pem> -keystore C:\keystore`
- Note** The `-alias` option must be updated with a value unique to the Java keystore, otherwise the import operation will result in an error similar to the following: “Certificate not imported, alias <cup01> already exists.”
- Step 11** You can view the **tomcat.pem** in the keystore using the following command, updating the command with the values for your keytool command path and keystore location as applicable for your environment:
- ```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe -list -v -alias cup01 -keystore C:\keystore
```
- Note** The `-alias` option must match the value used in Step 10, otherwise the keystore entry may not be found.
- Step 12** Skip to Step 16.
- Step 13** Identify the CA root certificates and any intermediate certificates that were used to sign your IM and Presence Service Tomcat certificate. Download the required certificates (CA root certificates and any intermediate certificates) from your CA to your OpenAM server.
- Step 14** Import these certificates into the keystore on the OpenAM server as trusted certificates. Open a command prompt on the Windows server (OpenAM) and execute the following command for each downloaded certificate, updating the command with the values for your keytool command path and keystore location as applicable for your environment, and answer “yes” to the prompt “Trust this certificate?”.
- ```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe" -import -alias root_ca -trustcacerts -file <full_filepath_of_the_certificate> -keystore C:\keystore
```
- Note** The `-alias` option must be updated with a value unique to the Java keystore, otherwise the import operation will result in an error similar to the following: “Certificate not imported, alias <root_ca> already exists.”
- Step 15** You can view the certificate in the keystore using the following command, updating the command with the values for your keytool command path and keystore location as applicable for your environment:
- ```
C:\>"C:\Program Files\Java\jdk1.7.0_03\bin\keytool.exe -list -v -alias root_ca -keystore C:\keystore
```
- Note** The `-alias` option must match the value used in Step 14, otherwise the keystore entry may not be found.
- Step 16** Repeat this procedure for each IM and Presence node for which SSO is to be enabled.

**Note** In the case of CA-signed certificates used on the IM and Presence Service node, it is not necessary to import the same CA and intermediate certificate into the OpenAM keystore more than once. If you find that an IM and Presence Service node has been signed by the same CA and intermediate certificate, there is no need to import those certificates into the OpenAM keystore again.

## Install Tomcat

OpenAM requires that the Apache Tomcat Web Container be installed on the OpenAM Windows server base system. This procedure provides details on how to install Apache Tomcat on the OpenAM Windows server base system. See the following table for descriptions of the variables referred to in this procedure.

**Table 3: Variable Descriptions**

| Variable             | Description                                                                                                                                                                                                                                    |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <certstore-path>     | The file path to the Java keystore used by Java applications and Apache Tomcat. Trusted server public certificates are stored in this keystore. See Steps 5 or 11 of the following procedure to determine the file path for the Java keystore. |
| <certstore-password> | The password used to access the Java keystore located at <certstore-path>. See Step 6 or 12 of the following procedure to determine the value used for the Java keystore password:                                                             |

### Procedure

**Step 1** Download the recommended version of Apache Tomcat to your Windows server that forms the OpenAM base system. For a list of recommended software and versions, see topics related to third-party software and system requirements for Single Sign-On .

**Note** Download the 32bit/64bit Windows Service Installer executable file.

**Step 2** Double-click the downloaded file to begin the installation of Apache Tomcat.

**Step 3** From the Apache Tomcat Setup wizard, click **Next**.

**Step 4** In the **License Agreement** dialog box, click **I Agree**.

**Step 5** In the **Choose Components** dialog box, choose **Minimum** as the type of install and click **Next**.

**Step 6** In the **Configuration** dialog box, accept the default settings and click **Next**.

**Step 7** In the **Java Virtual Machine** dialog box, ensure the installed JRE path is set to the value of jre-path.

**Note** If you are using the recommended version of Java, the path will display by default. If you are not using the recommended version of Java, ensure that the path entered matches the path that was used when you installed Java.

**Step 8** Click **Next**.

- Step 9** In the **Choose Install Location** dialog box, accept the default settings and click **Install**. Note the Tomcat install location, because it is required later
- Note** The installation location is referred to as **tomcat-dir** later in this procedure.
- Step 10** Click **Finish**.
- Step 11** Configure Apache Tomcat to start automatically.
- Choose **Start > All Programs > Apache Tomcat 7.0 Tomcat7 > Configure Tomcat**.
  - From the **General** tab, set the **Startup type** as **Automatic**.
  - Click **Apply**.
  - Click **OK**.
- Step 12** Configure the Apache Tomcat runtime parameters:
- Choose **Start > All Programs > Apache Tomcat 7.0 Tomcat7 > Configure Tomcat**.
  - From the **Java** tab, add the following Java options:
 

```
-Djavax.net.ssl.trustStore=<certstore-path>
-Djavax.net.ssl.trustStorePassword=<certstore-password>
-XX:MaxPermSize=256m
```

**Tip** See the parameter table at the beginning of this procedure for variable descriptions.

**Example:**

```
-Djavax.net.ssl.trustStore=C:\keystore
-Djavax.net.ssl.trustStorePassword=cisco!123
-XX:MaxPermSize=256m
```
  - Set the **Initial memory pool** to 512.
  - Set the **Maximum memory pool** to 1024.
  - Click **Apply**.
  - Click **OK**.
- Step 13** Using a Text Editor, open the server.xml file under <tomcat-dir>\conf folder. See Step 9 to determine the value for <tomcat-dir>.
- Example:**
- An example value is "C:\Program Files\Apache Software Foundation\Tomcat 7.0\conf"
- Step 14** Comment out the 8080 connector port. Enter the code as follows:
- Example:**
- ```
<!-- <Connector port="8080" protocol="HTTP/1.1"
connectionTimeout="20000"
redirectPort="8443" /> -->
```
- Step 15** Uncomment the 8443 connector port. Remove the <!-- code at the beginning and --> at the end of the 8443 connector. You must add three more attributes to the connector configuration:
- keystoreFile (location of the keystore file that was created when you installed Java. In this example, it was created under C:\keystore)
 - keystorePass
 - keystoreType

Enter the code as follows:

Example:

```
<Connector port="8443" protocol="HTTP/1.1" SSLEnabled="true"
maxThreads="150" scheme="https" secure="true"
clientAuth="false" sslProtocol="TLS"
keystoreFile="<certstore-path>"
keystorePass="<certstore-password>"
keystoreType="JKS"/>
```

Tip See the parameter table at the beginning of this procedure for variable descriptions.

Step 16 Save the server.xml file.

Step 17 Start the Tomcat service.

a) **Start** > **All Programs** > **Apache Tomcat 7.0 Tomcat7** > **Configure Tomcat**

b) From the **General** tab, click **Start**. If the Tomcat service was already running, click **Stop**, then **Start**.

Step 18 To test the configuration, launch a web browser on the Windows Server that contains the Tomcat instance and go to `https://localhost:8443/tomcat.gif`. The web browser may present warning dialogs about insecure connections because the web browser does not trust the security certificates that are presented by the Tomcat instance. Either examine the certificates and add them to your local certificate store so that the browser trusts them or proceed to the web application (less secure option) using the available browser controls. If the configuration is correct, the Tomcat logo appears in the web browser window.

Step 19 Configure Windows firewall to allow incoming connections to Apache Tomcat.

a) Choose **Start** > **Administrative Tools** > **Windows Firewall and Advanced Security**.

b) Choose **Windows Firewall and Advanced Security** > **Inbound Rules**.

c) Right-click **Inbound Rules**.

d) Click **New Rule**.

e) From the **What type of rule would you like to create** list of options, choose **Port**.

f) Click **Next**.

g) From the **Does this rule apply to TCP or UDP?** list of options, choose **TCP**.

h) From the **Does this rule apply to all local ports or specific local ports?** list of options, choose **Specific local ports**.

i) Enter 8443 and click **Next**.

j) From the **What action should be taken when a connection matches the specified conditions?** list of options, choose **Allow the connection**.

k) Click **Next**.

l) From the **When does the rule apply?** list of options, choose **Domain** only.

m) Click **Next**.

n) Enter a name and description of your choosing and click **Finish**.

Step 20 To test the configuration, log in to another host on the network, launch a web browser on the Windows server that contains the Tomcat instance and go to `https://<openam-fqdn>:8443/tomcat.gif`, where `<openam-fqdn>` is the Fully Qualified Domain Name of the Windows Server that contains the Tomcat instance. The web browser may present warning dialogs about insecure connections because the web browser does not trust the security certificates that are presented by the Tomcat instance. Either examine the certificates and add them to your local certificate store so that the browser trusts them or proceed to the web application anyway (this is less secure) using the available browser controls. If the configuration is correct, the Tomcat logo appears loaded into the web browser window.

Deploy OpenAM War On Apache Tomcat

Procedure

- Step 1** Download the recommended OpenAM release from the ForgeRock website.
- Tip** See topics related to third-party software and system requirements for Single Sign-On for details.
- Step 2** Extract the .zip file and locate the opensso.war file that is contained within it.
- Step 3** Copy the WAR file to the Windows server that is to be your OpenAM server. This Windows server should be running the previously configured Tomcat service.
- Step 4** Stop the Apache Tomcat service if it is running:
- Choose **Start > All Programs > Apache Tomcat 7.0 Tomcat7 > Configure Tomcat**.
 - From the **General** tab, click **Stop**.
- Step 5** Deploy the WAR file on the Windows server that contains the Tomcat instance by copying the WAR file to the following location: `<tomcat-dir>\webapps`.
- Example:**
- ```
C:\Program Files\Apache Software Foundation\Tomcat 7.0\webapps
```
- Note** For a description of the `<tomcat-dir>` variable, see topics related to installing the Tomcat.
- Step 6** Start the Apache Tomcat service:
- Choose **Start > All Programs > Apache Tomcat 7.0 Tomcat7 > Configure Tomcat Tomcat7**
  - From the **General** tab, click **Start**.
- Note** The WAR file will fully deploy within a couple minutes. Under the webapps folder, a new folder is created with the same name as the WAR file but with the .war extension removed.
- Step 7** Verify your configuration by launching a web browser and entering `https://<openam-fqdn>:8443/<war-file-name>`, where `<openam-fqdn>` is the FQDN of the Windows server that contains the OpenAM/Tomcat instance and `<war-file-name>` is the name of the OpenAM WAR file with the .war extension removed. If the configuration is correct, the OpenAM administration interface should load in the web browser window.

---

### Related Topics

[Third-Party Software and System Requirements for Single Sign-On](#), on page 3

## Set Up OpenAM Using GUI Configurator

The following procedure specifies a method of configuring OpenAM. If you have an existing OpenAM server or a solid understanding of OpenAM, you can configure the server differently.

OpenAM server and J2EE Policy Agents require FQDNs for the hostname of the machines on which you will perform your installations. To avoid problems with installation, configuration, and usage, Cisco highly recommends that you avoid using hostnames like “localhost” or numeric IP addresses like “192.168.1.2”.

OpenAM provides a web-based administration interface that must be accessed using a web browser, for example Mozilla Firefox. When accessing OpenAM for the first time, you must use the FQDN of the OpenAM server in the URL, for example, `https://server1.cisco.com:8443/opensso`, where the sample URL value assumes that the OpenAM WAR file is deployed as `opensso`.

OpenAM configuration and logging information is typically stored in two directories that can be found in the home directory of the user running the OpenAM/Tomcat instance, for example:

- `C:\opensso` (where the folder name matches the deployed URI for the OpenAM WAR file. For example, `opensso`.)
- `C:\.openssocfg`

If a problem occurs during the configuration, the Configurator displays an error message. If possible, correct the error and retry the configuration. The following log file directories may provide useful information.

- Tomcat Web Container logs: `tomcat-dir\logs`
- OpenAM Install log: `C:\opensso` (where the folder name matches the deployed URI for the OpenAM WAR file. For example, `opensso`.)

By default, OpenAM is deployed under `C:\opensso` on Windows platforms.

## Procedure

---

**Step 1** Open the web browser and navigate to the OpenAM server using the following URL: `https://<fqdn of openam server>:8443/<WAR filename>`.

### Example:

`https://server1.cisco.com:8443/opensso`

**Note** When you access OpenAM for the first time, you are directed to the Configurator to perform the initial configuration of the OpenAM. The Configuration Options window appears when you access the OpenAM for the first time.

**Step 2** Choose **Create Default Configuration**.

**Note** If you encounter an error, repeat steps 1 and 2 on your local machine.

**Step 3** In the **OpenSSO Configurator** window, specify and confirm passwords for the OpenAM administrator (`amAdmin`) and the default policy agent user (`UrlAccessAgent`). The default policy agent user is not used later in this example configuration; `amAdmin` is used each time you log in to OpenAM to change the configuration.

**Note** `amAdmin` is only a suggested value for the OpenAM Administrator.

**Step 4** Click **Create Configuration**.

You are notified when the configuration is complete.

**Step 5** Choose **Proceed to Login**.

**Step 6** Log in to your deployed OpenAM web application using the previously configured username and password for “`amAdmin`”.

- Step 7** From the **Access Control** tab, click **/(Top Level Realm)**.
- Step 8** From the **Authentication** tab, click **Core**.
- Step 9** Click **All Core Settings**.
- Step 10** Set the **User Profile** to **Ignored**.
- Step 11** Click **Save** to update the profile.
- Step 12** Log out of the OpenAM GUI.

## Set Up Policies On OpenAM Server

Set up policies on the OpenAM server using the policy rules detailed in the following table.

**Table 4: Policy Rules**

| Service Type                          | Name          | Resource Name                  | Action                                                |
|---------------------------------------|---------------|--------------------------------|-------------------------------------------------------|
| URL Policy Agent (with resource name) | <hostname>-01 | https://<IMP FQDN>/*           | Enable GET, Value = Allow Enable POST , Value = Allow |
|                                       | <hostname>-02 | https://<IMP FQDN>/?**         |                                                       |
|                                       | <hostname>-03 | https://<IMP FQDN>/?*?**       |                                                       |
|                                       | <hostname>-04 | https://<IMP FQDN>:8443/*      |                                                       |
|                                       | <hostname>-05 | https://<IMP FQDN>:8443/*?**   |                                                       |
|                                       | <hostname>-06 | https://<IMP FQDN>:8443/*?*?** |                                                       |

When you apply the policy rules as defined in this procedure, the IM and Presence Administration/User interfaces can only be accessed with the web browser using the following URL formats:

- https://<IMP FQDN> - For example, https://IMP-Node-01.cisco.com
- https://<IMP FQDN>:8443 - For example https://IMP-Node-01.cisco.com:8443/

It is *not* possible to access the Cisco Unified CM IM and Presence Administration/User interface using a URL that only specifies a hostname such as https://<IMP HOSTNAME> (for example, https://IMP-Node-01/).

### Procedure

- Step 1** Log in to the OpenAM Administration interface.
- Step 2** From the **Access Control** tab, choose **/(Top Level Realm)**.
- Step 3** From the **Policies** tab, click **New Policy**.

**Step 4** In the **Name** field, enter the PolicyName (for example, IMPPolicy) and click **OK**.

IMPPolicy is only a suggested value. You can use any valid name value. This value is not required later in this configuration

**Step 5** Choose the new policy, IMPPolicy, for editing.

**Step 6** Click **Rules**.

**Step 7** Add the rules in the following order:

- a) Under the **Rules** section, click **New**.
- b) Choose **Service Type** as **URL Policy Agent (with resource name)**
- c) Click **Next**.
- d) In the **Name** field, enter the suggested rule Name from the Policy Rules table above, replacing <hostname> with the actual hostname of the IM and Presence node.
- e) In the ResourceName field provided, enter the corresponding Resource Name for this rule, replacing <IMP FQDN> with the actual Fully Qualified Domain Name of the IM and Presence node.
- f) Check the **GET** action with a value of **Allow**.
- g) Check the **POST** action with a value of **Allow**.
- h) Click **Finish** to complete the rule update.
- i) Click **Save** to save the policy update.
- j) Repeat this entire step for each rule in the above table, then click **Finish**.

You must add this set of six rules for each IM and Presence Service node that is enabled for SSO.

**Step 8** You must add a single Subject to the policy. Add the Subject as follows:

- a) Under the **Subjects** section, click **New**.
- b) Choose **Authenticated Users** as Subject Type.
- c) Click **Next**.
- d) Enter **IMPSubject** as the **Name** value.

IMPSubject is only a suggested value. You can use any valid value. This value is not required later in this configuration.

- e) Click **Finish** to complete the Subject update.
- f) Click **Save** to save the policy update.

Only a single Subject is required for this policy even if multiple IM and Presence Service nodes are enabled for Single Sign-On.

**Step 9** You must add a single Condition to the policy. Add the Condition as follows:

- a) Under the **Conditions** section, click **New**.
- b) Choose **Active Session Time** as Condition Type.
- c) Click **Next**.
- d) Enter **IMPTimeOutCondition** as the **Name** value.

IMPTimeOutCondition is only a suggested value. You can use any valid name value. This value required later in this configuration.

- e) Enter **120** as the **Maximum Session Time (minutes)**.
- f) Ensure the **Terminate Session** field is set to **No**.
- g) Click **Finish** to complete the Subject update.
- h) Click **Save** to save the policy update.

Note that only a single Condition is required for this policy, even if multiple IM and Presence Service nodes are enabled for SSO.

## Set Up SSO Module Instance

This single module instance can be shared by multiple IM and Presence Service nodes that are configured for SSO as long as the same Active Directory domain is used throughout the deployment. Deployment scenarios involving more than one Active Directory domain are not covered in this documentation.

### Procedure

- Step 1** Log in to the OpenAM administration interface.
- Step 2** From the **Access Control** tab, click **Top Level Realm**.
- Step 3** From the **Authentication** tab, click **Module Instances**.
- Step 4** In the **Module Instances** window, click **New**.
- Step 5** Enter a name for the new login module instance (for example, IMPKRB) and choose **Windows Desktop SSO** from the **Type** list.
- Step 6** Click **OK**.
- This module instance name will be used later when enabling SSO on the IM and Presence node.
- Step 7** Click **Save**.
- Step 8** In the **Module Instances** window, choose the name of the new login module (for example, IMPKRB) and provide the following information:

| Parameter                               | Description                                                                                                                                                                                                                                                                 |
|-----------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Service Principal                       | This value should exactly match the value specified that was specified when you provisioned the Active Directory for Single Sign-On. For example, -princ value.<br><br>For example, HTTP/server1.cisco.com@CISCO.COM (using openAM server name and domain).                 |
| Keytab File Name                        | This value should be the location of the keytab file that was created when you provisioned the Active Directory for Single Sign-On.<br><br>For example, C:\keytab\server1.HTTP.keytab (on Windows platform).                                                                |
| Kerberos Realm                          | Domain for OpenAM server. For example, CISCO.COM.                                                                                                                                                                                                                           |
| Kerberos Server Name (Active Directory) | Provide the FQDN of the AD server. The AD server is normally the Kerberos Domain Controller. If multiple Kerberos Domain Controllers exist for failover purposes, all Kerberos Domain Controllers can be set using a colon (:) as the separator. For example, ad.cisco.com. |
| Authentication Level                    | For example, 22                                                                                                                                                                                                                                                             |

**Step 9** Click **Save**.

The module instance is created and called IMPKRB.

**Step 10** Validate that the SSO Module is working correctly by logging in to a Windows Desktop session as a valid Windows user (a valid end user that exists in the AD; do not use the Administrator account). Access the following URL:

**Note** The browser must be configured for SSO.

`https://<openam-FQDN>:8443/<war-file-name>/UI/Login?module=<SSO_Module>`

Where:

| Parameter                          | Description                                                    |
|------------------------------------|----------------------------------------------------------------|
| <code>&lt;openam-FQDN&gt;</code>   | The FQDN of the OpenAM server.                                 |
| <code>&lt;war-file-name&gt;</code> | The name of the deployed OpenAM WAR file, for example opensso. |
| <code>&lt;SSO_Module&gt;</code>    | The name of the WindowsDesktopSSO module.                      |

A screen notifies you that login was successful.

## Set Up J2EE Agent Profile On OpenAM Server

The J2EE Agent is an internal component that is instantiated on each IM and Presence Service node with SSO enabled. You must configure an associated J2EE Agent Profile on the OpenAM server for each J2EE Agent. As such, a J2EE Agent Profile is required for every IM and Presence Service node with SSO enabled. If multiple nodes are to be configured for SSO, a J2EE Agent Profile must be created for each additional node.

The following table lists the J2EE profile agent parameters required for the IM and Presence Service node.

**Table 5: J2EE Profile Agent Setup Parameter Descriptions**

| Parameter     | Description                                                                                                                                                                                                             |
|---------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Name          | Name of the J2EE Policy Agent. For example, <code>&lt;hostname-j2ee-agent&gt;</code> where <i>hostname</i> is the hostname of the IM and Presence Service node, for example, <code>impNode01-j2ee-agent</code> .        |
| Password      | Password of the J2EE Policy Agent.<br><b>Note</b> The password will be used when you enable SSO on IM and Presence Service.                                                                                             |
| Configuration | Controls where the J2EE Policy Agent configuration is stored.<br>Choose <b>Centralized</b>                                                                                                                              |
| Server URL    | The complete URL of the OpenAM server.<br>For example, <code>https://&lt;OpenAM FQDN&gt;:8443/opensso</code> where <code>opensso</code> is the name of the OpenAM WAR file with the <code>.war</code> extension removed |

| Parameter | Description                                                                                                                                                                                                                                                                                                                                                                                   |
|-----------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Agent URL | <p>The URL of the J2EE Policy Agent to which OpenAM publishes notifications.</p> <p>For example, <code>https://&lt;IMP_FQDN&gt;:8443/agentapp</code></p> <p><b>Note</b> The value “agentapp” is the key item from the sample URL above. If you use the agentapp value, enter agentapp when you were prompted to <b>Enter the relative path where the policy agent should be deployed</b>.</p> |

The following table lists the login form URIs for each web GUI application on IM and Presence Service.

**Table 6: Login Form URIs for Web GUI Applications On IM and Presence Service**

| Application                                     | Sample value                         |
|-------------------------------------------------|--------------------------------------|
| Cisco Unified CM IM and Presence Administration | /cupadmin/WEB-INF/pages/logon.jsp    |
| Cisco Unified IM and Presence Serviceability    | /ccmservice/WEB-INF/pages/logon.jsp  |
| Cisco Unified IM and Presence Reporting         | /cucreports/WEB-INF/pages/logon.jsp  |
| Cisco Unified IM and Presence OS Administration | /cmpatform/WEB-INF/pages/logon.jsp   |
| IM and Presence Disaster Recovery System        | /drf/WEB-INF/pages/logon.jsp         |
| Real-Time Monitoring Tool (RTMT)                | /ast/WEB-INF/pages/logon.jsp         |
| Cisco Client Profile Agent                      | /ssoservlet/WEB-INF/pages/logon.html |

## Procedure

- 
- Step 1** Log in to OpenAM administration interface.
  - Step 2** From the **Access Control** tab, click **/(Top Level Realm)**.
  - Step 3** From the **Agents** tab, choose the **J2EE** tab.
  - Step 4** In the **Agents** section, click **New**.
  - Step 5** Enter the J2EE setup parameters.
  - Step 6** Click **Create**.  
A J2EE Agent with the name of <hostname-j2ee-agent> is created.
  - Step 7** Choose the J2EE agent that you created.
  - Step 8** From the **Application** tab, under the **Login Processing** section, add the Login Form URIs for each web GUI application on IM and Presence Service.
  - Step 9** Click **Save**.
  - Step 10** From the **OpenAM Services** tab, add OpenSSO Login URL as `https://<OpenAM_FQDN>:8443/<war-file-name>/UI/Login?module=<SSO_Module>`.

**Tip** The `<SSO_Module>` value you enter should match the value you entered when you set up the SSO module instance. For example,  
`https://server1.cisco.com:8443/opensso/UI/Login?module=IMPKRB`.

- Step 11** In the text area, remove all URLs other than the Login URL. Only the Login URL specified in the previous step should be listed in the text area.
- Step 12** Click **Save**.
- Step 13** Click **Back to Main Page**.
- Step 14** Repeat Steps 4 through 13 to create a J2EE Profile Agent for every other IM and Presence Service node to be enabled for SSO.

---

#### Related Topics

[Enable Single Sign-On Using GUI](#), on page 28

## Set OpenAM Session Timeout

The OpenAM session timeout must be set to a value that is higher than the session timeout parameter that is set on the IM and Presence Service node. To determine the session timeout value on the IM and Presence Service node, enter the following command using the CLI:

```
show webapp session timeout
```

#### Procedure

---

- Step 1** Log in to the OpenAM Administration interface.
- Step 2** From the **Configuration** tab, choose **Global**.
- Step 3** Click **Session**.
- Step 4** Click **Dynamic Attributes**.
- Step 5** Enter a value in the **Maximum Idle Time** field.
- Step 6** Click **Save**.
- 

## Import OpenAM Certificate Into IM and Presence Service

IM and Presence Service nodes with SSO communicate with the OpenAM server over an encrypted channel. Establishing an encrypted communication channel requires each IM and Presence Service node with SSO to trust the security certificate presented by the OpenAM server. An IM and Presence Service node trusts a security certificate by importing the required security certificates into the tomcat-trust trust store.

The required procedure is dependent on the security configuration that you used when you created the Java keystore for the OpenAM Server.

- Use a self-signed security certificate for OpenAM/Tomcat instance
- Use a CA signed security certificate for OpenAM/Tomcat instance



**Caution** Importing OpenAM certificates affects service; Cisco highly recommends that you import the OpenAM certificates during a maintenance window.



**Note** For information about importing certificates, see *Cisco Unified System Maintenance Guide for IM and Presence*.

## Procedure

- Step 1** Sign in to the Cisco Unified CM IM and Presence Administration for the IM and Presence database publisher node that is to be enabled with SSO.
- Step 2** Choose **System > Security > Certificate Import Tool**.
- Step 3** Choose **Tomcat Trust** as the **Certificate Trust Store**.
- Step 4** Enter the Fully Qualified Domain Name of the OpenAM server as the **Peer Server**.
- Step 5** Enter 8443 as the **Peer Server Port**.
- Step 6** Click **Submit**.

The Certificate Import Tool executes two tests:

- **Verify reachability of the specified certificate server (pingable)** - checks that the OpenAM server is reachable by this IM and Presence node. If this test fails, it may be due to the firewall on the OpenAM base Windows system blocking the ping operation. See topics related to importing the OpenAM certificate into IM and Presence Service to allow a ping through a Windows firewall.
- **Verify SSL connectivity to the specified certificate server** - checks if this IM and Presence node can securely connect to the OpenAM server. If this test fails due to “Missing certificates”, the required certificates are missing and a secure connection can not be established. If this test fails, proceed to the next step. If this test passes, proceed to Step 15.

**Note** If this test fails with the message “The Troubleshooter has encountered an internal error”, troubleshoot the certificate failure before you continue to the next step.

- Step 7** Click **Configure** to open the Certificate Viewer. The Certificate Viewer provides a visual representation of the certificate chain presented by OpenAM during a TLS connection handshake. This indicates which certificates must be imported into this IM and Presence Service node.
- Step 8** Inspect the certificates in the chain and ensure that you trust the issuers.
- Step 9** Check **Accept Certificate Chain** and click **Save**.  
  
The required certificates from the chain are now imported into the tomcat-trust trust store of this IM and Presence Service node.
- Step 10** Click **Close**.  
  
The Certificate Import Tool reports that the “Certificates verified successfully”.
- Step 11** Restart the Cisco Intercluster Sync Agent service on this node using the following CLI command: **utils service restart Cisco Intercluster Sync Agent**.
- Step 12** Restart the Tomcat service on this node using the following CLI command: **utils service restart Cisco Tomcat**

- Step 13** Repeat Steps 11 and 12 for each IM and Presence Service subscriber node in this cluster.
- Step 14** Verify the secure connection by using the Certificate Import Tool on each subscriber node in this cluster.
- Sign in to Cisco Unified CM IM and Presence Administration of the IM and Presence Service subscriber node that is being configured for SSO.
  - Choose **System > Security > Certificate Import Tool**.
  - Choose **Tomcat Trust** as the **Certificate Trust Store**
  - Enter the FQDN of the OpenAM server as the **Peer Server**.
  - Enter **8443** as the **Peer Server Port**.
- Step 15** Repeat this procedure for all IM and Presence Service clusters for which you will be enabling SSO.

---

### Related Topics

[Important Information Before Single Sign-On Setup](#), on page 4  
[Certificate Failure](#)

## Activate Single Sign-On

When enabling SSO, you must perform the following tasks in the order indicated.




---

### Caution

Enabling SSO affects service; Cisco highly recommends that you enable SSO during a maintenance window.

---

## Configure Access Permissions Before Enable SSO

It is important to understand the user access permissions that should be in place before and after SSO is enabled. Understanding the permissions can help avoid situations in which users have incorrect permissions when accessing IM and Presence Service applications.

*Table 7: Prerequisites for Enabling Single-Sign On*

| Application | Notes |
|-------------|-------|
|-------------|-------|

|                                                                                                                                                                                                                                           |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <p>Cisco Unified CM IM and Presence Administration</p> <ul style="list-style-type: none"> <li>• Cisco Unified CM IM and Presence Administration</li> <li>• IM and Presence Serviceability</li> <li>• IM and Presence Reporting</li> </ul> | <p>Before enabling SSO, ensure that an end user who is a member of the necessary User Groups exists in order to facilitate administration access.</p> <p>The default administrator application user that was created at the time of installation has the following:</p> <p>Groups:</p> <ul style="list-style-type: none"> <li>• Standard Audit Users</li> <li>• Standard CCM Super Users</li> </ul> <p>Roles:</p> <ul style="list-style-type: none"> <li>• Standard AXL API Access</li> <li>• Standard Admin Rep Tool Admin</li> <li>• Standard Audit Log Administration</li> <li>• Standard CCM Admin Users</li> <li>• Standard CCMADMIN Administration</li> <li>• Standard CUREporting</li> <li>• Standard EM Authentication Proxy Rights</li> <li>• Standard SERVICEABILITY Administration</li> <li>• Standard SSO Config Admin</li> </ul> <p>Any end user that is a member of the above User Groups with those Roles will have full access rights to IM and Presence Service, similar to that of the default administrator.</p> <p>To view the default application user on IM and Presence Service, choose <b>Cisco Unified CM Administration &gt; User Management &gt; Application User &gt; Find</b>. Choose the default application user (that was created during install) to view their details.</p> <p>To assign an end user to these groups on IM and Presence Service, choose <b>Cisco Unified CM Administration &gt; User Management &gt; User Settings &gt; Access Control Group &gt; Find</b>. Choose a group and click <b>Add End Users</b>. Search for the desired end user, choose the user, and click <b>Add End Users to Group</b>.</p> |
|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                                                                                                                                                                                                                              |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <p>Cisco Unified IM and Presence Operating System Administration</p> <ul style="list-style-type: none"> <li>• IM and Presence Operating System Administration</li> <li>• IM and Presence Disaster Recovery System</li> </ul> | <p>Normally, the default administrator application user does not have access to these web applications. These web applications are only accessible by the Cisco Unified IM and Presence Operating System administrator. This administrator has access to the Administration CLI in addition to these web applications.</p> <p>After SSO is enabled for these applications, the applications are accessible by any end user that has the same permissions as the default administrator application user.</p> |
| <p>Real-Time Monitoring Tool</p>                                                                                                                                                                                             | <p>Before enabling SSO, ensure that an end user exists that is a member of the necessary user groups to allow administrative access to the Real-Time Monitoring Tool.</p> <p>Refer to the note for Cisco Unified CM IM and Presence Administration above.</p>                                                                                                                                                                                                                                               |

## Enable Single Sign-On Using GUI

This Cisco Unified IM and Presence Operating System Administration application is split into three components:

- Status
- Server Settings
- Select Applications

### Status

A warning message displays indicating that the change in SSO settings causes Tomcat to restart.

The following error messages may display when you enable the SSO application:

- Invalid Open Access Manager (OpenAM) server URL - This error message displays when you enter an invalid OpenAM server URL.
- Invalid profile credentials - This error message displays when you enter a wrong profile name or wrong profile password or both.
- Security trust error - This error message displays when this IM and Presence Service node does not trust the certificate chain presented by the OpenAM server.




---

**Note** If you see any of the above error messages while enabling SSO, then the status changes to that error.

---

### Server Settings

You can edit the server settings only when SSO is disabled for all applications.

### Select Applications

You can enable or disable SSO on any of the following applications:

- Cisco Unified CM IM and Presence Administration – Enables SSO for Cisco Unified CM IM and Presence Administration, Cisco Unified IM and Presence Serviceability, and Cisco Unified IM and Presence Reporting.

- Cisco Unified IM and Presence Operating System Administration – Enables SSO for Cisco Unified IM and Presence Operating System Administration and Disaster Recovery System.
- RTMT – Enables the web application for the Real-Time Monitoring Tool.
- Cisco UP Client Profile Agent – Enables SSO for the Cisco UP Client Profile Agent service. This option is only applicable to customers using Common Access Card (CAC) sign-on.

### Procedure

- 
- Step 1** Choose **Cisco Unified IM and Presence Operating System Administration > Security > Single Sign On**.
- Step 2** Enter the URL of the Open Access Manager (OpenAM) server:
- Example:**
- ```
https://server1.cisco.com:8443/opensso
```
- Step 3** Enter the relative path where the policy agent should be deployed. The relative path must be alphanumeric, such as *agentapp* for example.
- Step 4** Enter the name of the profile that is configured for this policy agent, for example "cupnode01-j2ee-agent".
- Step 5** Enter the password of the profile name.
- Step 6** Enter the login Module instance name that is configured for Windows Desktop SSO, such as IMPKRB. See topics related to setting up the SSO module instance for more information..
- Step 7** Click **Save**.
- Step 8** In the **Confirmation** dialog box, click **OK** to restart Tomcat.
-

Deactivate Single Sign-On

If you choose to disable SSO, you must perform the following tasks in the order indicated.

Configure Access Permissions Before Disable SSO

If SSO is disabled for any IM and Availability web application that supports SSO, all users accessing that application need to provide a username and password. Cisco recommends that if you are an IM and Presence Service administrator intending to disable SSO for any IM and Availability web applications, ensure that users can access the application after SSO is disabled. This action is important to avoid inadvertently locking out the active IM and Presence Service administration account.

Table 8: Prerequisites for Disabling Single Sign-On

Application	Notes
-------------	-------

Cisco Unified CM IM and Presence Administration (Cisco Unified CM IM and Presence Administration, IM and Presence Serviceability, IM and Presence Reporting)	<p>Before disabling SSO, ensure that an application user exists with a known username/password and that this user is a member of the necessary User Groups.</p> <p>The default administrator application user that was created at the time of installation has the following:</p> <p>Groups:</p> <ul style="list-style-type: none"> • Standard Audit Users • Standard CCM Super Users <p>Roles:</p> <ul style="list-style-type: none"> • Standard AXL API Access • Standard Admin Rep Tool Admin • Standard Audit Log Administration • Standard CCM Admin Users • Standard CCMADMIN Administration • Standard CUReporting • Standard EM Authentication Proxy Rights • Standard SERVICEABILITY Administration • Standard SSO Config Admin <p>Any application user that is a member of the above User Groups with those Roles will have full access rights to IM and Presence Service if SSO is disabled.</p> <p>To view the application users on IM and Presence, select Cisco Unified CM Administration > User Management > Application User > Find. Select a user to view their details.</p>
Cisco Unified IM and Presence Operating System Administration (IM and Presence Operating System Administration, IM and Presence DRS)	<p>Before disabling SSO, ensure that an OS Administration user exists with a known username/password and that this user has access to the Cisco Unified IM and Presence Operating System Administration CLI. After SSO is disabled, this user has access rights to the Cisco Unified IM and Presence Operating System Administration GUIs.</p>
Real-Time Monitoring Tool	<p>Before disabling SSO, ensure that an application user with a known username/password exists and that this user has the same access rights as the user specified for Cisco Unified CM IM and Presence Administration (Cisco Unified CM IM and Presence Administration, IM and Presence Serviceability, and IM and Presence Reporting).</p>

Disable Single Sign-On

You can disable SSO using either the GUI, as described in this procedure, or the CLI. For information about how to disable SSO using the CLI, see the **utils sso disable** command in the *Command Line Interface Guide for Cisco Unified Communications Solutions*.

Procedure

- Step 1** Choose **Cisco Unified OS Administration > Security > Single Sign On**.
 - Step 2** Deselect all applications that were previously enabled for SSO.
 - Step 3** Click **Save**.
 - Step 4** In the **Confirmation** dialog box, click **OK** to restart Tomcat.
-

Uninstall OpenAM on Windows

Before you begin

Ensure that you have completed the following tasks before you uninstall OpenAM:

- Configure access permissions before disabling SSO.
- Disable Single Sign-On

Procedure

- Step 1** Access the OpenAM server Windows desktop and choose **Start > All Programs > Apache Tomcat 7.0 Tomcat7 > Configure Tomcat**.
Note This menu path assumes you are using Tomcat 7.
- Step 2** From the **General** tab, click **Stop** to stop the Tomcat service if it is running on the OpenAM server.
- Step 3** Delete the OpenAM configuration data. This data is typically stored in two directories that can be found in the home directory of the user running the Tomcat instance. For example, `C:\opensso` (where the folder name matches the deployed URI for the OpenAM WAR file such as `opensso`) and `C:\.openssoconfig`.
- Step 4** Delete the deployed OpenAM WAR file and the WAR file itself from the following location on the OpenAM/Tomcat instance: `tomcat-dir\webapps`.
Example:
`C:\Program Files\Apache Software Foundation\Tomcat 7\webapps`
Tip See topics related to Tomcat installation for a description of the `tomcat-dir` variable.
- Step 5** Access the Windows desktop of the OpenAM server and choose **Start > All Programs > Apache Tomcat 7.0 Tomcat7 > Configure Tomcat**.

Step 6 From the **General** tab, click **Start** to start the Tomcat service.

Related Topics

[Configure Access Permissions Before Disable SSO](#), on page 29

[Disable Single Sign-On](#), on page 31

[Install Tomcat](#), on page 14

Set Debug Level

You can gather additional debug information the IM and Presence Service node by setting the log level for the J2EE Policy Agent accordingly. The log level for this component is configured on the OpenAM server itself. The default log level is Error. You can change the log level to Message to provide additional debug information. Cisco recommends that you use the Message log level only for short periods of time, because the associated log files can grow quite large.

Procedure

-
- Step 1** Sign in to OpenAM (https://<OpenAM_FQDN>:8443/opensso) from your web browser (for example, Mozilla Firefox).
- Step 2** From the **Access Control** menu, choose **Top Level Realm > Agents > J2EE**.
- Step 3** Under the **General** heading, choose **Agent Debug Level**.
- Step 4** Under the **Agent Debug Level**, specify the desired level (**Message** or **Error**).
- Step 5** Click **Save**.
- Step 6** On the IM and Presence Service node, restart the Cisco Tomcat service.
- Access the IM and Presence Administration CLI.
 - Execute the following command: **utils service restart Cisco Tomcat**.
- Step 7** Retrieve the logs using Cisco Unified Real Time Monitoring Tool for IM and Presence Service by browsing and downloading the logs for the Cisco SSO component.

Note If users experience problems while SSO is enabled, you must disable SSO and then re-enable it in order to access the debug.out logs from Cisco Unified Real Time Monitoring Tool.
