



Configuring Dynamic DNS

This chapter describes how to configure DDNS update methods and includes the following topics:

- [Information About DDNS, page 15-1](#)
- [Licensing Requirements for DDNS, page 15-2](#)
- [Guidelines and Limitations, page 15-2](#)
- [Configuring DDNS, page 15-2](#)
- [Configuration Examples for DDNS, page 15-3](#)
- [DDNS Monitoring Commands, page 15-9](#)
- [Feature History for DDNS, page 15-9](#)

Information About DDNS

DDNS update integrates DNS with DHCP. The two protocols are complementary: DHCP centralizes and automates IP address allocation; DDNS update automatically records the association between assigned addresses and hostnames at predefined intervals. DDNS allows frequently changing address-hostname associations to be updated frequently. Mobile hosts, for example, can then move freely on a network without user or administrator intervention. DDNS provides the necessary dynamic update and synchronization of the name-to-address mapping and address-to-name mapping on the DNS server. To configure the DNS server for other uses, see the [“Configuring the DNS Server” section on page 13-13](#). To configure DHCP, see the [“Configuring the DHCP Server” section on page 14-4](#).

EDNS allows DNS requesters to advertise the size of their UDP packets and facilitates the transfer of packets larger than 512 octets. When a DNS server receives a request over UDP, it identifies the size of the UDP packet from the OPT resource record (RR) and scales its response to contain as many resource records as are allowed in the maximum UDP packet size specified by the requester. The size of the DNS packets can be up to 4096 bytes for BIND or 1280 bytes for the Windows 2003 DNS Server. Several additional **message-length maximum** commands are available:

- The existing global limit: **message-length maximum 512**
- A client or server specific limit: **message-length maximum client 4096**
- The dynamic value specified in the OPT RR field: **message-length maximum client auto**

If the three commands are present at the same time, the ASA enforces the minimum of the three specified values.

Licensing Requirements for DDNS

The following table shows the licensing requirements for DDNS:

Model	License Requirement
All models	Base License.

Guidelines and Limitations

Failover Guidelines

Supports Active/Active and Active/Standby failover.

Firewall Mode Guidelines

Supported in routed firewall mode.

Context Mode Guidelines

Supported in single and multiple context modes.

Supported in transparent mode for the DNS Client pane.

IPv6 Guidelines

Supports IPv6.

Configuring DDNS

This section describes examples for configuring the ASA to support Dynamic DNS. When you use DHCP and dynamic DNS update, this configures a host automatically for network access whenever it attaches to the IP network. You can locate and reach the host using its permanent, unique DNS hostname. Mobile hosts, for example, can move freely without user or administrator intervention.

DDNS provides address and domain name mapping so that hosts can find each other, even though their DHCP-assigned IP addresses change frequently. The DDNS name and address mapping is held on the DHCP server in two resource records: the A RR includes the name-to-IP address mapping, while the PTR RR maps addresses to names. Of the two methods for performing DDNS updates—the IETF standard defined by RFC 2136 and a generic HTTP method—the ASA supports the IETF method in this release.

The two most common DDNS update configurations are the following:

- The DHCP client updates the A RR, while the DHCP server updates the PTR RR.
- The DHCP server updates both the A RR and PTR RR.

In general, the DHCP server maintains DNS PTR RRs on behalf of clients. Clients may be configured to perform all desired DNS updates. The server may be configured to honor these updates or not. To update the PTR RR, the DHCP server must know the FQDN of the client. The client provides an FQDN to the server using a DHCP option called Client FQDN.

Configuration Examples for DDNS

The following examples present five common scenarios:

- [Example 1: Client Updates Both A and PTR RRs for Static IP Addresses, page 15-3](#)
- [Example 2: Client Updates Both A and PTR RRs; DHCP Server Honors Client Update Request; FQDN Provided Through Configuration, page 15-4](#)
- [Example 3: Client Includes FQDN Option Instructing Server Not to Update Either RR; Server Overrides Client and Updates Both RRs., page 15-5](#)
- [Example 4: Client Asks Server To Perform Both Updates; Server Configured to Update PTR RR Only; Honors Client Request and Updates Both A and PTR RR, page 15-6](#)
- [Example 5: Client Updates A RR; Server Updates PTR RR, page 15-7](#)

Example 1: Client Updates Both A and PTR RRs for Static IP Addresses

The following example shows how to configure the client to request that it update both A and PTR resource records for static IP addresses.

To configure this scenario, perform the following steps:

Detailed Steps

	Command	Purpose
Step 1	ddns update method <i>name</i> Example: ciscoasa(config)# ddns update method ddns-2	Creates a DDNS update method ddns-2 that dynamically updates DNS resource records (RRs).
Step 2	ddns both Example: ciscoasa(DDNS-update-method)# ddns both	Specifies that the client updates both the DNS A and PTR resource records (RRs).
Step 3	interface <i>mapped_name</i> Example: ciscoasa(DDNS-update-method)# interface eth1	Configures an interface eth1 and enters interface configuration mode.

	Command	Purpose
Step 4	<pre>ddns update [method-name hostname hostname]</pre> <p>Example:</p> <pre>ciscoasa(config-if)# ddns update ddns-2 ciscoasa(config-if)# ddns update hostname asa.example.com</pre>	Associates the the DDNS method ddns-2 with the eth1 interface and an update hostname.
Step 5	<pre>ip address ip_address [mask] [standby ip_address]</pre> <p>Example:</p> <pre>ciscoasa(config-if)# ip address 10.0.0.40 255.255.255.0</pre>	Configures a static IP address for the interace eth1.

Example 2: Client Updates Both A and PTR RRs; DHCP Server Honors Client Update Request; FQDN Provided Through Configuration

The following example shows how to configure the DHCP client to request that it update both the A and PTR RRs, and the DHCP server to honor these requests.

To configure this scenario, perform the following steps:

Detailed Steps

	Command	Purpose
Step 1	<pre>dhcp-client update dns [server {both none}]</pre> <p>Example:</p> <pre>ciscoasa(config)# dhcp-client update dns server none</pre>	Configures the DHCP client to request that the DHCP server perform no updates
Step 2	<pre>ddns update method name</pre> <p>Example:</p> <pre>ciscoasa(config)# ddns update method ddns-2</pre>	Creates a DDNS update method ddns-2 that dynamically updates DNS resource records (RRs)
Step 3	<pre>ddns both</pre> <p>Example:</p> <pre>ciscoasa(DDNS-update-method)# ddns both</pre>	Specifies that the client updates both the DNS A and PTR resource records (RRs).
Step 4	<pre>interface mapped_name</pre> <p>Example:</p> <pre>ciscoasa(DDNS-update-method)# interface Ethernet0</pre>	Configures an interface Ethernet 0and enters interface configuration mode.

	Command	Purpose
Step 5	ddns update [<i>method-name</i> hostname <i>hostname</i>] Example: <pre>ciscoasa(config-if)# ddns update ddns-2 ciscoasa(config-if)# ddns update hostname asa.example.com</pre>	Associates the DDNS method ddns-2 with the Ethernet0 interface and an update hostname.
Step 6	ip address dhcp Example: <pre>ciscoasa(if-config)# ip address dhcp</pre>	Uses DHCP to obtain an IP address for the interface.
Step 7	dhcpd update dns [both] [override] [interface <i>srv_ifc_name</i>] Example: <pre>ciscoasa(if-config)# dhcpd update dns</pre>	Configures DHCP server to perform DDNS updates.

Example 3: Client Includes FQDN Option Instructing Server Not to Update Either RR; Server Overrides Client and Updates Both RRs.

The following example shows how to configure the DHCP client to include the FQDN option that instruct the DHCP server not to honor either the A or PTR updates. The example also shows how to configure the server to override the client request. As a result, the client does not perform any updates.

To configure this scenario, perform the following steps:

Detailed Steps

	Command	Purpose
Step 1	ddns update method <i>name</i> Example: <pre>ciscoasa(config)# ddns update method ddns-2</pre>	Creates a DDNS update method ddns-2 that dynamically updates DNS resource records (RRs).
Step 2	ddns both Example: <pre>ciscoasa(DDNS-update-method)# ddns both</pre>	Specifies that the client updates both the DNS A and PTR resource records (RRs).
Step 3	interface <i>mapped_name</i> Example: <pre>ciscoasa(DDNS-update-method)# interface Ethernet0</pre>	Configures an interface Ethernet 0 and enters interface configuration mode.

	Command	Purpose
Step 4	<pre>ddns update [method-name hostname hostname]</pre> <p>Example:</p> <pre>ciscoasa(config-if)# ddns update ddns-2 ciscoasa(config-if)# ddns update hostname asa.example.com</pre>	Associates the the DDNS method ddns-2 with the Ethernet0 interface and an update hostname.
Step 5	<pre>dhcp-client update dns [server {both none}]</pre> <p>Example:</p> <pre>ciscoasa(config)# dhcp-client update dns server none</pre>	Configures the DHCP client to request that the DHCP server perform no updates.
Step 6	<pre>ip address dhcp</pre> <p>Example:</p> <pre>ciscoasa(if-config)# ip address dhcp</pre>	Uses DHCP to obtain an IP address for the interface.
Step 7	<pre>dhcpcd update dns [both] [override] [interface srv_ifc_name]</pre> <p>Example:</p> <pre>ciscoasa(if-config)# dhcpcd update dns both override</pre>	Configures DHCP server to override the client update requests.

Example 4: Client Asks Server To Perform Both Updates; Server Configured to Update PTR RR Only; Honors Client Request and Updates Both A and PTR RR

The following example shows how to configure the server to perform only PTR RR updates by default. However, the server honors the client request that it perform both A and PTR updates. The server also forms the FQDN by appending the domain name (example.com) to the hostname that the client (asa) has provided.

To configure this scenario, perform the following steps:

Detailed Steps

	Command	Purpose
Step 1	interface <i>mapped_name</i> Example: ciscoasa(config)# interface Ethernet0	Configures an interface Ethernet 0.
Step 2	dhcp-client update dns [server { both none }] Example: ciscoasa(config-if)# dhcp-client update dns both	DHCP client requests that the DHCP server update both the DNS A and PTR resource records.
Step 3	ddns update [<i>method-name</i> hostname <i>hostname</i>] Example: ciscoasa(config-if)# ddns update hostname asa	Configures the DHCP client on interface Ethernet 0.
Step 4	dhcpd update dns [both] [override] [interface <i>srv_ifc_name</i>] Example: ciscoasa(config-if)# dhcpd update dns	Configures DHCP server to perform DDNS updates.
Step 5	dhcpd domain <i>domain_name</i> [interface <i>if_name</i>] Example: ciscoasa(config-if)# dhcpd domain example.com	Defines the DNS domain name for DHCP clients.

Example 5: Client Updates A RR; Server Updates PTR RR

The following example shows how to configure the client to update the A resource record and how to configure the server to update the PTR records. Also, the client uses the domain name from the DHCP server to form the FQDN.

To configure this scenario, perform the following steps:

Detailed Steps

	Command	Purpose
Step 1	ddns update method <i>name</i> Example: <pre>ciscoasa(config)# ddns update method ddns-2</pre>	Creates a DDNS update method ddns-2 that dynamically updates DNS resource records (RRs).
Step 2	ddns [both] Example: <pre>ciscoasa(DDNS-update-method)# ddns</pre>	Specifies a dynamic DNS (DDNS) update method.
Step 3	interface <i>mapped_name</i> Example: <pre>ciscoasa(DDNS-update-method)# interface Ethernet0</pre>	Configures an interface Ethernet 0.
Step 4	dhcp-client update dns [server { both none }] Example: <pre>ciscoasa(config-if)# dhcp-client update dns</pre>	Configures the update parameters that the DHCP client passes to the DHCP server.
Step 5	ddns update [<i>method-name</i> hostname <i>hostname</i>] Example: <pre>ciscoasa(config-if)# ddns update ddns-2 ciscoasa(config-if)# ddns update hostname asa</pre>	Associates the the DDNS method ddns-2 with the Ethernet0 interface and an update hostname.
Step 6	dhcpd update dns [both] [override] [interface <i>srv_ifc_name</i>] Example: <pre>ciscoasa(if-config)# dhcpd update dns</pre>	Configures DHCP server to perform DDNS updates.
Step 7	dhcpd domain <i>domain_name</i> [interface <i>if_name</i>] Example: <pre>ciscoasa(config-if)# dhcpd domain example.com</pre>	Defines the DNS domain name for DHCP clients.

DDNS Monitoring Commands

To monitor DDNS, enter one of the following commands:

Command	Purpose
<code>show running-config ddns</code>	Shows the current DDNS configuration.
<code>show running-config dns server-group</code>	Shows the current DNS server group status.

Feature History for DDNS

Table 15-1 lists each feature change and the platform release in which it was implemented.

Table 15-1 Feature History for DDNS

Feature Name	Releases	Feature Information
DDNS	7.0(1)	We introduced this feature. We introduced the following commands: ddns , ddns update , dhcp client update dns , dhcpd update dns , show running-config ddns , and show running-config dns server-group .

