

Configure a Gateway of Last Resort that Uses IP Commands

Contents

[Introduction](#)

[Prerequisites](#)

[Requirements](#)

[Components Used](#)

[Conventions](#)

[Background Information](#)

[Use Command ip default-gateway](#)

[Use Command ip default-network](#)

[Flag a Default Network](#)

[Use Different Routing Protocols](#)

[Use Command ip route 0.0.0.0 0.0.0.0](#)

[Summary](#)

[Related Information](#)

Introduction

This document describes how to configure a default route or gateway of last resort.

Prerequisites

Requirements

There are no specific requirements for this document.

Components Used

This document is not restricted to specific software and hardware versions. The command outputs shown were taken from a Cisco 3900 Series router with Cisco IOS® Software Release 15M.

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, ensure that you understand the potential impact of any command.

Conventions

For more information on document conventions, see the [Cisco Technical Tips Conventions](#).

Background Information

Default routes are used to direct packets addressed to networks not explicitly listed in the routing table.

Default routes are invaluable in topologies where it is not desirable to learn all the more specific networks, as in case of stub networks, or not feasible due to limited system resources such as memory and limited resources.

The next IP commands are used and described in more detail:

- **ip default-gateway**
- **ip default-network**
- **ip route 0.0.0.0 0.0.0.0**


Use Command **ip default-gateway**

The **ip default-gateway** command differs from the other two commands as it must only be used when ip routing is disabled on the Cisco router. For instance, if the router is a host in the IP world, you can use this command to define a default gateway for it. You can also use this command when your low end Cisco router is in boot mode in order to TFTP a Cisco IOS® Software image to the router. In boot mode, the router does not have ip routing enabled. This example defines the router on IP address 172.16.15.4 as the default route:

```
ip default-gateway 172.16.15.4
```

Use Command **ip default-network**

Unlike the **ip default-gateway** command, you can use **ip default-network** when ip routing is enabled on the Cisco router. When you configure **ip default-network**, the router considers routes to that network for installation as the gateway of last resort on the router. For every network configured with **ip default-network**, if a router has a route to that network, that route is flagged as a candidate default route. This network diagram displays the routing table taken from router R1:



```
<#root>
```

```
R1#
```

```
show ip route
```

```
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PfR
```

```
Gateway of last resort is not set
```

```
10.0.0.0/8 is variably subnetted, 4 subnets, 2 masks
C 10.44.192.0/24 is directly connected, GigabitEthernet0/0
L 10.44.192.1/32 is directly connected, GigabitEthernet0/0
C 10.108.99.0/24 is directly connected, GigabitEthernet0/1
L 10.108.99.1/32 is directly connected, GigabitEthernet0/1
S 192.168.1.0/24 [1/0] via 10.44.192.2
```

Notice that the static route to 192.168.1.0 via 10.44.192.2 and that the gateway of last resort is not set. If you configure ip default-network 192.168.1.0, the routing table changes as follows:

```
<#root>
```

```
R1#
```

```
configure terminal
```

```
Enter configuration commands, one per line. End with CNTL/Z.
```

```
R1(config)#
```

```
ip default-network 192.168.1.0
```

```
R1(config)#
```

```
end
```

```
R1#
```

```
R1#
```

```
show ip route
```

```
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP  
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area  
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2  
E1 - OSPF external type 1, E2 - OSPF external type 2  
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2  
ia - IS-IS inter area, * - candidate default, U - per-user static route  
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP  
a - application route  
+ - replicated route, % - next hop override, p - overrides from PFR
```

```
Gateway of last resort is 10.44.192.2 to network 192.168.1.0
```

```
S* 0.0.0.0/0 [1/0] via 10.44.192.2
```

```
10.0.0.0/8 is variably subnetted, 4 subnets, 2 masks
```

```
C 10.44.192.0/24 is directly connected, GigabitEthernet0/0
```

```
L 10.44.192.1/32 is directly connected, GigabitEthernet0/0
```

```
C 10.108.99.0/24 is directly connected, GigabitEthernet0/1
```

```
L 10.108.99.1/32 is directly connected, GigabitEthernet0/1
```

```
S* 192.168.1.0/24 [1/0] via 10.44.192.2
```

```
R1#
```

```
R1#
```

```
show ip protocols
```

```
*** IP Routing is NSF aware ***
```

```
Routing Protocol is "application"
```

```
Sending updates every 0 seconds
```

```
Invalid after 0 seconds, hold down 0, flushed after 0
```

```
Outgoing update filter list for all interfaces is not set
Incoming update filter list for all interfaces is not set
Maximum path: 32
Routing for Networks:
Routing Information Sources:
Gateway Distance Last Update
Distance: (default is 4)
```

```
R1#
```

The gateway of last resort is now set as 10.44.192.2. This result is independent of any routing protocol, as shown by the **show ip protocols** command output, no routing protocol is configured. You can add another candidate default route with the configuration of another instance of ip default-network:

```
<#root>
```

```
R1#
```

```
configure terminal
```

```
Enter configuration commands, one per line. End with CNTL/Z.
```

```
R1(config)#
```

```
ip route 172.17.24.0 255.255.255.0 10.108.99.2
```

```
R1(config)#
```

```
ip default-network 172.17.24.0
```

```
R1(config)#
```

```
end
```

```
R1#
```

```
R1#
```

```
show ip route
```

```
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PFR
```

```
Gateway of last resort is 10.44.192.2 to network 192.168.1.0
```

```
S* 0.0.0.0/0 [1/0] via 10.44.192.2
```

```
10.0.0.0/8 is variably subnetted, 4 subnets, 2 masks
```

```
C 10.44.192.0/24 is directly connected, GigabitEthernet0/0
```

```
L 10.44.192.1/32 is directly connected, GigabitEthernet0/0
```

```
C 10.108.99.0/24 is directly connected, GigabitEthernet0/1
```

```
L 10.108.99.1/32 is directly connected, GigabitEthernet0/1
```

```
172.17.0.0/16 is variably subnetted, 2 subnets, 2 masks
S 172.17.0.0/16 [1/0] via 172.17.24.0
S 172.17.24.0/24 [1/0] via 10.108.99.2
S* 192.168.1.0/24 [1/0] via 10.44.192.2
```

 **Note:** After the **ip default-network** command was entered, you can observe that the network was not flagged as a default network. The [Flag a Default Network](#) section explains the reason.

Flag a Default Network

The **ip default-network** command is classful, this means that if the router has a route to the subnet indicated by this command, it installs the route to the major network. At this point neither network has been flagged as the default route. The **ip default-network** command must be run again, this time with the use of the major network in order to flag the candidate as a default route.

```
<#root>

R1#

configure terminal

Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#

ip default-network 172.17.0.0

R1(config)#

end

R1#sh
*Jul 15 22:32:42.829: %SYS-5-CONFIG_I: Configured from console by conso

R1#

show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is 172.17.24.0 to network 172.17.0.0

S* 0.0.0.0/0 [1/0] via 172.17.24.0
10.0.0.0/8 is variably subnetted, 4 subnets, 2 masks
C 10.44.192.0/24 is directly connected, GigabitEthernet0/0
L 10.44.192.1/32 is directly connected, GigabitEthernet0/0
C 10.108.99.0/24 is directly connected, GigabitEthernet0/1
```

```
L 10.108.99.1/32 is directly connected, GigabitEthernet0/1
* 172.17.0.0/16 is variably subnetted, 2 subnets, 2 masks

S* 172.17.0.0/16 [1/0] via 172.17.24.0

S 172.17.24.0/24 [1/0] via 10.108.99.2

S* 192.168.1.0/24 [1/0] via 10.44.192.2
```

If the original static route had been configured to the major network, the previous step would not have been necessary.

There are still no IP Protocols configured in the router. Without any dynamic protocols, you can configure your router to choose from a number of candidate default routes based on whether the routing table has routes to networks other than 0.0.0.0/0. The **ip default-network** command allows you to configure robustness into the selection of a gateway of last resort. Rather than the use of static routes to specific next-hops, you can have the router choose a default route to a particular network based in the routing table information.

If you lose the route to a particular network, the router selects the other candidate default. In that scenario, you can then remove the lost route from the configuration as shown in the next output:

```
<#root>
R1#
configure terminal

Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#
no ip route 172.17.24.0 255.255.255.0 10.108.99.2

R1(config)#
end

*Jul 15 22:52:59.047: %SYS-5-CONFIG_I: Configured from console by console
```

After you remove the static route to the network, the routing table looks like this:

```
<#root>
R1#
show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
```

E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PFR

Gateway of last resort is 10.44.192.2 to network 192.168.1.0

```
s* 0.0.0.0/0 [1/0] via 10.44.192.2
```

```
10.0.0.0/8 is variably subnetted, 4 subnets, 2 masks  
C 10.44.192.0/24 is directly connected, GigabitEthernet0/0  
L 10.44.192.1/32 is directly connected, GigabitEthernet0/0  
C 10.108.99.0/24 is directly connected, GigabitEthernet0/1  
L 10.108.99.1/32 is directly connected, GigabitEthernet0/1
```

```
s* 192.168.1.0/24 [1/0] via 10.44.192.2
```

R1#

Use Different Routing Protocols

Gateways of last resort selected via the **ip default-network** command are propagated differently based on which routing protocol is used. For EIGRP there are different methods to [Configure a Default Route in EIGRP](#) which are preferred. The default route announced with the **ip default-network** command is not propagated by Open Shortest Path First (OSPF) or by Intermediate System-to-Intermediate System (IS-IS). For more detailed information on behavior of default routes with OSPF, refer to [How Does OSPF Generate Default Routes?](#).

Use Command **ip route 0.0.0.0 0.0.0.0**

A static route configured with the command **ip route 0.0.0.0 0.0.0.0** is another way to set the gateway of last resort on a router. As with the **ip default-network** command, the use of the static route to 0.0.0.0 is not dependent on any routing protocols. However, ip routing must be enabled on the router.

 **Note:** EIGRP propagates a route to network 0.0.0.0, but the static route must be redistributed into the routing protocol.

In earlier versions of RIP, the default route created through the **ip route 0.0.0.0 0.0.0.0** was automatically advertised by RIP routers. In Cisco IOS Software Release 12 and later, RIP does not advertise the default route if the route is not learned via RIP. It can be necessary to redistribute the route into RIP.

The default routes configured with the **ip route 0.0.0.0 0.0.0.0** command are not propagated by OSPF and IS-IS. Additionally, this default route cannot be redistributed into OSPF or IS-IS through the redistribute command. Use the **default-information originate** command to generate a default route into an IS-IS or OSPF routing domain. For more detailed information about the behavior of default routes with OSPF, please refer to [How Does OSPF Generate Default Routes?](#). The next output is an example on how to configure a gateway of last resort with the use of the **ip route 0.0.0.0 0.0.0.0** command:

<#root>

R1#

configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

R1(config)#

ip route 0.0.0.0 0.0.0.0 10.108.99.2

R1(config)#

end

R1#

R1#

show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is 10.108.99.2 to network 0.0.0.0

S* 0.0.0.0/0 [1/0] via 10.108.99.2

10.0.0.0/8 is variably subnetted, 4 subnets, 2 masks
C 10.44.192.0/24 is directly connected, GigabitEthernet0/0
L 10.44.192.1/32 is directly connected, GigabitEthernet0/0
C 10.108.99.0/24 is directly connected, GigabitEthernet0/1
L 10.108.99.1/32 is directly connected, GigabitEthernet0/1
D 192.168.1.0/24 [90/130816] via 10.44.192.2, 00:20:24, GigabitEthernet0/0

R1#

show ip route 0.0.0.0 0.0.0.0

Routing entry for 0.0.0.0/0, supernet
Known via "

static

", distance 1, metric 0, candidate default path

Routing Descriptor Blocks:

* 10.108.99.2

Route metric is 0, traffic share count is 1

 **Note:** If you configure multiple networks as candidate default routes via the **ip default-network** command, the network that has the lowest administrative distance is chosen as the network for the gateway of last resort. If all the networks have the same administrative distance, then the network listed first in the routing table is chosen as the network for the gateway of last resort. If you use both the **ip default-network** and **ip route 0.0.0.0 0.0.0.0** commands to configure candidate default networks, the **ip route 0.0.0.0 0.0.0.0** command takes precedence and is chosen for the gateway of last resort. If you use multiple **ip route 0.0.0.0 0.0.0.0** commands to configure a default route, traffic is load-balanced over the multiple routes.

Summary

Use the **ip default-gateway** command when ip routing is disabled on a Cisco router. Use the **ip default-network** or **ip route 0.0.0.0 0.0.0.0** commands to set the gateway of last resort on Cisco routers that have ip routing enabled. The way in which routing protocols propagate the default route information varies for each protocol.

Related Information

- [IP Routed Protocols Technology Support Page](#)
- [Technical Support - Cisco Systems](#)