



## **Installation Guide for Cisco Unified Provisioning Manager**

Software Release 1.2

Cisco Unified Communications Management Suite

### **Americas Headquarters**

Cisco Systems, Inc.  
170 West Tasman Drive  
San Jose, CA 95134-1706  
USA  
<http://www.cisco.com>  
Tel: 408 526-4000  
800 553-NETS (6387)  
Fax: 408 527-0883

Text Part Number: OL-15348-01

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

CCVP, the Cisco logo, and Welcome to the Human Network are trademarks of Cisco Systems, Inc.; Changing the Way We Work, Live, Play, and Learn is a service mark of Cisco Systems, Inc.; and Access Registrar, Aironet, Catalyst, CCDA, CCDP, CCIE, CCIP, CCNA, CCNP, CCSP, Cisco, the Cisco Certified Internetwork Expert logo, Cisco IOS, Cisco Press, Cisco Systems, Cisco Systems Capital, the Cisco Systems logo, Cisco Unity, Enterprise/Solver, EtherChannel, EtherFast, EtherSwitch, Fast Step, Follow Me Browsing, FormShare, GigaDrive, HomeLink, Internet Quotient, IOS, iPhone, IP/TV, iQ Expertise, the iQ logo, iQ Net Readiness Scorecard, iQuick Study, LightStream, Linksys, MeetingPlace, MGX, Networkers, Networking Academy, Network Registrar, PIX, ProConnect, ScriptShare, SMARTnet, StackWise, The Fastest Way to Increase Your Internet Quotient, and TransPath are registered trademarks of Cisco Systems, Inc. and/or its affiliates in the United States and certain other countries.

All other trademarks mentioned in this document or Website are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (0711R)

Any Internet Protocol (IP) addresses used in this document are not intended to be actual addresses. Any examples, command display output, and figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses in illustrative content is unintentional and coincidental.

*Installation Guide for Cisco Unified Provisioning Manager*  
© 2007 Cisco Systems, Inc. All rights reserved.



# CONTENTS

## **Preface** v

- Open Source License Acknowledgements 1-vi
- OpenSSL/Open SSL Project 1-vii
- License Issues 1-vii

---

## **CHAPTER 1**

### **Prerequisites** 1-1

- Product Overview 1-1
- New Features in Cisco Unified Provisioning Manager 1.2 1-2
- Server Requirements 1-2
- Client Requirements 1-3
- Additional Server Software 1-4

---

## **CHAPTER 2**

### **Installing, Upgrading and Uninstalling Cisco Unified Provisioning Manager** 2-1

- Preparing to Install Provisioning Manager 2-1
  - Preparing the Server 2-1
    - Enabling the Full 4 GB of RAM 2-2
    - Enabling SSL on the Provisioning Manager Server 2-2
  - Preparing End Systems 2-4
    - Cisco Unified Communications Manager Preconfiguration Dependencies 2-4
    - Cisco Unified Communications Manager Express Preconfiguration Dependencies 2-5
    - Cisco Unity and Cisco Unity Connection System Preconfiguration Dependencies 2-7
    - Cisco Unity Express Preconfiguration Dependencies 2-9
  - Interfaces that Provisioning Manager Uses 2-9
  - Ports that Provisioning Manager Uses 2-10
  - Gathering Information to Provide During Installation 2-10
- Installing Provisioning Manager 2-11
  - Adding the Provisioning Manager Home Page to the Internet Explorer Trusted Sites Zone 2-14
  - Cleaning Up a Failed New Installation 2-14
    - Removing the CUPM Windows User 2-15
- Upgrading Provisioning Manager 1.1 to Provisioning Manager 1.2 2-15
  - Upgrading Provisioning Manager on One System (Application and Database on the Same System) 2-16
  - Upgrading Provisioning Manager on a Distributed System (Application and Database Are on Separate Systems) 2-18

Provisioning Manager Database Backup	2-18
Backing up the Single-Machine Provisioning Manager Database	2-18
Backing up Provisioning Manager on a Distributed Database	2-19
Restoring Provisioning Manager 1.1 when Provisioning Manager 1.2 Installation Fails	2-20
Cleaning Up the Old Installation	2-21
Restoring Provisioning Manager 1.1	2-22
Uninstalling Provisioning Manager	2-25

---

**APPENDIX A****Licensing A-1**

Licensing Overview	A-1
Verifying Provisioning Manager License Status	A-1
Licenses that Can Be Purchased	A-2
Licensing Scenarios	A-2
Licensing Process	A-3
Obtaining a PAK	A-3
Obtaining a License File	A-3
Registering a License File with Provisioning Manager	A-4
Licensing Warnings	A-4
Evaluation Version: Before Expiry	A-4
Purchased Version: Phone Limit Exceeded	A-4

---

**INDEX**



## Preface

---

This manual describes Cisco Unified Provisioning Manager (Provisioning Manager) and provides instructions for using and administering it.

## Audience

The audience for this document includes network administrators and operators who monitor, maintain, and configure the status of the IP telephony systems and applications.

## Conventions

This document uses the following conventions:

Item	Convention
Commands and keywords	<b>boldface</b> font
Variables for which you supply values	<i>italic</i> font
Displayed session and system information	<code>screen</code> font
Information you enter	<b>boldface screen</b> font
Variables you enter	<i>italic screen</i> font
Menu items and button names	<b>boldface</b> font
Selecting a menu item in paragraphs	<b>Option&gt;Network Preferences</b>
Selecting a menu item in tables	Option>Network Preferences



### Note

Means *reader take note*. Notes contain helpful suggestions or references to material not covered in the publication.

---



### Caution

Means *reader be careful*. In this situation, you might do something that could result in equipment damage or loss of data.

---

# Product Documentation


**Note**

We sometimes update the printed and electronic documentation after original publication. Therefore, you should also review the documentation on Cisco.com for any updates.

[Table 1](#) describes the product documentation that is available.

**Table 1**      **Product Documentation**

Document Title	Available Formats
<i>Supported Devices Table for Cisco Unified Provisioning Manager 1.2</i>	On Cisco.com at the following URL: <a href="http://www.cisco.com/en/US/products/ps7125/products_device_support_tables_list.html">http://www.cisco.com/en/US/products/ps7125/products_device_support_tables_list.html</a>
<i>Release Notes for Cisco Unified Provisioning Manager 1.2</i>	<ul style="list-style-type: none"> <li>• In PDF on the product CD-ROM</li> <li>• On Cisco.com at the following URL: <a href="http://www.cisco.com/en/US/products/ps7125/prod_release_notes_list.html">http://www.cisco.com/en/US/products/ps7125/prod_release_notes_list.html</a></li> </ul>
<i>Installation Guide for Cisco Unified Provisioning Manager 1.2</i>	<ul style="list-style-type: none"> <li>• In PDF on the product CD-ROM</li> <li>• On Cisco.com at the following URL: <a href="http://www.cisco.com/en/US/products/ps7125/prod_installation_guides_list.html">http://www.cisco.com/en/US/products/ps7125/prod_installation_guides_list.html</a></li> </ul>
<i>User Guide for Cisco Unified Provisioning Manager 1.2</i>	<ul style="list-style-type: none"> <li>• In PDF on the product CD-ROM</li> <li>• On Cisco.com at the following URL: <a href="http://www.cisco.com/en/US/products/ps7125/products_user_guide_list.html">http://www.cisco.com/en/US/products/ps7125/products_user_guide_list.html</a></li> </ul>

## Obtaining Documentation and Submitting a Service Request

For information on obtaining documentation, submitting a service request, and gathering additional information, see the monthly *What's New in Cisco Product Documentation*, which also lists all new and revised Cisco technical documentation, at:

<http://www.cisco.com/en/US/docs/general/whatsnew/whatsnew.html>

Subscribe to the *What's New in Cisco Product Documentation* as a Really Simple Syndication (RSS) feed and set content to be delivered directly to your desktop using a reader application. The RSS feeds are a free service and Cisco currently supports RSS version 2.0.

## Open Source License Acknowledgements

The following acknowledgements pertain to this software license.

## OpenSSL/Open SSL Project

This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>).

This product includes cryptographic software written by Eric Young (eay@cryptsoft.com).

This product includes software written by Tim Hudson (tjh@cryptsoft.com).

## License Issues

The OpenSSL toolkit stays under a dual license, i.e. both the conditions of the OpenSSL License and the original SSLeay license apply to the toolkit. See below for the actual license texts. Actually both licenses are BSD-style Open Source licenses. In case of any license issues related to OpenSSL please contact [openssl-core@openssl.org](mailto:openssl-core@openssl.org).

### OpenSSL License:

© 1998-1999 The OpenSSL Project. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions, and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgment: “This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit. (<http://www.openssl.org/>)”
4. The names “OpenSSL Toolkit” and “OpenSSL Project” must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact [openssl-core@openssl.org](mailto:openssl-core@openssl.org).
5. Products derived from this software may not be called “OpenSSL” nor may “OpenSSL” appear in their names without prior written permission of the OpenSSL Project.
6. Redistributions of any form whatsoever must retain the following acknowledgment:  
“This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>)”

THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT “AS IS” AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OpenSSL PROJECT OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This product includes cryptographic software written by Eric Young (eay@cryptsoft.com). This product includes software written by Tim Hudson (tjh@cryptsoft.com).

**Original SSLeay License:**

© 1995-1998 Eric Young (eay@cryptsoft.com). All rights reserved.

This package is an SSL implementation written by Eric Young (eay@cryptsoft.com).

The implementation was written so as to conform with Netscapes SSL.

This library is free for commercial and non-commercial use as long as the following conditions are adhered to. The following conditions apply to all code found in this distribution, be it the RC4, RSA, lhash, DES, etc., code; not just the SSL code. The SSL documentation included with this distribution is covered by the same copyright terms except that the holder is Tim Hudson (tjh@cryptsoft.com).

Copyright remains Eric Young's, and as such any Copyright notices in the code are not to be removed. If this package is used in a product, Eric Young should be given attribution as the author of the parts of the library used. This can be in the form of a textual message at program startup or in documentation (online or textual) provided with the package.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgement:  
 "This product includes cryptographic software written by Eric Young (eay@cryptsoft.com)".  
 The word 'cryptographic' can be left out if the routines from the library being used are not cryptography-related.
4. If you include any Windows specific code (or a derivative thereof) from the apps directory (application code) you must include an acknowledgement: "This product includes software written by Tim Hudson (tjh@cryptsoft.com)".

THIS SOFTWARE IS PROVIDED BY ERIC YOUNG "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The license and distribution terms for any publicly available version or derivative of this code cannot be changed. i.e. this code cannot simply be copied and put under another distribution license [including the GNU Public License].



# CHAPTER 1

## Prerequisites

---

This chapter describes the prerequisites for installing Cisco Unified Provisioning Manager on a Windows system. It includes:

- [Product Overview, page 1-1](#)
- [New Features in Cisco Unified Provisioning Manager 1.2, page 1-2](#)
- [Server Requirements, page 1-2](#)
- [Client Requirements, page 1-3](#)
- [Additional Server Software, page 1-4](#)

## Product Overview

Cisco Unified Provisioning Manager (Provisioning Manager) provides a scalable web-based solution to manage a company's next-generation communication services. Provisioning Manager manages IP communication services in an integrated IP telephony, voicemail, and unified messaging environment that includes Cisco Unified Communications Manager, Cisco Unified Communications Manager Express, Cisco Unity, Cisco Unity Express, and Cisco Unity Connection systems.

Provisioning Manager is a product from the Cisco Unified Communications Management Suite. It provides provisioning for Cisco Unified Communications initial deployments and implementations, and then remains deployed to provide ongoing operational provisioning and activation services for individual subscriber changes. Provisioning Manager provides a single, consolidated view of subscribers across the organization. It provides a set of business-level management abstractions, which are policy-driven through the use of automation, for managing subscriber services across the Cisco Unified Communications infrastructure.

A template capability permits defining standard configurations that can be reused for new sites or location deployments. Batch provisioning permits the rollout of large numbers of subscribers at the same time.

Administrators can configure policy at various levels to determine who can do delegated management, for whom that delegation applies, and how business-level services apply to Cisco Unified Communications voice and messaging applications and which types of end users (subscribers) are permitted to order which standard services. Through the use of this policy and standard configuration approach, provisioning and activating subscriber services is greatly simplified, while retaining the overall ability to manage and provide services that make use of the underlying Cisco Unified Communications applications.

# New Features in Cisco Unified Provisioning Manager 1.2

Cisco Unified Provisioning Manager adds the following:

- Support for Cisco Unified Communications Manager 6.1.
- Support for Cisco Unified Communications Manager Express 4.2.
- Support for Cisco Unity Connection 2.1.
- Support for Cisco Unity Express 3.1.
- Line Group as a provisioning attribute on a line.
- The ability to change the attributes of a Line.
- Support for the Cisco Unified Communications Manager Auto-Register Phone Tool in Cisco Unified Communications Manager.
- CTI Route Point as a new configuration template.
- Support for alternate extensions in Cisco Unity voicemail.

## Server Requirements

Table 1-1 lists the minimum server system requirements for different levels of performance and scale.

**Table 1-1** Server System Requirements

Requirement Type	Minimum Requirements
System Processor	<p>Server platform with one of the following processor configurations:</p> <ul style="list-style-type: none"> <li>• (Up to 1,000 phones) Single Intel Pentium 4, 3.0 GHz.</li> <li>• (Up to 10,000 phones) Dual-core Intel Pentium 4, 3.0 GHz.</li> <li>• (Up to 30,000 phones) Two-system deployment, with the following configuration:               <ul style="list-style-type: none"> <li>– Two Intel Xeon, 3.0 GHz, for the Web and application server.</li> <li>– Two Intel Xeon, 3.0 GHz, for the database.</li> </ul> </li> </ul> <p><b>Note</b> If you are going to have more than five operators placing concurrent orders, two dual-core Intel Xeon processors should be used.</p>
Other System Hardware	<ul style="list-style-type: none"> <li>• Color monitor.</li> <li>• CD-ROM drive.</li> <li>• 100 Mbps NIC</li> </ul>

**Table 1-1** Server System Requirements (continued)

Requirement Type	Minimum Requirements
Memory (RAM)	<ul style="list-style-type: none"> <li>• 2 GB—Up to 1000 phones.</li> <li>• 4 GB—Up to 10,000 phones.</li> <li>• 4 GB on each system—Up to 30,000 phones.</li> </ul> <p><b>Note</b> Provisioning Manager will not install either the medium (up to 10,000 phones) or the large (up to 30,000 phones) configuration, if Windows 2003 reports that less than 4 GB of memory is installed. There is a known issue with Windows 2003 when working with certain hardware. Even though 4 GB of memory is installed on the system Windows 2003 reports that there is less than 4 GB of memory installed. For more details, see <a href="http://msdn2.microsoft.com/en-us/library/ms791485.aspx">http://msdn2.microsoft.com/en-us/library/ms791485.aspx</a>.</p>
Swap File Space	Same as RAM, with a maximum size of twice that of RAM.
Available Drive Space	<ul style="list-style-type: none"> <li>• 30 GB—Up to 1000 phones.</li> <li>• 60 GB—Up to 10,000 phones.</li> <li>• Two-system configuration (up to 30,000 phones); requires the following: <ul style="list-style-type: none"> <li>– 30 GB on the Web and application system.</li> <li>– 80 GB on the database system.</li> </ul> </li> </ul>
<b>Note</b> SAS or SCSI drives in a RAID configuration are recommended for servers supporting 1000 to 10,000 phones. SAS drives in a RAID (1+0) configuration are recommended for servers supporting over 10,000 phones.	
System Software <sup>1</sup>	Windows Server 2003 with Service Pack 1 or Service Pack 2, Standard or Enterprise Edition.

1. You must install Provisioning Manager on a dedicated system. Do not install Provisioning Manager on a Primary Domain Controller (PDC) or Backup Domain Controller (BDC).

## Client Requirements

Table 1-2 lists the minimum client system requirements for installing Provisioning Manager.

**Table 1-2** Client System Requirements

Requirement Type	Minimum Requirements
System Hardware	<ul style="list-style-type: none"> <li>• Any PC or server platform with a Pentium 4 processor greater than 1.0 GHz.</li> <li>• Color monitor with video card set to 24 bits color depth.</li> <li>• Screen resolution of 1024 x 768 dpi.</li> </ul> <p><b>Note</b> Not every LCD projector or monitor provides a clear display at the minimum resolution. On LCD projectors and monitors, dot pitch impacts the readability of the screen.</p>

Table 1-2 Client System Requirements (continued)

Requirement Type	Minimum Requirements
System Software	<ul style="list-style-type: none"> <li>• One of the following: <ul style="list-style-type: none"> <li>– Windows XP with Service Pack 2.</li> <li>– Windows Server 2003 with Service Pack 1 or Service Pack 2, Standard or Enterprise Edition.</li> </ul> </li> <li>• One of the following <ul style="list-style-type: none"> <li>– Internet Explorer 6.0 with Service Pack 2 or 7.0.</li> <li>– Mozilla 1.7.x.</li> <li>– Firefox 2.0</li> </ul> </li> </ul>
Memory (RAM)	1 GB recommended.
Environment	<p>Clients must be able to access Provisioning Manager:</p> <ul style="list-style-type: none"> <li>• From outside a firewall—Refer to the documentation for your firewall for information on how to configure client access.</li> <li>• Across a Virtual Private Network (VPN)—The VPN tunnel should connect the client and a VPN router or similar device. See <a href="#">Ports that Provisioning Manager Uses, page 2-10</a>.</li> </ul>

## Additional Server Software

Provisioning Manager has undergone interoperability testing with the following software:

- Cisco Security Agent 5.0



**Note** Cisco Security Agent must be disabled during installation of Provisioning Manager.

- Third-party virus protection software:
  - McAfee Virus Scan Enterprise 8.0

For McAfee Enterprise VirusScan 8.0, you must have patch version 11 installed. Install the McAfee VirusScan Enterprise 8.0 Patch Version 11 before installing Provisioning Manager on the system.



**Note** You should exclude the following from virus scanning:

- The *pgsql* folder (if you selected the default location during installation, it is C:\CUPM\pgsql).
- The *postmaster.exe* file (located in the CUPM\pgsql\bin folder).



## CHAPTER 2

# Installing, Upgrading and Uninstalling Cisco Unified Provisioning Manager

---

This chapter describes installing Cisco Unified Provisioning Manager.

It includes:

- [Preparing to Install Provisioning Manager, page 2-1](#)
- [Installing Provisioning Manager, page 2-11](#)
- [Upgrading Provisioning Manager 1.1 to Provisioning Manager 1.2, page 2-15](#)
- [Uninstalling Provisioning Manager, page 2-25](#)

## Preparing to Install Provisioning Manager

The information in this section helps you to deploy Provisioning Manager in your network. Do the following before you install Provisioning Manager:

- Make sure that hardware and software requirements for the server are met. (See [Server Requirements, page 1-2](#).)
- Preparing the Provisioning Manager server for installation. (See [Preparing the Server, page 2-1](#).)
- Configure end systems so that Provisioning Manager can obtain correct information from them. ([Preparing End Systems, page 2-4](#).)
- Determine whether your existing applications are already using ports that Provisioning Manager uses. (Existing applications should not use the ports that Provisioning Manager requires.) See [Ports that Provisioning Manager Uses, page 2-10](#).
- Gather information that you might need to provide during the Provisioning Manager installation. (See [Gathering Information to Provide During Installation, page 2-10](#).)

## Preparing the Server

This section describes procedures that you may need to perform to prepare your server for installing Provisioning Manager on it.

**Note**

The system that you use for your Provisioning Manager server should meet all the security guidelines that Microsoft recommends for Windows 2003 Server. See the Microsoft website for security guidance <http://www.microsoft.com/technet/security/prodtech/WindowsServer2003.msp>).

## Enabling the Full 4 GB of RAM

Provisioning Manager will not install either the medium (up to 10,000 phones) or the large (up to 30,000 phones) configuration, if Windows 2003 reports that less than 4 GB of memory is installed. There is a known issue with Windows 2003 when working with certain hardware. Even though 4 GB of memory is installed on the system Windows 2003 reports that there is less than 4 GB of memory installed. For more details, see <http://msdn2.microsoft.com/en-us/library/ms791485.aspx>.

To enable all 4 GB of RAM on the system, use the following procedure:

- 
- Step 1** On the Provisioning Manager system, in Windows right-click **My Computer**.
  - Step 2** Select **Properties**.
  - Step 3** Select the **Advanced** tab.
  - Step 4** Under Startup and Recovery, click **Settings**.
  - Step 5** Click **Edit**. The boot.ini file opens.
  - Step 6** In the file, add **"/PAE"** in line starting with "multi(0)disk(0)rdisk(0)partition(1)\WINDOWS=..."
  - Step 7** Restart the system.
- 

## Enabling SSL on the Provisioning Manager Server

Secure Socket Layer (SSL) is an application-level protocol that enables secure transactions of data through privacy, authentication, and data integrity. It relies upon certificates, public keys, and private keys.

Provisioning Manager supports SSL between clients and the server.

When you start Provisioning Manager, the login page always opens in secure mode, providing secure access between the client browser and the Provisioning Manager server. In secure mode, SSL is used to encrypt the transmission channel between the browser and the server. To use secure mode throughout Provisioning Manager, you must enable SSL.

To enable SSL, you must install Win32 OpenSSL and then configure the Apache server.

### Installing OpenSSL and Generating a Certificate

- 
- Step 1** On the Provisioning Manager system, install Win32 OpenSSL v0.9.7m in C:\OpenSSL. You can find Win32 OpenSSL at: <http://www.slproweb.com/products/Win32OpenSSL.html>.
  - Step 2** In a command prompt, go to <Install directory>\httpd\conf.

**Note**

If you accepted the default location during installation, the installation directory is C:\CUPM.

**Step 3** In the command prompt, run the following command:

```
c:\OpenSSL\bin\openssl.exe genrsa -des3 -out server.key 1024
```

**Step 4** A prompt appears asking for a pass-phrase. Enter a phrase.

**Step 5** Run the following command:

```
c:\OpenSSL\bin\openssl.exe req -new -x509 -days 365 -key server.key -out server.crt
```



---

**Note** The above command assumes the certificate is valid for 365 days. If you need a longer license, enter a higher number of days.

---

**Step 6** You will be prompted for the pass-phrase you previously entered. Enter it again.

**Step 7** Enter the information for the Distinguished Name fields for the certificate.

**Step 8** Run the following command:

```
c:\OpenSSL\bin\openssl.exe rsa -in server.key.orig -out server.key
```

**Step 9** Enter the pass-phrase you used previously. This removes the need to enter the pass-phrase every time you start up.

---

## Configuring the Apache Server

**Step 1** On the Provisioning Manager system, in the httpd.conf file (located at <install directory>/httpd/conf), uncomment the line, `LoadModule ssl_module modules/mod_ssl.so`.

**Step 2** If you upgraded from Provisioning Manager 1.1 you must update the ssl.conf file. Set `@DOCROOT@` to, <install directory>/httpd/htdocs (it should be changed in two places).

If this is a new install, you can skip this step.

**Step 3** Restart the Windows Service, Apache2.

Now you can log into Provisioning Manager using HTTPS.



---

**Note** When using SSL, remember the following:

- The URL for logging in uses HTTPS. (For example, `https://<host name or IP address>/cupm/Login`.)
  - If you upgraded from Provisioning Manager 1.1, the ssl.conf file may be read only. Remove the read only property using Windows Explorer.
  - By default, port 443 is configured in the ssl.conf file. If you need to change the port number, in the ssl.conf file, change the line `Listen 443` to the desired port.
  - If you want to exclusively run only HTTPS, you must disable the non secure HTTP by commenting out the line `Listen 80` in the `C:\CUPM\httpd\conf\httpd.conf` file and restart the Apache server.
-

## Preparing End Systems

In Provisioning Manager, the physical resources (end systems that deliver voice and messaging services) are modeled as Processors. For example, a Cisco Unified Communications Manager or Cisco Unified Communications Manager Express system is modeled as a Call Processor and a Cisco Unity, Cisco Unity Express, or Cisco Unity Connection voicemail/unified messaging system is modeled as a Unified Message Processor.

Using Provisioning Manager, an administrator creates and configures these various processors. After the processors have been configured, all configuration and interaction with the end systems is handled by Provisioning Manager.

Some minimal configuration is required on the end systems before you can use them with Provisioning Manager. This section describes the preconfiguration steps required for Cisco Unified Communications Manager, Cisco Unified Communications Manager Express, Cisco Unity systems, Cisco Unity Connection, and Cisco Unity Express.

### Cisco Unified Communications Manager Preconfiguration Dependencies

The Cisco Unified Communications Manager is the software-based, call-processing component of the Cisco IP telephony solution, and is part of Cisco Architecture for Voice, Video and Integrated Data (AVVID).

Additional data, voice, and video services such as unified messaging, multimedia conferencing, collaborative contact centers, and interactive multimedia response systems interact with the IP telephony solution through Cisco Communications Manager's open telephony application programming interface (API). Cisco Communications Manager is installed on the Cisco Media Convergence Server (MCS).

No specific preconfiguration is generally required on the Cisco Unified Communications Manager for Provisioning Manager. However, the following conditions should already have been met during a normal installation or upgrade, and are noted here as installation dependencies for creating a Call Processor in Provisioning Manager:

- Install Cisco Unified Communications Manager.
- If Cisco Unity is used in this configuration, configure the Cisco Unified Communications Manager voicemail ports.
- Create a user and password with administrator privileges that can be used by Provisioning Manager to access Cisco Unified Communications Manager. The requirements of the user and password vary depending on whether multilevel administration access (MLA) is enabled (see [Table 2-1](#)).

**Note**

---

All interactions with Cisco Unified Communications Manager and Provisioning Manager are through the AVVID XML Layer APIs (AXL/SOAP).

---

### Determining the Media Server Account to Use for Cisco Unified Communications Manager Access

To enable Provisioning Manager to access a Cisco Unified Communications Manager, you must supply the username and password for an account on the media server. The account to use depends upon the Cisco Unified Communications Manager version and might also depend on whether MLA is enabled for the Cisco Unified Communications Manager. [Table 2-1](#) lists the options.

**Table 2-1 Accounts Required to Access Cisco Unified Communications Manager**

Cisco Unified Communications Manager Version on Media Server	MLA Enabled or Disabled for Cisco Unified Communications Manager	Required Account
4.x	Enabled	Multilevel administration access account with full access to the Standard Serviceability Functional Group.
	Disabled	Valid Windows 2000 administrator account on the media server.
5.x	N/A	A Unified Communications Manager user who is assigned a role with the privilege to use the AXL Database API resource in the Cisco Call Manager AXL Database application.  <i>Standard AXL API Access</i> is one of the predefined roles in Unified Communications Manager that has this privilege.
6.x	N/A	A Unified Communications Manager user who is assigned a role with the privilege to use the AXL Database API resource in the Cisco Call Manager AXL Database application.  <i>Standard AXL API Access</i> is one of the predefined roles in Unified Communications Manager that has this privilege.

## Cisco Unified Communications Manager Express Preconfiguration Dependencies

Cisco Unified Communications Manager Express is a solution, embedded in Cisco IOS Software, that provides call processing for Cisco Unified IP Phones.

Like Cisco Unified Communications Manager, Cisco Unified Communications Manager Express is modeled in Provisioning Manager as a Call Processor. The only difference from an administrative aspect is that it is represented by a different type of Call Processor.

Provisioning Manager requires that the Cisco Unified Communications Manager Express be installed on a supported platform with the appropriate Cisco IOS Software version and Cisco Unified Communications Manager Express load.

Before you can create a Call Processor based on a Cisco Unified Communications Manager Express in Provisioning Manager, you must do the following:

- Disable the auto-allocation of directory numbers. Do this through the Cisco IOS interface (see [Disabling the Auto-Allocation of Directory Numbers and Ephone Auto-Registration, page 2-6](#)).
- Disable the ephone auto-registration. You must do this through for Cisco Unified Communications Manager Express 4.0 or later (see [Disabling the Auto-Allocation of Directory Numbers and Ephone Auto-Registration, page 2-6](#)).

- If you have changed the Rivest, Shamir, and Adelman (RSA) key pair for Secure Shell Version 2 (on the router where Cisco Unified Communications Manager Express resides) to a length less than 512 bits, you must reconfigure the RSA key back to a length equal to or greater than 512 bits. For information on configuring the RSA keys in Secure Shell Version 2, see your router's documentation.

## Disabling the Auto-Allocation of Directory Numbers and Ephone Auto-Registration

Do the following configurations through the Cisco IOS interface.

### Step 1 First, verify that auto-allocation is enabled.

```
$ telnet 172.19.50.247
Trying 172.19.50.247...
Connected to 172.19.50.247.
Escape character is '^]'.

User Access Verification

Password:

CCME-1>enable
Password:
CCME-1#show telephony
CONFIG (Version=3.0)
=====
Cisco Communications Manager Express
ip source-address 172.19.50.247 port 2000
max-ephones 24
max-dn 100
max-conferences 4
max-redirect 5
time-format 12
date-format mm-dd-yy
keepalive 30
timeout interdigit 10
timeout busy 10
timeout ringing 180
web admin system name root password cisco
web admin customer name cisco password cisco
edit DN through Web: enabled.
edit TIME through web: enabled.
Log (table parameters):
  max-size: 150
  retain-timer: 15
  (password): abcd
create cnf-files version-stamp 7960 Jan 15 2004 16:48:05
auto assign 1 to 100 type 7960 cfw 5001 timeout 30
local directory service: enabled.
xml schema http://gkar.cisco.com/schema/axlsoap.xsd
```

In this case, auto-allocation is on, as shown by the *auto assign* line.

### Step 2 To disable auto-allocation, run the following command at the *enable* prompt:

```
CCME-1#config term
Enter configuration commands, one per line. End with CNTL/Z.
CCME-1(config)#telephony-service
CCME-1(config-telephony)#no auto assign 1 to 100 type 7960 cfw 5001 timeout 30
CCME-1(config-telephony)#no auto-reg-ephone
```



**Note** The **no auto-reg-ephone** command is required for Cisco Unified Communications Manager Express 4.0 or later.

```
CCME-1(config-telephony)#exit
CCME-1(config)#exit
CCME-1#show telephony
```

- Step 3** To verify that the change has taken effect, run another **show telephony** command. The *auto assign* line should no longer appear.
- Step 4** Run a **write memory** command, which will write the changes out to the system's nonvolatile memory in case of a reboot.

### How Provisioning Manager Manages Communications Manager Express

Cisco Unified Communications Manager Express uses two main commands to provision phones for end subscribers:

- **telephony ephone-dn**—Manages directory numbers.
- **telephony ephone**—Assigns directory numbers to lines on one or more phones.

Both commands allow subscriber information to be associated to the directory number or the line. Provisioning Manager uses these native abilities in Cisco Unified Communications Manager Express to store and synchronize subscriber information.

Provisioning Manager is able to synchronize back the phones, lines, directory numbers, and subscriber information from an existing Cisco Unified Communications Manager Express. Depending on how the subscriber information was used in the **telephony ephone** and **telephony ephone-dn** commands, Provisioning Manager is able to fully construct a user account for that subscriber. Provisioning Manager supports shared lines and directory numbers while doing this.

When provisioning, Provisioning Manager uses the **description** command in the ephone configlet to hold the subscriber name and department information. Provisioning Manager also uses the **name** command in the ephone-dn configlet to hold the subscriber's first and last names.



**Note** The Cisco Unified Communications Manager Express ephone-dn name field is limited to 30 characters. If the subscriber's first and last names (combined) exceed that limit, you may get an error.

### Cisco Unity and Cisco Unity Connection System Preconfiguration Dependencies



**Note** Provisioning Manager does not support Cisco Unity when it is configured with multiple Cisco Unified Communications Manager clusters.

Before you can create a Unified Message Processor based on Cisco Unity in Provisioning Manager, you must do the following:

- Install and configure the message store using Microsoft Exchange 2000 or 2003. (Required for Cisco Unity only.)
- Configure an integration with one corresponding Cisco Unified Communications Manager.

- Create a SQL Server user and password that can be used by Provisioning Manager to access the SQL Server database on Cisco Unity. The SQL Server user requires access to both the Cisco Unity and master databases. See [Creating a SQL Server User and Password for Cisco Unity, page 2-8](#). (Required for Cisco Unity only.)
- Verify the TCP/IP port used by Cisco Unity. This port number is required when you create a Unified Message Processor. (Required for Cisco Unity only.)
- Define Class of Service and Subscriber templates.
- Configure IMAP in Cisco Unity Connection. This is required, so that Provisioning Manager can provision email and Unified Messaging Services in Cisco Unity Connection. (Required for Cisco Unity Connection only.)



**Note** To configure IMAP: on the Cisco Unity Connection system, go to **System Settings > External Services > Add New**, and fill in all the fields required to add external services.

### Creating a SQL Server User and Password for Cisco Unity

- 
- Step 1** On the Cisco Unity system, select **Start > SQL Server > Enterprise Manager**. The Enterprise Manager window appears.
- Step 2** In the navigation tree, select **Microsoft SQL Servers > SQL Server Group > (local) (Windows NT)**.
- Step 3** Right-click **(local) (Windows NT)** and select **Properties**. The SQL Server Properties (Configure) window appears.
- Step 4** Click the Security tab.
- Step 5** Under Authentication, select **SQL Server and Windows**.
- Step 6** In the navigation tree under (local) (Windows NT), select **Security > Logins**.
- Step 7** Create a new login. Do the following:
- Right-click **Logins**. The SQL Server Login Properties - New Login window appears.
  - Enter a name for the login.
  - Select **SQL Server Authentication**.
  - Select **UnityDb**.
  - Click the **Database Access** tab.
  - Select both the **UnityDb** and the **master** database.
  - For both databases, select the following roles: db\_owner, db\_datareader, and db\_datawriter.
  - Reboot the SQL server.
- 

### Verifying the TCP/IP Port Used by Cisco Unity

- 
- Step 1** On the Cisco Unity system, select **Start > SQL Server > Enterprise Manager**. The Enterprise Manager appears.
- Step 2** From the menu, click **Action**. Then select **Properties**. The SQL Server Properties (Configure) dialog box appears.
- Step 3** In the General tab, click **Network Configuration**. The SQL Server Network Utility window appears.

- Step 4** Select **TCP/IP**, then click **Properties**.
- Step 5** In the window that appears, the default TCP/IP port is displayed. You will need to know this port number when you create a Unified Message Processor.

## Cisco Unity Express Preconfiguration Dependencies

Before you can create a Unified Message Processor based on Cisco Unity Express in Provisioning Manager, you must do the following:

- If you have changed the RSA key pair for Secure Shell Version 2 (on the router where Cisco Unity Express resides) to a length less than 512 bits, you must reconfigure the RSA key back to a length equal to or greater than 512 bits. For information on configuring the RSA keys in Secure Shell Version 2, see your router's documentation.
- Determine the Service Engine Interface number for Cisco Unity Express. The Service Engine Interface number is required when adding a Cisco Unity Express to Provisioning Manager (see [Determining the Service Engine Interface Number for Cisco Unity Express, page 2-9](#)).

### Determining the Service Engine Interface Number for Cisco Unity Express

The Service Engine Interface number is located on the router that hosts Cisco Unity Express.

- Step 1** Log in to the router that hosts Cisco Unity Express.
- Step 2** Run the command `show running-config`.

In the resulting output, look for the following:

```
Interface Service-Engine 2/0
```

In this example, 2/0 is the Service Engine Interface number.

## Interfaces that Provisioning Manager Uses

[Table 2-2](#) lists the interfaces that Provisioning Manager uses to communicate with the end systems.

**Table 2-2** *Interfaces that Provisioning Manager Uses*

Call Processor/ Unified Message Processor	Interface
Cisco Unified Communications Manager	AXL and SOAP
Cisco Unified Communications Manager Express	CLI over Telnet and SSH
Cisco Unity	JDBC
Cisco Unity Connection	Webservice API
Cisco Unity Express	CLI over Telnet and SSH

## Ports that Provisioning Manager Uses

Before installing Provisioning Manager, make sure that the appropriate ports are available.

[Table 2-3](#) lists the ports that need to be open on the Provisioning Manager system. [Table 2-4](#) lists the ports that need to be open on the firewall between Provisioning Manager and the device.

**Table 2-3** Ports Used on the Provisioning Manager System

Port Numbers	Additional Information
1098	—
1099	—
1602	Network Interface and Configuration Engine (NICE). This is configurable during the advanced installation process.
4444	—
4445	—
5432	PostgreSQL database. This is configurable during the advanced installation process.
8008	JBoss Application Server. This is configurable during the advanced installation process.
8009	—
8083	—
8093	—
80	HTTP/Apache Web Server. This is configurable during the advanced installation process.

**Table 2-4** Ports Used to Communicate with Other Devices

Port Numbers	Service Name/Protocols	Application
80	HTTP/Apache Web Server	Cisco Unified Communications Manager.
8443	HTTPS	Cisco Unified Communications Manager 5.0.
22	SSH	Cisco Unified Communications Manager Express and Cisco Unity Express.
23	Telnet	Cisco Unified Communications Manager Express and Cisco Unity Express.

## Gathering Information to Provide During Installation

You might need to supply the following information while you are installing Provisioning Manager:

- For a simple installation, you will need to have the following:
  - A license file, or you can choose to use the evaluation version.
  - Password for the administrator user.
  - Username and password for the PostgreSQL administrator (default is postgres).

- For an advanced installation, what you need depends on your installation. The following list contains information you may need to have:
  - A license file, or you can choose to use the evaluation version.
  - A port number for the Apache web server.
  - A port number for the PostgreSQL database.
  - Hostname or IP address for the systems that can connect to the PostgreSQL database.
  - Username and password for the Windows user that the PostgreSQL database uses.
  - Username and password for the PostgreSQL administrator (default is postgres).
  - The JBoss application server name.
  - The port number for the JBoss application server.
  - Username and password for the application database user.
  - Password for the administrator user.
  - Port number for the NICE service.

## Installing Provisioning Manager

The installation process takes approximately 60 minutes to complete.

Follow these guidelines when installing Provisioning Manager:

- Provisioning Manager requires a dedicated system; do not install it on a system with:
  - Third-party management software (such as HP OpenView or NetView).
  - Cisco Secure Access Control Server (ACS).
  - Any Cisco applications other than those that are documented to be able to coexist with Provisioning Manager.
- If installing on a system with Cisco Security Agent, before installing Provisioning Manager disable Cisco Security Agent.
- Do not install on any of your voice application servers on a Cisco Unified Communications Manager server.
- Verify that the system date and time are set properly.
- To speed up installation, disable all virus-scan software while installing.

---

**Step 1** Make sure your system meets these prerequisites:

- Required (or desired) operating system upgrades have been performed.
- Required service packs are installed.

For system requirements, see [Server Requirements, page 1-2](#).

**Step 2** Close all open or active programs. Do not run other programs during the installation process.

**Step 3** As the local administrator, log in to the machine on which you will install the Provisioning Manager software, and insert the Cisco Unified Provisioning Manager CD-ROM into the CD-ROM drive. The Cisco Unified Provisioning Manager 1.2 window opens.




---

**Note** If the CD-ROM is already in the CD-ROM drive and you stopped the installation process to close programs or if Autostart is disabled, click **cupm1.2-setup.exe** to restart the process.

---

**Step 4** Click **Install**. The Welcome window appears.

**Step 5** Click **Next**. The Software License Agreement window appears.

**Step 6** Accept the Software License Agreement and then click **Next**.

**Step 7** In the Destination Directory window, click **Next** to accept the default installation directory.




---

**Note** Do not install Provisioning Manager under any directory where the directory name contains a space (for example, Program Files).

---

**Step 8** Select the appropriate sizing for your Provisioning Manager installation.




---

**Note** The options that appear depend on the amount of memory that your system has.

---

**Step 9** Click **Next**.

**Step 10** Choose an installation type, Simple or Advanced:

- Select **Simple**, and click **Next**.
  - a. Select one of the following, and then click **Next**:
    - If you have a license file for this product, specify its location—Browse to enter the location.
    - Select this option to evaluate the product—You can complete the installation and then register the license file later.
  - b. Enter a username and password for the PostgreSQL administrator (default is postgres), then click **Next**.




---

**Note** Only enter alphabetical or numerical characters for the password. Do not enter any special characters.

---

- c. Enter a password for the administrator user.




---

**Note** Provisioning Manager is preconfigured with a permanent administrator account (padmin).

---

- d. Click **Next**.
  - e. Select the appropriate time zone, then click **Next**. The Summary page appears.
  - f. Click **Install**.
- Select **Advanced**, and click **Next**. The advanced installation has two distribution options. In the first, all of Provisioning Manager (application and database) is installed on one system. In the second, the Provisioning Manager application and database are installed on separate systems. This scenario requires that you enter the IP address of the two systems.
    - a. Choose the components:
      - Database—Installs the Provisioning Manager database only.

- CUPM—Installs the Provisioning Manager application only.



**Note** If you choose to install the database and the application on separate systems, Provisioning Manager is not completely installed until both the database and application are installed. When you install the database on a separate machine, at the end of the installation you will receive a message that states Provisioning Manager was installed successfully. But only the database is installed on that system.

Advanced installation enables you to configure the following information, depending on which components you are installing:

- Port number for the Apache web server.
- Port number for PostgreSQL database.
- Hostname or IP address for the systems that can connect to the PostgreSQL database. This is required if the database is being installed on a separate system.
- Host name or IP Address of the computers that can connect to the PostgreSQL database. This is required if the application is being installed on a separate system.
- Username and password for the Windows user that the PostgreSQL database uses—Only enter alphabetical or numerical characters for the password. Do not enter any special characters.



**Note** If the username already exists on the system, the password entered must be the current password for that user. Also, the Windows user should not have administrator privileges.

- Username and password for the PostgreSQL administrator (default is postgres)—Only enter alphabetical or numerical characters for the password. Do not enter any special characters.
  - Application (JBoss) server name.
  - Port number for the JBoss application server.
  - Username and password for the application database user—Only enter alphabetical or numerical characters for the password. Do not enter any special characters.
  - Password for the Provisioning Manager administrator user.
  - Port number for the NICE service.
- b.** Select one of the following, and then click **Next**:
- If you have a license file for this product, specify its location—Browse to enter the location.
  - Select this option to evaluate the product—You can complete the installation and then register the license file later.
- c.** Select the appropriate time zone, then click **Next**. The Summary page appears.
- d.** Click **Install**.



**Note**

If an error message appears similar to the following appears, it means that the installation has failed:

```
Postgres install failed with error code 1603
```

Before trying to install Provisioning Manager again, you must clean up the system. See [Cleaning Up a Failed New Installation](#), page 2-14.

**Step 11** Eject the CD-ROM.



**Note** Store the CD-ROM in a secure, climate-controlled area for safekeeping.

**Step 12** Click **Finish**.

**Step 13** After the installation completes, verify that Provisioning Manager is installed correctly by accessing the Provisioning Manager login page. From the Windows desktop, select **Start > Programs > Cisco Unified Provisioning Manager > Log in to Cisco Unified Provisioning Manager**.



**Note** If Enhanced Security is enabled on the Windows 2003 system, you must add the Provisioning Manager home page to the Internet Explorer Trusted Sites Zone. You will not be able to access the Cisco Unified Provisioning Manager home page until it is added to the trusted sites. See [Adding the Provisioning Manager Home Page to the Internet Explorer Trusted Sites Zone, page 2-14](#).

## Adding the Provisioning Manager Home Page to the Internet Explorer Trusted Sites Zone

If Enhanced Security is enabled on the Windows 2003 system, you must perform the following procedure before you can access the Provisioning Manager home page.

- Step 1** Open Provisioning Manager and select **Start > Programs > Cisco Unified Provisioning Manager**.
- Step 2** From the File menu, select **Add this site to**.
- Step 3** Click **Trusted Sites Zone**.
- Step 4** In the Trusted Sites dialog box, click **Add** to move the site to the list.
- Step 5** Click **Close**.
- Step 6** Refresh the page to view the site from its new zone.
- Step 7** Check the Status bar of the browser to confirm that the site is in the Trusted Sites Zone.

## Cleaning Up a Failed New Installation

If Provisioning Manager did not install correctly, you must first clean up the system before trying to install Provisioning Manager again. These procedures are for a failed new installation of Provisioning Manager 1.2. If you need to clean up a failed upgrade of Provisioning Manager 1.1 to 1.2, see [Provisioning Manager Database Backup, page 2-18](#).

After a failed installation, do the following:

- Delete the CUPM installation folder. If you selected the default location during installation, it is C:\CUPM.
- Delete the Documents and Settings\cupmuser folder.

- Remove the Windows user cupmuser (cupmuser is the default name provided during installation). The Windows username can be different, if you changed it during installation. For instructions on removing the Windows cupmuser, see [Removing the CUPM Windows User, page 2-15](#).

## Removing the CUPM Windows User

---

**Step 1** On the Windows desktop, select **Start > Settings > Control Panel**.

**Step 2** Double-click **Administrative Tools**.

**Step 3** Double-click **Computer Management**.

**Step 4** In the console tree, under Local Users and Groups, click **Users**.

**Step 5** Right click the user account **cupmuser** and delete it.



---

**Note** The Windows username, cupmuser, is the default name provided during installation. The Windows username can be different, if you changed it during installation.

---

**Step 6** Delete cupmuser's home directory. The default location is in the directory C:\Documents and Settings\.

---

# Upgrading Provisioning Manager 1.1 to Provisioning Manager 1.2

There are two upgrade scenarios; select the procedure that matches your scenario:

- [Upgrading Provisioning Manager on One System \(Application and Database on the Same System\), page 2-16](#)
- [Upgrading Provisioning Manager on a Distributed System \(Application and Database Are on Separate Systems\), page 2-18](#)

### Before Upgrading

Provisioning Manager 1.2 has discontinued support for older versions of devices. If your Provisioning Manager 1.1 installation is incorporated with any of these devices, before you can upgrade to Provisioning Manager 1.2, you must first upgrade the devices to a currently supported version. For device support information, see the *Supported Devices Table for Cisco Unified Provisioning Manager 1.2* at [http://www.cisco.com/en/US/products/ps7125/products\\_device\\_support\\_tables\\_list.html](http://www.cisco.com/en/US/products/ps7125/products_device_support_tables_list.html).



---

**Note** After upgrading the device, you must update the device version information in Provisioning Manager 1.1 to the supported version for Provisioning Manager 1.2. If you do not perform this update, you will not be able to upgrade Provisioning Manager.

---

Following are the devices for which support has been dropped in Provisioning Manager 1.2:

- Cisco Unified Communications Manager 4.0.2
- Cisco Unified Communications Express 3.3 and 3.4

- Cisco Unity Connection 1.1.1
- Cisco Unity Express 2.1.3 and 2.2.2

## Upgrading Provisioning Manager on One System (Application and Database on the Same System)

**Step 1** Manually back up your database. For instructions, see [Provisioning Manager Database Backup, page 2-18](#).



**Note** This manual backup is not the same backup that occurs automatically during upgrade. Both backups must be performed.

**Step 2** On the system where Provisioning Manager 1.1 is installed, make sure the following prerequisites are met:

- Required (or desired) operating system upgrades have been performed.
- Required service packs are installed.

For system requirements, see [Server Requirements, page 1-2](#).

**Step 3** Close all open or active programs. Do not run other programs during the installation process.

**Step 4** As the local administrator, log in to the machine on which you will install the Provisioning Manager software, and insert the Cisco Unified Provisioning Manager CD-ROM into the CD-ROM drive. The Cisco Unified Provisioning Manager 1.2 window opens.



**Note** If the CD-ROM is already in the CD-ROM drive and you stopped the installation process to close programs or if Autostart is disabled, click **cupm1.2-setup.exe** to restart the process.

**Step 5** Click **Install**. The Welcome window appears.

**Step 6** Click **Next**. The Software License Agreement window appears.

**Step 7** Accept the Software License Agreement and then click **Next**.

**Step 8** A confirmation box appears, telling you that an upgrade to Provisioning Manager 1.2 will occur. Click **Next**. A check of the system is performed, which verifies the following:

- No orders are in the Released state.
- All service actions are in the Closed state.
- All workflows are in the Finished state.
- No infrastructure, subscriber, or Domain synchronizations are running.
- No batch projects are running or are in the Active state.
- That there are not any unsupported devices configured in Provisioning Manager.



**Note** For device support information, see the *Supported Devices Table for Cisco Unified Provisioning Manager 1.2* at [http://www.cisco.com/en/US/products/ps7125/products\\_device\\_support\\_tables\\_list.html](http://www.cisco.com/en/US/products/ps7125/products_device_support_tables_list.html).

If any of these conditions are not met, the installation will stop.

**Note**

If you are upgrading only the database or only the application (because you have a distributed setup) not all the screens will appear during the upgrade process. Also, to complete the upgrade of a distributed setup, you must run the Cisco Unified Provisioning Manager 1.2 installation CD on both systems.

When only upgrading the database (for distributed setup), you will be required to re-enter the PostgreSQL database administrator password and the application database user username (the default is cupm) and password.

**Step 9** Select a directory in which to back up the Provisioning Manager 1.1 data during upgrade. Click **Next**. The Summary page appears.

**Step 10** Click **Install**.

**Note**

If an error message appears similar to the following appears, it means that the installation has failed:

```
C:\CUPM\httpd\conf\httpd.conf exists on this system and it has been modified since
instillation. Do you want to remove this file?
```

Before trying to install Provisioning Manager again, you must clean up the system. See [Provisioning Manager Database Backup, page 2-18](#).

**Step 11** Eject the CD-ROM.

**Note**

Store the CD-ROM in a secure, climate-controlled area for safekeeping.

**Step 12** Click **Finish**.

**Step 13** After the installation completes, verify that Provisioning Manager is installed correctly by accessing the Provisioning Manager login page. From the Windows desktop, select **Start > Programs > Cisco Unified Provisioning Manager > Log in to Cisco Unified Provisioning Manager**.

**Note**

After upgrading Provisioning Manager, you must synchronize all your Unified Message Processors in Provisioning Manager before placing any orders for a processor.

**Note**

If Enhanced Security is enabled on the Windows 2003 system, you must add the Provisioning Manager home page to the Internet Explorer Trusted Sites Zone. You will not be able to access the Cisco Unified Provisioning Manager home page until it is added to the trusted sites. See [Adding the Provisioning Manager Home Page to the Internet Explorer Trusted Sites Zone, page 2-14](#).

## Upgrading Provisioning Manager on a Distributed System (Application and Database Are on Separate Systems)

You must upgrade both the Provisioning Manager application and the Provisioning Manager database systems.

- 
- Step 1** Back up the Provisioning Manager 1.1 database. For information, see [Provisioning Manager Database Backup, page 2-18](#).
- Step 2** Upgrade the Provisioning Manager 1.1 database to 1.2. The installation program will only take you through the applicable upgrade screens. If you need additional information, see [Upgrading Provisioning Manager on One System \(Application and Database on the Same System\), page 2-16](#).
- Step 3** Upgrade the Provisioning Manager 1.1 application to 1.2. The installation program will only take you through the applicable upgrade screens. If you need additional information, see [Upgrading Provisioning Manager on One System \(Application and Database on the Same System\), page 2-16](#).



### Note

After upgrading Provisioning Manager, you must synchronize all your Unified Message Processors in Provisioning Manager before placing any orders for a processor.

---

## Provisioning Manager Database Backup

There are two backup scenarios; select the procedure that matches your scenario:

- Backing up on a single machine, see [Backing up the Single-Machine Provisioning Manager Database, page 2-18](#).
- Backing up for a distributed scenario, see [Backing up Provisioning Manager on a Distributed Database, page 2-19](#).



### Note

When backing up files, you should place the files on a different file server. Also, you should burn the backup data onto a CD.

---

## Backing up the Single-Machine Provisioning Manager Database



### Note

This procedure requires that you have administrator level access to the Provisioning Manager database (the PostgreSQL database).

---

- Step 1** On the Provisioning Manager system, stop the following services:
- Apache
  - cupm JBossService
  - cupm NiceService
- a. On the Windows desktop, select **Start > Control Panel > Administrative Tools > Services**.

b. Right-click each of the services and click **Stop**.

**Step 2** On the Windows desktop, select **Start > All Programs > PostgreSQL8.2 > Command Prompt**. A command prompt opens in the <Install directory>\pgsql\bin directory.



**Note** If you accepted the default location during installation, the installation directory is C:\CUPM.

**Step 3** In the command prompt, run the following command and enter the PostgreSQL administrator password when prompted.

```
pg_dumpall -o -U<username> >[path and fileForBackup]
```

Where <username> is the username of the PostgreSQL administrator. If you accepted the default, the administrator username is *postgres*.



**Note** Enter the password each time that you are prompted.

This command is used to backup the database, by storing the database information in a file.

**Step 4** If you are backing up on the same installation, proceed to the next step. If you are backing up for a new installation, make backup copies as described in this step.

- a. In a backup folder, make copies of the following files and directories:
- <installLocation>/install.log
  - <installLocation>/sep/dfc.properties
  - <installLocation>/sep/dfc.keystore
  - <installLocation>/jboss-4.0.3SP1/server/cupm/conf/login-config.xml

**Step 5** Start the following services:

- Apache
  - cupm JBossService
  - cupm NiceService
- a. On the Windows desktop, select **Start > Control Panel > Administrative Tools > Services**.
- b. Right-click each of the services and click **Start**.

## Backing up Provisioning Manager on a Distributed Database



**Note** This procedure requires that you have administrator level access to the Provisioning Manager database (the PostgreSQL database)

**Step 1** On the system where Provisioning Manager is running, stop the following services:

- Apache
- cupm JBossService

- cupm NiceService
- a. On the Windows desktop where Provisioning Manager is running, select **Start > Control Panel > Administrative Tools > Services**.
- b. Right-click each of the services and click **Stop**.

**Step 2** On the Windows desktop where the Provisioning Manager database is running, select **Start > All Programs > PostgreSQL8.2 > Command Prompt**. A command prompt opens in the <Install directory>\pgsql\bin directory.



**Note** If you accepted the default location during installation, the installation directory is C:\CUPM.

**Step 3** In the command prompt, run the following command and enter the PostgreSQL administrator password when prompted.

```
pg_dumpall -o -U<username> > [path and fileForBackup]
```

Where <username> is the username of the PostgreSQL administrator. If you accepted the default, the administrator username is *postgres*.



**Note** Enter the password each time that you are prompted.

This command is used to backup the database, by storing the database information in a file.

**Step 4** If you are backing up on the same installation, proceed to the next step. If you are backing up for a new installation, either with the same or a new IP address, do the following. On the machine where Provisioning Manager is running, in a backup folder, make copies of the following files and directories:

- <installLocation>/install.log
- <installLocation>/sep/dfc.properties
- <installLocation>/sep/dfc.keystore
- <installLocation>/jboss-4.0.3SP1/server/cupm/conf/login-config.xml

**Step 5** Start the following services:

- Apache
- cupm JBossService
- cupm NiceService
- a. On the Windows desktop, select **Start > Control Panel > Administrative Tools > Services**.
- b. Right-click each of the services and click **Start**.

## Restoring Provisioning Manager 1.1 when Provisioning Manager 1.2 Installation Fails

If Provisioning Manager did not upgrade correctly, you must first clean up the system before trying to install Provisioning Manager again. These procedures are only for a failed upgrade. If you need to restore a failed new installation of Provisioning Manager, see [Cleaning Up a Failed New Installation, page 2-14](#).

After a failed upgrade, do the following:

- Clean up the old installation of Provisioning Manager 1.1 (see [Cleaning Up the Old Installation, page 2-21](#)).
- Restore Provisioning Manager 1.1 (see [Restoring Provisioning Manager 1.1, page 2-22](#)).

## Cleaning Up the Old Installation

---

**Step 1** Uninstall the Provisioning Manager installation. Depending upon where the installation failed, the installed application may appear as Provisioning Manager 1.1 or Provisioning Manager 1.2. Try to use the standard uninstallation process (see [Uninstalling Provisioning Manager, page 2-25](#)).

If the standard uninstallation process does not work, go to [Step 2](#).

**Step 2** If standard uninstallation fails, you will have to perform some or all of the following steps:

- a. Uninstall Postgres 8.2 if it still exists. If PostgreSQL 8.2 is listed under **Windows Control Panel > Add or Remove Programs**, click **Remove** to uninstall it.
- b. Remove the installation directory *CUPM*. This step may require a system reboot if the Provisioning Manager services are still running and using the resources from the installation location.



---

**Note** If you selected the default location during installation, it is C:\CUPM.

---

- c. Remove the *cupmuser* (Windows user) if it still exists:
  1. Select **Start > Settings > Control Panel**.
  2. Double-click **Administrative Tools**.
  3. Double-click **Computer Management**.
  4. In the console tree, under Local Users and Groups, click **Users**.
  5. Right-click the user account **cupmuser** and delete it.
  6. Delete cupmuser's home directory. The default location is in the directory C:\Documents and Settings\.
- d. Remove the folder C:\Program Files\Common Files\InstallShield\Universal\common\Gen1.
- e. (Optional) You may need to delete the Provisioning Manager services. Make sure the services are not running before you delete them.

Provisioning Manager services that need to be deleted:

- Apache2
- cupm JbossService
- cupm NICEService
- pgsq1-8.2

Use the following command to delete Windows services: `sc.exe delete <service name>`.

---

## Restoring Provisioning Manager 1.1

There are two restore scenarios; select the procedure that matches your scenario:

- Restoring on a single machine, see [Restoring the Single-Machine Provisioning Manager Database, page 2-22](#).
- Restoring for a distributed scenario, see [Restoring Provisioning Manager for a Distributed Database, page 2-23](#).

### Restoring the Single-Machine Provisioning Manager Database



**Note** This procedure requires that you have administrator level access to the Provisioning Manager database (the PostgreSQL database).

- Step 1** Stop Provisioning Manager services (for information on which services to stop, see [Step 1 on page 2-18](#)).
- Step 2** On the Windows desktop, select **Start > All Programs > PostgreSQL8.2 > Command Prompt**. A command prompt opens in folder <Install directory>\pgsql\bin.



**Note** If you accepted the default location during installation, the installation directory is C:\CUPM.

- Step 3** To enter the PostgreSQL prompt, run the following command and enter the PostgreSQL administrator password for the current installation when prompted:

```
psql.exe -U<username>
```

Where <username> is the username of the PostgreSQL administrator. If you accepted the default, the administrator username is *postgres*.

- Step 4** Before restoring the database, you must drop the database name and role. In the command prompt, run the following commands exactly as shown, one at a time and in the following order:

- **DROP DATABASE cupm;**

Where *cupm* is the database name to be removed.

Expected output: DROP DATABASE

- **DROP ROLE <rolename>;**

Where <rolename> is the username for the SEP database user. If you accepted the default, the username is *cupm*.

Expected output: DROP ROLE

- **ALTER ROLE <username> WITH PASSWORD '<password>';**

Where *username* is the username of the PostgreSQL administrator user, and *password* should be the password set for the PostgreSQL administrator with backed up data. If you accepted the default administrator username, the username is *postgres*.

Expected output: ALTER ROLE

- Step 5** Enter \q to quit the PostgreSQL prompt.

**Step 6** From the command line, run the following command, entering the password set in the previous step for the PostgreSQL user when prompted:

```
psql.exe -U<username> -d postgres < [path and fileToRestoreFrom]
```

Where *<username>* is the username of the PostgreSQL administrator. If you accepted the default, the administrator username is *postgres*.

This command restores the database.

**Step 7** Copy back the following backed up files:

- <installLocation>/install.log
- <installLocation>/sep/dfc.properties
- <installLocation>/sep/dfc.keystore
- <installLocation>/jboss-4.0.3SP1/server/cupm/conf/login-config.xml

**Step 8** Start the following services:

- Apache
  - cupm JBossService
  - cupm NiceService
- a. On the Windows desktop, select **Start > Control Panel > Administrative Tools > Services**.
  - b. Right-click each of the services and click **Start**.
- 

## Restoring Provisioning Manager for a Distributed Database



**Note** This procedure requires that you have administrator level access to the Provisioning Manager database (the PostgreSQL database)

---

**Step 1** On the Provisioning Manager application system, stop the Provisioning Manager services (for information on which services to stop, see [Step 1 on page 2-19](#)).

**Step 2** On the Windows desktop where the Provisioning Manager database is running, select **Start > All Programs > PostgreSQL8.2 > Command Prompt**.

A command prompt opens in folder <Install directory>\pgsql\bin.



**Note** If you accepted the default location during installation, the installation directory is C:\CUPM.

---

**Step 3** To enter the PostgreSQL prompt, run the following command and enter the PostgreSQL administrator password for the current installation when prompted:

```
psql.exe -U<username>
```

Where *<username>* is the username of the PostgreSQL administrator. If you accepted the default, the administrator username is *postgres*.

**Step 4** Before restoring the database, you must drop the database name and role. In the command prompt, run the following commands exactly as shown, one at a time and in the following order:

- **DROP DATABASE cupm;**

Where *cupm* is the database name to be removed.

Expected output: DROP DATABASE

- **DROP ROLE <rolename>;**

Where <rolename> is the username for the SEP database user. If you accepted the default, the username is *cupm*.

Expected output: DROP ROLE

- **ALTER ROLE <username> WITH PASSWORD '<password>;'**

Where <username> is the username of the PostgreSQL administrator, and *password* is the password set for the PostgreSQL administrator with backed up data. If you accepted the default administrator username, the username is *postgres*.

Expected output: ALTER ROLE

**Step 5** Enter \q to quit the PostgreSQL prompt.

**Step 6** From the command line, run the following command, entering the password set in the previous step for the PostgreSQL user when prompted:

```
psql.exe -U<username> -d postgres < [path and fileToRestoreFrom]
```

Where <username> is the username of the PostgreSQL administrator. If you accepted the default, the administrator username is *postgres*.

This command restores the database.

**Step 7** Copy back the following backed up files on the machine where the Provisioning Manager application is running:

- <installLocation>/install.log
- <installLocation>/sep/dfc.properties
- <installLocation>/sep/dfc.keystore
- <installLocation>/jboss-4.0.3SP1/server/cupm/conf/login-config.xml

**Step 8** On the system where the Provisioning Manager application is running, start the following services:

- Apache
  - cupm JBossService
  - cupm NiceService
- a. On the Windows desktop, select **Start > Control Panel > Administrative Tools > Service**.
  - b. Right-click each of the services and click **Start**.
-

# Uninstalling Provisioning Manager

**Caution**

You must use the Provisioning Manager uninstallation program to remove Provisioning Manager from your system. If you try to remove the files and programs manually, you can seriously damage your system.

- 
- Step 1** Close all applications that are using Provisioning Manager files.
- Step 2** As the local administrator, log in to the system on which Cisco Unified Provisioning Manager is installed.
- Step 3** To start the uninstallation process, from the Windows desktop select **Start > Programs > Cisco Unified Provisioning Manager > Uninstall Cisco Unified Provisioning Manager**.
- Step 4** Click **Next** to begin uninstalling.  
A window appears, listing the components selected for uninstallation.
- Step 5** Click **Uninstall**.  
Messages showing the progress of the uninstallation appears.
- Step 6** A message appears, reminding you that the *cupmuser* (Windows user) directory and the *CUPM* installation folder must be removed manually. Click **Next**.

**Note**

The default Windows user name provided during installation is *cupmuser*. If you changed it during installation, the Windows user name may be different.

- 
- Step 7** Click **Finish**.
- Step 8** If you want to reboot the system, select **Yes, restart my computer**, then click **Finish**.
- Step 9** Manually delete the following folders from the Provisioning Manager system:
- The CUPM installation folder. If you selected the default location during installation, it is C:\CUPM.
  - The Documents and Settings\cupmuser folder.
-





# APPENDIX A

## Licensing

---

This appendix provides licensing information for Cisco Unified Provisioning Manager (Provisioning Manager). It contains the following sections:

- [Licensing Overview, page A-1](#)
- [Licensing Warnings, page A-4](#)

## Licensing Overview

Provisioning Manager features software-based product registration and license key technologies. Licensing ensures that you possess a licensed copy of Provisioning Manager 1.2.



### Note

---

Licensing uses node-locking technology. The license file can only be used with the MAC address that you supply.

---

To determine whether Provisioning Manager is licensed, see [Verifying Provisioning Manager License Status, page A-1](#). If you do not have a license or you want to upgrade your license, see [Licensing Scenarios, page A-2](#).

## Verifying Provisioning Manager License Status

---

- Step 1** Select **System Administration > License Information**. The Licensing Status Information page appears, displaying the following information:
- Unavailable features—Any features in Provisioning Manager that you do not have access to, because you do not have the appropriate license or because you have reached the limit for the use of the feature.
  - Features in overdraft state—Any features that you are using that have exceeded their allowable use limit.
  - All valid features—List of features and their corresponding use limit (Available), overuse allowed (Overdraft), current use (Used) and date of expiration (Expiry).
-

## Licenses that Can Be Purchased

The license that you purchase determines the number of phones that Provisioning Manager can provision.

You can purchase licenses in the following increments:

- Up to 500 phones.
- Up to 1,000 phones.
- Up to 2,000 phones.
- Up to 5,000 phones.
- Up to 10,000 phones.
- Up to 20,000 phones.
- Up to 30,000 phones.


**Note**

Licenses are cumulative. Meaning you can combine licenses to increase the number of phones you can support.

## Licensing Scenarios

[Table A-1](#) describes what to do in different scenarios if you do not have a licensed, registered copy of Provisioning Manager or if you want to increase phone support.

**Table A-1**      *How to Obtain and Register a License*

Scenario	What to Do
Installing with a purchased license.	<ol style="list-style-type: none"> <li>1. Before installing, obtain a license file. See <a href="#">Licensing Process, page A-3</a>.</li> </ol> <p><b>Note</b> You can install Provisioning Manager without the license file. You can upgrade your license after installation. See <a href="#">Registering a License File with Provisioning Manager, page A-4</a>.</p> <ol style="list-style-type: none"> <li>2. During installation, select License File Location, and provide the location of your license file.</li> </ol>
Installing with an evaluation license.	<p>During installation, select the option to evaluate the product. Evaluation versions are active for 90 days before you are required to purchase a license.</p> <p><b>Note</b> The evaluation license is limited to monitoring 100 phones, 5 Call Processors, and 2 Unified Message Processors.</p> <p>If you want to upgrade to a purchased license after installation, obtain a PAK and license file for the installed version of Provisioning Manager. For information on the licensing process, see <a href="#">Licensing Process, page A-3</a>.</p>

**Table A-1** *How to Obtain and Register a License (continued)*

Scenario	What to Do
Getting a license for additional devices (either upgrading from an evaluation license, or increasing the number of supported devices).	See <a href="#">Licensing Process, page A-3</a> .
Moving Provisioning Manager to another server.	Call the Cisco TAC for assistance.

## Licensing Process

The Provisioning Manager license file includes support for at least 1,000 phones. You can purchase incremental licenses for additional phone support and register up to 30,000 phones with a single Provisioning Manager. For each incremental license that you purchase, you will receive a Product Authorization Key (PAK), and you must use that PAK to obtain a license file.

This process applies to new installations and license upgrades.

1. Obtain a PAK—The PAK is used to register Provisioning Manager, and any additional device support that you might purchase for Provisioning Manager, on Cisco.com, and it contains resource limitations. See [Obtaining a PAK, page A-3](#).
2. Obtain a license file—A license file is sent to you after you register the PAK on Cisco.com. See [Obtaining a License File, page A-3](#).
3. Copy the license file to the server where Provisioning Manager is to be installed. If Provisioning Manager is already installed and you are upgrading your license file, you must register the license file with Provisioning Manager. See [Registering a License File with Provisioning Manager, page A-4](#).

## Obtaining a PAK

The PAK is located on the software claim certificate that is shipped with the Provisioning Manager product CD.

## Obtaining a License File

- Step 1** Register the PAK and the MAC address of the system where Provisioning Manager is installed with Cisco.com at <http://www.cisco.com/go/license>. You will be asked to log in. You must be a registered user of Cisco.com to log in.



**Note** The MAC address is required because licensing uses node-locking technology. The license file can only be used with the MAC address that you supply.

The license file will be emailed to you. After you obtain a license file, register the license with the Provisioning Manager server.

## Registering a License File with Provisioning Manager

- 
- Step 1** Copy the license file to the Provisioning Manager server, in the folder <Install Directory>\license. The system validates the license file and updates the license. The updated licensing information appears on the Licensing Status Information page.
- Step 2** The license should automatically take effect in a few minutes. If it does not, select **System Administration > License Information**.
- Step 3** Click **PERFORM AUDIT**. You will see the phones that you are licensed to update.
- Step 4** If you purchased more than one license, repeat [Step 1](#) to install each additional license.
- 

## Licensing Warnings

Provisioning Manager provides a licensing warning mechanism. A licensing warning icon (⚠) appears in the top right corner of the Provisioning Manager page when one of the following occurs:

- A license file does not exist or cannot be read.
- One or more features have reached or exceeded the limit specified in the licensing file.
- Entries for one or more features do not exist in the license file (this occurs only when the license file is not generated correctly or if the file is manually edited).

## Evaluation Version: Before Expiry

If you have installed the evaluation version of Provisioning Manager, you must obtain the license file from Cisco.com if you want to continue to use the product after the 90-day evaluation period. For details, see [Licensing Process, page A-3](#).

If you go past the 90-day evaluation period, you will see a licensing warning icon (⚠) in the top right corner of Provisioning Manager. You can view the expiry date on the Licensing Information page.

## Purchased Version: Phone Limit Exceeded

If you have a restricted license, Provisioning Manager displays the information on which of the phones have exceeded the limit on the Licensing Information page (see [Verifying Provisioning Manager License Status, page A-1](#)). You will not be able to add more phones.

If you go past the phone phone limit for your license, you will see a licensing warning icon (⚠) in the top right corner of Provisioning Manager.



## INDEX

---

### A

about Provisioning Manager [1-1](#)  
auto-allocation, disabling [2-5](#)

---

### B

backing up database [2-18](#)  
browsers, supported [1-3](#)

---

### C

cautions  
    Provisioning Manager, uninstalling [2-25](#)  
Cisco Security Agent, interoperability with [1-4](#)  
Cisco Unified Communications Manager  
    username and password [2-4](#)  
Cisco Unified Communications Manager Express  
    auto-allocation, disabling [2-5](#)  
    preparing for Provisioning Manager installation [2-5](#)  
configuring Provisioning Manager server  
    RAM [2-2](#)

---

### D

database, installing on separate system [2-13](#)  
database backup and restore [2-18](#)  
directory numbers, disabling auto-allocation [2-5](#)  
disabling  
    auto-allocation [2-5](#)  
drive space requirement, server [1-3](#)

---

### E

Enhanced Security, Windows 2003 [2-14, 2-17](#)  
evaluation license, limits for [A-2, A-4](#)

---

### F

firewalls  
    and client access [1-4](#)  
    and ports used by Provisioning Manager [2-10](#)

---

### I

installation fails  
    restoring [2-14](#)  
installation failure  
    cleaning up [2-21](#)  
installing Provisioning Manager [2-11 to 2-14](#)  
    preparing [2-1](#)  
        devices [2-4](#)  
        required input [2-10](#)  
        server [2-4](#)  
    verifying TCP and UDP port availability [2-10](#)

---

### L

license  
    directory [A-4](#)  
    evaluation, limits for [A-2, A-4](#)  
    file  
        obtaining [A-3](#)  
        registering [A-4](#)  
    incremental

- installing [A-3](#)
- purchasing [A-2](#)
- moving to another server [A-2](#)
- PAK, location of [A-3](#)
- reminders [A-4](#)
- status, verifying [A-1](#)

---

## M

- memory (RAM) requirements
  - client [1-4](#)
  - server [1-3](#)

---

## N

- new features in Provisioning Manager [1-2](#)

---

## P

- PAK, obtaining [A-3](#)
- phones
  - license limits [A-2](#)
  - server requirements related to [1-2](#)
- ports, occupied [2-10](#)
- preparing to install Provisioning Manager
  - Cisco Unified Communications Manager Express [2-5](#)
  - client requirements [1-3](#)
  - overview [2-1](#)
  - server requirements [1-2](#)
- processor requirements
  - client [1-3](#)
  - server [1-2](#)
    - RAM, enabling 4 GB [2-2](#)
- Product Authorization Key. *See* PAK
- Provisioning Manager, overview [1-1](#)

---

## R

- registering license [A-4](#)
- removing cupm Windows user [2-15](#)
- restore database [2-18](#)
- restoring Provisioning Manager 1.1 installation [2-18](#)

---

## S

- service packs, Windows
  - on client [1-4](#)
  - on server [1-3](#)
- software on server
  - not supported [2-11](#)
  - required [1-3](#)
  - supported [1-4](#)
- SQL server user for Cisco Unity [2-8](#)
- swap space requirement, server [1-3](#)

---

## T

- TCP ports
  - used by Cisco Unity [2-8](#)
  - used by Provisioning Manager [2-10](#)
- trusted site zone, adding Provisioning Manager to [2-14](#)

---

## U

- UDP and TCP ports used by Provisioning Manager [2-10](#)
- uninstalling Provisioning Manager [2-25, 2-25](#)
- upgrading Provisioning Manager [2-15 to 2-17](#)
  - distributed system [2-18](#)
- user and password
  - for Cisco Unified Communications Manager [2-4](#)
  - for Cisco Unity SQL server [2-8](#)

---

**V**

virus protection software

    disabling during installation [2-11](#)

    interoperability with [1-4](#)

VPN, and client access [1-4](#)

