



Cisco Network Planning Solution Design and Analysis Planning and Design User Guide

Software Release 11.5

Corporate Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 526-4100

Text Part Number: OL-7540-02



THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

CCSP, CCVP, the Cisco Square Bridge logo, Follow Me Browsing, and StackWise are trademarks of Cisco Systems, Inc.; Changing the Way We Work, Live, Play, and Learn, and iQuick Study are service marks of Cisco Systems, Inc.; and Access Registrar, Aironet, ASIST, BPX, Catalyst, CCDA, CCDP, CCIE, CCIP, CCNA, CCNP, Cisco, the Cisco Certified Internetwork Expert logo, Cisco IOS, Cisco Press, Cisco Systems, Cisco Systems Capital, the Cisco Systems logo, Cisco Unity, Empowering the Internet Generation, Enterprise/Solver, EtherChannel, EtherFast, EtherSwitch, Fast Step, FormShare, GigaDrive, GigaStack, HomeLink, Internet Quotient, IOS, IP/TV, iQ Expertise, the iQ logo, iQ Net Readiness Scorecard, LightStream, Linksys, MeetingPlace, MGX, the Networkers logo, Networking Academy, Network Registrar, *Packet*, PIX, Post-Routing, Pre-Routing, ProConnect, RateMUX, ScriptShare, SlideCast, SMARTnet, StrataView Plus, TeleRouter, The Fastest Way to Increase Your Internet Quotient, and TransPath are registered trademarks of Cisco Systems, Inc. and/or its affiliates in the United States and certain other countries.

All other trademarks mentioned in this document or Website are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (0502R)

*Cisco Network Planning Solution
Design and Analysis
Planning and Design User Guide*

Copyright © 2005 Cisco Systems, Inc. All rights reserved.

Copyright

Document Copyright

Document Title: Planning and Design User Guide
Document Part Number: D00267
Version: 6

© 1987-2005 OPNET Technologies, Inc.
All Rights Reserved. Reproduction, adaptation, or translation without prior written permission is prohibited, except as allowed under the copyright laws.

Software Copyright

Product Name: IT Guru
Product Release: 11.5

© 1987-2005 OPNET Technologies, Inc.
All Rights Reserved.

Documentation Conventions

OPNET documentation uses specific formatting and typographic conventions to present the following types of information:

- Objects, examples, and system I/O
- Object hierarchies, notes, and warnings
- Computer commands
- Lists and procedures

Objects, Examples, and System I/O

- Directory paths and file names are in plain Courier typeface:

```
opnet\release\models\std\ip
```

- Function names in body text are in italics:

```
op_dist_outcome()
```

- The names of functions of interest in example code are in bolded Courier typeface:

```
/* determine the object ID of packet's creation module */  
src_mod_objid = op_pk_creation_mod_get (pkptr);
```

- Variables are enclosed in angle brackets (< >):

```
<opnet_user_home>/op_admin/err_log
```

Object Hierarchies, Notes, and Warnings

Menu hierarchies are indicated by right angle brackets (>); for example:

```
Open File > Print Setup > Properties...
```

Attribute hierarchies are represented by angled arrows (▲) that indicate that you must drill down to a lower level of the hierarchy:

Attribute level 1 ▶ Attribute level 2 ▶ Attribute level 3

Note—Notes are indicated by text with the word Note at the beginning of the paragraph. Notes advise you of important supplementary information.

WARNING—Warnings are indicated by text with the word WARNING at the beginning of the paragraph. Warnings advise you of vital information about an operation or system behavior.

Computer Commands

These conventions apply to Windows systems and navigation methods that use the standard graphical-user-interface (GUI) terminology such as click, drag, and dialog box.

- Key combinations appear in the form “press <button>+x”; this means press the <button> and x keys *at the same time* to do the operation.
- The mouse operations *left-click* (or *click*) and *right-click* indicate that you should press the left mouse button or right mouse button, respectively.

Lists and Procedures

Information is often itemized in bulleted (unordered) or numbered (ordered) lists:

- In bulleted lists, the sequence of items is not important.
- In numbered lists, the sequence of items is important.

Procedures are contained within procedure headings and footings that indicate the start and end of the procedure. Each step of a procedure is numbered to indicate the sequence in which you should do the steps. A step may be followed by a description of the results of that step; such descriptions are preceded by an arrow.

Procedure FM-1 Sample Procedure Format

- 1 Procedure step.
 - ➔ Result of the procedure step.

- 2 Procedure step.

End of Procedure FM-1

For more information about using and maintaining OPNET documentation, see the Documentation Guide.

Document Revision History

| Release Date | Product Version | Chapter | Description of Change |
|--------------|-----------------|---|--|
| August 2005 | 11.5 | OPNET Design Actions | <ul style="list-style-type: none"> Updated Design Action Log section for new log viewer. |
| | | IP QoS Design Actions | <ul style="list-style-type: none"> New chapter with descriptions of the ip_qos_configuration and ip_qos_queue_sizing design actions |
| | | Project Pricing Reporter | <ul style="list-style-type: none"> New chapter |
| | | MPLS Differentiated-Service-Aware Traffic Engineering | <ul style="list-style-type: none"> New chapter |
| January 2004 | 10.5 | Link Dimensioning | <ul style="list-style-type: none"> New chapter |
| | | Link Dimensioning Resilient | <ul style="list-style-type: none"> New chapter |
| | | Ring Backbone | <ul style="list-style-type: none"> New chapter |
| | | Spanning Tree | <ul style="list-style-type: none"> New chapter |
| | | Dual Tree | <ul style="list-style-type: none"> New chapter |
| | | Design Actions | <ul style="list-style-type: none"> Moved chapter from Guru <i>User Guide</i> |

Contents

| | | |
|--|--|------------|
| | <i>Copyright</i> | DA-FM-iii |
| | <i>Documentation Conventions</i> | DA-FM-iv |
| | <i>Document Revision History</i> | DA-FM-vii |
| | <i>List of Figures</i> | DA-FM-xi |
| | <i>List of Tables</i> | DA-FM-xii |
| | <i>List of Procedures</i> | DA-FM-xiii |

| | | |
|----------|---|---------------|
| 1 | OPNET Design Actions | DA-1-1 |
| | Workflows for Design Actions | DA-1-2 |
| | Design Menu | DA-1-3 |
| | Configuring a Design Action | DA-1-3 |
| | Viewing Information about a Design Action | DA-1-4 |
| | Compound Actions, Roles, and Subactions | DA-1-4 |
| | Derived Actions | DA-1-5 |
| | Configure/Run Design Action Dialog Box | DA-1-6 |
| | Running a Design Action | DA-1-8 |
| | Quick Actions | DA-1-8 |
| | Run Action Dialog Box | DA-1-9 |
| | Viewing Results | DA-1-10 |
| | Design Action Log | DA-1-10 |
| | Custom Design Actions | DA-1-11 |

| | | |
|----------|---|---------------|
| 2 | Link Dimensioning | DA-2-1 |
| | Prerequisites | DA-2-2 |
| | Configuring and Running the link_dimensioning Design Action | DA-2-2 |
| | Log Messages | DA-2-4 |
| | Unsatisfactory Solutions | DA-2-4 |
| | Viewing Reports | DA-2-6 |

| | | |
|----------|---|---------------|
| 3 | Link Dimensioning Resilient | DA-3-1 |
| | Prerequisites | DA-3-1 |
| | Configuring and Running the link_dimensioning_resilient Design Action | DA-3-1 |
| | Failure Cases | DA-3-2 |
| | Viewing Logs | DA-3-3 |
| | Unsatisfactory Solutions | DA-3-4 |
| | Viewing Reports | DA-3-4 |

| | | |
|----------|---|---------------|
| 4 | Ring Backbone Topology Design | DA-4-1 |
| | Prerequisites | DA-4-1 |
| | Background Knowledge | DA-4-2 |
| | Design Action and Attribute Descriptions | DA-4-2 |
| | Configuring and Running the Ring Backbone Design Action | DA-4-2 |
| | Graph Engine | DA-4-3 |

| | | |
|----------|---|----------------|
| | Log Messages | DA-4-5 |
| | Available Reports | DA-4-6 |
| | Link Summary | DA-4-6 |
| | Summary | DA-4-7 |
| <hr/> | | |
| 5 | Spanning Tree Topology Design | DA-5-1 |
| | Prerequisites | DA-5-1 |
| | Background Knowledge | DA-5-2 |
| | Design Action and Attribute Descriptions | DA-5-2 |
| | Configuring and Running the Spanning Tree Design Action | DA-5-2 |
| | Log Messages | DA-5-4 |
| | Available Reports | DA-5-5 |
| | Link Summary | DA-5-5 |
| | Summary | DA-5-6 |
| <hr/> | | |
| 6 | Dual Tree Topology Design | DA-6-1 |
| | Prerequisites | DA-6-1 |
| | Background Knowledge | DA-6-2 |
| | Design Action and Attribute Descriptions | DA-6-2 |
| | Configuring and Running the Dual Tree Design Action | DA-6-2 |
| | Log Messages | DA-6-3 |
| | Available Reports | DA-6-4 |
| | Link Summary | DA-6-4 |
| | Summary | DA-6-5 |
| <hr/> | | |
| 7 | IP QoS Design Actions | DA-7-1 |
| | IP QoS Configuration | DA-7-1 |
| | IP QoS Queue Sizing | DA-7-1 |
| <hr/> | | |
| 8 | Project Pricing Reporter | DA-8-1 |
| | Workflow Description | DA-8-1 |
| | Configuring the Pricing Preference Object | DA-8-2 |
| | Regions | DA-8-3 |
| | Cost Elements | DA-8-3 |
| | Cost Categories | DA-8-4 |
| | Work Package | DA-8-5 |
| | Specifying Pricing Information on Nodes and Links | DA-8-6 |
| | Pricing Information Compound Attribute | DA-8-6 |
| | Running the project_pricing_reporter Design Action | DA-8-8 |
| | Configuring the project_pricing_reporter Design Action | DA-8-9 |
| | Viewing Results | DA-8-9 |
| <hr/> | | |
| | Index | DA-IX-1 |

List of Figures

| | | |
|-------------|---|---------|
| Figure 1-1 | Attribute Table for a Design Action (Example) | DA-1-4 |
| Figure 1-2 | Subactions Table (Example) | DA-1-5 |
| Figure 1-3 | Configure/Run Design Action Dialog Box | DA-1-6 |
| Figure 1-4 | Run Action Dialog Box | DA-1-9 |
| Figure 1-5 | Design Action Log | DA-1-10 |
| Figure 4-1 | Types of Ring Designs | DA-4-4 |
| Figure 5-1 | Types of Spanning Trees | DA-5-3 |
| Figure 8-1 | Attribute table in the Pricing Preference Object | DA-8-2 |
| Figure 8-2 | “Regions” Attribute Table | DA-8-3 |
| Figure 8-3 | “Cost Elements” Compound Attribute | DA-8-3 |
| Figure 8-4 | “Applicable To” Attribute of “Cost Elements” Compound Attribute | DA-8-4 |
| Figure 8-5 | “Cost Categories” Attribute Table | DA-8-4 |
| Figure 8-6 | “Definition” Attribute of “Cost Categories” Compound Attribute | DA-8-5 |
| Figure 8-7 | “Work Packages” Attribute Table | DA-8-5 |
| Figure 8-8 | Pricing Attributes on Supported Models | DA-8-6 |
| Figure 8-9 | “Pricing Information” Attribute Table | DA-8-6 |
| Figure 8-10 | “Pricing Definition” Attribute Table | DA-8-7 |
| Figure 8-11 | Configure/Run Design Action Dialog Box | DA-8-8 |
| Figure 8-12 | project_pricing_report Attribute Table | DA-8-9 |
| Figure 8-13 | Results for project_pricing_reporter Design Action | DA-8-9 |

List of Tables

| | | |
|-----------|---|--------|
| Table 1-1 | Workflows for Design Actions | DA-1-2 |
| Table 1-2 | Design Menu Operations. | DA-1-3 |
| Table 1-3 | Configure/Run, Design Action Dialog Box. | DA-1-7 |
| Table 1-4 | Run Action Dialog Box | DA-1-9 |
| Table 2-1 | Operations on Individual Links | DA-2-1 |
| Table 2-2 | Categories of link_dimensioning Log Messages | DA-2-4 |
| Table 2-3 | Classes of link_dimensioning Log Messages | DA-2-4 |
| Table 2-4 | Messages for Unsatisfactory Solutions | DA-2-5 |
| Table 2-5 | link_dimensioning Reports | DA-2-6 |
| Table 3-1 | Categories of link_dimensioning_resilient Log Messages. | DA-3-3 |
| Table 3-2 | Classes of link_dimensioning_resilient Log Messages | DA-3-3 |
| Table 3-3 | link_dimensioning_resilient Reports | DA-3-4 |
| Table 4-1 | Ring Backbone Graph Engine Characteristics | DA-4-3 |
| Table 4-2 | Categories of Ring Backbone Design Log Messages | DA-4-5 |
| Table 4-3 | Classes of Ring Backbone Design Log Messages | DA-4-5 |
| Table 4-4 | Link Summary Report Statistics | DA-4-6 |
| Table 4-5 | Summary Report Statistics | DA-4-7 |
| Table 5-1 | Categories of Spanning Tree Design Action Log Messages. | DA-5-4 |
| Table 5-2 | Classes of Spanning Tree Design Action Log Messages | DA-5-4 |
| Table 5-3 | Link Summary Report Statistics | DA-5-5 |
| Table 5-4 | Summary Report Statistics | DA-5-6 |
| Table 6-1 | Categories of Dual Tree Design Action Log Messages. | DA-6-3 |
| Table 6-2 | Classes of Dual Tree Design Action Log Messages | DA-6-3 |
| Table 6-3 | Link Summary Report Statistics | DA-6-4 |
| Table 6-4 | Summary Report Statistics | DA-6-5 |

List of Procedures

| | | |
|---------------|--|--------|
| Procedure 1-1 | Creating a Derived Action | DA-1-5 |
| Procedure 1-2 | Creating a Quick Action | DA-1-8 |
| Procedure 8-1 | Running the project_pricing_reporter Design Action | DA-8-8 |

1 OPNET Design Actions

A *design action* is a high-level operation that automates the process of changing a network model, usually to achieve a design goal. With a design action, you can modify your network models with one operation. For example, you can run the MPLS TE design action to find primary and protection explicit routes (ERs) for each LSP.

The OPNET Model Library includes a set of standard design action models. Each design action combines internal design logic with a set of configurable attributes. You can configure a design action in the same way that you configure other types of objects. If you own a license to the OPNET Development Kit, you can also extend the standard design action models to embed your custom logic or create completely new custom design actions.

Note—To use this feature, you must have a Design Module license.

Workflows for Design Actions

Design actions provide a very flexible way to make automated changes to your network. The workflow for a design action varies in complexity, depending on the extent of customization required.

Table 1-1 Workflows for Design Actions

| Extent of Customization | Workflow / References |
|------------------------------------|---|
| No customization | <ul style="list-style-type: none"> • Run action (Design > Run Design Action) • View results (Viewing Results on page DA-1-10) |
| Configure action | <ul style="list-style-type: none"> • Select action (Design > Configure/Run Design Action) • Configure attributes (Configuring a Design Action on page DA-1-3) • Run action (Running a Design Action on page DA-1-8) • View results (Viewing Results on page DA-1-10) |
| Select subactions / program blocks | <ul style="list-style-type: none"> • Select action (Design > Configure/Run Design Action) • Select subactions to fill specific functional roles (Compound Actions, Roles, and Subactions on page DA-1-4) • Configure attributes (Configuring a Design Action on page DA-1-3) • Run action (Running a Design Action on page DA-1-8) • View results (Viewing Results on page DA-1-10) |
| Modify / customize existing action | <ul style="list-style-type: none"> • Open existing action in Design Action Editor (Custom Design Actions on page DA-1-11) • Add new control attributes • Change embedded C/C++ code • Rebuild action |
| Create custom action | <ul style="list-style-type: none"> • Create entirely new action in Design Action Editor (Custom Design Actions on page DA-1-11) • Specify all information, including attributes and C/C++ code |
| End of Table 1-1 | |

Design Menu

The Design menu includes operations for selecting, configuring, running, and the viewing the results of design actions. Table 1-2 lists the Design menu operations.

Table 1-2 Design Menu Operations


| Menu item | | Reference |
|-----------------------------|--|--|
| Configure/Run Design Action | Select, configure, and run a design action | Configuring a Design Action on page DA-1-3 |
| Run Design Action | Select and run a design action without configuring it | Running a Design Action on page DA-1-8 |
| Quick Actions | Run a design action directly from the menu, without configuring it | Quick Actions on page DA-1-8 |
| Results | <p>View Latest Log—Displays the log messages generated by the last design action run.</p> <p>View Latest Reports—Displays the results of the last design action run.</p> <p>View Logs—Displays a list of log files generated by design action runs that were performed on the current project-scenario. From the list, you can select a log file to view.</p> <p>View Reports—Displays a list of results generated by design action run that were performed on the current project-scenario. From the list, you can select a set of results to view.</p> | — |
| End of Table 1-2 | | |

Configuring a Design Action

To configure a design action, choose Design > Configure/Run Design Action. The Configure/Run Design Action dialog box (Figure 1-3) shows a treeview of all available actions, a description of the selected action, and the list of visible attributes for the selected actions.

Every design action has one or more attributes that you can configure from this dialog box. You can also save a configured action under a new name, and thus create your own set of configured actions.

Figure 1-1 Attribute Table for a Design Action (Example)



Viewing Information about a Design Action

Because a design action can cause extensive changes to a scenario, it is good practice to research the effects and options of a design action thoroughly before you run it. There are three primary sources of information about a specific design action:

- Documentation—This manual includes chapters about specific design actions such as link dimensioning and MPLS traffic engineering.
- Action description—To view the action description, open the design action in the Configure / Run Action Dialog box and click the View Comments button.
- Attribute descriptions—To view descriptions of individual attributes, open the design action in the Configure / Run Action Dialog box; then click Edit Attributes. To view information about a specific attribute, click the Help ('?') icon as illustrated in Figure 1-1

Compound Actions, Roles, and Subactions

A *compound action* is a design action that can run other actions. A compound action has the following characteristics:

- Each compound action has one or more *roles* that define function blocks in the flowchart of the action. The function block is known by its role name, and runs other actions according to the internal flowchart of the compound action.

- The order in which the roles are listed in the user interface is not significant. Each compound action has its own internal flowchart that defines when and how each role is used.
- When an action is run by a role, it is called a *subaction*. If a compound action needs to execute a function block, it retrieves the subactions assigned to that role and runs each subaction in sequence.
- You can assign zero, one, or multiple subactions to a role. You might not want or need to assign a subaction to every role; a compound action skips over any role that has no subaction assigned. If a role has multiple subactions assigned, it runs subactions in the order in which they are listed.

Figure 1-2 Subactions Table (Example)

| | Role | Action(s) | |
|---|---------------|----------------------------|---------------------------------------|
| ? | Initializer | link_pricer_2kb_100km | |
| ? | Link Selector | link_price_selector_geq_25 | |
| ? | Link Action | remove_links | |
| ? | Link Analyzer | link_price_analyzer | Click to configure... |
| ? | Finalizer | | |

The Subactions table appears in the bottom right in the Configure Design Action dialog box. This table lists the roles and subactions defined for a specific compound action. To assign one or more subactions to a role, click in the Action(s) field for that role. In Figure 1-2, the compound action is configured to run four subactions:

- Set the financial cost on each link (“Initializer”)
- Select all links with a financial cost greater than 25 (“Link Selector”)
- Remove these links from the network (“Link Action”)
- Analyze the cost of the remaining links (“Link Analyzer”)

Derived Actions

A *derived action* is an action with customized attribute settings. You might want to create your own derived actions to perform common actions. For example, you might want to create actions to price links according to different criteria. You can derive actions from the link_pricer base action and then run the derived actions as needed.

Procedure 1-1 Creating a Derived Action

- 1 Choose Design > Configure/Run Design Action and select the action you want to use as a base model.
- 2 Configure the attributes and subactions (if any) for the base model.

- 3 Click Save As and save the action under a new name.


Note—You cannot overwrite a base action in the Project Editor; you can only save it under a new name. For this reason, the Save button is disabled when you configure a base action.

End of Procedure 1-1

Configure/Run Design Action Dialog Box

Figure 1-3 shows the Configure/Run Design Action dialog box and indicates the types of information that appear in the panes of the dialog box. The display and control elements in this dialog box are described in Table 1-3 on page DA-1-7.

Figure 1-3 Configure/Run Design Action Dialog Box



Treeview pane

Description pane

Attribute pane

Subactions pane

Table 1-3 Configure/Run, Design Action Dialog Box

| Item | Description |
|--|---|
| <p>Panes:</p> <ul style="list-style-type: none"> <li data-bbox="483 384 651 411">• Treeview (left) <li data-bbox="483 447 797 474">• Action description (right top) <li data-bbox="483 510 797 537">• Attributes table (right center) <li data-bbox="483 604 824 659">• Subactions table (right bottom, compound actions only) | <p>Select an action in this pane to view, configure, or run.</p> <p>Description of the selected action.</p> <p>Visible attributes of the selected action. Click Edit to configure these attributes.</p> <p>To assign one or more subactions to a role, click in the Action(s) field for that role. The Choose Subactions dialog box lists all assignable action models. To be assignable, an action model must have a Subaction Type self-description value that matches the role type.</p> |
| <p>Arrange By menu</p> | <p>Arrange the treeview based on the self-descriptions of action models. Thus you can arrange actions based on author, technology, or some other criteria.</p> |
| <p>Run</p> | <p>Run the selected action. If the action cannot be run directly, this button is disabled.</p> |
| <p>Save</p> | <p>Save the action based on the current configuration. If you change the configuration of a standard action, this button is disabled. You must choose Save As and save the current configuration under a new name.</p> |
| <p>Save As</p> | <p>Save the current configuration under a new name.</p> |
| <p>Set as Quick Action</p> | <p>Create a Quick Action from the current action and configuration. For more information, see Quick Actions on page DA-1-8.</p> |
| <p>Target Scenario menu</p> | <p>Choose the target scenario for the design action. The target scenario can be either the current scenario or a new scenario.</p> <p>NOTE—It is good practice to choose a new target scenario for any design action that can modify the network. This ensures that you retain a copy of the original (pre-design action) network state.</p> |
| <p>End of Table 1-3</p> | |

Running a Design Action

Every design action has an attribute called “runnable,” which specifies whether you can run the action directly. If this attribute is set to FALSE, the action can be run by a compound action only (that is, as a subaction). This means that

- when you choose Design > Run Design Action, only runnable actions appear.
- when you choose Design > Configure/Run Design Action and select an unrunnable action, the Run operation is unavailable.

You can run an action using any of the following operations:

- 1) Choose Design > Run Design Action (see Table 1-4 Run Action Dialog Box on page DA-1-9)
- 2) If you want to configure an action before running it, choose Design > Configure/Run Design Action (see Table 1-3 Configure/Run, Design Action Dialog Box on page DA-1-7)
- 3) If you have an action that you want to run quickly and repeatedly, you might want to create a quick action. You can then run the action from the Design > Quick Actions submenu (see Quick Actions on page DA-1-8)

Quick Actions

A *quick action* is an action that you can run directly from the Design > Quick Actions submenu. When you choose an action in this submenu, the action executes immediately. You can create your own quick actions, and thereby create your own “action toolbox” for a specific scenario.

Note—Each Project Editor session maintains its own Quick Actions list, so the Design > Quick Actions submenu is persistent within the current Project Editor session only.

Procedure 1-2 Creating a Quick Action

- 1 Choose Design > Quick Actions > Create New Quick Action to open the Configure/Run Design Action dialog box.
- 2 Select the action you want to use as the base for your quick action.

Note—You can only create a quick action from an action whose “runnable” attribute is set to TRUE. If you select an action and the Run button appears dimmed, this means that the action (as currently configured) is not runnable. If the “runnable” attribute is not visible, then you cannot use that action to create a quick action.

- 3 Click Edit.


- 4 Configure the attributes so that the action performs the behavior you want.
 - Note**—Because a quick action executes automatically, you must specify the exact behavior you want the quick action to perform.
- 5 Verify that the “runnable” attribute is set to TRUE, then click OK to return to the Configure/Run Design Action dialog box.
- 6 Click Save As and save the action under the name you want to use for the quick action.
- 7 Click Quick Action.
 - ➔ The action appears in the Design > Quick Actions submenu.

End of Procedure 1-2

Run Action Dialog Box

Figure 1-4 shows the Run Action dialog box and indicates the types of information that appear in the panes of the dialog box.

Figure 1-4 Run Action Dialog Box



Treeview pane (only runnable actions appear in this tree)

Table 1-4 lists the display and control elements in the Run Action dialog box.

Table 1-4 Run Action Dialog Box

| Item | Description |
|--------------------------------|---|
| Treeview pane (left) | Select an action in this pane to configure or run. |
| Action description (right top) | Description of the selected action |
| Configure | Configure the attributes and subactions (if any) before running the action. |
| Run Design Action | Run the selected action. |
| End of Table 1-4 | |

Viewing Results


You can view the results of a design action using two different reporting mechanisms:

- The Design Action Log shows all network changes and significant events generated by the last action run; see Design Action Log for more information.
- In some cases, a design action generates an output table of results. You can view these tables by choosing Design > Results > View Last Report or Design > Results > View Reports. For general information about viewing results, see Results Viewer on page ITU-14-46 of the *User Guide*.

Design Action Log

The design action log (Figure 1-5) shows all network changes and significant events generated by the last action run. The messages that appear in this log depend on the specific action. Generally, actions generate Summary messages to provide a high-level snapshot of the action results. Because a design action can generate many types of log messages, you might want to filter the log to show only messages of interest.

Figure 1-5 Design Action Log



Design action logs are displayed in the IT Guru log viewer (as described in Log Viewer on page ITU-4-22). You can view a design action log using one of these methods:

- If a design action completes successfully: click the View Log button in the Action Completed dialog box.
- To view the design action log for the last run: choose Design > Results > View Latest Log.
- To view any available design action log: choose Design > Results > View Logs...

Custom Design Actions

If you have a license for the OPNET Development Kit, you can create your own custom design models using the Design Action Editor. You can open this window in one of two ways:

- To create a new action model, open the New File dialog box (File > New) and select Design Action.
- To edit an existing action model, open the Open File dialog box (File > Open) and select Design Action.

A design action includes the following components:

- **Implementation**—The implementation is C or C++ code that defines the internal behavior of the model. Each base action must have an implementation for its run function. This implementation is stored within the model file. An action model can also use code defined in external C/C++ or object files. The external files may be shared among multiple action models. Derived models inherit their base models implementation and cannot define their own code.

The OPNET Development Kit includes a set of Design Action-related functions that you can use to develop your own implementations. To view the declarations for these functions, go to the `<reldir>/sys/include` directory and look in the `odan* .h` set of header files.

- **Attributes**—To define the attributes for an action, choose Design Action > Edit Attributes.
- **Self-Description**—The self-description of a model determines how the action appears in the action treeview of the Run Design Action and Configure Design Action dialog boxes. To edit the self-description, choose Design Action > Edit Self-Description.
- **Subactions**—To edit the roles and subactions for a compound action, choose Design Action > Edit Subactions.

2 Link Dimensioning

The objective of a link_dimensioning run is to determine the best link configuration that accommodates the current traffic patterns in an IP network. This design action can add, remove, reconnect, or replace links, but does not change the existing network connectivity—that is, it will never remove the last link between two nodes or add a link between unconnected nodes.

A link_dimensioning run starts by analyzing the existing network and traffic patterns. Then it upgrades, downgrades, or leaves unchanged the bandwidth for each link bundle in the selection set; a *link bundle* is a set of one or more links between the same node pair. For each link bundle, the design action calculates the best solution based on the following criteria:

- 1) The link bundle accommodates current traffic patterns.
- 2) The dimensioned links are neither over-utilized nor underutilized—that is, link utilizations fall within a specified range.
- 3) If cost parameters are specified, the solution results in the lowest possible cost while still meeting the criteria.

To adjust the bandwidth of a link bundle, link_dimensioning can do any of the operations described in Table 2-1. If link_dimensioning cannot find a satisfactory solution for an individual link bundle, it generates a log message; for more information, see Log Messages on page DA-2-4.

Table 2-1 Operations on Individual Links

| Operation Type | Details | Before | After |
|-------------------------|---|--------|--|
| Replace | Change the data rate or model of the link, but do not change the port/interface connections to its end nodes | Link A | Link A with new model |
| Move | Change the data rate or model of the link, and also change the port/interface connections to its end nodes. This happens when the new link model cannot use the original ports. | Link A | Link A with new model and ports |
| Remove | Remove the link from the current scenario | Link A | None |
| Add | Create a new link and copy its configuration from a parallel link that existed before the current design-action run. Certain configurations such as IP address are not copied. | None | New link object with new model and ports. Configuration is based on the most recent target link. |
| End of Table 2-1 | | | |

Prerequisites

Like all design actions, link_dimensioning is an advanced feature. This section describes the recommended background knowledge you should have before you run this design action.

- **Link Dimensioning Tutorial**

The Guru documentation includes a tutorial about link dimensioning. It is recommended that you complete this tutorial before you run a link_dimensioning design action. For more information, see Design Actions: Link Dimensioning tutorial.
- **Background Knowledge**

To use this design action most effectively, you should have some familiarity with the following topics:

 - Routers, ports, and their supported links
 - The relationships between link utilizations and IP traffic flows
 - IP routing protocols and their load-balancing options
 - OPNET node and link models
 - The Flow Analysis module
- **Design Action and Attribute Descriptions**

In addition to the information in this chapter, you should also view the action description and individual attribute descriptions available in the Configure/Run Design Action dialog box. For more information, see Viewing Information about a Design Action on page DA-1-4.

Configuring and Running the link_dimensioning Design Action

This design action sizes links based on the following inputs:

- In the initial IP network:
 - Nodes, links, and link connectivity
 - Available ports and supported interface types on existing nodes
 - Initial traffic levels (specified by the existing traffic flows)
 - Initial link utilizations (determined by running Flow Analysis)
- Attribute settings in the link_dimensioning design action. Attributes of interest include:
 - The specified target utilization range (upper bound and lower bound)
 - The set of input links (all links in the scenario or a subset of links)
 - The available link models (defined by the candidate link palette for the design action)
 - Link pricing criteria (optional—specified in the link_pricer subaction)

For more information, see

- [Configuring a Design Action on page DA-1-3](#)
- [Running a Design Action on page DA-1-8](#)

Log Messages

The link_dimensioning design action generates several types of log messages to show the summary and network changes. Table 2-2 and Table 2-3 list these log messages.

Table 2-2 Categories of link_dimensioning Log Messages

| Use This Category... | To View... |
|-------------------------|---|
| Detail | Candidate link models considered when adding or replacing individual links. |
| Design Manager | Which subactions ran successfully. |
| Network Changes | Which links bundles were upgraded, downgraded, and unchanged. |
| Warning | Warning messages generated during the run. |
| Summary | A list of statistics that were generated before and after the run. |
| End of Table 2-2 | |

Table 2-3 Classes of link_dimensioning Log Messages

| Use This Class... | To View... |
|-------------------------|---|
| Link Pool | Candidate link models considered when adding or replacing individual links. |
| Unchanged | Link bundles whose bandwidths were unchanged by the design action. |
| Upgraded | Link bundles whose bandwidths were upgraded by the design action. |
| Downgraded | Link bundles whose bandwidths were downgraded by the design action. |
| Summary | Summary statistics about the design action |
| Success | Whether the design action ran successfully. |
| End of Table 2-3 | |

Unsatisfactory Solutions

In some cases, the new solution for a specific link bundle still cannot satisfy the utilization range and criteria. These cases can be categorized in two types:

- **Unchanged** - A link bundle is selected because it fit in selection criteria, but link dimensioning action cannot change it due to different constraints. Detailed reasons are listed in Table 2-4.

- Upgrade/downgrade but still Invalid - The new solution is not valid because no valid solution can be found within current constraints. A best invalid solution is provided and all possible reasons described in Table 2-4.

Table 2-4 Messages for Unsatisfactory Solutions

| ID | Bundle status | Utilization Range | Reason | Message |
|-------------------------|-------------------------|-------------------|---|---|
| 0 | Unchanged | | No candidate links are compatible | <p>The initial link bundle has this message as default. For bundles below range, an additional reason is that no smaller links are available (log ID #5). In this case, the initial solution uses small-capacity links and does not meet the utilization range.</p> <p>During the process of finding another appropriate solution, the target link bundle retains this message by default. Whenever a compatible link model is selected and tested, the design action removes this message.</p> |
| 1 | Upgraded or unchanged | Above or within | Limited port in the first node | <p>These three reason codes are added during the solution search process. Whenever a compatible link model is considered for inclusion in the solution, these reason codes might be added into reason code of the new solution</p> |
| 2 | Upgraded or unchanged | Above or within | Limited port in the second node | |
| 3 | Upgraded or unchanged | Above or within | Limited by the maximum number of parallel links | |
| 4 | Upgraded or unchanged | Above | Not compliant with the utilization upper bound | <p>This message is generated when the action finds no feasible solution under current constraints, and uses the best infeasible solution: use the largest candidate links to give the lowest maximum link utilization.</p> |
| 5 | Downgraded or unchanged | Below | No smaller links available | <p>This message is generated when the action finds no feasible solution under current constraints, and uses the best infeasible solution: use the smallest candidate links to give the highest minimum link utilization.</p> |
| 6 | Upgraded or Unchanged | Above | Link Analyzer problem | <p>Current solution should be feasible but the Link Analyzer subaction might give different results than expected. For examples that illustrate how this can occur, see the Design Actions: Link Dimensioning tutorial</p> |
| 7 | Unchanged | Above or Below | Limited by algorithm attribute | <p>Current solution is unchanged because the maximum number of links dimensioned per iteration is reached.</p> |
| 8 | Warning | Any state | Unspecified reason | <p>Unknown reason, please report to OPNET technical support.</p> |
| End of Table 2-4 | | | | |

Viewing Reports

After a link_dimensioning run finishes, you can view reports about the run from the View Results window (Design > Results > View Output Reports). Table 2-5 describes the available reports.

Table 2-5 link_dimensioning Reports

| Report Name | Description |
|--------------------------|---|
| Link Bundle Summary | Shows the operations performed on each link bundle during the run. The Link Bundle Operation column includes links that enable you to see details about an individual operation (how a link bundle was upgraded, or why a link bundle was unchanged). |
| Design Action Statistics | A list of statistics that were generated during the run. |
| Object Tables | Intermediate statistics for individual failure cases. |
| End of Table 2-5 | |

3 Link Dimensioning Resilient

The objective of a `link_dimensioning_resilient` run is to determine the best link configuration that will accommodate current traffic patterns in the normal case (no link failures) and in a set of defined failure cases. Like `link_dimensioning`, `link_dimensioning_resilient` can add, remove, reconnect, or replace links, but does not change the existing network connectivity—that is, it never removes the last link between two nodes or adds a link between unconnected nodes.

`link_dimensioning` and `link_dimensioning_resilient` differ in the following ways:

- `link_dimensioning` considers the normal case (no failures) only; `link_dimensioning_resilient` considers the normal case and a set of failure cases, and sizes the links to accommodate traffic for all failure cases.
- `link_dimensioning` can upgrade or downgrade links, or leave links unchanged; `link_dimensioning_resilient` can upgrade links or leave them unchanged (it never downgrades links).

Prerequisites

Like all design actions, `link_dimensioning_resilient` is an advanced feature. Before you work with `link_dimensioning_resilient`, you should be familiar with the `link_dimensioning` design action. For more information, see the Link Dimensioning.

Configuring and Running the `link_dimensioning_resilient` Design Action

This design action sizes links based on the following inputs:

- In the initial IP network:
 - Nodes, links, and link connectivity
 - Available ports and supported interface types on existing nodes
 - Initial traffic levels (specified by the existing traffic flows)
 - Initial link utilizations (determined by running Flow Analysis)
- Attribute settings in the `link_dimensioning_resilient` design action. Attributes of interest include:
 - Specified failure cases (For more information, see Failure Cases)
 - The maximum utilization (upper bound)
 - The set of input links (all links in the scenario or a subset of links)
 - The available link models (defined by the candidate link palette for the design action)
 - Link pricing criteria (optional—specified in the `link_pricer` subaction)

Failure Cases

A *failure case* is a scenario in which a set of one or more network objects is failed. `link_dimensioning_resilient` includes attributes that define the failure cases to consider when the design action is run. During a run, `link_dimensioning_resilient` sizes each link to accommodate current traffic levels in the normal case (no link failures) and in each possible failure case.

You can configure the following characteristics of failure scenarios:

- **Failure object type**—A failure case can fail links, nodes, and shared risk groups (SRGs). A shared risk group defines a failure relationship between two sets of network objects, where failures in one set cause failures in the other set. For more information, see Shared Risk Groups on page ITU-6-43 of the *IT Guru User Guide*.
- **Failure object set**—This is the set of all objects to be failed during the run. You can include failure cases for all eligible objects or a subset of eligible objects.
- **Failure object occurrence**—You can specify a run to test single failure scenarios (one object failed), pairwise scenarios (two objects failed), or simultaneous scenarios (all eligible objects failed simultaneously).

Note—A `link_dimensioning_resilient` run can take several minutes or more to complete, depending on the size and complexity of your network. Factors that can increase run times include: a large number of input links, a complex network with many links and node, a run that tests pairwise failures, and a large number of repetitions for each failure case.

For general information about configuring and running design actions, see

- Configuring a Design Action on page DA-1-3
- Running a Design Action on page DA-1-8

Viewing Logs

The link_dimensioning_resilient design action generates several types of log messages to show the summary and network changes. Table 3-1 and Table 3-2 list these log messages.

Table 3-1 Categories of link_dimensioning_resilient Log Messages

| Use This Category... | To View... |
|-------------------------|---|
| Detail | Intermediate statistics for individual failure cases |
| Design Manager | Which subactions ran successfully |
| Network Changes | Which links bundles were upgraded, downgraded, and unchanged |
| Warning | Warning messages generated during the run |
| Summary | A list of statistics that were generated before and after the run |
| End of Table 3-1 | |

Table 3-2 Classes of link_dimensioning_resilient Log Messages

| Use This Class... | To View... |
|-------------------------|--|
| Link Pool | Candidate link models considered when adding or replacing individual links |
| Unchanged | Link bundles whose bandwidths were unchanged by the design action |
| Upgraded | Link bundles whose bandwidths were upgraded by the design action |
| Summary | Summary statistics about the design action |
| Statistics | Intermediate statistics for individual failure cases |
| Success | Whether the design action ran successfully |
| End of Table 3-2 | |

Unsatisfactory Solutions

When it determines an unsatisfactory solutions, the link_dimensioning_resilient design action generates messages similar to link_dimensioning; for more information, see Unsatisfactory Solutions on page DA-2-4. (Because it never downgrades links, link_dimensioning_resilient does not generate “Downgrade” messages.)

Viewing Reports

After a link_dimensioning_resilient run finishes, you can view reports about the run by choosing Design > Results > View Latest Reports. Table 3-3 describes the available reports.

Table 3-3 link_dimensioning_resilient Reports

| Report Name | Description |
|-------------------------|---|
| Failure Cases | Provides a summary of all failure cases considered in the link_dimensioning_resilient run. If a single failure case has multiple failed objects, the failure case contains multiple rows. |
| Link Bundle Summary | Shows the operations performed on each link bundle during the run. The Link Bundle Operation column includes links that enable you to see details about an individual operation (how a link bundle was upgraded, or why a link bundle was unchanged). |
| Summary Statistics | A list of statistics that were generated before and after the run. |
| Intermediate Statistics | Intermediate statistics for individual failure cases |
| End of Table 3-3 | |

4 Ring Backbone Topology Design

The design actions for topology design help you determine where to place links in a network. Three design actions are available, depending on the type of network you are building. You can use the topology design actions to create a ring-based backbone, a spanning tree, or dual spanning trees. This chapter describes the `ring_backbone` design action.

The topology design actions work on network topologies that contain only nodes. This type of design is also referred to as a Greenfield design. You can also use the design actions on networks that have existing links or traffic demands. In this type of incremental design, the design action can use the existing links when it determines where to place additional links.

When the design action adds links to a network, it considers the following:

- cost
- connectivity
- hop count
- utilization
- port constraints
- distance

The `ring_backbone` design action lets you build network designs that are resilient to failure and insensitive to traffic. These network designs provide paths that have low delays and low cost. The design action builds the network designs by constructing a near-symmetric 2-connected or 3-connected topology with a small diameter. The diameter is the maximum number of hops between any node pair.

Symmetric topologies are less sensitive to traffic fluctuations in demands. A symmetric topology can be an effective design for a backbone when you do not have any traffic information, when the traffic is very variable, or when you are planning for future applications. The design action can use existing traffic information to bias the design to have direct links between high-traffic pairs.

Prerequisites

This section describes what you need to know before you run the `ring_backbone` design action.

Background Knowledge

To use this design action most effectively, you should be familiar with the following topics:

- Topology design, including greenfield and brownfield design
- Routers, ports, and their supported links
- OPNET node and link models

Design Action and Attribute Descriptions

In addition to the information in this chapter, you should also view the action description and individual attribute descriptions available in the Configure/Run Design Action dialog box. For more information, see *Viewing Information about a Design Action* on page DA-1-4.

Configuring and Running the Ring Backbone Design Action

This design action creates links based on the following inputs:

- In the initial network:
 - Nodes
 - Existing links, if any
 - Traffic demands, if any
- Attribute settings in the ring_backbone design action. Attributes of interest include:
 - The available link models (defined by the candidate link palette for the design action)
 - The target utilization
 - The type of ring topology (defined by the Graph Engine attribute)
 - Link pricing criteria (optional—specified in the link_pricer_custom_db subaction)

For more information, see

- *Configuring a Design Action* on page DA-1-3
- *Running a Design Action* on page DA-1-8


Graph Engine

The design action can create five types of ring backbone designs. All designs consists of a ring that contains all of the input nodes. The degree of connectivity within the ring differentiates ring types.

Table 4-1 Ring Backbone Graph Engine Characteristics

| Graph Engine | Connectivity | Symmetry | Number of Edges | Description |
|---------------------------|--------------|----------------|-----------------|---|
| Ring | 2-connected | Symmetric | N | A ring that passes through each node |
| Semi-Regular Chordal Ring | 2-connected | Near symmetric | 5N/4 | A ring with chords incident to every other node |
| Wheel | 3-connected | Symmetric | 3N/2 | A ring with chords connecting each node to the node N/2 away in rotational distance around the ring |
| Chordal Ring | 3-connected | Near symmetric | 3N/2 | A ring with chords connecting each node to the node +/- w away in rotational distance around the ring. |
| Multilength Chordal Ring | 3-connected | Near symmetric | 3N/2 | Similar to the chordal ring, but with two chord lengths, w1 and w2, which minimize the diameter of the network. |
| End of Table 4-1 | | | | |

Figure 4-1 Types of Ring Designs



Log Messages

The ring_backbone design action generates several types of log messages to show the summary and network changes. Table 4-2 and Table 4-3 list these log messages.

Table 4-2 Categories of Ring Backbone Design Log Messages

| Use This Category... | To View... |
|-------------------------|--|
| Detail | Candidate link models considered when adding or replacing individual links |
| Design Manager | A list of subactions that ran successfully. |
| Network Changes | A list of the links that were created. |
| Error | Error messages generated during the run. |
| Warning | Warning messages generated during the run. |
| Summary | A list of statistics that were generated before and after the run. Statistics include: average cost per link, cost of new links, and the number of links added and reused. |
| End of Table 4-2 | |

Table 4-3 Classes of Ring Backbone Design Log Messages

| Use This Class... | To View... |
|-------------------------|---|
| Link Pool | Candidate link models considered when adding or replacing individual links. |
| Filtered | Nodes that were excluded from the design. These are usually configuration objects or nodes with no available ports. |
| Created | Links that were added by the design action. |
| Reused | Links that existed in the topology and were reused by the design action. |
| Summary | Summary statistics about the design action. |
| Success | Whether or not the design action ran successfully. |
| End of Table 4-3 | |

Available Reports

Detailed results are displayed as output tables in the Results Viewer, as described in Viewing Results on page DA-1-10. The mpls_te design action generates the following reports:

- Link Summary
- Summary

Link Summary

The link summary report contains results for each link in the topology. The results given in the link summary report are described in the following table.

Table 4-4 Link Summary Report Statistics

| Result | Description |
|-------------------------|--|
| Link Name | The name of the link that was added, reused, or upgraded. |
| Node A, Node B | The endpoints of the link. |
| Operation | Indicates the action taken on the link by the design action: created, reused, upgraded. |
| Model | The link model assigned to the link by the design action. |
| BW (kbps) | The bandwidth, or data rate, of the link after any modifications by the design action. |
| Cost | The cost of the link after any modifications by the design action. Costs are calculated using the Link Pricer subaction; by default, this is the link_pricer_custom_db action. |
| End of Table 4-4 | |

Summary

The summary report contains a general statistics about the design action run. The results given in the summary report are described in the following table.

Table 4-5 Summary Report Statistics (Part 1 of 2)

| Result | Description |
|-----------------------------------|---|
| Vertices in Graph | The number of vertices in the graph that was used by the design action. The design action creates a graph to represent the network and uses this graph when constructing the ring design. The graph is then mapped back to the network topology. The graph contains all nodes from the input node object set, with the exception of filtered nodes. |
| Links in Graph | The number of links in the final (output) graph. This is the graph that results after the design algorithm has run. |
| Links Added | The number of links added to the topology. |
| Links Reused | The number of links that existed in the topology and were used by the design action. |
| Links Upgraded | The number of existing links that were upgraded to use a different model by the design action. |
| Cost of New Links | The cost of all links added to the topology. |
| Cost of Upgraded Links | The net cost of upgrading existing links in the topology. This is the new cost minus the existing cost for all upgraded links. |
| Value of Reused Links | The total cost of all reused links. |
| Cost of Reused Links (discounted) | The cost of reusing links in the network. If the discount factor is 100 percent, the cost is 0. Otherwise, the cost is: $(1 - \text{discount factor}) * \text{Value of Reused Links}$ |
| Total Cost of Topology Change | The cost of the new, upgraded, and reused (discounted) links in the topology. The Total Cost of Topology Change equals the sum of the following statistics: <ul style="list-style-type: none"> • Cost of New Links • Cost of Upgraded Links • Cost of Reused Links (discounted) |
| Average Cost Per Link | Total cost of topology change divided by the number of added, reused, and upgraded links. |
| Graph Diameter | The maximum number of hops between any node pair in the graph. |
| Graph Average Distance | The average number of hops between any node pair in the graph (excludes 0-hop paths from source to source). |

Table 4-5 Summary Report Statistics (Part 2 of 2)

| Result | Description |
|-------------------------------|---|
| Traffic Averaged Distance | The traffic averaged number of hops between any node pair in the graph. For each pair, the minimum hop distance is weighted by the total traffic between the node pair. |
| Graph Connectivity | The minimum number of node disjoint paths between all of the node pairs. |
| Graph Average Connectivity | The average number of node disjoint paths over all of the node pairs. |
| Traffic Averaged Connectivity | The connectivity for each node pair is weighted by the total traffic between the node pair. |
| End of Table 4-5 | |

5 Spanning Tree Topology Design

The design actions for topology design help you determine where to place links in a network. Three design actions are available, depending on the type of network you are building. You can use the topology design actions to create a ring-based backbone, a spanning tree, or dual spanning trees. This chapter describes the `spanning_tree` design action.

The topology design actions work on network topologies that contain only nodes. This type of design is also referred to as a Greenfield design. You can also use the design actions on networks that have existing links or traffic demands. In this type of incremental design, the design action can use the existing links when it determines where to place additional links.

The spanning tree design action is useful for finding a near minimum cost topology that connects a set of nodes. This can serve as a baseline for understanding the lowest cost network option. The spanning tree may not meet the performance or redundancy requirements for your operational network design, but it may serve as a good starting point for building a final design.

When the design action adds links to a network, it considers the following requirements:

- cost
- connectivity
- hop count
- utilization
- port constraints
- distance

The spanning tree design action is very similar in functionality to the `ring_backbone` design action, which is described in Chapter 4 Ring Backbone Topology Design on page DA-4-1. The difference is that instead of using a ring-based graph as the network structure, the algorithm builds a spanning tree graph. A spanning tree graph is a connected, acyclic graph.

Prerequisites

This section describes what you need to know before you run the `spanning_tree` design action.

Background Knowledge

To use this design action most effectively, you should be familiar with the following topics:

- Topology design, including greenfield and brownfield design
- Routers, ports, and their supported links
- OPNET node and link models

Design Action and Attribute Descriptions

In addition to the information in this chapter, you should also view the action description and individual attribute descriptions available in the Configure/Run Design Action dialog box. For more information, see *Viewing Information about a Design Action* on page DA-1-4.

Configuring and Running the Spanning Tree Design Action


This design action creates links based on the following inputs:

- In the initial network:
 - Nodes
 - Existing links, if any
 - Traffic demands, if any
- Attribute settings in the `spanning_tree` design action. Attributes of interest include:
 - The available link models (defined by the candidate link palette for the design action)
 - The target utilization
 - The type of spanning tree (defined by the Spanning Tree Weight attribute)
 - The root node (defined by the Root Criteria attribute)
 - Link pricing criteria (optional—specified in the `link_pricer_custom_db` subaction)

For more information, see

- *Configuring a Design Action* on page DA-1-3
- *Running a Design Action* on page DA-1-8

Figure 5-1 Types of Spanning Trees



Log Messages

The spanning tree design action generates several types of log messages to show the summary and network changes. Table 5-1 and Table 5-2 list these log messages.

Table 5-1 Categories of Spanning Tree Design Action Log Messages

| Use This Category... | To View... |
|-------------------------|--|
| Detail | Candidate link models considered when adding or replacing individual links |
| Design Manager | A list of subactions that ran successfully. |
| Network Changes | A list of the links that were created. |
| Error | Error messages generated during the run. |
| Warning | Warning messages generated during the run. |
| Summary | A list of statistics that were generated before and after the run. Statistics include: average cost per link, cost of new links, and the number of links added and reused. |
| End of Table 5-1 | |

Table 5-2 Classes of Spanning Tree Design Action Log Messages

| Use This Class... | To View... |
|-------------------------|---|
| Link Pool | Candidate link models considered when adding or replacing individual links. |
| Filtered | Nodes that were excluded from the design. These are usually configuration objects or nodes with no available ports. |
| Created | Links that were added by the design action. |
| Reused | Links that existed in the topology and were reused by the design action. |
| Summary | Summary statistics about the design action. |
| Success | Whether or not the design action ran successfully. |
| End of Table 5-2 | |

Available Reports

Detailed results are displayed as output tables in the Results Viewer, as described in Viewing Results on page DA-1-10. The mpls_te design action generates the following reports:

- Link Summary
- Summary

Link Summary

The link summary report contains results for each link in the topology. The results given in the link summary report are described in the following table.

Table 5-3 Link Summary Report Statistics

| Result | Description |
|-------------------------|--|
| Link Name | The name of the link that was added, reused, or upgraded. |
| Node A, Node B | The endpoints of the link. |
| Operation | Indicates the action taken on the link by the design action: created, reused, upgraded. |
| Model | The link model assigned to the link by the design action. |
| BW (kbps) | The bandwidth, or data rate, of the link after any modifications by the design action. |
| Cost | The cost of the link after any modifications by the design action. Costs are calculated using the Link Pricer subaction; by default, this is the link_pricer_custom_db action. |
| End of Table 5-3 | |

Summary

The summary report contains a general statistics about the design action run. The results given in the summary report are described in the following table.

Table 5-4 Summary Report Statistics (Part 1 of 2)

| Result | Description |
|-----------------------------------|--|
| Vertices in Graph | The number of vertices in the graph that was used by the design action. The design action creates a graph to represent the network and uses this graph when constructing the tree. The graph is then mapped back to the network topology. The graph contains all nodes from the input node object set, with the exception of filtered nodes. |
| Links in Graph | The number of links in the final (output) graph. This is the graph that results after the design algorithm has run. |
| Links Added | The number of links added to the topology. |
| Links Reused | The number of links that existed in the topology and were used by the design action. |
| Links Upgraded | The number of existing links that were upgraded to use a different model by the design action. |
| Cost of New Links | The cost of all links added to the topology. |
| Cost of Upgraded Links | The net cost of upgrading existing links in the topology. This is the new cost minus the existing cost for all upgraded links. |
| Value of Reused Links | The total cost of all reused links. |
| Cost of Reused Links (discounted) | The cost of reusing links in the network. If the discount factor is 100 percent, the cost is 0. Otherwise, the cost is: (1 – discount factor) * Value of Reused Links |
| Total Cost of Topology Change | The cost of the new, upgraded, and reused (discounted) links in the topology. The Total Cost of Topology Change equals the sum of the following statistics: <ul style="list-style-type: none"> • Cost of New Links • Cost of Upgraded Links • Cost of Reused Links (discounted) |
| Average Cost Per Link | Total cost of topology change divided by the number of added, reused, and upgraded links. |
| Graph Diameter | The maximum number of hops between any node pair in the graph. |
| Graph Average Distance | The average number of hops between any node pair in the graph (excludes 0-hop paths from source to source). |

Table 5-4 Summary Report Statistics (Part 2 of 2)

| Result | Description |
|-------------------------------|---|
| Traffic Averaged Distance | The traffic averaged number of hops between any node pair in the graph. For each pair, the minimum hop distance is weighted by the total traffic between the node pair. |
| Graph Connectivity | The minimum number of node disjoint paths between all of the node pairs. |
| Graph Average Connectivity | The average number of node disjoint paths over all of the node pairs. |
| Traffic Averaged Connectivity | The connectivity for each node pair is weighted by the total traffic between the node pair. |
| End of Table 5-4 | |

6 Dual Tree Topology Design

The design actions for topology design help you determine where to place links in a network. Three design actions are available, depending on the type of network you are building. You can use the topology design actions to create a ring-based backbone, a spanning tree, or dual spanning trees. This chapter describes the `dual_tree` design action.

The topology design actions work on network topologies that contain only nodes. This type of design is also referred to as a Greenfield design. You can also use the design actions on networks that have existing links or traffic demands. In this type of incremental design, the design action can use the existing links when it determines where to place additional links.

The dual tree design action is useful for finding a near minimum cost two-connected design for a given set of nodes. It builds on the low cost of the spanning tree design, but guarantees that there are at least 2 disjoint paths between all node pairs. The diameter and average hop distance are also generally significantly lower than the spanning tree.

When the design action adds links to a network, it considers the following requirements:

- cost
- connectivity
- hop count
- utilization
- port constraints
- distance

The dual tree design action is based on a spanning tree design. After constructing the first spanning tree, the design builds a second spanning tree by connecting the leaf nodes from the first tree. This creates a near-minimum cost 2-connected topology.

Prerequisites

This section describes what you need to know before you run the `dual_tree` design action.

Background Knowledge

To use this design action most effectively, you should be familiar with the following topics:

- Topology design, including greenfield and brownfield design
- Routers, ports, and their supported links
- OPNET node and link models

Design Action and Attribute Descriptions

In addition to the information in this chapter, you should also view the action description and individual attribute descriptions available in the Configure/Run Design Action dialog box. For more information, see *Viewing Information about a Design Action* on page DA-1-4.

Configuring and Running the Dual Tree Design Action

This design action creates links based on the following inputs:

- In the initial network:
 - Nodes
 - Existing links, if any
 - Traffic demands, if any
- Attribute settings in the dual_tree design action. Attributes of interest include:
 - The available link models (defined by the candidate link palette for the design action)
 - The target utilization
 - The types of spanning trees (defined by the Spanning Tree Weight attribute for the first tree and the Dual Tree Weight attribute for the second tree)
 - The root node (defined by the Root Criteria attribute)
 - Link pricing criteria (optional—specified in the link_pricer_custom_db subaction)

For more information, see

- *Configuring a Design Action* on page DA-1-3
- *Running a Design Action* on page DA-1-8

Log Messages

The dual tree design action generates several types of log messages to show the summary and network changes. Table 6-1 and Table 6-2 list these log messages.

Table 6-1 Categories of Dual Tree Design Action Log Messages

| Use This Category... | To View... |
|-------------------------|--|
| Detail | Candidate link models considered when adding or replacing individual links |
| Design Manager | A list of subactions that ran successfully. |
| Network Changes | A list of the links that were created. |
| Error | Error messages generated during the run. |
| Warning | Warning messages generated during the run. |
| Summary | A list of statistics that were generated before and after the run. Statistics include: average cost per link, cost of new links, and the number of links added and reused. |
| End of Table 6-1 | |

Table 6-2 Classes of Dual Tree Design Action Log Messages

| Use This Class... | To View... |
|-------------------------|---|
| Link Pool | Candidate link models considered when adding or replacing individual links. |
| Filtered | Nodes that were excluded from the design. These are usually configuration objects or nodes with no available ports. |
| Created | Links that were added by the design action. |
| Reused | Links that existed in the topology and were reused by the design action. |
| Summary | Summary statistics about the design action. |
| Success | Whether or not the design action ran successfully. |
| End of Table 6-2 | |

Available Reports

Detailed results are displayed as output tables in the Results Viewer, as described in Viewing Results on page DA-1-10. The mpls_te design action generates the following reports:

- Link Summary
- Summary

Link Summary

The link summary report contains results for each link in the topology. The results given in the link summary report are described in the following table.

Table 6-3 Link Summary Report Statistics

| Result | Description |
|-------------------------|--|
| Link Name | The name of the link that was added, reused, or upgraded. |
| Node A, Node B | The endpoints of the link. |
| Operation | Indicates the action taken on the link by the design action: created, reused, upgraded. |
| Model | The link model assigned to the link by the design action. |
| BW (kbps) | The bandwidth, or data rate, of the link after any modifications by the design action. |
| Cost | The cost of the link after any modifications by the design action. Costs are calculated using the Link Pricer subaction; by default, this is the link_pricer_custom_db action. |
| End of Table 6-3 | |

Summary

The summary report contains a general statistics about the design action run. The results given in the summary report are described in the following table.

Table 6-4 Summary Report Statistics (Part 1 of 2)

| Result | Description |
|-----------------------------------|--|
| Vertices in Graph | The number of vertices in the graph that was used by the design action. The design action creates a graph to represent the network and uses this graph when constructing the tree. The graph is then mapped back to the network topology. The graph contains all nodes from the input node object set, with the exception of filtered nodes. |
| Links in Graph | The number of links in the final (output) graph. This is the graph that results after the design algorithm has run. |
| Links Added | The number of links added to the topology. |
| Links Reused | The number of links that existed in the topology and were used by the design action. |
| Links Upgraded | The number of existing links that were upgraded to use a different model by the design action. |
| Cost of New Links | The cost of all links added to the topology. |
| Cost of Upgraded Links | The net cost of upgrading existing links in the topology. This is the new cost minus the existing cost for all upgraded links. |
| Value of Reused Links | The total cost of all reused links. |
| Cost of Reused Links (discounted) | The cost of reusing links in the network. If the discount factor is 100 percent, the cost is 0. Otherwise, the cost is: $(1 - \text{discount factor}) * \text{Value of Reused Links}$ |
| Total Cost of Topology Change | The cost of the new, upgraded, and reused (discounted) links in the topology. The Total Cost of Topology Change equals the sum of the following statistics: <ul style="list-style-type: none"> • Cost of New Links • Cost of Upgraded Links • Cost of Reused Links (discounted) |
| Average Cost Per Link | Total cost of topology change divided by the number of added, reused, and upgraded links. |
| Graph Diameter | The maximum number of hops between any node pair in the graph. |
| Graph Average Distance | The average number of hops between any node pair in the graph (excludes 0-hop paths from source to source). |

Table 6-4 Summary Report Statistics (Part 2 of 2)

| Result | Description |
|-------------------------------|---|
| Traffic Averaged Distance | The traffic averaged number of hops between any node pair in the graph. For each pair, the minimum hop distance is weighted by the total traffic between the node pair. |
| Graph Connectivity | The minimum number of node disjoint paths between all of the node pairs. |
| Graph Average Connectivity | The average number of node disjoint paths over all of the node pairs. |
| Traffic Averaged Connectivity | The connectivity for each node pair is weighted by the total traffic between the node pair. |
| End of Table 6-4 | |

7 IP QoS Design Actions

This chapter provides high-level descriptions of the following IP QoS design actions:

- IP QoS Configuration
- IP QoS Queue Sizing

For more information about these design actions, open the Configure/Run Design Action dialog box (choose Design > Configure/Run Design Action in the Project Editor).

- For a complete description, select the design action and click View Comments.
- For information about individual attributes, click Edit Attributes. Then click the help (“question-mark”) button next to the attribute of interest.

IP QoS Configuration

You can use `ip_qos_configuration` to configure IP QoS parameters on routers in the network model. You can define QoS configuration templates and apply them to specific nodes and interfaces. QoS definitions in the design action (of traffic classes, traffic policies, queue profiles, and interface QoS schemes) are added to, but do not replace, existing definitions in the network. The only exception is if two definitions have the same name; in this case, the design action overwrites the existing definition.

IP QoS Queue Sizing

You can use `ip_qos_queue_sizing` to size the queue bandwidths or weights on IP interfaces based on the queue load and queue configuration rules. This design action uses Flow Analysis to compute the offered load to each queue based on the traffic flow. The design action attributes control how different queues are sized.

8 Project Pricing Reporter

You can use the `project_pricing_reporter` to generate detailed cost reports for proposed upgrades, build-outs, and other project plans. You can create highly detailed cost models, then apply a cost model to the links and nodes in a scenario. The `project_pricing_reporter` design action then generates a detailed report based on the cost model and the current network.

Workflow Description

The following steps outline the basic workflow for creating a cost report:

- 1) From the "Pricing" palette, place the "pricing preferences" utility into the project space. For simplicity, this node will be referred to as the "pricing preference object."
- 2) Configure the attributes of the pricing preference object (see *Configuring the Pricing Preference Object* on page DA-8-2).
- 3) Create nodes and links from the Pricing object palette. These models contain the attributes needed to apply the cost parameters specified in the pricing preference object.
- 4) Configure the cost attributes of the relevant nodes and links (see *Specifying Pricing Information on Nodes and Links* on page DA-8-6).


NOTE—You must configure the pricing preference object (step 2) before you can perform this step, because the node/link cost attributes depend on settings in the pricing preference object.

- 5) Configure and run the `project_pricing_reporter` design action (see *Running the project_pricing_reporter Design Action* on page DA-8-8).
- 6) View the cost reports generated by the design action (see *Viewing Results* on page DA-8-9).

Configuring the Pricing Preference Object

Figure 8-1 shows the attributes in the pricing preference object.

Figure 8-1 Attribute table in the Pricing Preference Object



It is good practice to configure the attributes in this order, as described in the following sections:

- 1) Regions on page DA-8-3
- 2) Cost Elements on page DA-8-3
- 3) Cost Categories on page DA-8-4
- 4) Work Package on page DA-8-5

Note—If you do not set the Regions attribute (which is permissible), you cannot assign a region to an object, and the area factor defaults to 1.0. If you do not set the Work Package attribute (which is also permissible), you can set the work package name to Default only.

Note—Make sure that the associations defined in the pricing preference object remain valid when its attributes are changed. For example, if you remove an entry in the Cost Elements table, then make sure that no entries in the Cost Categories attribute refer to that deleted entry.

Regions

A “region” is a user-defined geographic area with a name and an area cost factor. The area factor defines the relative cost of a region: the more costly the region, the higher the area factor.

Figure 8-2 “Regions” Attribute Table

| Name | Area Factor |
|----------------|-------------|
| Bethesda | 2.0 |
| North Carolina | 1.5 |
| Texas | 0.5 |

Cost Elements

Cost elements are user-provided descriptions of an activity (such as a site survey) that are assigned a default unit, a unit price, and the object types associated with this cost element. The Applicable To attribute defines the object types with which a cost element can be associated (such as nodes only, links only, or nodes and links).

Figure 8-3 “Cost Elements” Compound Attribute

| Title | Default Unit | Unit Price | Applicable To |
|---------------------------|--------------|------------|---------------|
| STM-16 Device | each | 10 | Nodes |
| STM-4 Device | each | 10 | Nodes |
| STM-1 Device | each | 10 | Nodes |
| Site Survey | Km | 10 | Links |
| Fiber Optic Survey | Km | 10 | Links |
| Fiber Optic Cabling & ... | Km | 10 | Links |

Figure 8-4 shows the Applicable To attribute, which is part of the Cost Elements compound attribute. (The significance of the Cost Category Default field will become clear in the following section.)

Figure 8-4 “Applicable To” Attribute of “Cost Elements” Compound Attribute

| Object Type | Status | Cost Category Default |
|-------------|----------------|-----------------------|
| Nodes | Applicable | No |
| Links | Not Applicable | No |

Cost Categories

Cost categories are user-specified categories that group together cost elements defined in the Cost Elements attribute.

Figure 8-5 “Cost Categories” Attribute Table

| Title | Definition | Applicable To |
|-------------------|------------|---------------|
| Electricity Nodes | [...] | Nodes |
| Railroad Nodes | [...] | Nodes |
| Electricity Links | [...] | Links |
| Railroad Links | [...] | Links |

The Applicable To attribute specifies the object types to which the cost category applies.

The compound attribute Definition defines the list of cost elements that are associated with a specific cost category. The value Add All Elements (in the Definition drop-down list) adds all the defined cost elements that

- 1) have the same object type association as the cost category, AND
- 2) have the Cost Category Default attribute set to Yes (see Figure 8-4).

This is simply a mechanism to populate the cost category with its cost elements.

Figure 8-6 shows the Definition compound attribute. If the Unit Price is set to Default, the corresponding cost-element unit price is inherited from the “Cost Elements” Compound Attribute. (You can override the default price if desired.)

Figure 8-6 “Definition” Attribute of “Cost Categories” Compound Attribute

| Cost Element | Unit Price |
|---------------|------------|
| STM-16 Device | Default |
| STM-4 Device | Default |
| STM-1 Device | Default |

Work Package

A work package groups together one more cost categories defined in the Cost Categories attribute. When the Definition attribute is set to None, all defined cost categories are associated with the work package.


Figure 8-7 “Work Packages” Attribute Table

| Title | Definition |
|------------------------|------------|
| Electricity | (...) |
| All Categories Package | None |

Specifying Pricing Information on Nodes and Links

After you specify the cost settings in the pricing preference object, the next step is to assign cost settings to the links and nodes in your scenario. Some node and link models contain a Pricing compound attribute, which is used to map the cost models defined in the pricing preference object. These models are available on the Pricing object palette.

Figure 8-8 Pricing Attributes on Supported Models




The Pricing attribute contains the following attributes:

- 1) Pricing Region—Selected from the list of regions that were defined in the Regions attribute of the pricing preference object. The pricing region defines the object's area factor.
- 2) Pricing Information—Ties together the work package, the cost categories that belong to the work package, and the cost elements associated with each cost category.

Pricing Information Compound Attribute

Figure 8-9 “Pricing Information” Attribute Table



By default, each Pricing Information entry has its work package set to Default. This special value enables you to select all the defined entries for the Cost Categories compound attribute in the pricing preference object.

Figure 8-10 “Pricing Definition” Attribute Table

| Cost Category | Cost Element | Quantity | Unit | Unit Price | Area Factor |
|-------------------|------------------------|-----------------|------|------------|-------------|
| Electricity Links | Site Survey | Use Link Length | Km | Default | Default |
| Electricity Links | Fiber Optic Cabling... | Use Link Length | Km | Default | Default |

The Pricing Definition table defines the applicable cost category and its elements. For each Cost Category/Cost Element pair, you can specify the following:

- **Quantity**—Specifies the number of units for the corresponding cost element entry. Links support a special value called Use Link Length when the unit of the cost element is in kilometers. In this case, the quantity is obtained from the Manual Length attribute of the link model. If the value of the Quantity attribute is set to As Calculated, the value of the Calculated Length attribute is used.
- **Unit Price**—Specifies the unit price for the corresponding cost category and cost element pair. If the value for Unit Price is Default, then the value for the unit price is obtained from the corresponding entry in the Cost Categories attribute of the pricing preference object. You can override this value here.
- **Area Factor**—A factor that multiplies the final cost of the corresponding cost category and cost element pair. If the value for Area Factor is Default, then the value for the area factor is obtained from the Area Factor entry in the Regions attribute of the pricing preference object. If the Pricing Region value is unspecified, the area factor is defaulted to 1.0. You can override the default here.
- **Unit**—Specifies the unit of the Cost Element. The value for the Unit is picked up from the corresponding entry in the Cost Elements attribute of the pricing preference object. You cannot override this value here; you can do this in the pricing preference object only.


Running the project_pricing_reporter Design Action

The "project_pricing_reporter" design action generates cost reports based on the cost data you specified in the pricing preference object and in the links and nodes.

Procedure 8-1 Running the project_pricing_reporter Design Action

- 1 Choose Design > Configure/Run Design Action... in the Project Editor menu.
 - ➔ The Configure/Run Design Action dialog box (Figure 8-11) appears.
- 2 Select Purpose from the "Arrange by" menu (top left corner).

Figure 8-11 Configure/Run Design Action Dialog Box




- 3 Select Current from the Target Scenario menu (bottom left corner).
- 4 Select project_pricing_reporter under the Project Pricing entry in the treeview.
- 5 Configure the project_pricing_reporter design action and click Run to generate the reports (for more information, see Configuring the project_pricing_reporter Design Action on page DA-8-9).
- 6 The design action generates four kinds of reports. View the resulting reports as described in Viewing Results on page DA-8-9.

End of Procedure 8-1

Configuring the project_pricing_reporter Design Action

Figure 8-12 shows the configurable attributes defined on the project_pricing_reporter design action.

Figure 8-12 project_pricing_report Attribute Table




The following attributes are particularly relevant:

- Link Length Scaling Factor—Multiplies the link length when it is computed using the calculated length. This attribute is used to account for physical links that do not follow a straight path.
- Report By (Output Options)—Specifies which generated report will be exported to a CSV (comma-separated value) file. By default, the work package report is exported to CSV. Each report consists of a detailed report and a corresponding summary report.

Viewing Results

To view all the generated reports, select the menu Design > Results > View Output Tables, which launches the dialog box in Figure 8-13. Select the report type and click Show to display the corresponding table. Choose File > Export to export the resulting report to various formats.

Figure 8-13 Results for project_pricing_reporter Design Action



Index

C

compound action, [DA-1-4](#)
 cost categories, in pricing preference object, [DA-8-4](#)
 cost elements, in pricing preference object, [DA-8-3](#)

D

derived action, [DA-1-5](#)
 design action
 attributes, viewing descriptions, [DA-1-4](#)
 compound action, [DA-1-4](#)
 configuring, [DA-1-4](#)
 output tables, [DA-1-10](#)
 quick action, [DA-1-8](#)
 creating, [DA-1-8](#)
 Run Action dialog box, [DA-1-9](#)
 runnable vs. nonrunnable actions, [DA-1-8](#)
 subaction, [DA-1-5](#)
 workflow descriptions, [DA-1-2](#)
 dual tree design
 log messages
 categories, [DA-6-3](#)
 classes, [DA-6-3](#)

I

ip_qos_configuration design action, [DA-7-1](#)
 ip_qos_queue_sizing design action, [DA-7-1](#)

L

link bundle
 defined, [DA-2-1](#)
 link_dimensioning
 attributes of interest, [DA-2-2](#)
 changes to link bundles, [DA-2-1](#)
 Design Action Statistics report, [DA-2-6](#)
 inputs considered, [DA-2-2](#)
 Link Bundle Summary report, [DA-2-6](#)
 log messages
 categories, [DA-2-4](#)
 classes, [DA-2-4](#)
 for unsatisfactory solutions, [DA-2-5](#)
 Object Tables report, [DA-2-6](#)
 prerequisites, [DA-2-2](#)
 reports, [DA-2-6](#), [DA-3-4](#)
 tutorial, [DA-2-2](#)
 unsatisfactory solutions, [DA-2-4](#)
 link_dimensioning_resilient
 failure cases, [DA-3-2](#)

Failure Cases report, [DA-3-4](#)
 Intermediate Statistics report, [DA-3-4](#)
 Link Bundle Summary report, [DA-3-4](#)
 log messages
 categories, [DA-3-3](#)
 classes, [DA-3-3](#)
 shared risk groups, [DA-3-2](#)
 Summary Statistics report, [DA-3-4](#)

O

operations
 Scenarios menu, [DA-1-3](#)

P

project_pricing_reporter design action, [DA-8-1](#)

Q

quick action (design action), [DA-1-8](#)

R

regions, in pricing preference object, [DA-8-3](#)
 ring backbone design
 log messages
 categories, [DA-4-5](#)
 classes, [DA-4-5](#)
 roles, [DA-1-4](#)
 Run Action dialog box, [DA-1-9](#)
 runnable design actions, [DA-1-8](#)

S

Scenarios menu
 operations, [DA-1-3](#)
 spanning tree design
 log messages
 categories, [DA-5-4](#)
 classes, [DA-5-4](#)
 subaction, [DA-1-5](#)

T

topology design
 attributes of interest, [DA-4-2](#), [DA-5-2](#), [DA-6-2](#)
 inputs considered, [DA-4-2](#), [DA-5-2](#), [DA-6-2](#)
 prerequisites, [DA-4-1](#), [DA-5-1](#), [DA-6-1](#)

W

work packages, in pricing preference object, [DA-8-5](#)

