



Managing Address Space

Address blocks provide an organizational structure for addresses used across the network. Address blocks can consist of static addresses or dynamic addresses allocated to DHCP servers for lease assignment. An address block can have any number of child address blocks and can culminate in one or more child subnets. The address block administrator is responsible for these objects. This administrator can create parent and child address blocks or subnets, which are always the leaf nodes of the address space. Static subnets can be further subdivided into one or more IP address ranges. However, dynamically added subnets create their own subnets that the administrator cannot modify or delete.

Address Block Administrator Role

The address block administrator role manages address space at a higher level than that of specific subnet or static address allocations. This is actually a middle manager role, as there is likely to be a higher authority handing out address blocks to the system.

Required Permissions

To exercise the functions available to the address administrator, you must have:

- At the regional cluster:
 - The `addrspace` license entered in the system
 - The `regional-addr-admin` role assigned—This role should probably be unencumbered by further `subnet-utilization`, `lease-history`, `ric-management`, and `dhcp-management` subrole restrictions
- At the local cluster, the `addrblock-admin` role assigned.

Role Functions

These functions are available to the address block administrator:

- At the regional cluster:
 - **Address aggregation**—For example, if the `10.0.0.0/16` address block exists at the regional cluster and a local cluster administrator creates the `10.1.1.0/24` address block, the local address block (through replication) is rolled up under its parent at the regional cluster. This allows a unified view of the address space at the regional cluster without affecting the local cluster configuration.

- Address delegation—Administrators can delegate address space to the local cluster, thereby giving up authority of the delegated object.
- Subnet utilization reports—The regional cluster supports subnet utilization reporting across regions, protocol servers, and sets of network hardware. The central configuration administrator can poll the local clusters for subnet utilization by VPN (if defined), time range and criteria that contain the following choices: owner, region, address type, address block, subnet, or all. For details on querying subnet utilization, see the [“Generating Subnet Utilization History Reports” section on page 8-13](#).
- Lease history reports—This provides a single vantage point on the lease history of multiple DHCP servers. The administrator can query the history data at the local cluster to constrain the scope of the history report. Lease histories can be queried by VPN (if defined), time range and criteria that contain the following choices: IP address, MAC address, IP address range, or all. This is an important feature to meet government and other agency mandates concerning address traceability. For details on querying lease history, see the [“Querying Leases” section on page 21-21](#).
- Polling configurations—The administrator can control the intervals and periods of local cluster polling for replication, IP histories, and subnet utilization. You can also set the lease history and subnet utilization trimming ages and compacting intervals at the CCM server level. (See [Chapter 5, “Managing the Central Configuration.”](#))
- Check the DHCP and address data consistency.
- At the local cluster:
 - Manage address blocks, subnets, and address types.
 - Check the DHCP and address data consistency.

Viewing Unified Address Space

You can view the static and dynamic address space on the View Unified Address Space page (see [Figure 8-1](#)). This address space is a hierarchical tree of address blocks and subnets, sorted in IP address order. You can choose the level of depth at which to display the tree. You can also expand and contract nodes, which recursively expands or contracts all child nodes. If you pick a new level, this overrides the previous expansion or contraction. This page is available in the local cluster and regional cluster Web UI.

Figure 8-1 View Unified Address Space Page (Local)

Address/Mask	Type	Owner	Region	Address Type	Current Usage	Description
192.168.50.0/24	Subnet	[none]	[none]	[none]	↔	
192.168.60.0/24	Address Block	[none]	[none]	[none]	↔	
192.168.70.0/24	Address Block	[none]	[none]	[none]	↔	

Pulling Replica Address Space from Local Clusters

You may choose to pull address space from the replica data of the local clusters instead of explicitly creating them.



Note

Pulling replica address space from a local cluster where subnets were removed does not clear the server name on the subnet. Although the subnet is no longer used, it is still considered allocated to the server. Hence, the delete operation does not appear for the subnet, so that you cannot delete the subnet from the regional cluster. To push or reallocate the subnet to a different cluster, or remove it from the regional cluster, you must first reclaim the subnet (see the “[Reclaiming Subnets](#)” section on page 8-9). This clears the reference to the local server.

To pull the replica address space:

- Step 1** On the View Unified Address Space page, click **Pull Replica Address Space**.
- Step 2** Choose the data synchronization mode on the Select Pull Replica Address Space page (see [Figure 8-2](#)).

Figure 8-2 Select Pull Replica Address Space Page (Regional)

Home Administration Servers Clusters Routers Replica Data DHCP DNS Hosts Address Space Reports Address Space Address Blocks Subnets Address Types Subnet Utilization Lease History			
Select Pull Replica Address Space			
Data To Pull			
All Replica Address Space Data			
Data Synchronization Mode	<input checked="" type="radio"/> Update	<input type="radio"/> Complete	<input type="radio"/> Exact
Subnets	Add new subnets.	Add new subnets. Replace existing (and collapsed) subnets.	Add new subnets. Replace existing (and collapsed) subnets. Delete subnets not in the replica address space.
Address Blocks	Add new address blocks.	Add new address blocks. Replace existing (and collapsed or expanded) address block trees.	Add new address blocks. Replace existing (and collapsed or expanded) address block trees. Delete address block trees not in the replica address space.
Failover Pairs	Add new failover pair relationships.	Add new failover pair relationships. Replace failover pair relationships for existing subnets.	Add new failover pair relationships. Replace failover pair relationships for existing subnets. Delete failover pair relationships not in the replica address space.

- Step 3** Click **Report** at the bottom of the page.
- Step 4** Click **Run** on the Report Pull Replica Address Space page.
- Step 5** Click **OK** on the Run Pull Replica Address Space page.

149681

Address Blocks and Subnets

An address block is an aggregate of IP addresses based on a power-of-two address space that can be delegated to an authority. For example, the 192.168.0.0/16 address block (part of the RFC 1918 private address space) includes 2^{16} (or 65536) addresses. Address blocks can be further divided into child address blocks and subnets. For example, you might want to delegate the 192.168.0.0/16 address block further into four child address blocks—192.168.0.0/18, 192.168.64.0/18, 192.168.128.0/18, and 192.168.192.0/18.



Note

The DHCP server also uses address blocks to manage subnet allocation for on-demand address pools (see the [“Configuring Virtual Private Networks and Subnet Allocation”](#) section on page 22-12). Address blocks used for dynamic address pools must be created using the `dhcp-address-block` command in the CLI. The unified address view in the Web UI also displays these dynamic address blocks, but does not provide an edit link to them, because they have been delegated in their entirety to the DHCP server. They should not be further subdivided for subnet allocation. The DHCP server automatically handles these address blocks as it receives subnet requests. These address pools are indicated by a **D** (for “Delegated”).

A subnet is the leaf node of the address space and cannot be further subdivided. If you create the 192.168.50.0/24 subnet, you can subsequently create an address block by that same name, and the subnet will become a child of the address block. However, you cannot further subdivide or delegate the 192.168.50.0/24 subnet.

Subnets can have one or more defined address ranges. Address blocks cannot have address ranges. When you create an address range for a subnet using the Web UI, it becomes a static range, meaning that it cannot be allocated dynamically using DHCP. However, the Web UI shows any dynamic ranges defined by DHCP scopes for the subnet. Displaying the ranges as such indicates where overlaps may occur between assigning static addresses for the address space and dynamic addresses for scopes.


The address space view shows the hierarchy of address block and subnets and their parent-child relationships. The hierarchy does not go down to the level of address ranges for each subnet. These are displayed when you access the subnet.

Viewing Address Blocks and Subnets

To view the address blocks and subnets created for a network in both the local cluster and regional cluster Web UIs, click **Address Space**, then **Address Space** again. This opens the View Unified Address Space page (see [Figure 8-1](#) on page 8-2).

To choose a level of depth for the address space, click one of the numbers across the top, or click **All** to get all levels. The address space appears below the row of numbers. The Address Type column identifies the type of object displayed, an address block or a subnet. The Owner column identifies the owner of the address space, and the Region column identifies the assigned region for the address space.

Address spaces that were assigned dynamically are indicated by a **D** (for “Delegated”) in the Address Type column. You cannot delete this delegated address space.

To refresh the view, click the Refresh icon (.

Knowing When to Add Address Blocks

This use case describes the set of user actions associated with adding a new address block to the network in a shared management network. These preconditions are assumed:

1. From summary IP address utilization reports (see the “[Enabling Subnet Utilization Collection](#)” section on page 5-9), an address block administrator notes that the company’s top level address block is nearing the 90% utilization mark.
2. The address block administrator submits a request for more address space from ARIN (or some other numbering authority) and the request is granted.

Once the address space is made available, the regional address administrator:

1. Adds the new blocks to the central address block map, and based on a review of the utilization reports, creates and delegates address blocks to be used by the local clusters. The action of delegating the address blocks causes them to be pushed to the local clusters.
2. Allocates the new address space to network elements as needed, using router and failover synchronization features to simplify the configuration tasks:
 - Allocates subnets to a failover pair—Gets a scope template for the subnet, either from the subnet or the failover pair.
 - Allocates subnets to a router interface configuration (RIC) server interface and failover pair.
 - Finds a free subnet—Finds the address block of the right type.
 - Allocates the free subnet to an address destination (DHCP server or other destination).

Adding Address Blocks

To view CCM address blocks in the local cluster and regional cluster Web UIs, click **Address Blocks** to open the List/Add Address Blocks page (see [Figure 8-3](#) for a partial view of the regional cluster version of this page).

Figure 8-3 List/Add Address Blocks Page (Local)

To add an address block, enter its network address in the Address/Mask field, then choose the address mask from the drop-down list. For example, enter 192.168.50.0 in the Address Mask field, then choose 24 in the drop-down list to create the 192.168.50.0/24 address block, which is all the addresses in the range 192.168.50.0 through 192.168.50.256.

For a review of the number of available addresses for each subnet mask, see [Table 8-1](#). These available hosts exclude the two network and broadcast addresses in each range.

Table 8-1 Subnet Masking

Network Mask	Octet Designation	Available Hosts in Each Address Range
/8	255.0.0.0	16777214
/9	255.128.0.0	8338606
/10	255.192.0.0	4194302
/11	255.224.0.0	2097150
/12	255.240.0.0	1048574
/13	255.248.0.0	524286
/14	255.252.0.0	262142
/15	255.254.0.0	131070
/16	255.255.0.0	65534
/17	255.255.128.0	32766
/18	255.255.192.0	16382
/19	255.255.224.0	8190
/20	255.255.240.0	4084
/21	255.255.248.0	2046
/22	255.255.252.0	1022
/23	255.255.254.0	5010
/24	255.255.255.0	254
/25	255.255.255.128	126
/26	255.255.255.192	62
/27	255.255.255.224	30
/28	255.255.255.240	14
/29	255.255.255.248	6
/30	255.255.255.252	2

Delegating Address Blocks


Address block delegation is the coordinated actions of marking the delegated address block at the regional cluster as being delegated to a local cluster and creating the delegated address block in the local cluster. To delegate an address block to a local cluster, the address block cannot have child address blocks or subnets. The delegated address block created at the local server must have the same address size as the one at the regional cluster.

You can delegate only one address block to one local cluster at a time; you cannot delegate it to multiple local clusters. You can also delegate an address block to an owner.

To delegate an address block, you must:

1. Have the central configuration administrator create a local cluster to which to delegate the address block (see the “[Configuring Server Clusters](#)” section on page 5-1).
2. Have the central configuration administrator synchronize the regional cluster with the local cluster (see the “[Synchronizing with Local Clusters](#)” section on page 5-5). The local cluster will have address source references to the regional cluster through the synchronization process.
3. Delegate the address block to the cluster or an owner.

For example, in the regional cluster Web UI:

-
- Step 1** Have the central configuration administrator create a local cluster, ServProv-One:
- a. Log in to the regional cluster as the central configuration administrator.
 - b. Click **Clusters**, then **Cluster List**.
 - c. Click **Add Cluster** on the List Server Clusters page to open the Add Server Cluster page.
 - d. Enter the cluster name **ServProv-One** and the connection data, then click **Add Cluster**.
 - e. On the List Server Clusters page, click the Resynchronize icon () next to ServProv-One.
- Step 2** As regional address administrator, create an address block:
- a. Log in to the regional cluster as the regional address administrator.
 - b. Click **Address Space**, then **Address Blocks** to open the List/Add Address Blocks page.
 - c. Enter **192.168.50.0** in the Address/Mask field, then choose **24** in the mask drop-down list.
 - d. Click **Add Address Block**.
- Step 3** Delegate the address block to a cluster or owner:
- a. Click the name of the address block to open the Edit Address Block page.
 - b. In the Address Block Delegation section of the page, choose either a local cluster or an owner to which to delegate the address block.
 - c. Click **Delegate Block**. The Edit Address Block page now indicates that the address block is delegated.
 - d. If there are further modifications to the address block, click **Modify Address Block**, otherwise click **Cancel**.
 - e. The List/Add Address Blocks page now identifies the address block as being delegated (**D**). To undelegate it, edit the address block again, then click **Reclaim Address Block**.
-

Pushing Subnets to Local DHCP Servers and Routers

-
- Step 1** Have the central configuration administrator create a local cluster and resynchronize it with the local cluster. If pushing to a router, also ensure that a router license exists at the regional cluster.
- Step 2** Create a subnet at the regional cluster:
- a. Click **Address Space**, then **Subnets**. This opens the List/Add Subnets page (see [Figure 4-5 on page 4-16](#)).
 - b. Enter at least the network address and choose the mask of the subnet, then click **Add Subnet**.

- Step 3** Have the central configuration administrator create a scope template so that it can create a scope to contain a subnet:
- Log in to the regional cluster as the central configuration administrator.
 - Click **DHCP**, then **Scope Templates** to open the List DHCP Scope Templates page.
 - Click **Add Scope Template** to open the Add DHCP Scope Template page.
 - Among other entries on this page, enter the **create-range** expression in the Range Expression field to create a scope with that subnet. (If you choose a policy for the scope template, be sure that the policy exists at the local cluster, or you must push the policy to the local cluster. See the “[Pushing Policies to Local Clusters](#)” section on page 5-12.) Click **Add Scope Template**.
- Step 4** As regional address administrator, add the subnet to the local cluster’s DHCP server:
- Log in to the regional cluster as the regional address administrator.
 - Click **Address Space**, then **Subnets** to open the List/Add Subnets page.
 - Click the name of the subnet to open the Edit Subnet page (see [Figure 8-4](#)).

Figure 8-4 Edit Subnet Page (Regional)

Home | Administration | Servers | Clusters | Routers | Replica Data | DHCP | DNS | Hosts | **Address Space** | Reports
 Address Space | Address Blocks | **Subnets** | Address Types | Subnet Utilization | Lease History

Edit Subnet 192.168.50.0/24

Parent Block	DNS Host Bytes	Owner	Region	Address Type	Description
[no parent]	[none]	[none]	[none]	[none]	
Primary Subnet					Unset?
[] / 24					<input type="checkbox"/>
<input type="button" value="Modify Subnet"/> <input type="button" value="Push Subnet"/> <input type="button" value="Reclaim Subnet"/> <input type="button" value="Cancel"/>					
Subnet State	dhcp-allocated				
DHCP Server	example-cluster				
Replica Scope List	Cluster	Connect			
example-scope	example-cluster	<input type="button" value="Connect"/>			
IP Ranges					
Start	End			Type	
[]	[]			static	
<input type="button" value="Add IP Range"/>					

149387

- Click **Push Subnet**. This opens the Push Subnet page (see [Figure 8-5](#)).

Figure 8-5 Push Subnet Page (Regional)

Home | Administration | Servers | Clusters | Routers | Replica Data | DHCP | DNS | Hosts | **Address Space** | Reports
 Address Space | Address Blocks | **Subnets** | Address Types | Subnet Utilization | Lease History

Push Subnet 192.168.50.0/24

Scope Template	[none]
Push to Router Interface	
Router	[none]
Router Interface	[none]
<input type="button" value="Push Subnet"/> <input type="button" value="Cancel"/>	

149388

- Choose the scope template from the drop-down list.

- f. Choose the router and the router interface from the drop-down lists.
 - g. Choose the DHCP Server radio button, then choose the cluster from the drop-down list.
 - h. Click **Push Subnet**.
-

Creating Reverse Zones from Subnets

In the Web UI, you can create reverse zones from subnets. For details, see the [“Adding Reverse Zones from Subnets”](#) section on page 14-11.

Reclaiming Subnets

Once you delegate a subnet to the DHCP or RIC server, you can reclaim it if necessary:

-
- Step 1** Click **Address Space**, then **Subnets** to open the List/Add Subnets page (see [Figure 4-5 on page 4-16](#)).
 - Step 2** Click the name of the subnet to open the Edit Subnet page (see [Figure 8-4 on page 8-8](#)).
 - Step 3** Click **Reclaim Subnet** to open the Reclaim Subnet page.
 - Step 4** If you want to force deleting the subnet, click a check mark in the Force Delete box.
 - Step 5** Click **Reclaim Subnet**.
-

**Note**

When you push or reclaim subnets for a managed or virtual router, this sets the primary and secondary relationships that are set for the router for all the related subnets and scopes as well. For details on routers, see the [“Pushing and Reclaiming Subnets for Routers”](#) section on page 10-3.

Adding Children to Address Blocks

You might want to subdivide undelegated address blocks into child address blocks or subnets. You can do this at the regional and local cluster.

-
- Step 1** Click **Address Space**, then **Address Blocks** to open the List/Add Address Blocks page (see [Figure 8-3 on page 8-5](#)).
 - Step 2** Click the name of an address block that is not marked as delegated (**D**). This opens the Edit Address Block page (see [Figure 8-6](#) for the local cluster page).

Figure 8-6 Edit Address Block Page (Local)

- Step 3** To add a child address block, add an address in the Address/Mask field of the Child Address Blocks section of the page that is part of the address block network address, but choose a higher mask value than the parent address block. Then click **Add**.

An error message appears if you try to set the same network address for a child address block as for a child subnet.

If you omit a value when you click **Add**, this automatically adds the subdivisions of the parent address space with the appropriate mask value. For example, if the parent space is 192.168.50.0/24, you omit any child subnet value, and click **Add**, the Web UI adds the children in this order:

```
192.168.50.0/26
192.168.50.64/26
192.168.50.128/26
192.168.50.192/26
```

- Step 4** To add a child subnet, add an address in the Address/Mask field of the Child Subnets section of the page that is part of the address block network address, but choose a higher mask value than the parent address block. Then click **Add**.

An error message appears if you try to set the same network address for a child address block as for a child subnet.

If you omit a value when you click **Add**, this automatically adds the subdivisions of the parent address space with the appropriate mask value. For example, if the parent space is 192.168.50.0/24, you omit any child subnet value, and click **Add**, the Web UI adds the children in this order:

```
192.168.50.0/26
192.168.50.64/26
192.168.50.128/26
192.168.50.192/26
```

Adding Address Ranges to Subnets

You can edit the subnet data and add any number of address ranges to a subnet. These ranges must be in the subnet's designated network.

-
- Step 1** Click **Address Space**, then **Subnets** to open the List/Add Subnets page (see [Figure 4-5 on page 4-16](#)).
 - Step 2** Click the name of the subnet to which you want to add address ranges. This opens the Edit Subnet page (see [Figure 8-4 on page 8-8](#)).
 - Step 3** Enter the starting address of the range in the Start field in the IP Ranges area of the page, then add the ending address in the End field. If you add just the host numbers in these fields, the relative address in the range determined by the address mask is used.
 - Step 4** Click **Add IP Range**.
-

Viewing Address Utilization for Address Blocks, Subnets, and Scopes

You can view the current address utilization for address blocks, subnets, and scopes in both the local and regional cluster Web UIs. The function is available on the View Unified Address Space page (see [Figure 8-1 on page 8-2](#)), List/Add Address Blocks page (see [Figure 8-3 on page 8-5](#)), and List/Add Subnets page (see [Figure 4-5 on page 4-16](#)). When you click the View icon (🔍) in the Current Usage column, the View Current Utilization Report page appears (see [Figure 8-7](#)).

Figure 8-7 View Current Utilization Report Page (Local)

Utilization Detail	Type	Active Dynamic	Free Dynamic	Active Reserved
192.168.50.0/24	Subnet	0	0	0
example-scope	Scope	0	0	0

Navigation: [Previous] [Next] [Page Size: 10] [Change Page Size] [OK]




Note

To ensure the proper subnet-to-server mapping on this page, you must update the regional address space view so that it is consistent with the relevant local cluster. Do this by pulling the replica address space, or reclaiming the subnet to push to the DHCP server (see the [“Reclaiming Subnets” section on page 8-9](#)). Also ensure that the particular DHCP server is running.

The Utilization Detail column items are expandable on the View Current Utilization Report page so that you can view the scope data for an address block or subnet. If you click the address block, subnet, or scope name in this column, this opens the View Utilization Detail page (see [Figure 8-8](#) for a partial view of a subnet page).

Figure 8-8 View Utilization Detail Page (Local)



The other columns on the View Current Utilization Report page identify:

- Whether the address space is an address block, subnet, or scope.
- Active Dynamic—Addresses that are part of a dynamic range managed by DHCP and that are currently leased, but not reserved.
- Free Dynamic—Addresses that are not currently leased.
- Active Reserved—Addresses that are part of a dynamic range and are reserved.
- View Utilization History—Appears at the regional cluster only. Clicking the Report icon (📄) opens the List Subnet Utilization Records page, where you can refine the subnet utilization history query.

The View Utilization Detail page is a read-only page that shows detailed address utilization attributes for the address block, subnet, or scope. The address utilization attributes are described in [Table 8-2](#).

Table 8-2 Address Utilization Attributes

Utilization Attribute	Description
Total Addresses	
total-dynamic	Total number of leases, excluding reserved ones.
total-reserved	Total number of reserved leases.
Free Dynamic	
avail	Number of dynamic leases that are currently available for issue to clients.
other-avail	Number of dynamic leases that the DHCP failover partner currently has available for issue to clients.
Active Dynamic	
offered	Number of dynamic leases that are currently offered to clients, but not yet acknowledged as being leased.
leased	Number of dynamic leases that are currently acknowledged as leased to clients.
expired	Number of dynamic leases that are past the lease expiration period, but will not be available for other clients (except after the policy grace-period expires).

Table 8-2 Address Utilization Attributes (continued)

Utilization Attribute	Description
pend-avail	Number of dynamic leases that are waiting acknowledgement from the failover partner that it did not reissue the lease.
Reserved	
reserved-active	Number of reserved leases that clients are actively using.
reserved-inactive	Number of reserved leases that clients are not actively using.
Unavailable	
unavail	Number of unreserved dynamic leases that a client declines or the server marks with an address conflict (usually indicating configurations that need correcting).
reserved-unavail	Number of reserved leases that a client declines or the server marks with an address conflict (usually indicating configurations that need correcting).
Deactivated	
leased-deactivated	Number of dynamic leases that clients are actively leasing (that are not offered, expired, or released), but that an administrator deactivated.
reserved-leased-deactivated	Number of reserved leases that clients are actively leasing (that are not offered, expired, or released), but that an administrator deactivated.

Generating Subnet Utilization History Reports

You can extract subnet utilization history data so that you can determine how many addresses in the subnet were allocated and what the free address space is. You can use additional administrative functions to trim and compact the subnet utilization database of records, to manage the size of the database.

Enabling Subnet Utilization History Collection at the Local Cluster

You must explicitly enable subnet utilization collection for the local cluster DHCP server. You can do this in the local Web UI:

-
- Step 1** Click **DHCP**, then **DHCP Server**.
 - Step 2** On the Manage DHCP Server page, click the **Local DHCP Server** link.
 - Step 3** On the Edit DHCP Server page, look for the Subnet Utilization Settings attributes, which determine how frequently snapshots of the data occur and over which period of time the data should be maintained:
 - *collect-addr-util-duration*—Maximum period, in hours, the DHCP server maintains address utilization data. This value is set to 0 by default. To disable DHCP server from collecting any address utilization data, unset this parameter or set it of 0.
 - *collect-addr-util-interval*—Frequency, in minutes or hours, that the DHCP server should maintain address utilization data snapshots, assuming that the *collect-addr-util-duration* attribute is not unset or set to 0. This value is set to 15 minutes by default.

Note that both of these parameters can impact DHCP server memory. Each snapshot of data collected for every interval is 68 bytes. For example, if there are 10 scopes, the collection duration is set to 24 hours, and the collection interval is set to one hour, memory used by the DHCP server to maintain address utilization data is 24 times 68 bytes for each scope, or 16 K.

- Step 4** Click **Modify Server** at the bottom of the page.
- Step 5** Reload the DHCP server.

Querying Subnet Utilization History Data

You collect subnet utilization by first having subnets and setting up the scopes, address ranges, and collection criteria at the local cluster. You then set up the local cluster containing the DHCP server as part of the regional cluster, and enable polling the subnet utilization data from the regional cluster:

- Step 1** Click **Clusters**, then **Cluster List** to open the List Server Clusters page.
- Step 2** Click the name of the local cluster to open the Edit Cluster page.
- Step 3** Look for the Subnet Utilization Settings attributes:
- *poll-subnet-util-interval*—Polling interval; be sure that this is set to a reasonable time interval greater than 0.
 - *poll-subnet-util-retry*—Retry count in case of a polling failure; by default, this is set to one retry.
 - *poll-subnet-util-offset*—Fixed time when polling occurs. For example, setting the offset to 13h (1 P.M.) with the polling interval set to 2h means that polling occurs every two hours, but it must occur at 1 P.M. each day.
- Step 4** At the regional cluster, you must also set the selection criteria for querying the subnet utilization data—Click **Address Space**, then **Subnet Utilization** to open the Query Subnet Utilization page (see Figure 8-9).

Figure 8-9 Query Subnet Utilization Page (Regional)

- Step 5** You can query subnet utilization history based on the following criteria:
- Time range for the query—Choose from one of the following time ranges for the lease history data:
 - last 10 days
 - last 30 days
 - last 60 days
 - last 90 days
 - from/to (limited to 90 days)

If you choose this value, also choose the Start Date and End Date month, day, and year from the drop-down lists. The result depends on the value of the *poll-subnet-util-interval* attribute.

- b. Criteria—Choose the criteria on which you want to base the query:
 - By Owner—Choose the owner from the adjacent drop-down list.
 - By Region—Choose the region from the adjacent drop-down list.
 - By Address Type—Choose the address type from the adjacent drop-down list.
 - By Address Block—Choose the address block from the adjacent drop-down list.
 - By Subnet—Choose the subnet from the adjacent drop-down list.
 - All—Choose by all owners, regions, address types, address blocks, and subnets.
- Step 6** Click **Query Subnet Utilization** to open the List Subnet Utilization Records page (see the “[Viewing Subnet Utilization History Data](#)” section on page 8-16).

Trimming and Compacting Subnet Utilization History Data

If you enable subnet utilization, its database is trimmed automatically based on each record’s expiration time. You can also compact the data so that you can view subsets of the records older than a certain age. The CCM server performs background trimming at the regional cluster, which trims off the subnet utilization data older than a certain age at regular intervals. The trimming interval is set by default to 24 hours, and the age (how far back to go in time before trimming) to 24 weeks.

In the regional cluster Web UI, you must be a central configuration administrator assigned the database subrole to adjust the values of and perform subnet utilization database trimming and compacting:

- Step 1** Click **Administration**, then **Servers**. This opens the Manage Servers page.
- Step 2** Click the **Local CCM Server** link to open the Edit CCM Server page.
- Step 3** Under the Subnet Utilization Settings, set the following attributes:
 - *trim-subnet-util-interval*—How often to trim the old subnet utilization data automatically, the default being not to trim the data. You must set this to a value to trigger any background trimming. The bounded values are 0 to one year, and you can use units in seconds (s), minutes (m), hours (h), days (d), weeks (w), months (m), and years (y).
 - *trim-subnet-util-age*—How far back in time to trim the old subnet utilization data automatically, the default being 24 weeks. (However, the *trim-subnet-util-interval* value must be set to other than 0 for trimming to be in effect at all.) The bounded values are 24 hours to one year, and you can use units in seconds (s), minutes (m), hours (h), days (d), weeks (w), months (m), and years (y).
- Step 4** You can also force immediate trimming and compacting—Find the Trim/Compact Inputs section:
 - a. Trim/Compact age—How far in time to go back to trim the data. There are no bounds to this value. However, if you set a very small value (such as 1m), it trims or compacts very recent data, which can be undesirable. In fact, if you set it to zero, you lose all of the collected data. Setting the value too high (such as 10y) may end up not trimming or compacting any data.
 - b. Compact interval— Time interval at which to compact the subnet utilization records older than the Trim/Compact age. This interval can be some multiple of the polling interval. For example, if the compact interval is set to twice the polling interval, it eliminates every other record.
- Step 5** If you are trimming immediately, click **Trim All Subnet Utilization** among the controls at the bottom of the page. If you are compacting the data, click **Compact All Subnet Utilization**.

Viewing Subnet Utilization History Data

The DHCP server gathers subnet utilization data into three broad categories:

- Active Reserved
- Active Unreserved
- Free Reserved

Each of these categories has a current value for a given collection interval, and low and high values over the life of the DHCP server.

To illustrate the three subnet utilization categories, consider this DHCP scope configuration:

```
Scope 10.10.10.0/24
Range 10.10.10.1 10.10.10.10
Range 10.10.10.20 10.10.10.30
Reservation 10.10.10.1 MAC-1
Reservation 10.10.10.2 MAC-2
Reservation 10.10.10.41 MAC-3
Reservation 10.10.10.42 MAC-4
```

Of the 254 potential leases, only 31 are configured, and two reservations are outside the address range.

Immediately after configuring the scope, adding the ranges and reservations, and reloading the DHCP server, these counters appear for subnet utilization:

```
Active Reserved 0
Active Unreserved 0
Free Unreserved 20
```

As soon as clients MAC-1 and MAC-2 get their reserved leases, subnet utilization then shows as:

```
Active Reserved 2
Active Unreserved 0
Free Unreserved 20
```



When the client MAC-5 gets lease 10.10.10.3, subnet utilization then shows as:

```
Active Reserved 2
Active Unreserved 1
Free Unreserved 19
```

Access to the report is through **Address Space**, then **Subnet Utilization**. This opens the List Subnet Utilization Records page.



Tip

At the top left corner of the List Subnet Utilization Records page is either the Log icon () for the Netscape browsers that you can click to view a text version of the report, or the Save icon () for the Internet Explorer browser so that you can save the report to a file (.txt by default).

Click one of the records to open the View Subnet Utilization Record page for that record.

Viewing Data Consistency and Adding Rules

Using consistency rules, you can check data inconsistencies, such as overlapping address ranges and subnets. You can set data consistency rules at the regional and local clusters. See [Table 8-3](#) and [Table 8-4](#) for the consistency rules you can set in each case.

Table 8-3 Data Consistency Rule Settings at the Regional Cluster

Regional Consistency Rule	Description
Attributes Consistency Rule	Ensures that policies and client-classes with the same names at replication have the same values.
Broadcast Address Rule	Ensures that the dynamic address range for a scope should not include a broadcast address.
Cable Helper Consistency Rule	Ensures that cable helpers and DHCP failover are consistent.
Client-Class Selection Match Tag Rule	Ensures that all client-classes have a scope-selection tag defined by some scope.
Ensure Scope for Subnet Rule	Ensures that a scope is present for every subnet.
Ensure Subnets for Scopes Rule	Ensures that a subnet is present for every scope.
IP Range Consistency Rule	Identifies any overlapping static or dynamic address ranges.
Owner Match Rule	Ensures that each subnet on the router has the same owner as the subinterface.
Router Subnets in Database Rule	Ensures that each subnet on the router has a corresponding subnet in the regional database.
Selection Tags Consistency Rule	Ensures that scope-selection tags on scopes match with one of those defined in the address types.
Subnet Consistency Rule	Identifies any overlapping subnets.
Utilization Collection Rule	Ensures that the DHCP server collection interval is greater than the regional server collection interval.

Table 8-4 Data Consistency Rule Settings at the Local Cluster

Local Consistency Rule	Description
Broadcast Address Rule	Ensures that the dynamic address range for a scope should not include a broadcast address.
Client-Class Selection Match Tag Rule	Ensures that all client-classes have a scope-selection tag defined by some scope.
IP Range Consistency Rule	Identifies any overlapping static or dynamic address ranges.
Subnet Consistency Rule	Identifies any overlapping subnets.

- Step 1** Click **Home**, then **Consistency Rules** to open the List Consistency Rules page (see [Figure 8-10](#) for the local cluster version of this page).

Figure 8-10 List Consistency Rules Page (Local)

Rule Name	Description
<input type="checkbox"/> Broadcast Address Rule	Rule to ensure that dynamic address ranges in a scope do not include any broadcast addresses.
<input type="checkbox"/> CNAME RR and Host Alias Consistency Rule	Rule to ensure CNAME RR and Host alias Consistency.
<input type="checkbox"/> Client Class Selection Match Tag Rule	Rule to ensure that all client classes have a selection tag defined by some scope.
<input type="checkbox"/> Failover Pair Consistency Rule	Rule to ensure that CCM Server and DHCP Server have same versions of FailoverPair objects
<input type="checkbox"/> IP Range Consistency Rule	Rule to determine if there are any overlapping static and/or dynamic IP ranges.
<input type="checkbox"/> Lame Delegation Rule	Rule to ensure that no lame delegation exists for managed subzones.
<input type="checkbox"/> Missing Hosts Consistency Rule	Rule to find missing Hosts for PTR Records.
<input type="checkbox"/> Missing PTR Records Consistency Rule	Rule to find missing PTR Records for Hosts .
<input type="checkbox"/> Owner Match Rule	Rule to ensure that each subnet on a router has the same owner as the router interface does.
<input type="checkbox"/> Router Subnets in Database Rule	Rule to ensure that each subnet on a router has a corresponding subnet in the regional database.
<input type="checkbox"/> Subnet Consistency Rule	Rule to determine if there are any overlapping subnets.
<input type="checkbox"/> Zone Reference Rule	Rule to ensure that UpdatePolicy, ACL and Key objects referenced from zones are resolvable.

149384

- Step 2** Click check marks for each of the listed consistency rules that you want to apply (see [Table 8-3](#) on page 8-17 and [Table 8-4](#) on page 8-17).
- Step 3** Click **Run Rules**. This opens the Consistency Rules Result page. If violations were found, the page has the display columns indicated in [Table 8-5](#).

Table 8-5 Display Columns on the Consistency Rules Result Page

Column	Description
Violation	How the consistency was violated. Results include violation values such as duplicated or overlapped. If you click the violation value, the Consistency Rule Details page appears.
Primary Object Name	Shows a range of primary addresses or subnets.
Primary Object Type	Includes primary object types such as CCMIPRange and CCMSubnet.
Secondary Object Name	Shows a range of secondary addresses or subnets.
Secondary Object Type	Includes secondary object types such as CCMIPRange and CCMSubnet.