



CHAPTER 11

Configuring Event Action Rules

You can define different event action rules policies to apply to your virtual sensors. This chapter explains how to add event action rules policies and how to configure event action rules. It contains the following sections:

- [Understanding Policies, page 11-1](#)
- [Event Action Rules Components, page 11-2](#)
- [Configuring Event Action Rules Policies, page 11-9](#)
- [rules0 Pane, page 11-11](#)
- [Configuring Event Action Overrides, page 11-11](#)
- [Configuring Event Action Filters, page 11-14](#)
- [Configuring Target Value Rating, page 11-17](#)
- [Configuring OS Identifications, page 11-19](#)
- [Configuring Event Variables, page 11-24](#)
- [Configuring Risk Category, page 11-26](#)
- [Configuring General Settings, page 11-28](#)

Understanding Policies



Note

You cannot create event action rules policies for AIM-IPS and NME-IPS.

You can create multiple security policies and apply them to individual virtual sensors. A security policy is made up of a signature definition policy, an event action rules policy, and an anomaly detection policy. Cisco IPS 6.1 contains a default signature definition policy called sig0, a default event action rules policy called rules0, and a default anomaly detection policy called ad0. You can assign the default policies to a virtual sensor or you can create new policies.

The use of multiple security policies lets you create security policies based on different requirements and then apply these customized policies out per VLAN or physical interface.

Event Action Rules Components

This section describes the various components of event action rules, and contains the following topics:

- [Understanding Event Action Rules, page 11-2](#)
- [Calculating the Risk Rating, page 11-2](#)
- [Understanding Threat Rating, page 11-4](#)
- [Understanding Event Action Overrides, page 11-4](#)
- [Understanding Event Action Filters, page 11-4](#)
- [Event Action Summarization, page 11-5](#)
- [Event Action Aggregation, page 11-5](#)
- [Signature Event Action Processor, page 11-6](#)
- [Event Actions, page 11-7](#)

Understanding Event Action Rules

Event action rules are a group of settings you configure for the event action processing component of the sensor. These rules dictate the actions the sensor performs when an event occurs.

The event action processing component is responsible for the following functions:

- Calculating the risk rating
- Adding event action overrides
- Filtering event action
- Executing the resulting event action
- Summarizing and aggregating events
- Maintaining a list of denied attackers

**Note**

Rate limiting and blocking are not supported for IPv6 traffic. If a signature is configured with a block or rate limit event action and is triggered by IPv6 traffic, an alert is generated but the action is not carried out.

Calculating the Risk Rating

A risk rating is a value between 0 and 100 that represents a numerical quantification of the risk associated with a particular event on the network. The calculation takes into account the value of the network asset being attacked (for example, a particular server), so it is configured on a per-signature basis (attack severity rating and signature fidelity rating) and on a per-server basis (target value rating). The risk rating is calculated from several components, some of which are configured, some collected, and some derived.

**Note**

The risk rating is associated with alerts not signatures.

Risk ratings let you prioritize alerts that need your attention. These risk rating factors take into consideration the severity of the attack if it succeeds, the fidelity of the signature, and the overall value of the target host to you. The risk rating is reported in the `evIdsAlert`.

The following values are used to calculate the risk rating for a particular event:

- Signature fidelity rating (SFR)—A weight associated with how well this signature might perform in the absence of specific knowledge of the target. The signature fidelity rating is configured per signature and indicates how accurately the signature detects the event or condition it describes.

The signature fidelity rating is calculated by the signature author on a per-signature basis. The signature author defines a baseline confidence ranking for the accuracy of the signature in the absence of qualifying intelligence on the target. It represents the confidence that the detected behavior would produce the intended effect on the target platform if the packet under analysis were allowed to be delivered. For example, a signature that is written with very specific rules (specific regular expression) has a higher signature fidelity rating than a signature that is written with generic rules.



Note The signature fidelity rating does not indicate how bad the detected event may be.

- Attack severity rating (ASR)—A weight associated with the severity of a successful exploit of the vulnerability.

The attack severity rating is derived from the alert severity parameter (informational, low, medium, or high) of the signature. The attack severity rating is configured per signature and indicates how dangerous the event detected is.



Note The attack severity rating does not indicate how accurately the event is detected.

- Target value rating (TVR)—A weight associated with the perceived value of the target.

Target value rating is a user-configurable value (zero, low, medium, high, or mission critical) that identifies the importance of a network asset (through its IP address). You can develop a security policy that is more stringent for valuable corporate resources and looser for less important resources. For example, you could assign a target value rating to the company web server that is higher than the target value rating you assign to a desktop node. In this example, attacks against the company web server have a higher risk rating than attacks against the desktop node. Target value rating is configured in the Event Action Rules policy.

- Attack relevance rating (ARR)—A weight associated with the relevancy of the targeted OS.

The attack relevance rating is a derived value (relevant, unknown, or not relevant), which is determined at alert time. The relevant OSEs are configured per signature.

- Promiscuous delta (PD)—A weight associated with the promiscuous delta, which can be subtracted from the overall risk rating in promiscuous mode.

The promiscuous delta is in the range of 0 to 30 and is configured per signature.



Note If the trigger packet is not inline, the promiscuous delta is subtracted from the rating.

- Watch list rating (WLR)—A weight associated with the CSA MC watch list in the range of 0 to 100 (CSA MC only uses the range 0 to 35).

If the attacker for the alert is found on the watch list, the watch list rating for that attacker is added to the rating.

Figure 11-1 illustrates the risk rating formula:

Figure 11-1 Risk Rating Formula

$$RR = \frac{ASR * TVR * SFR}{10000} + ARR - PD + WLR$$

191016

Understanding Threat Rating

Threat rating is risk rating that has been lowered by event actions that have been taken. Nonlogging event actions have a threat rating adjustment. The largest threat rating from all the event actions taken is subtracted from the risk rating.

The event actions have the following threat ratings:

- Deny attacker inline—45
- Deny attacker victim pair inline—40
- Deny attacker service pair inline—40
- Deny connection inline—35
- Deny packet inline—35
- Modify packet inline—35
- Request block host—20
- Request block connection—20
- Reset TCP connection—20
- Request rate limit—20

Understanding Event Action Overrides

You can add an event action override to change the actions associated with an event based on the risk rating of that event. Event action overrides are a way to add event actions globally without having to configure each signature individually. Each event action has an associated risk rating range. If a signature event occurs and the risk rating for that event falls within the range for an event action, that action is added to the event. For example, if you want any event with a risk rating of 85 or more to generate an SNMP trap, you can set the risk rating range for Request SNMP Trap to 85-100. If you do not want to use action overrides, you can disable the entire event action override component.

Understanding Event Action Filters

Event action filters are processed as an ordered list and you can move filters up or down in the list.

Filters let the sensor perform certain actions in response to the event without requiring the sensor to perform all actions or remove the entire event. Filters work by removing actions from an event. A filter that removes all actions from an event effectively consumes the event.

**Note**

When filtering sweep signatures, we recommend that you do not filter the destination addresses. If there are multiple destination addresses, only the last address is used for matching the filter.

Event Action Summarization

Summarization decreases the volume of alerts sent out from the sensor by providing basic aggregation of events into a single alert. Special parameters are specified for each signature and they influence the handling of the alerts. Each signature is created with defaults that reflect a preferred normal behavior. However, you can tune each signature to change this default behavior within the constraints for each engine type.

The nonalert-generating actions (deny, block, TCP reset) go through the filters for each signature event unsummarized. The alert-generating actions are not performed on these summarized alerts; instead the actions are applied to the one summary alert and then put through the filters.

If you select one of the other alert-generating actions and do not have it filtered out, the alert is created even if you do not select Produce Alert. To prevent alerts from being created, you must have all alert-generating actions filtered out.

Summarization and event actions are processed after the Meta engine has processed the component events. This lets the sensor watch for suspicious activity transpiring over a series of events.

Event Action Aggregation

Basic aggregation provides two operating modes. The simple mode involves configuring a threshold number of hits for a signature that must be met before the alert is sent. A more advanced mode is timed-interval counting. In this mode, the sensor tracks the number of hits per second and only sends alerts when that threshold is met. In this example, a hit is a term used to describe an event, which is basically an alert, but it is not sent out of the sensor as an alert until the threshold number of hits has been exceeded.

You can choose from the following summarization options:

- **Fire All**—Fire All mode fires an alert each time the signature is triggered. If the threshold is set for summarization, alerts are fired for each execution until summarization occurs. After summarization starts only one alert every summary interval fires for each address set. Alerts for other address sets are either all seen or separately summarized. The signature reverts to Fire All mode after a period of no alerts for that signature.
- **Summary**—Summary mode fires an alert the first time a signature is triggered, and then additional alerts for that signature are summarized for the duration of the summary interval. Only one alert every summary interval should fire for each address set. If the global summary threshold is reached, the signature goes into Global Summarization mode.
- **Global Summarization**—Global Summarization mode fires an alert for every summary interval. Signatures can be preconfigured for global summarization.
- **Fire Once**—Fire Once mode fires an alert for each address set. You can upgrade this mode to Global Summarization mode.

Signature Event Action Processor

The Signature Event Action Processor coordinates the data flow from the signature event in the alarm channel to processing through the Signature Event Action Override, the Signature Event Action Filter, and the Signature Event Action Handler. It consists of the following components:

- Alarm channel
The unit that represents the area to communicate signature events from the SensorApp inspection path to signature event handling.
- Signature Event Action Override
Adds actions based on the risk rating value. The Signature Event Action Override applies to all signatures that fall in the range of the configured risk rating threshold. Each Signature Event Action Override is independent and has a separate configuration value for each action type.
- Signature Event Action Filter
Subtracts actions based on the signature ID, addresses, and risk rating of the signature event. The input to the Signature Event Action Filter is the signature event with actions possibly added by the Signature Event Action Override.




Note The Signature Event Action Filter can only subtract actions, it cannot add new actions.

The following parameters apply to the Signature Event Action Filter:

- Signature ID
- Subsignature ID
- Attacker address
- Attacker port
- Victim address
- Victim port
- Risk rating threshold range
- Actions to subtract
- Sequence identifier (optional)
- Stop-or-continue bit
- Enable action filter line bit
- Victim OS relevance or OS relevance
- Signature Event Action Handler
Performs the requested actions. The output from the Signature Event Action Handler is the actions being performed and possibly an evIdsAlert written to the Event Store.

[Figure 11-2 on page 11-7](#) illustrates the logical flow of the signature event through the Signature Event Action Processor and the operations performed on the action for this event. It starts with the signature event with configured action received in the alarm channel and flows top to bottom as the signature event passes through the functional components of the Signature Event Action Processor.

Figure 11-2 Signature Event Through the Signature Event Action Processor

132188

For More Information

For more information on calculating the risk rating, see [Calculating the Risk Rating, page 11-2](#).

Event Actions

Cisco IPS 6.1 has the following event actions:

- Alert and Log Actions
 - Product Alert—Writes the event to the Event Store as an alert.

**Note**

The Product Alert action is not automatic when you enable alerts for a signature. To have an alert created in the Event Store, you must select Product Alert. If you add a second action, you must include Product Alert if you want an alert sent to the Event Store. Also, every time you configure the event actions, a new list is created and it replaces the old list. Make sure you include all the event actions you need for each signature.

- Produce Verbose Alert—Includes an encoded dump of the offending packet in the alert. This action causes an alert to be written to the Event Store, even if Produce Alert is not selected.
- Log Attacker Packets—Starts IP logging on packets that contain the attacker address and sends an alert. This action causes an alert to be written to the Event Store, even if Produce Alert is not selected.
- Log Victim Packets—Starts IP Logging on packets that contain the victim address and sends an alert. This action causes an alert to be written to the Event Store, even if Produce Alert is not selected.
- Log Attacker/Victim Pair Packets—Starts IP Logging on packets that contain the attacker/victim address pair. This action causes an alert to be written to the Event Store, even if Produce Alert is not selected.
- Request SNMP Trap—Sends a request to the Notification Application component of the sensor to perform SNMP notification. This action causes an alert to be written to the Event Store, even if Produce Alert is not selected. You must have SNMP configured on the sensor to implement this action.
- Deny Actions
 - Deny Packet Inline—(Inline only) Terminates the packet.



Note You cannot delete the event action override for Deny Packet Inline because it is protected. If you do not want to use that override, disable it.

- Deny Connection Inline—(Inline only) Terminates the current packet and future packets on this TCP flow.
- Deny Attacker Victim Pair Inline—(Inline only) Does not transmit this packet and future packets on the attacker/victim address pair for a specified period of time.



Note For deny actions, to set the specified period of time and maximum number of denied attackers, choose **Configuration > sensor_name > Policies > Event Action Rules > rules0 > General Settings**.

- Deny Attacker Service Pair Inline—(Inline only) Does not transmit this packet and future packets on the attacker address victim port pair for a specified period of time.
- Deny Attacker Inline—(Inline only) Terminates the current packet and future packets from this attacker address for a specified period of time.

The sensor maintains a list of attackers being denied by the system. To remove an entry from the denied attacker list, you can view the list of attackers and clear the entire list, or you can wait for the timer to expire. The timer is a sliding timer for each entry. Therefore, if attacker A is being denied, but issues another attack, the timer for attacker A is reset and attacker A remains in the denied attacker list until the timer expires. If the denied attacker list is at capacity and cannot add a new entry, the packet is still denied.



Note This is the most severe of the deny actions. It denies current and future packets from a single attacker address. To clear all denied attacker entries, choose **Configuration > sensor_name > Sensor Monitoring > Time-Based Actions > Denied Attackers > Clear List**, which permits the addresses back on the network.

- Modify Packet Inline— Modifies packet data to remove ambiguity about what the end point might do with the packet.



Note Modify Packet Inline is not an option for Add Event Action Filter or Add Event Action Override.

- Other Actions

- Request Block Connection—Sends a request to ARC to block this connection. You must have blocking devices configured to implement this action.
- Request Block Host—Sends a request to ARC to block this attacker host. You must have blocking devices configured to implement this action.



Note For block actions, to set the duration of the block, choose **Configuration > sensor_name > Policies > Event Action Rules > rules0 > General Settings**.

- Request Rate Limit—Sends a rate limit request to ARC to perform rate limiting. You must have rate limiting devices configured to implement this action.



Note Request Rate Limit applies to a select set of signatures.

- Reset TCP Connection—Sends TCP resets to hijack and terminate the TCP flow. Reset TCP Connection only works on TCP signatures that analyze a single connection. It does not work for sweeps or floods.

For More Information

- For the procedure for configuring the general settings, see [Configuring General Settings, page 11-28](#).
- For the procedure for configuring SNMP, see [Chapter 15, “Configuring SNMP.”](#)
- For the procedure for configuring denied attackers, see [Configuring and Monitoring Denied Attackers, page 18-4](#).

Configuring Event Action Rules Policies

This section describes how to create event action rules policies, and contains the following topics:

- [Event Action Rules Pane, page 11-10](#)
- [Event Action rules Pane Field Definitions, page 11-10](#)
- [Add and Clone Policy Dialog Boxes Field Definitions, page 11-10](#)
- [Adding, Cloning, and Deleting Event Action Rules Policies, page 11-10](#)

Event Action Rules Pane


Note

You must be administrator or operator to add, clone, or delete event action rules policies.


Note

In the Event Action Rules pane, you can create event action rules policies and configure them. You can also configure event action rules in the lower half of the IPS Policies pane: **Configuration > sensor_name > Policies > IPS Policies**.

You can define different event action rules policies to apply to your virtual sensors.

In the Event Action Rules pane, you can add, clone, or delete an event action rules policy. The default event action rules policy is rules0. When you add a policy, a control transaction is sent to the sensor to create the policy instance. If the response is successful, the new policy instance is added under Event Action Rules. If the control transaction fails, for example because of resource limitations, an error message appears.

If your platform does not support virtual policies, this means you can only have one instance for each component and you cannot create new ones or delete the existing one. In this case, the Add, Clone, and Delete buttons are disabled.


Caution

AIM-IPS and NME-IPS do not support sensor virtualization and therefore do not support multiple policies.

Event Action rules Pane Field Definitions

The following fields are found in the Event Action Rules pane:

- Policy Name—Identifies the name of this event action rules policy.
- Assigned Virtual Sensor—Identifies the virtual sensor for which this event action rules policy is assigned.

Add and Clone Policy Dialog Boxes Field Definitions

The following field is found in the Add and Clone Policy dialog boxes:

- Policy Name—Lets you create a unique name for the new policy.

Adding, Cloning, and Deleting Event Action Rules Policies

To add, clone, or delete an event action rules policy, follow these steps:

-
- Step 1** Log in to IME using an account with administrator or operator privileges.
 - Step 2** Choose **Configuration > sensor_name > Policies > Event Action Rules**, and then click **Add**.
 - Step 3** In the Policy Name field, enter a name for the event action rules policy.



Tip To discard your changes and close the dialog box, click **Cancel**.

Step 4 Click **OK**.

The event action rules policy appears in the list in the Event Action Rules pane.

Step 5 To clone an existing event action rules policy, select it in the list, and then click **Clone**.

The Clone Policy dialog box appears with “_copy” appended to the existing event action rules policy name.

Step 6 In the Policy Name field, enter a unique name.



Tip To discard your changes and close the dialog box, click **Cancel**.

Step 7 Click **OK**.

The cloned event action rules policy appears in the list in the Event Action Rules pane.

Step 8 To remove an event action rules policy, select it, and then click **Delete**.

The Delete Policy dialog box appears asking if you are sure you want to delete this policy permanently.



Caution You cannot delete the default event action rules policy, rules0.

Step 9 Click **Yes**.

The event action rules policy no longer appears in the list in the Event Action Rules pane.

rules0 Pane

The Event Action Rules (rules0) pane contains seven tabs on which you can configure event action overrides, event action filters, target value ratings, OS identifications, event variables, risk categories, and general settings for the event action rules policies that you added in the **Configuration > sensor_name > Policies > Event Action Rules** pane.

You can also configure event action rules in the lower half of the **Configuration > sensor_name > Policies > IPS Policies** pane.

Configuring Event Action Overrides

This section describes how to configure event action overrides, and contains the following topics:

- [Event Action Overrides Tab, page 11-12](#)
- [Event Action Overrides Tab Field Definitions, page 11-12](#)
- [Add and Edit Event Action Override Dialog Boxes Field Definitions, page 11-12](#)
- [Adding, Editing, Deleting, Enabling, and Disabling Event Action Overrides, page 11-12](#)

Event Action Overrides Tab



Note

You must be administrator or operator to add or edit event action overrides.

On the Event Action Overrides tab, you can add an event action override to change the actions associated with an event based on specific details about that event.

Event Action Overrides Tab Field Definitions

The following fields are found on the Event Action Overrides tab:

- **Use Event Action Overrides**—If checked, lets you use any event action override that is enabled.
- **Risk Rating**—Indicates the risk rating level that should be used to trigger this event action override. If an event occurs with a risk rating that matches this level, the event action is added to this event.
- **Actions to Add**—Specifies the event action that will be added to an event if the conditions of this event action override are satisfied.
- **Enabled**—Indicates whether or not the override is enabled.

Add and Edit Event Action Override Dialog Boxes Field Definitions

The following fields are found in the Add and Edit Event Action Override dialog boxes:

- **Risk Rating**—Indicates the risk rating range, either low, medium, or high risk, that should be used to trigger this event action override. If an event occurs with a risk rating that corresponds to the risk you configure, the event action is added to this event.
- **Available Actions to Add**—Specifies the event action that will be added to an event if the conditions of this event action override are satisfied.
- **Enabled**—Check the check box to enable the action when the event action override is triggered.

Adding, Editing, Deleting, Enabling, and Disabling Event Action Overrides

To add, edit, delete, enable, and disable event action overrides, follow these steps:

-
- Step 1** Log in to IME using an account with administrator or operator privileges.
 - Step 2** Choose **Configuration** > *sensor_name* > **Policies** > **Event Action Rules** > **rules0** > **Event Action Overrides**.
 - Step 3** To create a event action override, click **Add**.
 - Step 4** From the Risk Rating drop-down menu, assign a risk rating range to this network asset.
 - Step 5** From the Available Actions to Add list, check the event actions this event action override will correspond to.
 - Step 6** Check the Enabled check boxes for the actions you want to enable in the override.



Tip To discard your changes and close the Add Event Action Override dialog box, click **Cancel**.

Step 7 Click **OK**.

The new event action override now appears in the list on the Event Action Overrides tab.

Step 8 Check the **Use Event Action Overrides** check box.



Note You must check the **Use Event Action Overrides** check box on the Event Action Overrides tab or none of the event action overrides will be enabled regardless of the value you set.

Step 9 To edit an existing event action override, select it in the list, and then click **Edit**.

Make any changes needed.



Tip To discard your changes and close the Edit Event Action Override dialog box, click **Cancel**.

Step 10 Click **OK**.

The edited event action override now appears in the list on the Event Action Overrides tab.

Step 11 Check the **Use Event Action Overrides** check box.



Note You must check the **Use Event Action Overrides** check box on the Event Action Overrides tab or none of the event action overrides will be enabled regardless of the value you set.

Step 12 To delete an event action override, select it in the list, and then click **Delete**.

The event action override no longer appears in the list on the Event Action Overrides tab.



Note You cannot delete the event action override for Deny Packet Inline because it is protected. If you do not want to use that override, disable it.

Step 13 To enable or disable an event action override, select it in the list, and then click **Edit**.

Step 14 To disable an event action override, clear the **Enabled** check boxes for any event actions that you have assigned to that event action override. To enable an event action override, check any **Enabled** check boxes for any event actions that you have assigned to that event action override.



Tip To discard your changes, click **Reset**.

Step 15 Click **Apply** to apply your changes and save the revised configuration.

Configuring Event Action Filters

This section describes how to configure event action filters, and contains the following topics:

- [Event Action Filters Tab, page 11-14](#)
- [Event Action Filters Tab Field Definitions, page 11-14](#)
- [Add and Edit Event Action Filter Dialog Boxes Field Definitions, page 11-15](#)
- [Adding, Editing, Deleting, Enabling, Disabling, and Moving Event Action Filters, page 11-15](#)

Event Action Filters Tab

**Note**

You must be administrator or operator to add, edit, enable, disable, or delete event action filters.

You can configure event action filters to remove specific actions from an event or to discard an entire event and prevent further processing by the sensor. You can use the variables that you defined on the Event Variables pane to group addresses for your filters.

**Note**

You must preface the variable with a dollar sign (\$) to indicate that you are using a variable rather than a string. Otherwise, you receive the `Bad source and destination error`.

Event Action Filters Tab Field Definitions

The following fields are found on the Event Action Filters tab:

- **Name**—Lets you name the filter you are adding. You need to name your filters so that you can move them around in the list and move them to the inactive list if needed.
- **Enabled**—Indicates whether or not this filter is enabled.
- **Sig ID**—Identifies the unique numerical value assigned to this signature. This value lets the sensor identify a particular signature. You can also enter a range of signatures.
- **SubSig ID**—Identifies the unique numerical value assigned to this subsignature. The subSig ID identifies a more granular version of a broad signature. You can also enter a range of subSig IDs.
- **Attacker (address/port)**—Identifies the IP address and/or port of the host that sent the offending packet. You can also enter a range of addresses.
- **Victim (address/port)**—Identifies the IP address and/or port used by the attacker host. This is the port from where the offending packet originated. You can also enter a range of ports.
- **Risk Rating**—Indicates the risk rating range between 0 and 100 that should be used to trigger this event action filter. If an event occurs with a risk rating that falls within the minimum-maximum range you configure here, the event is processed against the rules of this event filter.
- **Actions to Subtract**—Indicates the actions that should be removed from the event, should the conditions of the event meet the criteria of the event action filter.

Add and Edit Event Action Filter Dialog Boxes Field Definitions

The following fields are found in the Add and Edit Event Action Filters dialog boxes:

- **Name**—Lets you name the filter you are adding. You need to name your filters so that you can move them around in the list and move them to the inactive list if needed.
- **Enabled**—Lets you enable this filter.
- **Signature ID**—Identifies the unique numerical value assigned to this signature. This value lets the sensor identify a particular signature. You can also enter a range of signatures.
- **Subsignature ID**—Identifies the unique numerical value assigned to this subsignature. The subsignature ID identifies a more granular version of a broad signature. You can also enter a range of subsignature IDs.
- **Attacker Address**—Identifies the IP address of the host that sent the offending packet. You can also enter a range of addresses.
- **Attacker Port**—Identifies the port used by the attacker host. This is the port from where the offending packet originated. You can also enter a range of ports.
- **Victim Address**—Identifies the IP address of the host being attacked (the recipient of the offending packet). You can also enter a range of addresses.
- **Victim Port**—Identifies the port through which the offending packet was received. You can also enter a range of ports.
- **Risk Rating**—Indicates the risk rating range between 0 and 100 that should be used to trigger this event action filter. If an event occurs with a risk rating that falls within the minimum-maximum range you configure here, the event is processed against the rules of this event filter.
- **Actions to Subtract**—Opens the Edit Actions dialog box and lets you choose the actions that should be removed from the event, should the conditions of the event meet the criteria of the event action filter.
- **Active**—Lets you add the filter to the filter list so that it takes effect on filtering events.
- **OS Relevance**—Lets you filter out events where the attack is not relevant to the victim OS.
- **Deny Percentage**—Determines the percentage of packets to deny for deny attacker features. The valid range is 0 to 100. The default is 100 percent.
- **Stop on Match**—Determines whether or not this event will be processed against remaining filters in the event action filters list.

If set to No, the remaining filters are processed for a match until a Stop flag is encountered.

If set to Yes, no further processing is done. The actions specified by this filter are removed and the remaining actions are performed.
- **Comments**—Displays the user comments associated with this filter.

Adding, Editing, Deleting, Enabling, Disabling, and Moving Event Action Filters

To add, edit, delete, enable, disable, and move event action filters, follow these steps:

-
- Step 1** Log in to IME using an account with administrator or operator privileges.
 - Step 2** Choose **Configuration > sensor_name > Policies > Event Action Rules > rules0 > Event Action Filters**, and then click **Add**.

- Step 3** In the Name field, enter a name for the event action filter.
A default name is supplied, but you can change it to a more meaningful name.
- Step 4** In the Enabled field, click the **Yes** radio button to enable the filter.
- Step 5** In the Signature ID field, enter the signature IDs of all signatures to which this filter should be applied.
You can use a list (2001, 2004), or a range (2001–2004) or one of the SIG variables if you defined them on the Event Variables tab. Preface the variable with \$.
- Step 6** In the SubSignature ID field, enter the subsignature IDs of the subsignatures to which this filter should be applied.
- Step 7** In the Attacker Address field, enter the IP address of the source host.
You can use one of the variables if you defined them on the Event Variables tab. Preface the variable with \$. You can also enter a range of addresses (for example, 0.0.0.0-255.255.255.255).
- Step 8** In the Attacker Port field, enter the port number used by the attacker to send the offending packet.
- Step 9** In the Victim Address field, enter the IP address of the recipient host.
You can use one of the variables if you defined them on the Event Variables tab. Preface the variable with \$. You can also enter a range of addresses (for example, 0.0.0.0-255.255.255.255).
- Step 10** In the Victim Port field, enter the port number used by the victim host to receive the offending packet.
- Step 11** In the Risk Rating field, enter a risk rating range for this filter.
If the risk rating for an event falls within the range you specify, the event is processed against the criteria of this filter.
- Step 12** In the Actions to Subtract field, click the note icon to open the Edit Actions dialog box.
- Step 13** Check the check boxes of the actions you want this filter to remove from the event.

**Tip**

To choose more than one event action in the list, hold down the **Ctrl** key.

- Step 14** In the Active field, click the **Yes** radio button to add this filter to the list so that it takes effect on filtering events.
- Step 15** In the OS Relevance drop-down list, choose whether you want to know if the alert is relevant to the OS that has been identified for the victim.
- Step 16** In the Deny Percentage field, enter the percentage of packets to deny for deny attacker features.
The default is 100 percent.
- Step 17** In the Stop on Match field, click one of the following radio buttons:
- a. **Yes**—If you want the Event Action Filters component to stop processing after the actions of this particular filter have been removed.
Any remaining filters will not be processed; therefore, no additional actions can be removed from the event.
 - b. **No**—If you want to continue processing additional filters.
- Step 18** In the Comments field, enter any comments that you want to store with this filter, such as the purpose of this filter or why you have configured this filter in a particular way.

**Tip**

To discard your changes and close the Add Event Action Filter dialog box, click **Cancel**.

Step 19 Click **OK**.

The new event action filter now appears in the list on the Event Action Filters tab.

Step 20 To edit an existing event action filter, select it in the list, and then click **Edit**.

Step 21 Make any changes needed.



Tip To discard your changes and close the Edit Event Action Filter dialog box, click **Cancel**.

Step 22 Click **OK**.

The edited event action filter now appears in the list on the Event Action Filters tab.

Step 23 To delete an event action filter, select it in the list, and then click **Delete**.

The event action filter no longer appears in the list on the Event Action Filters tab.

Step 24 To move an event action filter up or down in the list, select it, and then click the **Move Up** or **Move Down** arrow icons.



Tip To discard your changes, click **Reset**.

Step 25 Click **Apply** to apply your changes and save the revised configuration.

Configuring Target Value Rating

This section describes how to configure the target value rating, and contains the following topics:

- [Target Value Rating Tab, page 11-17](#)
- [Target Value Rating Tab Field Definitions, page 11-18](#)
- [Add and Edit Target Value Rating Dialog Boxes Field Definitions, page 11-18](#)
- [Adding, Editing, and Deleting Target Value Ratings, page 11-18](#)

Target Value Rating Tab



Note You must be administrator or operator to add, edit, or delete target value ratings.

You can assign a target value rating to your network assets. The target value rating is one of the factors used to calculate the risk rating value for each alert. You can assign different target value ratings to different targets. Events with a higher risk rating trigger more severe signature event actions.

Target Value Rating Tab Field Definitions

The following fields are found on the Target Value Rating tab:

- Target Value Rating (TVR)—Identifies the value assigned to this network asset. The value can be High, Low, Medium, Mission Critical, or No Value.
- Target IP Address—Identifies the IP address of the network asset you want to prioritize with a target value rating.

Add and Edit Target Value Rating Dialog Boxes Field Definitions

The following fields are found in the Add and Edit Target Value Rating dialog boxes:

- Target Value Rating (TVR)—Lets you assign a value to this network asset. The value can be High, Low, Medium, Mission Critical, or No Value.
- Target IP Address(es)—Identifies the IP address of the network asset you want to prioritize with a target value rating.

Adding, Editing, and Deleting Target Value Ratings

To add, edit, and delete the target value rating for network assets, follow these steps:

-
- Step 1** Log in to IME using an account with administrator or operator privileges.
- Step 2** Choose **Configuration > sensor_name > Policies > Event Action Rules > rules0 > Target Value Rating**, and then click **Add**.
- Step 3** To assign a target value rating to a new group of assets, follow these steps:
- From the Target Value Rating (TVR) drop-down list, choose a rating.
The values are High, Low, Medium, Mission Critical, or No Value.
 - In the Target IP Address(es) field, enter the IP address of the network asset.
To enter a range of IP addresses, enter the lowest address followed by a hyphen and then the highest address in the range. For example: 10.10.2.1-10.10.2.30.



Tip To discard your changes and close the Add Target Value Rating dialog box, click **Cancel**.

- Step 4** Click **OK**.
The new target value rating for the new asset appears in the list on the Target Value Rating tab.
- Step 5** To edit an existing target value rating, select it in the list, and then click **Edit**.
- Step 6** Make any changes needed.



Tip To discard your changes and close the Edit Target Value Rating dialog box, click **Cancel**.

- Step 7** Click **OK**.
The edited network asset now appears in the list on the Target Value Rating tab.

- Step 8** To delete a network asset, select in the list, and then click **Delete**.
The network asset no longer appears in the list on the Target Value Rating tab.



Tip To discard your changes, click **Reset**.

- Step 9** Click **Apply** to apply your changes and save the revised configuration.

Configuring OS Identifications

This section describes how to configure OS identifications, and contains the following topics:

- [OS Identifications Tab, page 11-19](#)
- [Understanding Passive OS Fingerprinting, page 11-20](#)
- [Configuring Passive OS Fingerprinting, page 11-21](#)
- [OS Identifications Tab Field Definitions, page 11-21](#)
- [Add and Edit Configured OS Map Dialog Boxes Field Definitions, page 11-22](#)
- [Adding, Editing, Deleting, and Moving Configured OS Maps, page 11-22](#)

OS Identifications Tab



Note

You must be administrator or operator to add, edit, and delete configured OS maps.

Use the OS Identifications tab to configure OS host mappings, which take precedence over learned OS mappings. On the OS Identifications tab you can add, edit, and delete configured OS maps. You can move them up and down in the list to change the order in which the sensor computes the Attack Relevance Rating and Risk Rating for that particular IP address and OS type combination.

You can also move them up and down in the list to change the order in which the sensor resolves the OS associated with a particular IP address. Configured OS mappings allow for ranges, so for network 192.168.1.0/24 an administrator might define the following ([Table 11-1](#)):

Table 11-1 Example Configured OS Mapping

IP Address Range Set	OS
192.168.1.1	IOS
192.168.1.2-192.168.1.10,192.168.1.25	UNIX
192.168.1.1-192.168.1.255	Windows

More specific mappings should be at the beginning of the list. Overlap in the IP address range sets is allowed, but the entry closest to the beginning of the list takes precedence.

Understanding Passive OS Fingerprinting

Passive OS fingerprinting lets the sensor determine the OS that hosts are running. The sensor analyzes network traffic between hosts and stores the OS of these hosts with their IP addresses. The sensor inspects TCP SYN and SYNACK packets exchanged on the network to determine the OS type.

The sensor then uses the OS of the target host OS to determine the relevance of the attack to the victim by computing the attack relevance rating component of the risk rating. Based on the relevance of the attack, the sensor may alter the risk rating of the alert for the attack and/or the sensor may filter the alert for the attack. You can then use the risk rating to reduce the number of false positive alerts (a benefit in IDS mode) or definitively drop suspicious packets (a benefit in IPS mode). Passive OS fingerprinting also enhances the alert output by reporting the victim OS, the source of the OS identification, and the relevance to the victim OS in the alert.

Passive OS fingerprinting consists of three components:

- Passive OS learning

Passive OS learning occurs as the sensor observes traffic on the network. Based on the characteristics of TCP SYN and SYNACK packets, the sensor makes a determination of the OS running on the host of the source IP address.

- User-configurable OS identification

You can configure OS host mappings, which take precedence over learned OS mappings.

- Computation of attack relevance rating and risk rating

The sensor uses OS information to determine the relevance of the attack signature to the targeted host. The attack relevance is the attack relevance rating component of the risk rating value for the attack alert. The sensor uses the OS type reported in the host posture information imported from the CSA MC to compute the attack relevance rating.

There are three sources of OS information. The sensor ranks the sources of OS information in the following order:

1. Configured OS mappings—OS mappings you enter.

Configured OS mappings reside in the Event Action Rules policy and can apply to one or many virtual sensors.

**Caution**

You can specify multiple operating systems for the same IP address. The last one in the list is the operating system that is matched.

2. Imported OS mappings—OS mappings imported from an external data source.

Imported OS mappings are global and apply to all virtual sensors.



Note Currently CSA MC is the only external data source.

3. Learned OS mappings—OS mappings observed by the sensor through the fingerprinting of TCP packets with the SYN control bit set.

Learned OS mappings are local to the virtual sensor that sees the traffic.

When the sensor needs to determine the OS for a target IP address, it consults the configured OS mappings. If the target IP address is not in the configured OS mappings, the sensor looks in the imported OS mappings. If the target IP address is not in the imported OS mappings, the sensor looks in the learned OS mappings. If it cannot find it there, the sensor treats the OS of the target IP address as unknown.

**Note**

Passive OS fingerprinting is enabled by default and the IPS contains a default vulnerable OS list for each signature.

Configuring Passive OS Fingerprinting

You do not have to configure passive OS fingerprinting for it to function. IPS provides a default vulnerable OS list for each signature and passive analysis is enabled by default.

You can configure the following aspects of passive OS fingerprinting:

- Define OS mappings

We recommend configuring OS mappings to define the identity of the OS running on critical systems. It is best to configure OS mappings when the OS and IP address of the critical systems are unlikely to change.
- Limit the attack relevance rating calculation to a specific IP address range

This limits the attack relevance rating calculations to IP addresses on the protected network.
- Import OS mappings

Importing OS mappings provides a mechanism for accelerating the learning rate and fidelity of the OS identifications made through passive analysis. If you have an external product interface, such as the CSA MC, you can import OS identifications from it.
- Define event action rules filters using the OS relevancy value of the target

This provides a way to filter alerts solely on OS relevancy.
- Disable passive analysis

Stops the sensor from learning new OS mappings.
- Edit signature vulnerable OS lists

The vulnerable OS list specifies what OS types are vulnerable to each signature. The default, `general-os`, applies to all signatures that do not specify a vulnerable OS list.

OS Identifications Tab Field Definitions

The following fields are found on the OS Identifications tab:

- Enable passive OS fingerprinting analysis—When checked, lets the sensor perform passive OS analysis.
- Restrict OS mapping and ARR to these IP addresses—Lets you configure the mapping of OS type to a specific IP address and have the sensor calculate the attack relevance rating for that IP address.
- Configured OS Map—Displays the attributes of the configured OS map.
 - Name—The Name you give the configured OS map.
 - Active—Whether this configured OS map is active or inactive.
 - IP Address—The IP address of this configured OS map.
 - OS Type—The OS type of this configured OS map.

Add and Edit Configured OS Map Dialog Boxes Field Definitions

The following fields are found in the Add and Edit Configured OS Map dialog boxes:

- Name—Lets you name this configured OS map.
- Active—Lets you choose to have the configured OS map active or inactive.
- IP Address—Lets you enter the IP address associated with this configured OS map.

The IP address for configured OS mappings (and *only* configured OS mappings) can be a set of IP addresses and IP address ranges. The following are all valid IP address values for configured OS mappings:

- 10.1.1.1,10.1.1.2,10.1.1.15
 - 10.1.2.1
 - 10.1.1.1-10.2.1.1,10.3.1.1
 - 10.1.1.1-10.1.1.5
- OS Type—Lets you choose one of the following OS Types to associate with the IP address:
 - AIX
 - BSD
 - General OS
 - HP UX
 - IOS
 - IRIX
 - Linux
 - Mac OS
 - Netware
 - Other
 - Solaris
 - UNIX
 - Unknown OS
 - Win NT
 - Windows
 - Windows NT/2K/XP

Adding, Editing, Deleting, and Moving Configured OS Maps

To add, edit, delete, and move configured OS maps, follow these steps:

-
- Step 1** Log in to IME using an account with administrator or operator privileges.
 - Step 2** Choose **Configuration > sensor_name > Policies > Event Action Rules > rules0 > OS Identifications**, and then click **Add**.
 - Step 3** In the Name field, enter a name for the configured OS map.

Step 4 In the Active field, click the **Yes** radio button to add this configured OS map to the list so that it takes effect.

Step 5 In the IP Address field, enter the IP address of the host that you are mapping to an OS.
For example, use this format, 10.10.5.5,10.10.2.1-10.10.2.30.

Step 6 From the OS Type drop-down list, choose the OS that will be mapped to the IP address.



Tip To discard your changes and close the Add Configured OS Map dialog box, click **Cancel**.

Step 7 Click **OK**.

The new configured OS map now appears in the list on the OS Identifications tab.

Step 8 Check the **Enable passive OS fingerprinting analysis** check box.



Note You must check the **Enable passive OS fingerprinting analysis** check box on the OS Identifications tab or none of the configured OS maps will be enabled regardless of the value you set in the Add Configured OS Map dialog box.

Step 9 To edit a configured OS map, select it in the list, and then click **Edit**.

Step 10 Make any changes needed.



Tip To discard your changes and close the Edit Configured OS Map dialog box, click **Cancel**.

Step 11 Click **OK**.

The edited configured OS map now appears in the list on the OS Identifications tab.

Step 12 Check the **Enable passive OS fingerprinting analysis** check box.



Note You must check the **Enable passive OS fingerprinting analysis** check box on the OS Identifications tab or none of the configured OS maps will be enabled regardless of the value you set in the Edit Configured OS Map dialog box.

Step 13 To delete a configured OS map, select it in the list, and then click **Delete**.

The configured OS map no longer appears in the list on the OS Identifications tab.

Step 14 To move a configured OS map up or down in the list, select it, and then click the **Move Up** or **Move Down** arrows.



Tip To discard your changes, click **Reset**.

Step 15 Click **Apply** to apply your changes and save the revised configuration.

Configuring Event Variables

This section describes how to configure event variables, and contains the following topics:

- [Event Variables Tab, page 11-24](#)
- [Event Variables Tab Field Definitions, page 11-24](#)
- [Add and Edit Event Variable Dialog Boxes Field Definitions, page 11-25](#)
- [Adding, Editing, and Deleting Event Variables, page 11-25](#)

Event Variables Tab

**Note**

You must be administrator or operator to add, edit, or delete event variables.

You can create event variables and then use those variables in event action filters. When you want to use the same value within multiple filters, use a variable. When you change the value of the variable, any filter that uses that variable is updated with the new value.

**Note**

You must preface the variable with a dollar (\$) sign to indicate that you are using a variable rather than a string.

Some variables cannot be deleted because they are necessary to the signature system. If a variable is protected, you cannot select it to edit it. You receive an error message if you try to delete protected variables. You can edit only one variable at a time.

When configuring IP addresses, specify the full IP address or ranges or set of ranges. For example:

- 10.89.10.10-10.89.10.23
- 10.90.1.1
- 192.56.10.1-192.56.10.255
- 10.1.1.1-10.2.255.255, 10.89.10.10-10.89.10.23

**Timesaver**

For example, if you have an IP address space that applies to your engineering group and there are no Windows systems in that group, and you are not worried about any Windows-based attacks to that group, you could set up a variable to be the IP address space of the engineering group. You could then use this variable to configure a filter that would ignore all Windows-based attacks for this group.

Event Variables Tab Field Definitions

The following fields are found on the Event Variables tab:

- **Name**—Lets you assign a name to this variable.
- **Type**—Identifies the variable as an address.
- **Value**—Lets you add the value(s) represented by this variable.

Add and Edit Event Variable Dialog Boxes Field Definitions

The following fields are found in the Add and Edit Event Variable dialog boxes:

- Name—Lets you assign a name to this variable.
- Type—Identifies the variable as an address.



Note This is the only available event variable in Cisco IPS 6.1.

- Value—Lets you add the value(s) represented by this variable.

Adding, Editing, and Deleting Event Variables

To add, edit, and delete event variables, follow these steps:

Step 1 Log in to IME using an account with administrator or operator privileges.

Step 2 Choose **Configuration > sensor_name > Policies > Event Action Rules > rules0 > Event Variables**, and then click **Add**.

Step 3 In the Name field, enter a name for this variable.



Note A valid name can only contain numbers or letters. You can also use a hyphen (-) or an underscore (_).

Step 4 In the Value field, enter the values for this variable.

Specify the full IP address or ranges or set of ranges. For example:

- 10.89.10.10-10.89.10.23
- 10.90.1.1
- 192.56.10.1-192.56.10.255



Note You can use commas as delimiters. Make sure there are no trailing spaces after the comma. Otherwise, you receive a `validation failed` error.



Tip To discard your changes and close the Add Event Variable dialog box, click **Cancel**.

Step 5 Click **OK**.

The new variable appears in the list on the Event Variables tab.

Step 6 To edit an existing variable, select it in the list, and then click **Edit**.

Step 7 Make any changes needed.



Tip To discard your changes and close the Edit Event Variable dialog box, click **Cancel**.

Step 8 Click **OK**.
The edited event variable now appears in the list on the Event Variables tab.

Step 9 To delete an event variable, select in the list, and then click **Delete**.
The event variable no longer appears in the list on the Event Variables tab.



Tip To discard your changes, click **Reset**.

Step 10 Click **Apply** to apply your changes and save the revised configuration.

Configuring Risk Category

This section describes how to configure risk categories, and contains the following topics:

- [Risk Category Tab, page 11-26](#)
- [Risk Category Tab Field Definitions, page 11-27](#)
- [Add and Edit Risk Level Dialog Boxes Field Definitions, page 11-27](#)
- [Adding, Editing, and Deleting Risk Categories, page 11-27](#)

Risk Category Tab



Note You must be administrator to add and edit risk levels.

On the Risk Category tab, you can use predefined risk categories (HIGHRISK, MEDIUMRISK, AND LOWRISK) or you can define your own labels. Risk categories link a category name to a numeric range defining the risk rating. You specify the low threshold for the category to make sure that the ranges are contiguous. The upper category is either the next higher category or 100.

You can then group the threats in red, yellow, and green categories. These red, yellow, and green threshold statistics are used in event action overrides and are also shown in the Network Security Gadget on the Home page.



Note You cannot delete a predefined risk category.

The red, yellow, and green threshold statistics represent the state of network security with red being the most critical. If you change a threshold, any event action overrides that had the same range as the risk category are changed to reflect the new range.

The new category is inserted in to the Risk Category list according to its threshold value and is automatically assigned actions that cover its range.

Risk Category Tab Field Definitions

The following fields are found on the Risk Category tab:

- Risk Category Name—Name of this risk level. The predefined categories have the following values:
 - HIGHRISK—90 (means 90 to 100)
 - MEDIUMRISK—70 (means 70-89)
 - LOWRISK—1 (means 1-69)
- Risk Threshold—Threshold number for this risk. The value is a number from 0 to 100.
- Risk Range—Risk Rating range for his risk category.

The risk rating is a range between 0 and 100 that represents a numerical quantification of the risk associated with a particular event on the network.
- Network Security Health Statistics—Lists the numbers for the red, yellow, and green thresholds. The overall network security value represents the least secure value (green is the most secure and red is the least secure).
 - Red Threat Thresholds
 - Yellow Threat Thresholds
 - Green Threat Thresholds

These color thresholds refer to the Sensor Health gadget on the Home pane.

Add and Edit Risk Level Dialog Boxes Field Definitions

The following fields are found in the Add and Edit Risk Level dialog boxes:

- Risk Name—Lets you name this risk level.
- Risk Threshold—Lets you assign a risk threshold for this risk level.

You specify or change only the lower threshold for the category so that the risk categories are contiguous. The upper threshold is either the next higher category or 100.
- Active—Lets you make this risk level active.

Adding, Editing, and Deleting Risk Categories

To add, edit, and delete risk categories, follow these steps:

-
- Step 1** Log in to IME using an account with administrator or operator privileges.
 - Step 2** Choose **Configuration > sensor_name > Policies > Event Action Rules > rules0 > Risk Category**, and then click **Add**.
 - Step 3** In the Risk Name field, enter a name for this risk category.
 - Step 4** In the Risk Threshold field, enter a numerical value for the risk threshold (minimum 0, maximum 100). This number represents the lower boundary of risk. The range appears in the Risk Range field and in the red, yellow, and green threshold fields.
 - Step 5** To make this risk category active, click the **Yes** radio button.



Tip To discard your changes and close the Add Risk Category dialog box, click **Cancel**.

Step 6 Click **OK**.

The new risk category appears in the list on the Risk Category tab.

Step 7 To edit an existing risk category, select it in the list, and then click **Edit**.

Step 8 Make any changes needed.



Tip To discard your changes and close the Edit Risk Category dialog box, click **Cancel**.

Step 9 Click **OK**.

The edited risk category now appears in the list on the Risk Category tab.

Step 10 To delete a risk category, select in the list, and then click **Delete**.

The risk category no longer appears in the list on the Risk Category tab.



Tip To discard your changes, click **Reset**.

Step 11 Click **Apply** to apply your changes and save the revised configuration.

Configuring General Settings

This section describes how to configure the general settings, and contains the following topics:

- [General Tab, page 11-28](#)
- [General Tab Field Definitions, page 11-29](#)
- [Configuring the General Settings, page 11-29](#)

General Tab



Note You must be administrator or operator to configure the general settings for event action rules.

You can configure the general settings that apply globally to event action rules, such as whether you want to use the Summarizer and the Meta Event Generator. The Summarizer groups events into a single alert, thus decreasing the number of alerts the sensor sends out. The Meta Event Generator processes the component events, which lets the sensor watch for suspicious activity transpiring over a series of events.



Caution Do not disable the Summarizer or Meta Event Generator except for troubleshooting purposes. If you disable the Summarizer, every signature is set to Fire All with no summarization. If you disable the Meta Event Generator, all Meta engine signatures are disabled.

You can also use Threat Rating adjustment, Event Action Filters, and you can enable One Way TCP Reset.

The one-way TCP reset operates for inline mode only and is an automatic addition to the deny packet inline actions. It sends a TCP reset to the victim of the alert, thus creating a black hole for the attacker and clearing the TCP resources of the victim.

**Note**

An inline sensor now denies packets for any alert with a risk rating of greater than or equal to 90. It also issues a one-way TCP reset on TCP alerts with a risk rating of greater than or equal to 90.

You can configure how long you want to deny attackers, the maximum number of denied attackers, and how long you want blocks to last.

General Tab Field Definitions

The following fields are found the on the General tab:

- Use Summarizer—Enables the Summarizer component.

By default, the Summarizer is enabled. If you disable it, all signatures are set to Fire All with no summarization. If you configure individual signatures to summarize, this configuration will be ignored if the Summarizer is not enabled.

- Use Meta Event Generator—Enables the Meta Event Generator.

By default, the Meta Event Generator is enabled. If you disable the Meta Event Generator, all Meta engine signatures are disabled.

- Use Threat Rating Adjustment—Enables threat rating adjustment, which adjusts the risk rating. If disabled, then risk rating is equal to threat rating.
- Use Event Action Filters—Enables the event action filter component. You must check this check box to use any filter that is enabled.
- Enable One Way TCP Reset—(inline mode only) Enables a one-way TCP reset for deny packet inline actions for TCP-based alerts. It sends a TCP reset to the victim of the alert thus clearing the TCP resources of the victim.
- Deny Attacker Duration—Number of seconds to deny the attacker inline. The valid range is 0 to 518400. The default is 3600.
- Block Attack Duration—Number of minutes to block a host or connection. The valid range is 0 to 10000000. The default is 30.
- Maximum Denied Attackers—Limits the number of denied attackers possible in the system at any one time. The valid range is 0 to 100000000. The default is 10000.

Configuring the General Settings

**Caution**

The general settings options operate at a global level, so enabling them affects all sensor processing of these features.

To configure the general settings for event action rules, follow these steps:

-
- Step 1** Log in to IME using an account with administrator or operator privileges.
- Step 2** Choose **Configuration > sensor_name > Policies > Event Action Rules > rules0 > General**.
- Step 3** To enable the summarizer feature, check the **Use Summarizer** check box.

**Caution**

Disable the Summarizer for troubleshooting purposes only. Otherwise, make sure the Summarizer is enabled so that all signatures you configure for summarization will actually summarize.

- Step 4** To enable the meta event generator, check the **Use Meta Event Generator** check box.

**Caution**

Disable the Meta Event Generator for troubleshooting purposes only. Otherwise, make sure the Meta Event Generator is enabled so that all Meta engine signatures are functional.

- Step 5** To enable threat rating adjustment, check the **Use Threat Rating Adjustment** check box.

- Step 6** To enable event action filters, check the **Use Event Action Filters** check box.

**Note**

You must check the Use Event Action Filters check box on the General pane so that any event action filters you configured in the **Configuration > sensor_name > Policies > Event Action Rules > rules0 > Event Action Filters** pane are active.

- Step 7** To enable one way TCP reset for deny packet inline actions, check the **Enable One Way TCP Reset** check box.
- Step 8** In the Deny Attacker Duration field, enter the number of seconds you want to deny the attacker inline.
- Step 9** In the Block Action Duration field, enter the number of minutes you want to block a host or connection.
- Step 10** In the Maximum Denied Attackers field, enter the maximum number of denied attackers you want at any one time.

**Tip**

To discard your changes, click **Reset**.

- Step 11** Click **Apply** to apply your changes and save the revised configuration.
-