



General API Concepts

Published: July 30, 2014

Introduction

This chapter describes the various concepts that are used when working with the Cisco Service Control Subscriber Manager C/C++ API.

- [Blocking API and Nonblocking API, page 2-1](#)
- [Reliability, page 2-2](#)
- [C API Versus C++ API, page 2-2](#)
- [API Initialization, page 2-4](#)
- [API Finalization, page 2-5](#)
- [ReturnCode Structure, page 2-6](#)
- [ErrorCode Structure, page 2-7](#)
- [Subscriber Name Format, page 2-7](#)
- [Network ID Mappings, page 2-7](#)
- [Subscriber Domains, page 2-9](#)
- [Subscriber Properties, page 2-10](#)
- [Custom Properties, page 2-10](#)
- [Logging Capabilities, page 2-10](#)
- [Disconnect Callback Listener, page 2-11](#)
- [Signal Handling, page 2-11](#)
- [Practical Tips, page 2-12](#)

Blocking API and Nonblocking API

This section describes the differences between the Blocking API and Nonblocking API operations.

- [Blocking API, page 2-2](#)
- [Nonblocking API, page 2-2](#)

Blocking API

For a Blocking API operation, which is the common type, every method returns *after* its operation is performed.

The Cisco Service Control Subscriber Manager Blocking C/C++ API provides a wide range of operations and is a *superset* of the Nonblocking API functionality.

Nonblocking API

For a Nonblocking API operation, every method returns *immediately*, even before the operation completes. The operation results are returned either to a set of user-defined callbacks or not returned at all.

The Nonblocking method is advantageous when the operation is lengthy and involves I/O. Operation is performed in a separate thread and this allows the calling program to continue doing other tasks, which improves overall system performance.

The Cisco Service Control Subscriber Manager Nonblocking C/C++ API contains a small number of nonblocking operations. The API supports retrieval of operation results by using result callbacks.

Reliability

The Service Control Management Suite (SCMS) SM C/C++ API is reliable in the sense that the operations performed on the API are kept until the Cisco Service Control Subscriber Manager returns their associated results. If the connection to the Cisco Service Control Subscriber Manager is lost, operations that were not sent to the Cisco Service Control Subscriber Manager and operations whose results did not yet return from the Cisco Service Control Subscriber Manager are sent to the Cisco Service Control Subscriber Manager immediately on reconnection. The order of operation invocation is maintained at all times.

C API Versus C++ API

The C and C++ APIs are essentially the same. The C API is actually a thin wrapper over the C++ API, with method prototype and signature changes imposed by the constraint of C not being an object-oriented programming language.

The following sections describe the differences between the C and C++ APIs and provide some examples:

- [Method Names, page 2-3](#)
- [Handle Pointers, page 2-3](#)

Method Names

The method names of the C API are the same as those of the C++ API, except that the C API method names have an identifying prefix:

- The Blocking C API method names are prefixed with `SMB_`.
- The Nonblocking C API methods names are prefixed with `SMNB_`.



Note

The descriptions of methods in this document use the name and signature of the C++ API methods.

For example, both the Blocking and Nonblocking C++ APIs provide a login method. The method in the Blocking C API is called `SMB_login` and the method in the Nonblocking C API is called `SMNB_login`.

Handle Pointers

The Blocking and Nonblocking APIs are C++ objects. Several API instances can co-exist in a single process; each has its own socket and state. The handle concept is introduced to provide the same functionality in the C API. Each C API method accepts a handle as its first argument. The handle identifies the C API instance on which the caller wants to operate. Calling the `SMB_init` or `SMNB_init` method creates a new C API instance; the return value of these methods provides the handle to the instance. For more information, see the [“API Initialization” section on page 2-4](#).

Blocking API—Example

The C++ Blocking API `logoutByName` method signature

```
ReturnCode* logoutByName(char* argName,
                        char** argMappings,
                        MappingType* argMappingTypes,
                        int argMappingsSize)
```

is translated into C Blocking API as follows:

```
ReturnCode* SMB_logoutByName(SMB_HANDLE argApiHandle,
                            char* argName,
                            char** argMappings,
                            MappingType* argMappingTypes,
                            int argMappingsSize);
```

Nonblocking API—Example

The C++ Nonblocking API `logoutByName` method signature

```
int logoutByName(char* argName,
                char** argMappings,
                MappingType* argMappingTypes,
                int argMappingsSize);
```

is translated into C Nonblocking API as follows:

```
int SMNB_logoutByName(SMNB_HANDLE argApiHandle,
                    char* argName,
                    char** argMappings,
                    MappingType* argMappingTypes,
                    int argMappingsSize);
```

API Initialization

There are three main steps in initializing the API:

-
- Step 1** Construct the API using one of its two constructors. See the [Constructing the API, page 2-4](#).
 - Step 2** Perform API-specific setup operations. See the [Performing Setup Operations, page 2-5](#).
 - Step 3** Connect the API to the Cisco Service Control Subscriber Manager. See the [Connecting to the Cisco Service Control Subscriber Manager, page 2-5](#).
-

You can find the initialization examples in the code examples section under each API.

Constructing the API

Both C and C++ Blocking and Nonblocking APIs must construct and initialize the API. Check whether the initialization succeeded before you proceed.

To construct and initialize the C++ API, construct an API object and call the init function as shown in the following example:

```
SmApiNonBlocking nbapi;
if (!nbapi.init(0,2000000,10,30)){
    exit(1);
}
```

To construct and initialize the C API, call the init function, which allocates and initializes the API. For example:

```
SMNB_HANDLE nbapi = SMNB_init(0,2000000,10,30);
if (nbapi == NULL){
    exit(1);
}
```

Setting the LEG Name

Set the Login Event Generator (LEG) name if you intend to turn on the Cisco Service Control Subscriber Manager LEG failure processing options in the Cisco Service Control Subscriber Manager. For more information about LEGs and Cisco Service Control Subscriber Manager-LEG failure handling, see [Cisco Service Control Management Suite Subscriber Manager User Guide](#).

To set the LEG name, call the relevant setName function in the API. The Cisco Service Control Subscriber Manager uses the LEG name when recovering from a connection failure. A constant string that identifies the API is appended to the LEG name as follows:

- For Blocking API—.B.SM-API.C
- For Nonblocking API—.NB.SM-API.C

Setting the LEG Name Example (Blocking API)

If the provided LEG name is my-leg.10.1.12.45-version-1.0, the actual LEG name is my-leg.10.1.12.45-version-1.0.B.SM-API.C.

If no name is set, the LEG uses the hostname of the machine as the prefix of the name.

For additional information about Cisco Service Control Subscriber Manager-LEG failure handling, see the “Configuration File Options” appendix of *Cisco Service Control Management Suite Subscriber Manager User Guide*.

Performing Setup Operations

The setup operations for the two APIs differ. Both APIs support setting a disconnect listener, which is described in the “[Disconnect Callback Listener](#)” section on page 2-11.

The following sections describe the setup operations for the Blocking API and the Nonblocking API:

- [Blocking API Setup, page 2-5](#)
- [Nonblocking API Setup, page 2-5](#)

Blocking API Setup

To set up the Blocking API, you must set an operation timeout value. For more information, see the [Chapter 3, “Blocking API”](#).

Nonblocking API Setup

To set up the Nonblocking API, you must set a disconnect callback. For more information, see the [Chapter 4, “Nonblocking API”](#).

Connecting to the Cisco Service Control Subscriber Manager

To connect to the Cisco Service Control Subscriber Manager, use one of the following connect methods:

- The following example shows how to connect when using the C++ APIs:

```
connect(char* host, Uint16 argPort = 14374)
```
- The following example shows how to connect when using the C Blocking API:

```
SMB_connect(SMB_HANDLE argApiHandle, char* host, Uint16 argPort)
```
- The following example shows how to connect when using the C Nonblocking API:

```
SMNB_connect(SMNB_HANDLE argApiHandle, char* host, Uint16 argPort)
```

The `argHostName` parameter can be either an IP address or a reachable hostname. At any time during the API operation, you can check if the API is connected by using one of the variants of the `isConnected` function.

API Finalization

Both C and C++ Blocking and Nonblocking APIs must disconnect from the Cisco Service Control Subscriber Manager and free the memory of the API:

- For the C++ APIs, call the disconnect method and free the API object.
- For the C APIs, call the appropriate disconnect function and then free the API by using the appropriate release function.

ReturnCode Structure

The results of the API operations are returned using a generic structure called ReturnCode. The ReturnCode structure contains several parameters:

- `u`—Union of all variables and pointers to variables that are the actual returned values.
- `type`—Return code type parameter (ReturnCodeType enumeration) that defines the type of the value (`u`) that the ReturnCode structure holds.
- `size`—Number of elements in the value. If `size` is equal to 1, there is one element in the value, such as a scalar, character string, void, or error. If `size` is greater than 1, there are several elements in the array, and the type should be one of the array types.

The API allocates the return code structure and the API user must free the structure. You can use the `freeReturnCode` utility function to safely free the structure.

Additional return code structure utility functions are:

- `printReturnCode`—Prints the ReturnCode structure value to the stdout.
- `isReturnCodeError`—Checks whether the ReturnCode structure is an error.

Definition

This is an example definition from the GeneralDefs.h header file:

```
OSAL_DllExport typedef struct ReturnCode_t
{
    ReturnCodeType type;
    int size;          /* number of elements in the union element */
                    /* (for example: stringVal will have size=1) */
    union { /* use union value according to the type value */
        bool boolVal;
        short shortVal;
        int intVal;
        long longVal;
        char* stringVal;
        bool* boolArrayVal;
        short* shortArrayVal;
        int* intArrayVal;
        long* longArrayVal;
        char** stringArrayVal;
        ErrorCode* errorCode;
        struct ReturnCode_t** objectArray;
    } u;
}ReturnCode;
```

Return Code Structure Example

In the following example, the API retrieves and displays the subscriber data of subscriber1. The returned structure contains an array of ReturnCode structures held by the `objectArray` union value. Each structure contains a different value type. For additional information, see the [“getSubscriber” section on page 3-22](#). This example uses the `isReturnCodeError` and `freeReturnCode` methods.

```
ReturnCode* subFields = bapi.getSubscriber("subscriber1");
if (isReturnCodeError(subFields) == false)
{
    printf("\tname:\t\t%s\n", subFields->u.objectArray[0]->u.stringVal);
}
```

```

printf("\tmapping:\t%s\n", subFields->u.objectArray[1]->u.stringArrayVal[0]);
printf("\tdomain:\t\t%s\n", subFields->u.objectArray[3]->u.stringVal);
printf("\tautologout:\t%d\n", subFields->u.objectArray[8]->u.intVal);
}
else
{
    printf("error in subscriber retrieval\n");
}
freeReturnCode(subFields);

```

ErrorCode Structure

The ErrorCode structure can be one of the values of the return code structure. This structure describes the error that occurred. The structure consists of the following parameters:

- **type**—ErrorCodeType enumeration that describes the error. See the GeneralDefs.h file for additional information.
- **message**—Specific error code.
- **name**—Currently not used.

Definition

This is an example definition from the GeneralDefs.h header file:

```

OSAL_DllExport typedef struct ErrorCode_t
{
    ErrorCodeType type; /* type of the error see enumeration */
    char* name;        /* currently not used */
    char* message;     /* error message */
}ErrorCode;

```

Subscriber Name Format

Most methods of the Blocking and Nonblocking APIs require the subscriber name as an input parameter. This section lists the formatting rules of a subscriber name.

- A subscriber name can contain up to 64 characters.
- A subscriber name can be made up of all printable characters with an ASCII code between 32 and 126 (inclusive), except for 34 ("), 39 ('), and 96 (^).
- If the subscriber name begins with a non-alphanumeric character, it must be preceded by a backslash (\).

Network ID Mappings

A network ID mapping is a network identifier that the SCE device can map to a specific subscriber record. A typical example of a network ID mapping (or simply, mapping) is an IP address. For additional information, see the [Cisco Service Control Management Suite Subscriber Manager User Guide](#). Currently, the Cisco Service Control Solution supports IP address, IP range, private IP address over VPN, private IP range over VPN, and VLAN mappings.

Both Blocking and Nonblocking APIs contain operations that accept mappings as a parameter. Examples are:

- The addSubscriber operation (Blocking APIs)
- The login operation (Blocking or Nonblocking APIs)

When passing mappings to an API method, the caller is requested to provide two parameters:

- A character string (char*) mapping identifiers or array of character strings (char**) mappings.
- A MappingType enumeration or array of MappingType variables.

When passing arrays, the MappingType variables array must contain the same number of elements as the mappings array.

The API supports the following subscriber mapping types (defined by the MappingType enumeration):

- IP addresses or IP ranges
- (From Cisco Service Control Subscriber Manager Release 3.8.5) IPv6 address
- Private IP addresses or private IP ranges over VPN
- VLAN tags

Specifying IP Address Mapping

The string format of an IP address is the commonly used decimal notation:

```
IP-Address=[0-255].[0-255].[0-255].[0-255]
```

Example:

```
216.109.118.66
```

The GeneralDefs.h header file provides the mapping type of an IP address:

- IP_RANGE specifies IP mapping (IP-Address or IP-Range that matches the mapping identifier with the same index in the mapping identifier array).

Specifying IP Range Mapping

The string format of an IP range is an IP address in decimal notation and a decimal specifying the number of 1s in a bit mask:

```
IP-Range=[0-255].[0-255].[0-255].[0-255]/[0-32]
```

Examples:

- 10.1.1.10/32 is an IP range with a complete mask, that is, a regular IP address.
- 10.1.1.0/24 is an IP range with a 24-bit mask, that is, all the addresses ranging between 10.1.1.0 and 10.1.1.255.



Note

The mapping type of an IP range is identical to the mapping type of the IP address.

Specifying Private IP Address or Private IP Range over VPN Mapping

The string format of an IP address and an IP range are described in the “[Specifying IP Address Mapping](#)” section on page 2-8 and the “[Specifying IP Range Mapping](#)” section on page 2-8, respectively. When the network ID mapping uses an IP address or range over VPN, the string format includes the VPN name.

Examples:

- 10.1.1.10@VPN1 is an IP address over the VPN named VPN1.
- 10.1.1.0/24@VPN2 is an IP range with a 24-bit mask, that is, all the addresses ranging between 10.1.1.0 and 10.1.1.255 over the VPN named VPN2.



Note

The mapping type of an IP address or IP range over VPN is identical to the mapping type of the IP address.

Specifying VLAN Tag Mapping

The string format for VLAN tag mapping is VLAN-tag = 0-4095. The string is a decimal in the specified range.

The GeneralDefs.h header file provides the mapping type of a VPN, which is used to specify VLAN-tags as network IDs.



Note

The mapping type, VLAN, is deprecated. Use the VPN mapping type instead.

Specifying IPv6 Address Mapping

The string format for an IPv6 address mapping is a hexadecimal string that follows the RFC 2373 standard.

Example:

2005:1:2:23::/64

The GeneralDefs.h header file provides the mapping type of an IPv6 address:

- TYPE_IPV6 specifies IPv6 mapping.

Subscriber Domains

The *Cisco Service Control Management Suite Subscriber Manager User Guide* describes the domain concept in detail. A domain is an identifier that tells the Cisco Service Control Subscriber Manager which Cisco SCE devices to update with the subscriber record.

A domain name is of type (char*). During system installation, the network administrator determines the system domain names, which vary from installation to installation. The APIs include methods that specify the domain to which a subscriber belongs and allow queries about the domain names of the

system. If an API operation specifies a domain name that does not exist in the Cisco Service Control Subscriber Manager domain repository, it is considered an error and an `ERROR_CODE_DOMAIN_NOT_FOUND` error `ReturnCode` is returned.

The Cisco Service Control Subscriber Manager automatic domain roaming feature enables you to move subscribers among domains by calling the `login` method for a subscriber with an updated domain parameter. For additional information, see the [“login” section on page 3-4](#).

**Note**

Automatic domain roaming is not backward compatible with previous versions of the Cisco Service Control Subscriber Manager API, which did not allow changing the domain of the subscriber.

Subscriber Properties

Several operations manipulate subscriber properties. A subscriber property is a key-value pair that affects the way the SCE analyzes and reacts to network traffic generated by the subscriber.

For more information about properties, see the [Cisco Service Control Management Suite Subscriber Manager User Guide](#) and the [Cisco Service Control Application for Broadband User Guide](#). The SCA BB user guide provides application-specific information. It lists the subscriber properties that exist in the application running on your system, the allowed value set, and the significance of each property value.

To format subscriber properties for C/C++ API operations, use the string arrays (`char**`) `propertyKeys` and `propertyValues`.

**Note**

The arrays must be of the *same length*, and NULL entries are forbidden. Each key in the keys array has a matching entry in the values array. The value for `propertyKeys[j]` resides in `propertyValues[j]`.

Example:

If the property keys array is `{"packageId","monitor"}` and the property values array is `{"5","1"}`, the properties are `packageId=5, monitor=1`.

Custom Properties

Some operations manipulate custom properties. Custom properties are similar to subscriber properties, but do not affect how the SCE analyzes and manipulates the subscriber traffic. The application management modules use custom properties to store additional information for each subscriber.

To format custom properties, use the string (`char**`) arrays `customPropertyKeys` and `customPropertyValues`, in the same manner as in the [“Subscriber Properties” section on page 2-10](#).

Logging Capabilities

The API package contains a `Logger` abstract class that can be inherited and used to integrate the Cisco Service Control Subscriber Manager API with the host application log. The `Logger` class exposes four basic levels of logging—error messages, warning messages, informative messages, and several levels of trace messages. Both the Blocking and Nonblocking API have this capability. The `Logger.h` header file provides the `Logger` class.

As you use the API, you should implement a logger by inheriting from the `Logger` class. To enable the API to use this logger, the code should call the `setLogger` method of the C++ implementation of the API.

To test and implement a LEG, the API package provides the `PrintLogger` class, which is a basic implementation of the `Logger` class that prints the log messages to the standard error (STDERR). With the API, you can initiate the `PrintLogger` object, set its logging level by using the `setLoggingLevels` method of the `PrintLogger` class, and pass the logger object to the API by using the API `setLogger` method. The `PrintLogger.h` header file provides the `PrintLogger` class.

Disconnect Callback Listener

Both Blocking and Nonblocking APIs enable you to set a disconnect callback listener to be notified when the API is disconnected from the Cisco Service Control Subscriber Manager. Define the disconnect callback as follows:

```
typedef void (*ConnectionIsDownCallBackFunc)();
```

To set the disconnect listener, use the `setDisconnectListener` method.

Disconnect Callback Listener Example

The following example is a basic implementation of a disconnect callback listener that prints a message to stdout and exits:

```
#include "GeneralDefs.h"
void connectionIsDown(){
    printf("Message: connection is down.");
    exit(0);
}
```

Signal Handling

The Cisco Service Control Subscriber Manager C/C++ API as a networking module might handle sockets that are closed by the Cisco Service Control Subscriber Manager, for example, if the Cisco Service Control Subscriber Manager is restarted, which might cause “Broken Pipe” signals. It is especially advisable for the UNIX environment to handle this signal.

To ignore the signal, add the following call:

```
sigignore(SIGPIPE);
```

Practical Tips

When implementing the code that integrates the API with your application, consider the following practical tips:

- Connect to the Cisco Service Control Subscriber Manager once and maintain an open API connection to the Cisco Service Control Subscriber Manager at all times, using the API many times. Establishing a connection is a timely procedure, which allocates resources on the Cisco Service Control Subscriber Manager side and the API client side.
- Share the API connection between your threads. It is best to have one connection per LEG. Multiple connections require more resources on the Cisco Service Control Subscriber Manager side and client side.
- Do not implement synchronization of the calls to the API. The client automatically synchronizes calls to the API.
- Place the API clients (LEGs) in the same order of the Cisco Service Control Subscriber Manager machine processor number.
- If the LEG application has bursts of logon operations, enlarge the internal buffer size accordingly to hold these bursts (Nonblocking flavor).
- During the integration, set the Cisco Service Control Subscriber Manager `logon_logging_enabled` configuration parameter to view the API operations in the Cisco Service Control Subscriber Manager log to troubleshoot the integration, if any problems arise.
- Use the debug mode for the LEG application that logs (prints) the return values of the nonblocking operations.
- Use the automatic reconnect feature to improve the resiliency of the connection to the Cisco Service Control Subscriber Manager.
- In cluster setups, connect the API by using the virtual IP address of the cluster, not the management IP address of one of the machines.