



Zone-Based Policy Firewall

First Published: February 22, 2006
Last Updated: February 18, 2011

This module describes the Cisco IOS XE unidirectional firewall policy between groups of interfaces known as zones.

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the [“Feature Information for Zone-Based Policy Firewall”](#) section on page 36.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to <http://www.cisco.com/go/cfn>. An account on Cisco.com is not required.

Contents

- [Prerequisites for Zone-Based Policy Firewall, page 2](#)
- [Restrictions for Zone-Based Policy Firewall, page 2](#)
- [Information About Zone-Based Policy Firewall, page 2](#)
- [How to Configure Zone-Based Policy Firewall, page 12](#)
- [Configuration Examples for Zone-Based Policy Firewall, page 31](#)
- [Additional References, page 34](#)
- [Feature Information for Zone-Based Policy Firewall, page 36](#)



Americas Headquarters:
Cisco Systems, Inc., 170 West Tasman Drive, San Jose, CA 95134-1706 USA

Prerequisites for Zone-Based Policy Firewall

The general guideline before you create zones is that you should group interfaces that are similar when they are viewed from a security perspective.

Restrictions for Zone-Based Policy Firewall

- Application-level maps (also referred to as Layer 7 class maps) are not supported in Cisco IOS XE software.
- In a Cisco Wide Area Application Services (WAAS) and Cisco IOS XE firewall configuration, all packets processed by a Wide Area Application Engine (WAE) device must go over the Cisco IOS XE firewall in both directions to support the Web Cache Coordination Protocol (WCCP) generic routing encapsulation (GRE) redirect. This situation occurs when the Layer 2 redirect is not available. If Layer 2 redirect is configured on the WAE, the system defaults to the GRE redirect to continue to function.
- When an in-to-out zone-based policy is configured to match the Internet Control Message Protocol (ICMP) on a Windows system, the **tracert** command works. However, the same configuration on an Apple system does not work because it uses a UDP-based traceroute. To overcome this issue, configure an out-to-in zone-based policy with the **icmp time-exceeded** and **icmp host unreachable** commands with the **pass** command (not the **inspect** command).
- In a WAAS and Cisco IOS XE firewall configuration, WCCP does not support traffic redirection using policy-based routing (PBR).
- Stateful inspection support for multicast traffic is not supported between any zones, including the self zone. Use [Control Plane Policing](#) for protection of the control plane against multicast traffic.
- A UDP-based traceroute is not supported through ICMP inspection.

Information About Zone-Based Policy Firewall

- [Top-level Class Maps and Policy Maps, page 3](#)
- [Overview of Zones, page 3](#)
- [Security Zones, page 3](#)
- [Virtual Interfaces as Members of Security Zones, page 4](#)
- [Zone Pairs, page 5](#)
- [Zones and Inspection, page 6](#)
- [Zones and ACLs, page 6](#)
- [Overview of Security Zone Firewall Policies, page 6](#)
- [Class Maps and Policy Maps for Zone-Based Policy Firewalls, page 6](#)
- [Layer 3 and Layer 4 Class Maps and Policy Maps, page 7](#)
- [Class-Map Configuration Restriction, page 7](#)
- [Class-Default Class Map, page 8](#)
- [Access Control List and Class Map, page 8](#)
- [Firewall and Network Address Translation, page 9](#)

- [WAAS and Firewall Integration Support, page 10](#)
- [WAAS Traffic Flow Optimization Deployment Scenarios, page 10](#)

Top-level Class Maps and Policy Maps

Top-level class maps allow you to identify the traffic stream at a high level. This is accomplished by using **match access-group** and **match protocol** commands. Top-level class maps are also referred to as Layer 3 and Layer 4 class maps.

Top-level policy maps allow you to define high-level actions by using the **inspect**, **drop**, and **pass** keywords. You can attach the policy maps to a target (zone pair).

**Note**

Only inspect type policies can be configured on a zone pair.

Overview of Zones

A zone is a group of interfaces that have similar functions or features. They provide a way for you to specify where a Cisco IOS XE software firewall is applied.

For example, on a router, gigabit ethernet interface 0/0/0 and gigabit ethernet interface 0/0/1 may be connected to the local LAN. These two interfaces are similar because they represent the internal network, so they can be grouped into a zone for firewall configurations.

By default, the traffic between interfaces in the same zone is not be subjected to any policy. The traffic passes freely. Firewall zones are used for security features.

**Note**

Zones may not span interfaces in different VPN routing and forwarding (VRF) instances.

Security Zones

A security zone is a group of interfaces to which a policy can be applied.

Grouping interfaces into zones involves the following two procedures:

- Creating a zone so that interfaces can be attached to it.
- Configuring an interface to be a member of a given zone.

By default, traffic flows among interfaces that are members of the same zone.

When an interface is a member of a security zone, all traffic to and from that interface (except traffic going to the router or initiated by the router) is dropped. To permit traffic to and from a zone-member interface, you must make that zone part of a zone pair and then apply a policy to that zone pair. If the policy permits traffic (through **inspect** or **pass** actions), traffic can flow through the interface.

Basic rules to consider when setting up your zones are as follows:

- Traffic from a zone interface to a nonzone interface or from a nonzone interface to a zone interface is always dropped.
- Traffic between two zone interfaces is inspected if there is a zone pair relationship for each zone and if there is a configured policy for that zone pair.

- By default, all traffic between two interfaces in the same zone is always allowed as if the “pass” action is configured.
- A zone pair can be configured with a zone as both the source and the destination zones. An inspect policy can be configured on this zone pair to inspect or drop the traffic between two interfaces in the same zone.


For traffic to flow among all the interfaces in a router, all the interfaces must be a member of one security zone or another.

It is not necessary for all router interfaces to be members of security zones.

Figure 1 illustrates the following:

- Interfaces E0 and E1 are members of security zone Z1.
- Interface E2 is a member of security zone Z2.
- Interface E3 is not a member of any security zone.

Figure 1 **Security Zone Restrictions**



The following situations exist:

- The zone pair and policy are configured in the same zone. Traffic flows freely between interfaces E0 and E1 because they are members of the same security zone (Z1).
- If no policies are configured, traffic will not flow between any other interfaces (for example, E0 and E2, E1 and E2, E3 and E1, and E3 and E2).
- Traffic can flow between E0 or E1 and E2 only when an explicit policy permitting traffic is configured between zone Z1 and zone Z2.
- Traffic can never flow between E3 and E0/E1/E2 unless default zones are enabled.

Virtual Interfaces as Members of Security Zones

A virtual interface is a logical interface configured with generic configuration information for a specific purpose or for configuration common to specific users, plus router-dependent information. The template contains Cisco IOS XE software interface commands that are applied to virtual access interfaces, as needed. To configure a virtual template interface, use the **interface virtual-template** command.

Zone member information is acquired from a RADIUS server and then the dynamically created interface is made a member of that zone.

The **zone-member security** command puts the dynamic interface into the corresponding zone.

Zone Pairs

A zone pair allows you to specify a unidirectional firewall policy between two security zones.

To define a zone pair, use the **zone-pair security** command. The direction of the traffic is specified by specifying a source and a destination zone. The source and destination zones of a zone pair must be security zones.


If desired, you can select the default or self zone as either the source or the destination zone. The self zone is a system-defined zone. It does not have any interfaces as members. A zone pair that includes the self zone, along with the associated policy, applies to traffic directed to the router or traffic generated by the router. It does not apply to traffic through the router.

The most common usage of firewalls is to apply them to traffic through a router, so you usually need at least two zones (that is, you cannot use the self zone).

To permit traffic between zone-member interfaces, you must configure a policy permitting (or inspecting) traffic between that zone and another zone. To attach a firewall policy map to the target zone pair, use the **service-policy type inspect** command.

[Figure 2](#) shows the application of a firewall policy to traffic flowing from zone Z1 to zone Z2, which means that the ingress interface for the traffic is a member of zone Z1 and the egress interface is a member of zone Z2.

Figure 2 Zone Pairs



If there are two zones and you require policies for traffic going in both directions (from Z1 to Z2 and Z2 to Z1), you must configure two zone pairs (one for each direction).

If a policy is not configured between a pair of zones, traffic is dropped. However, it is not necessary to configure a zone pair and a service policy solely for return traffic. Return traffic is allowed, by default, if a service policy permits the traffic in the forward direction. In [Figure 2](#), it is not mandatory that you configure a zone-pair source Z2 destination Z1 solely for allowing return traffic from Z2 to Z1. The service policy on the Z1-Z2 zone pair takes care of it.

Zones and Inspection

Zone-based policy firewalls examine the source and destination zones from the ingress and egress interfaces for a firewall policy. It is not necessary that all traffic flowing to or from an interface be inspected; you can designate that individual flows in a zone pair be inspected through your policy map that you apply across the zone pair. The policy map will contain class maps that specify the individual flows.

You can also configure **inspect** parameters like TCP thresholds and timeouts on a per-flow basis.

Zones and ACLs

Pinholes are not punched for return traffic in interface Access Control List (ACL).

ACLs applied to interfaces that are members of zones are processed before the policy is applied on the zone pair. So, you must relax interface ACLs when there are policies between zones so that they cannot interfere with the policy firewall traffic.

Overview of Security Zone Firewall Policies

A class is a way of identifying a set of packets based on its contents. Normally you define a class so that you can apply an action on the identified traffic that reflects a policy. A class is designated through class maps.

An action is a specific functionality. It typically is associated with a traffic class. For example, **inspect**, **drop**, and **pass** are actions.

To create firewall policies, you should complete the following tasks:

- Define a match criteria (class map)
- Associate actions to the match criteria (policy map)
- Attach the policy map to a zone pair (service policy)

The **class-map** command creates a class map to be used for matching packets to a specified class. Packets arriving at the targets (such as the input interface, output interface, or zone-pair), determined by how the **service-policy** command is configured, are checked against the match criteria configured for a class map to determine if the packet belongs to that class.

The **policy-map** command creates or modifies a policy map that can be attached to one or more targets to specify a service policy. Use the **policy-map** command to specify the name of the policy map to be created, added to, or modified before you can configure policies for classes whose match criteria are defined in a class map.

Class Maps and Policy Maps for Zone-Based Policy Firewalls

Quality of service (QoS) class maps have numerous match criteria; firewalls have fewer match criteria. Firewall class maps have type **inspect**; this information controls what shows up under firewall class maps.

A policy is an association of traffic classes and actions. It specifies what actions should be performed on the defined traffic classes. An action is a specific function, and it is typically associated with a traffic class. For example, **inspect** and **drop** are actions.

Layer 3 and Layer 4 Class Maps and Policy Maps

Layer 3 and Layer 4 class maps are used to identify traffic streams on which different actions should be performed.

A Layer 3 or Layer 4 policy map is sufficient for the basic inspection of traffic.

The following example shows how to configure class map `c1` with the match criteria of ACL 101 and the FTP protocol, and create an inspect policy map named `p1` to specify that packets will be dropped on the traffic at `c1`:

```
Router(config)# class-map type inspect match-all c1
Router(config-cmap)# match access-group 101
Router(config-cmap)# match protocol ftp

Router(config)# policy-map type inspect p1
Router(config-pmap)# class type inspect c1
Router(config-pmap-c)# drop
```

Supported Protocols

The following protocols are supported:

- FTP
- H.323
- ICMP
- Lightweight Directory Access Protocol (LDAP)
- LDAP over Transport Layer Security/Secure Socket Layer (LDAPS)
- Real-time Streaming Protocol (RTSP)
- Session Initiation Protocol (SIP)
- SCCP (Skinny Client Control Protocol)
- TCP
- TFTP
- UDP

Class-Map Configuration Restriction

If traffic meets multiple match criteria, the match criteria must be applied in the order of specific to less specific. For example, consider the following class map example:

```
class-map type inspect match-any my-test-cmap
  match protocol ftp
  match protocol tcp
```

In this example, FTP traffic must first encounter the **match protocol ftp** command to ensure that the traffic will be handled by the service-specific capabilities of FTP inspection. If the “match” lines were reversed so traffic encountered the **match protocol tcp** command before it was compared to the **match protocol ftp** command, the traffic would simply be classified as TCP traffic and inspected according to the capabilities of the Firewall’s TCP Inspection component.

Class-Default Class Map

In addition to user-defined classes, a system-defined class map named `class-default` represents all packets that do not match any of the user-defined classes in a policy. It always is the last class in a policy map.

You can define explicit actions for this group of packets. If you do not configure any actions for class default in an inspect policy, the default action is **drop**.

Access Control List and Class Map

Access Control Lists (ACLs) are commonly implemented on Cisco routers. Access lists are packet-classifying mechanisms. These access lists define actual network traffic that will be permitted or denied when it is applied to a particular router network interface. Thus, the ACL is a sequential collection of permit and deny conditions that applies to a packet. The router tests packets against the conditions in the ACL one at a time. A deny condition is interpreted as “do not match.” Packets matching a deny access control entry (ACE) cause an ACL process to terminate and the next match statement within the class to be examined.

Class maps are used to match a range of variables in an access list based on the following criteria:

- If a class map does not find a match or matches a permit or deny, then the ACL fails.
- If the class map is specified then the class map performs either an AND (match-all) or an OR (match-any) operation on these variables.
- If a match-all attribute is specified and any match, ACL, or protocol fails to match the packet, then further evaluation of the current class is stopped, and the next class in the policy is examined.
- If any match in a match-any attribute succeeds, then the class-map criteria are met and the action defined in the policy is performed.
- If an ACL matches the match-any attribute, then the firewall will attempt to ascertain the Layer 7 protocol based on the destination port.

If you specify the match-all attribute in a class map, the Layer 4 match criteria (TCP, UDP, and ICMP) are set and the Layer 7 match criteria are not set. Hence, the Layer 4 inspection is performed and Layer 7 inspection is omitted.

The access lists can create network devices that are configured to implement the network security policies for an organization. Access lists come in different forms: standard and extended access lists. Standard access lists are defined to permit or deny an IP address or range of IP addresses. Extended access lists define both the source and the destination IP address or the IP address range. Extended access lists can also be defined to permit or deny packets based on TCP, UDP, or ICMP protocol types and the destination port number of the packet.

When access lists are used for packet classification, the deny match criteria are regarded as “do not match.” Packets matching an ACE cause an ACL matching of the current ACL to terminate. Thus, the ACL match results in failure and the next match within the class to be examined.

The following example shows how a packet received from 10.2.3.4 is matched with class `test1`. In this example, the access list 102 entry matches the deny condition and stops processing other entries in the access list. Because the class map has been specified with a match all attribute, the “class-map test1” match fails. However, it is inspected if it matches one of the protocols listed in `test1` class map.

If the class map `test1` had a match-any attribute (instead of match-all), then the ACL would have matched deny and failed, but then the ACL would have matched the HTTP protocol and performed the inspection using “pmap1.”


```
access-list 102 deny ip 10.2.3.4 0.0.0. any
access-list 102 permit any any
class-map type inspect match-all test1
match access-list 102
match protocol http
class-map type inspect match-any test2

match protocol sip
match protocol ftp
match protocol http

parameter-map type inspect pmap1
tcp idle-time 15

parameter-map type inspect pmap2
udp idle-time 3600

policy-map type inspect test
class type inspect test1

inspect pmap1
class type inspect test2
inspect pmap2

class type inspect class-default
drop log
```

Firewall and Network Address Translation

Network Address Translation (NAT) enables private IP internetworks that use nonregistered IP addresses to connect to the Internet. NAT operates on a router, usually connecting two networks together, and translates the private (not globally unique) addresses in the internal network into legal addresses before packets are forwarded onto another network. NAT can be configured to advertise only one address for the entire network to the outside world. A router configured with NAT will have at least one interface to the inside network and one to the outside network.

In a typical environment, NAT is configured at the exit router between a stub domain and the backbone. When a packet is leaving the domain, NAT translates the locally significant source address into a globally unique address. When a packet is entering the domain, NAT translates the globally unique destination address into a local address. If more than one exit point exists, each NAT must have the same translation table. If the software cannot allocate an address because it has run out of addresses, it drops the packet and sends an ICMP host unreachable packet.

With reference to NAT, the term “inside” refers to those networks that are owned by an organization and that must be translated. Inside this domain, hosts will have addresses in one address space, while when they are outside, they will appear to have addresses in another address space when NAT is configured. The first address space is referred to as the local address space and the second is referred to as the global address space.

Consider a scenario where NAT translates both the source and the destination IP addresses. A packet is sent to a router from inside NAT with source address 192.168.1.1 and destination address 10.1.1.1. NAT translates these addresses and sends the packet to the external network with source address 209.165.200.225 and destination address 209.165.200.224.

Similarly, when the response comes back from outside NAT, the source address will be 209.165.200.225 and the destination address will be 209.165.200.224. Therefore, on inside NAT, the packets will have a source of 10.1.1.1 and a destination address of 192.168.1.1.

In this scenario, if you want to create an ACE to be used in a firewall policy, the pre-NAT IP addresses (also known as inside local and outside global addresses) 192.168.1.1 and 209.165.200.224 must be used.

WAAS and Firewall Integration Support

The WAAS software optimizes security-compliant WANs and application acceleration solutions with the following benefits:

- Optimizes a WAN through full stateful inspection capabilities
- Simplifies Payment Card Industry (PCI) compliance
- Protects transparent WAN accelerated traffic
- Integrates WAAS networks transparently
- Supports the Network Management Equipment (NME) WAE modules or standalone WAAS device deployment

WAAS has an automatic discovery mechanism that uses TCP options during the initial three-way handshake used to identify WAE devices transparently. After automatic discovery, optimized traffic flows (paths) experience a change in the TCP sequence number to allow endpoints to distinguish between optimized and nonoptimized traffic flows.

**Note**

Paths are synonymous with connections.

The Cisco IOS XE firewall automatically discovers WAAS optimized traffic by enabling the sequence number to change without compromising the stateful Layer 4 inspection of TCP traffic flows that contain internal firewall TCP state variables. These variables are adjusted for the presence of WAE devices.

If the Cisco IOS XE firewall notices that a traffic flow has successfully completed WAAS automatic discovery, it permits the initial sequence number shift for the traffic flow and maintains the Layer 4 state on the optimized traffic flow.


WAAS Traffic Flow Optimization Deployment Scenarios

The following sections describe three different WAAS traffic flow optimization scenarios for branch office deployments. WAAS traffic flow optimization works with the Cisco IOS XE firewall feature on a Cisco Aggregation Services Router (ASR).

- [WAAS Branch Deployment with an Off-Path Device, page 11](#)
- [WAAS Branch Deployment with an Inline Device, page 12](#)

Figure 3 shows an example of an end-to-end WAAS traffic flow optimization with the Cisco IOS XE firewall. In this particular deployment, an NME-WAE device is on the same router as CISCO IOS Integrated Services Router (ISR). WCCP is used to redirect traffic for interception.

Figure 3 End-to-End WAAS Optimization Path



Note


NME-WAE is not supported on ASR. Therefore, to support NME-WAE in branch office, the RTR-BR must be an ISR.

WAAS Branch Deployment with an Off-Path Device

A WAE device can be either an NME-WAE that is installed on an ISR as an integrated service engine (as shown in Figure 3) or a standalone WAE device.

Figure 4 shows a WAAS branch deployment that uses WCCP to redirect traffic to an off-path, standalone WAE device for traffic interception. The configuration for this option is the same as the WAAS branch deployment with an NME-WAE.

Figure 4 WAAS Off-Path Branch Deployment




Note

The RTR-BR (as shown in Figure 4) can be an Aggregation Services Router (ASR).

WAAS Branch Deployment with an Inline Device

Figure 5 shows a WAAS branch deployment that has an inline WAE device that is physically in front of the ISR router. Because the WAE device is in front of the router, Layer 7 inspection on the client side is not supported because the Cisco IOS XE firewall receives WAAS optimized packets.

Figure 5 WAAS Inline Path Branch Deployment



An edge WAAS device with the Cisco IOS XE firewall is applied at branch office sites that must inspect traffic moving to and from a WAN connection. The Cisco IOS XE firewall monitors traffic for optimization indicators (TCP options and subsequent TCP sequence number changes) and allows optimized traffic to pass, while still applying Layer 4 stateful inspection and deep packet inspection to all traffic, maintaining security while accommodating WAAS optimization advantages.



Note

If the WAE device is in the inline location, the device enters its bypass mode after the automatic discovery process. Although the router is not directly involved in WAAS optimization, the router must be aware that WAAS optimization is applied to the traffic in order to apply the Cisco IOS XE firewall inspection to network traffic and make allowances for optimization activity if optimization indicators are present.

How to Configure Zone-Based Policy Firewall

- [Configuring Layer 3 and Layer 4 Firewall Policies, page 12](#)
- [Configuring an Inspect Parameter Map, page 15](#)
- [Configuring NetFlow Event Logging, page 17](#)
- [Creating Security Zones and Zone Pairs, and Attaching a Policy Map to a Zone Pair, page 19](#)
- [Configuring the Firewall with WAAS, page 21](#)
- [Configuring an LDAP-Enabled Firewall, page 25](#)

Configuring Layer 3 and Layer 4 Firewall Policies

Layer 3 and Layer 4 policies are “top level” policies that are attached to the target (zone pair). Use the following tasks to configure Layer 3 and Layer 4 firewall policies:

- [Configuring a Class Map for a Layer 3 and Layer 4 Firewall Policy, page 13](#)
- [Creating a Policy Map for a Layer 3 and Layer 4 Firewall Policy, page 14](#)

Configuring a Class Map for a Layer 3 and Layer 4 Firewall Policy

Perform the following task to configure a class map for classifying network traffic.



Note

You must perform at least one step from Step 4, 5, or 6.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **class-map type inspect** [**match-any** | **match-all**] *class-map-name*
4. **match access-group** {*access-group* | **name** *access-group-name*}
5. **match protocol** *protocol-name*
6. **exit**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	class-map type inspect [match-any match-all] <i>class-map-name</i> Example: Router(config)# class-map type inspect match-all cl	Creates a Layer 3 or Layer 4 inspect type class map. <ul style="list-style-type: none"> • Enters class map configuration mode.
Step 4	match access-group { <i>access-group</i> name <i>access-group-name</i> } Example: Router(config-cmap)# match access-group 101	Configures the match criteria for a class map based on the ACL name or number.
Step 5	match protocol <i>protocol-name</i> Example: Router(config-cmap)# match protocol ftp	Configures the match criteria for a class map on the basis of a specified protocol.
Step 6	exit Example: Router(config-cmap)# exit	Returns to global configuration mode.

Creating a Policy Map for a Layer 3 and Layer 4 Firewall Policy

Perform the following task to create a policy map for a Layer 3 and Layer 4 firewall policy that will be attached to zone pairs.

If you are creating an inspect type policy map, note that only the following actions are allowed: drop, inspect, and pass.



Note

You must perform at least one step from Step 5, 6, or 7.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **policy-map type inspect** *policy-map-name*
4. **class type inspect** *class-name*
5. **inspect** [*parameter-map-name*]
6. **drop** [**log**]
7. **pass** [**log**]
8. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none">Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	policy-map type inspect <i>policy-map-name</i> Example: Router(config)# policy-map type inspect p1	Creates a Layer 3 and Layer 4 inspect type policy map. <ul style="list-style-type: none">Enters policy-map configuration mode.
Step 4	class type inspect <i>class-name</i> Example: Router(config-pmap)# class type inspect c1	Specifies the traffic (class) on which an action is to be performed.
Step 5	inspect [<i>parameter-map-name</i>] Example: Router(config-pmap-c)# inspect inspect-params	Enables Cisco IOS XE stateful packet inspection.

	Command or Action	Purpose
Step 6	<code>drop [log]</code> Example: <code>Router(config-pmap-c)# drop</code>	(Optional) Drops packets that are matched with the defined class. Note The actions drop and pass are exclusive, and the actions inspect and drop are exclusive; that is, you cannot specify both of them.
Step 7	<code>pass [log]</code> Example: <code>Router(config-pmap-c)# pass</code>	(Optional) Allows packets that are matched with the defined class.
Step 8	<code>end</code> Example: <code>Router(config-pmap-c)# end</code>	Returns to privileged EXEC mode.

Configuring an Inspect Parameter Map

An inspect parameter map is optional if you are using an inspect type policy. If you do not configure a parameter map, the software uses default parameters. Parameters associated with the inspect action apply to all nested actions (if any). If parameters are specified in both the top and lower levels, those in the lower levels override those in the top levels.

Changes to the parameter map are not reflected on connections already established through the firewall. Changes are applicable only to new connections permitted to the firewall. To ensure that your firewall enforces policies strictly, clear all the connections allowed in the firewall after you change the parameter map. To clear existing connections, use the **clear zone-pair inspect sessions** command.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **parameter-map type inspect** *parameter-map-name*
4. **alert** {on | off}
5. **audit-trail** {on | off}
6. **dns-timeout** *seconds*
7. **icmp idle-time** *seconds*
8. **max-incomplete** {low | high} *number-of-connections*
9. **one-minute** {low | high} *number-of-connections*
10. **sessions maximum** *sessions*
11. **tcp finwait-time** *seconds*
12. **tcp idle-time** *seconds*
13. **tcp max-incomplete host** *threshold* [**block-time** *minutes*]
14. **tcp synwait-time** *seconds*
15. **udp idle-time** *seconds*

16. exit

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	parameter-map type inspect <i>parameter-map-name</i> Example: Router(config)# parameter-map type inspect eng-network-profile	Configures an inspect parameter map for connecting thresholds, timeouts, and other parameters pertaining to the inspect keyword. <ul style="list-style-type: none"> Enters parameter-map type inspect configuration mode.
Step 4	alert {on off} Example: Router(config-profile)# alert on	(Optional) Turns on and off stateful packet inspection alert messages that are displayed on the console.
Step 5	audit-trail {on off} Example: Router(config-profile)# audit-trail on	(Optional) Turns audit trail messages on or off.
Step 6	dns-timeout <i>seconds</i> Example: Router(config-profile)# dns-timeout 60	(Optional) Specifies the DNS idle timeout (the length of time for which a DNS lookup session will continue to be managed while there is no activity).
Step 7	icmp idle-time <i>seconds</i> Example: Router(config-profile)# icmp idle-timeout 90	(Optional) Configures the timeout for ICMP sessions.
Step 8	max-incomplete {low high} <i>number-of-connections</i> Example: Router(config-profile)# max-incomplete low 800	(Optional) Defines the number of existing half-open sessions that will cause the Cisco IOS firewall to start and stop deleting half-open sessions.
Step 9	one-minute {low high} <i>number-of-connections</i> Example: Router(config-profile)# one-minute low 300	(Optional) Defines the number of new unestablished sessions that will cause the system to start deleting half-open sessions and stop deleting half-open sessions.

	Command or Action	Purpose
Step 10	sessions maximum sessions Example: Router(config-profile)# sessions maximum 200	(Optional) Sets the maximum number of allowed sessions for the class it is associated with. <ul style="list-style-type: none"> <i>sessions</i>—Maximum number of allowed sessions. Range: 1 to 2147483647.
Step 11	tcp finwait-time seconds Example: Router(config-profile)# tcp finwait-time 5	(Optional) Specifies how long a TCP session will be managed after the firewall detects a FIN-exchange.
Step 12	tcp idle-time seconds Example: Router(config-profile)# tcp idle-time 90	(Optional) Configures the timeout for TCP sessions.
Step 13	tcp max-incomplete host threshold [block-time minutes] Example: Router(config-profile)# tcp max-incomplete host 500 block-time 10	(Optional) Specifies threshold and blocking time values for TCP host-specific DoS detection and prevention.
Step 14	tcp synwait-time seconds Example: Router(config-profile)# tcp synwait-time 3	(Optional) Specifies how long the software will wait for a TCP session to reach the established state before dropping the session.
Step 15	udp idle-time seconds Example: Router(config-profile)# udp idle-time 75	(Optional) Configures the idle timeout of UDP sessions going through the firewall.
Step 16	exit Example: Router(config-profile)# exit	Returns to global configuration mode.

Configuring NetFlow Event Logging

Global parameter maps are used for NetFlow event logging. With NetFlow event logging enabled, logs are sent to an off-box high-speed log collector. By default, this functionality is not enabled. (If this functionality is not enabled, firewall logs are sent to a logger buffer located in the Route Processor or console.)

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **parameter-map type inspect global**
4. **log dropped-packets**

5. **log flow-export v9 udp destination** *ipv4-address port*
6. **log flow-export template timeout-rate** *seconds*
7. **end**
8. **show parameter-map type inspect global**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	parameter-map type inspect global Example: Router(config)# parameter-map type inspect global	Configures a global parameter map. <ul style="list-style-type: none"> Enters profile configuration mode.
Step 4	log dropped-packets Example: Router(config-profile)# log dropped-packets	Enables dropped packet logging.
Step 5	log flow-export v9 udp destination <i>ipv4-address port</i> Example: Router(config-profile)# log flow-export v9 udp destination 192.0.2.0 5000	Enables NetFlow event logging and provides the collector's IP address and port.
Step 6	log flow-export template timeout-rate <i>seconds</i> Example: Router(config-profile)# log flow-export template timeout-rate 5000	Specifies the template timeout value.
Step 7	end Example: Router(config)# end	Exits global configuration mode and enters privileged EXEC mode.
Step 8	show parameter-map type inspect global Example: Router# show parameter-map type inspect global	Displays logging configurations.

Creating Security Zones and Zone Pairs, and Attaching a Policy Map to a Zone Pair

You need two security zones to create a zone pair. However, you can create only one security zone and use a system-defined security zone called “self.” Note that if you select a self zone, you cannot configure inspect policing. An inspect policy can be present between a zone-self or self-zone zone pair.

Use this process to complete the following tasks:

- Create at least one security zone
- Define zone pairs
- Assign interfaces to security zones
- Attach a policy map to a zone pair



Tip

Before you create zones, think about what should constitute the zones. The general guideline is that you should group interfaces that are similar when they are viewed from a security perspective.

Security Zone Restrictions

- An interface can be a member of only one security zone.
- When an interface is a member of a security zone, all traffic to and from that interface is blocked unless you configure an explicit interzone policy on a zone pair involving that zone.
- Traffic cannot flow between an interface that is a member of a security zone and an interface that is not a member of a security zone because a policy can be applied only between two zones.
- For traffic to flow among all the interfaces in a router, all the interfaces must be members of one security zone or another. This is particularly important because after you make an interface a member of a security zone, a policy action (such as inspect or pass) must explicitly allow packets. Otherwise, packets are dropped.
- If an interface on a router cannot be part of a security zone or firewall policy, you may have to put that interface in a security zone and configure a “pass all” policy (that is, a “dummy” policy) between that zone and other zones to which a traffic flow is desired.
- An ACL on an interface that is a zone member should not be restrictive (strict).
- Traffic between interfaces in the same security zone is not subjected to any policy; the traffic passes freely. If you have created only one zone, you can use the system-defined default zone (self) as part of a zone pair. Such a zone pair and its associated policy applies to the traffic directed to the router or generated by the router.
- You can use the **default** keyword to include all the interfaces that are not configured on any of the security zones. In the default zone, the policy can be defined either as a source zone or a destination zone.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **zone security** {*zone-name* | **default**}
4. **description** *line-of-description*

5. **exit**
6. **zone-pair security** *zone-pair-name* [**source** {*source-zone-name* | **self** | **default**} **destination** [*destination-zone-name* | **self** | **default**]]
7. **description** *line-of-description*
8. **service-policy type inspect** *policy-map-name*
9. **exit**
10. **interface** *type number*
11. **zone-member security** *zone-name*
12. **exit**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	zone security { <i>zone-name</i> default } Example: Router(config)# zone security zone1	Creates a security zone to which interfaces can be assigned and enters security zone configuration mode.
Step 4	description <i>line-of-description</i> Example: Router(config-sec-zone)# description Internet Traffic	(Optional) Describes the zone.
Step 5	exit Example: Router(config-sec-zone)# exit	Returns to global configuration mode.
Step 6	zone-pair security <i>zone-pair-name</i> [source { <i>source-zone-name</i> self default } destination [<i>destination-zone-name</i> self default]] Example: Router(config)# zone-pair security self-default-zp source self destination zone1	Creates a zone pair and enters security zone configuration mode. Note To apply a policy, you must configure a zone pair.
Step 7	description <i>line-of-description</i> Example: Router(config-sec-zone)# description accounting network	(Optional) Describes the zone pair and enters security zone pair configuration mode.

	Command or Action	Purpose
Step 8	service-policy type inspect <i>policy-map-name</i> Example: Router(config-sec-zone-pair)# service-policy type inspect p1	Attaches a firewall policy map to the destination zone pair. Note If a policy is not configured between a pair of zones, traffic is dropped by default.
Step 9	exit Example: Router(config-sec-zone-pair)# exit	Returns to global configuration mode.
Step 10	interface <i>type number</i> Example: Router(config)# interface gigabitethernet 0	Specifies an interface for configuration and enters interface configuration mode.
Step 11	zone-member security <i>zone-name</i> Example: Router(config-if)# zone-member security zone1	Assigns an interface to a specified security zone. Note When you make an interface a member of a security zone, all traffic into and out of that interface (except traffic bound for the router or initiated by the router) is dropped by default. To let traffic through the interface, you must make the zone part of a zone pair to which you apply a policy. If the policy permits traffic, traffic can flow through that interface.
Step 12	exit Example: Router(config-if)# exit	Returns to global configuration mode.

Configuring the Firewall with WAAS

Perform the following task to configure an end-to-end WAAS traffic flow optimization for the firewall that uses WCCP to redirect traffic to a WAE device for traffic interception.

In Cisco IOS XE software, WAAS support is always enabled and WAAS processing is always discovered. Thus, the **ip inspect waas enable** command is not necessary and therefore not supported.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **ip wccp** *service-id*
4. **class-map type inspect** [**match-any** | **match-all**] *class-map-name*
5. **match protocol** *protocol-name*
6. **exit**
7. **policy-map type inspect** *policy-map-name*
8. **class type inspect** *class-name*

9. **inspect**
10. **class class-default**
11. **exit**
12. **exit**
13. **zone security** {*zone-name* | **default**}
14. **description** *line-of-description*
15. **exit**
16. **zone-pair security** *zone-pair-name* [**source** {*source-zone-name* | **self** | **default**} **destination** {*destination-zone-name* | **self** | **default**}]
17. **description** *line-of-description*
18. **service-policy type inspect** *policy-map-name*
19. **exit**
20. **interface** *type number*
21. **description** *line-of-description*
22. **zone-member security** *zone-name*
23. **ip address** *ip-address mask*
24. **ip wccp** {*service-id* {**group-listen** | **redirect** {**in** | **out**}} | **redirect exclude in** | **web-cache** {**group-listen** | **redirect** {**in** | **out**}}}
25. **exit**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	ip wccp <i>service-id</i> Example: Router(config)# ip wccp 61	Enters the WCCP dynamically defined service identifier number.
Step 4	class-map type inspect [match-any match-all] <i>class-map-name</i> Example: Router(config)# class-map type inspect match-any most-traffic	Creates an inspect type class map for the traffic class and enters class map configuration mode. Note The class-map type inspect most-traffic command is hidden.

	Command or Action	Purpose
Step 5	<p>match protocol <i>protocol-name</i></p> <p>Example: Router(config-cmap)# match protocol http</p>	<p>Configures the match criteria for a class map on the basis of a specified protocol and enters security zone configuration mode.</p> <ul style="list-style-type: none"> Only Cisco IOS XE stateful packet inspection supported protocols can be used as match criteria in inspect type class maps. signature—Signature-based classification for peer-to-peer (P2P) packets is enabled.
Step 6	<p>exit</p> <p>Example: Router(config-cmap)# exit</p>	<p>Returns to global configuration mode.</p>
Step 7	<p>policy-map type inspect match-any <i>policy-map-name</i></p> <p>Example: Router(config)# policy-map type inspect match-any pl</p>	<p>Creates a Layer 3 and Layer 4 inspect type policy map and enters policy-map configuration mode.</p>
Step 8	<p>class type inspect <i>class-name</i></p> <p>Example: Router(config-pmap)# class type inspect most-traffic</p>	<p>Specifies the firewall traffic (class) map on which an action is to be performed.</p> <ul style="list-style-type: none"> Enters policy-map class configuration mode.
Step 9	<p>inspect</p> <p>Example: Router(config-pmap-c)# inspect</p>	<p>Enables Cisco IOS XE stateful packet inspection.</p>
Step 10	<p>class class-default</p> <p>Example: Router(config-pmap-c)# class class-default</p>	<p>Specifies the matching of the system default class.</p> <ul style="list-style-type: none"> If the system default class is not to be specified, then unclassified packets are matched.
Step 11	<p>exit</p> <p>Example: Router(config-pmap-c)# exit</p>	<p>Returns to policy-map configuration mode.</p>
Step 12	<p>exit</p> <p>Example: Router(config-pmap)# exit</p>	<p>Returns to global configuration mode.</p>
Step 13	<p>zone security {<i>zone-name</i> default}</p> <p>Example: Router(config)# zone security zone1</p>	<p>Creates a security zone to which interfaces can be assigned and enters security zone configuration mode.</p>

	Command or Action	Purpose
Step 14	<p>description <i>line-of-description</i></p> <p>Example: Router(config-sec-zone)# description Internet Traffic</p>	(Optional) Describes the zone.
Step 15	<p>exit</p> <p>Example: Router(config-sec-zone)# exit</p>	Returns to global configuration mode.
Step 16	<p>zone-pair security <i>zone-pair-name</i> [source {<i>source-zone-name</i> self default} destination [<i>destination-zone-name</i> self default]]</p> <p>Example: Router(config)# zone-pair security self-default-zp source self destination zone1</p>	<p>Creates a zone pair and enters security zone configuration mode.</p> <p>Note To apply a policy, you must configure a zone pair.</p>
Step 17	<p>description <i>line-of-description</i></p> <p>Example: Router(config-sec-zone-pair)# description accounting network</p>	(Optional) Describes the zone pair.
Step 18	<p>service-policy type inspect <i>policy-map-name</i></p> <p>Example: Router(config-sec-zone-pair)# service-policy type inspect pl</p>	<p>Attaches a firewall policy map to the destination zone pair.</p> <p>Note If a policy is not configured between a pair of zones, traffic is dropped by default.</p>
Step 19	<p>exit</p> <p>Example: Router(config-sec-zone)# exit</p>	Returns to global configuration mode.
Step 20	<p>interface <i>type number</i></p> <p>Example: Router(config)# interface gigabitethernet 0</p>	Specifies an interface and enters interface configuration mode.
Step 21	<p>description <i>line-of-description</i></p> <p>Example: Router(config-if)# description 123</p>	(Optional) Describes the interface.

	Command or Action	Purpose
Step 22	<p>zone-member security zone-name</p> <p>Example: Router(config-if)# zone-member security zone1</p>	<p>Assigns an interface to a specified security zone.</p> <p>Note When you make an interface a member of a security zone, all traffic into and out of that interface (except traffic bound for the router or initiated by the router) is dropped by default. To let traffic through the interface, you must make the zone part of a zone pair to which you apply a policy. If the policy permits traffic, traffic can flow through that interface.</p>
Step 23	<p>ip address ip-address mask</p> <p>Example: Router(config-if)# ip address 10.70.0.1 255.255.255.0</p>	<p>Assigns the interface IP address for the security zone.</p>
Step 24	<p>ip wccp {service-id {group-listen redirect {in out}} redirect exclude in web-cache {group-listen redirect {in out}}}</p> <p>Example: Router(config-if)# ip wccp 61 redirect in</p>	<p>Specifies the following WCCP parameters on the interface:</p> <ul style="list-style-type: none"> • The <i>service-id</i> argument defines a service identifier number from 1 to 254. • The redirect exclude in keywords are used to exclude inbound packets from outbound redirection. • The web-cache keyword is used to define the standard web caching service. • The group-listen keyword is used for discovering multicast WCCP protocol packets. • The in keyword is used to redirect to a cache engine the appropriate inbound packets. • The out keyword is used to redirect to a cache engine the appropriate outbound packets.
Step 25	<p>exit</p> <p>Example: Router(config-if)# exit</p>	<p>Returns to global configuration mode.</p>

Configuring an LDAP-Enabled Firewall

Lightweight Directory Access Protocol (LDAP) is an application protocol that is used for querying and updating information stored on directory servers. The LDAP-Enabled Firewall feature enables Cisco firewalls to support Layer 4 LDAP inspection by default. Perform the following task to configure an LDAP-enabled firewall.

Prerequisites

You can configure an LDAP-enabled firewall in interface configuration mode or in global configuration mode. Before you configure an LDAP-enabled firewall in interface configuration mode, you must have configured a zone using the **zone security** command.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **zone security** {*zone-name* | **default**}
4. **exit**
5. **zone security** {*zone-name* | **default**}
6. **exit**
7. **class-map type inspect** [**match-any** | **match-all**] *class-map-name*
8. **match protocol** *protocol-name*
9. **exit**
10. **policy-map type inspect** *policy-map-name*
11. **class type inspect** *class-name*
12. **inspect**
13. **class class-default**
14. **exit**
15. **exit**
16. **zone-pair security** *zone-pair-name* [**source** {*source-zone-name* | **self** | **default**} **destination** {*destination-zone-name* | **self** | **default**}]
17. **service-policy type inspect** *policy-map-name*
18. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	zone security { <i>zone-name</i> default } Example: Router(config)# zone security private	Creates a security zone to which interfaces can be assigned and enters security zone configuration mode.
Step 4	exit Example: Router(config-sec-zone)# exit	Returns to global configuration mode.

	Command or Action	Purpose
Step 5	<p>zone security {<i>zone-name</i> default}</p> <p>Example: Router(config)# zone security internet</p>	Creates a security zone to which interfaces can be assigned and enters security zone configuration mode.
Step 6	<p>exit</p> <p>Example: Router(config-sec-zone)# exit</p>	Returns to global configuration mode.
Step 7	<p>class-map type inspect [match-any match-all] <i>class-map-name</i></p> <p>Example: Router(config)# class-map type inspect match-any internet-traffic-class</p>	Creates an inspect type class map for the traffic class and enters class map configuration mode. Note The class-map type inspect most-traffic command is hidden.
Step 8	<p>match protocol <i>protocol-name</i></p> <p>Example: Router(config-cmap)# match protocol ldap</p>	Configures the match criteria for a class map on the basis of a specified protocol.
Step 9	<p>exit</p> <p>Example: Router(config-cmap)# exit</p>	Returns to global configuration mode.
Step 10	<p>policy-map type inspect match-any <i>policy-map-name</i></p> <p>Example: Router(config)# policy-map type inspect private-internet-policy</p>	Creates a Layer 3 and Layer 4 inspect type policy map and enters policy-map configuration mode.
Step 11	<p>class type inspect <i>class-name</i></p> <p>Example: Router(config-pmap)# class type inspect internet-traffic-class</p>	Specifies the firewall traffic (class) map on which an action is to be performed. <ul style="list-style-type: none"> Enters policy-map class configuration mode.
Step 12	<p>inspect</p> <p>Example: Router(config-pmap-c)# inspect</p>	Enables Cisco IOS XE stateful packet inspection.
Step 13	<p>class class-default</p> <p>Example: Router(config-pmap-c)# class class-default</p>	Specifies the matching of the system default class. <ul style="list-style-type: none"> If the system default class is not to be specified, then unclassified packets are matched.
Step 14	<p>exit</p> <p>Example: Router(config-pmap-c)# exit</p>	Returns to policy-map configuration mode.

	Command or Action	Purpose
Step 15	exit Example: Router(config-pmap)# exit	Returns to global configuration mode.
Step 16	zone-pair security zone-pair-name [source {source-zone-name self default} destination {destination-zone-name self default}] Example: Router(config)# zone-pair security private-internet source private destination internet	Creates a zone pair and enters security zone configuration mode. Note To apply a policy, you must configure a zone pair.
Step 17	service-policy type inspect policy-map-name Example: Router(config-sec-zone-pair)# service-policy type inspect private-internet-policy	Attaches a firewall policy map to the destination zone pair. Note If a policy is not configured between a pair of zones, traffic is dropped by default.
Step 18	end Example: Router(config-sec-zone-pair)# end	Returns to privileged EXEC mode.

Configuring an SCCP-Enabled Firewall

SCCP enables voice communication between two Skinny clients through the use of a Cisco Unified Call Manager. The SCCP-Enabled Firewall feature enables Cisco firewalls to inspect Skinny control packets that are exchanged between a Skinny client and the Call Manager. Perform the following task to configure an SCCP-enabled firewall.

Prerequisites

When you enable SCCP (through the **match protocol** command) in a firewall configuration, you must also enable TFTP (through the **match protocol** command); otherwise, the IP phones that use SCCP cannot communicate with the Cisco Unified Call Manager.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **class-map type inspect [match-any | match-all] class-map-name**
4. **match protocol protocol-name**
5. **match protocol protocol-name**
6. **exit**
7. **policy-map type inspect match-any policy-map-name**
8. **class type inspect class-name**

9. **inspect**
10. **class class-default**
11. **exit**
12. **exit**
13. **zone security** {*zone-name* | **default**}
14. **exit**
15. **zone security** {*zone-name* | **default**}
16. **exit**
17. **zone-pair security** *zone-pair-name* [**source** {*source-zone-name* | **self** | **default**} **destination** {*destination-zone-name* | **self** | **default**}]
18. **service-policy type inspect** *policy-map-name*
19. **exit**
20. **interface** *type number*
21. **zone-member security** *zone-name*
22. **interface** *type number*
23. **zone-member security** *zone-name*
24. **exit**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none">Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	class-map type inspect [match-any match-all] <i>class-map-name</i> Example: Router(config)# class-map type inspect match-any internet-traffic-class	Creates an inspect type class map for the traffic class and enters class map configuration mode. Note The class-map type inspect most-traffic command is hidden.
Step 4	match protocol <i>protocol-name</i> Example: Router(config-cmap)# match protocol skinny	Configures SCCP as the match criteria for the class map.
Step 5	match protocol <i>protocol-name</i> Example: Router(config-cmap)# match protocol tftp	Configures TFTP as the match criteria for the class map.

	Command or Action	Purpose
Step 6	exit Example: Router(config-cmap)# exit	Returns to global configuration mode.
Step 7	policy-map type inspect <i>policy-map-name</i> Example: Router(config)# policy-map type inspect p1	Creates a Layer 3 and Layer 4 inspect type policy map and enters policy-map configuration mode.
Step 8	class type inspect <i>class-name</i> Example: Router(config-pmap)# class type inspect c-appl	Specifies the firewall traffic (class) map on which an action is to be performed. <ul style="list-style-type: none"> Enters policy-map class configuration mode.
Step 9	inspect Example: Router(config-pmap-c)# inspect	Enables Cisco IOS XE stateful packet inspection.
Step 10	class class-default Example: Router(config-pmap-c)# class class-default	Specifies the matching of the system default class. <ul style="list-style-type: none"> If the system default class is not to be specified, then unclassified packets are matched.
Step 11	exit Example: Router(config-pmap-c)# exit	Returns to policy-map configuration mode.
Step 12	exit Example: Router(config-pmap)# exit	Returns to global configuration mode.
Step 13	zone security { <i>zone-name</i> default } Example: Router(config)# zone security z-in	Creates a security zone to which interfaces can be assigned and enters security zone configuration mode.
Step 14	exit Example: Router(config-sec-zone)# exit	Returns to global configuration mode.
Step 15	zone security { <i>zone-name</i> default } Example: Router(config)# zone security z-out	Creates a security zone to which interfaces can be assigned and enters security zone configuration mode.
Step 16	exit Example: Router(config-sec-zone)# exit	Returns to global configuration mode.

	Command or Action	Purpose
Step 17	<p>zone-pair security <i>zone-pair-name</i> [source {<i>source-zone-name</i> self default} destination [<i>destination-zone-name</i> self default]]</p> <p>Example: Router(config)# zone-pair security in2out source z-in destination z-out</p>	<p>Creates a zone pair and enters security zone configuration mode.</p> <p>Note To apply a policy, you must configure a zone pair.</p>
Step 18	<p>service-policy type inspect <i>policy-map-name</i></p> <p>Example: Router(config-sec-zone-pair)# service-policy type inspect p1</p>	<p>Attaches a firewall policy map to the destination zone pair.</p> <p>Note If a policy is not configured between a pair of zones, traffic is dropped by default.</p>
Step 19	<p>exit</p> <p>Example: Router(config-sec-zone-pair)# exit</p>	<p>Returns to global configuration mode.</p>
Step 20	<p>interface <i>type number</i></p> <p>Example: Router(config)# interface gigabitethernet 0/0/0</p>	<p>Specifies an interface for configuration and enters interface configuration mode.</p>
Step 21	<p>zone-member security <i>zone-name</i></p> <p>Example: Router(config-if)# zone-member security z-in</p>	<p>Assigns an interface to a specified security zone.</p> <p>Note When you make an interface a member of a security zone, all traffic into and out of that interface (except traffic bound for the router or initiated by the router) is dropped by default. To let traffic through the interface, you must make the zone part of a zone pair to which you apply a policy. If the policy permits traffic, traffic can flow through that interface.</p>
Step 22	<p>interface <i>type number</i></p> <p>Example: Router(config-if)# interface gigabitethernet 0/0/1</p>	<p>Specifies an interface for configuration.</p>
Step 23	<p>zone-member security <i>zone-name</i></p> <p>Example: Router(config-if)# zone-member security z-out</p>	<p>Assigns an interface to a specified security zone.</p>

Configuration Examples for Zone-Based Policy Firewall

- [Example: Configuring a Policy-Map and Zone-Based Firewall, page 32](#)
- [Example: Firewall Configuration with WAAS, page 32](#)
- [Example: LDAP-Enabled Firewall Configuration, page 33](#)
- [Example: SCCP-Enabled Firewall Configuration, page 34](#)

Example: Configuring a Policy-Map and Zone-Based Firewall

The following example shows how to configure a policy map and allow TCP flows to pass from the private to public firewall zones:

```
class-map type inspect match-all no-http-inspect
match access-group 199
match protocol tcp

policy-map type inspect no-http-inspect
class type inspect no-http-inspect
inspect
class class-default
!
zone security private
zone security public
zone-pair security zp source private destination public
service-policy type inspect test
!
interface GigabitEthernet 0/1/0.1
encapsulation dot1Q 2
ip address 10.1.1.1 255.255.255.0
zone-member security private
!
interface GigabitEthernet 0/1/0.2
encapsulation dot1Q 3
ip address 10.2.1.1 255.255.255.0
zone-member security private
!
interface GigabitEthernet 0/1/1.1
encapsulation dot1Q 2
ip address 10.1.1.1 255.255.255.0
zone-member security public
!
interface GigabitEthernet 0/1/1.2
encapsulation dot1Q 3
ip address 10.2.1.1 255.255.255.0
zone-member security public
!
```

Example: Firewall Configuration with WAAS

The following example provides an end-to-end WAAS traffic flow optimization configuration for the firewall that uses WCCP to redirect traffic to a WAE device for traffic interception.

The following configuration example prevents traffic from being dropped between security zone members because the integrated-service-engine interface is configured on a different zone and each security zone member is assigned an interface.

```
ip wccp 61
ip wccp 62
class-map type inspect match-any most-traffic
match protocol icmp
match protocol ftp
match protocol tcp
match protocol udp
policy-map type inspect p1
class type inspect most-traffic
inspect
class class-default
```



```

zone security zone-hr
zone security zone-outside
zone security z-waas
zone-pair security hr-out source zone-hr destination zone-outside
  service-policy type inspect p1
zone-pair security out-hr source zone-outside destination zone-hr
  service-policy type inspect p1
zone-pair security eng-out source zone-eng destination zone-outside
  service-policy type inspect p1

interface GigabitEthernet 0/0/0
  description Trusted Interface
  ipaddress 10.70.0.1 255.0.0.0
  ip wccp 61 redirect in
  zone-member security zone-hr

interface GigabitEthernet 0/0/1
  description Trusted Interface
  ipaddress 10.71.0.2 255.0.0.0
  ip wccp 61 redirect in
  zone-member security zone-eng

interface GigabitEthernet 0/0/1
  description Untrusted Interface
  ipaddress 10.72.2.3 255.0.0.0
  ip wccp 62 redirect in
  zone-member security zone-outside

interface Integrated-Service-Engine 1/0
  ipaddress 10.70.100.1 255.0.0.0
  ip wccp redirect exclude in
  zone-member security z-waas

```

Example: LDAP-Enabled Firewall Configuration

The following example shows how to configure a firewall policy to inspect Layer 4 LDAP messages:

Interface Configuration

```

interface GigabitEthernet 0/1/5
  ip address 192.168.0.1 255.255.255.0
  zone-member security private
  no shutdown

interface GigabitEthernet 0/1/6
  ip address 192.168.1.1 255.255.255.0
  zone-member security internet
  no shutdown

```

Global Firewall Configuration

```

zone security private
zone security internet
class-map type inspect match-any internet-traffic-class
  match protocol ldap
  match protocol ldaps
  match protocol ldap-admin
policy-map type inspect private-internet-policy
  class type inspect internet-traffic-class
    inspect
  class class-default
zone-pair security private-internet source private destination internet

```

```
service-policy type inspect private-internet-policy
```

Example: SCCP-Enabled Firewall Configuration

The following example shows how to enable SCCP in a firewall configuration:

```
class-map type inspect match-any c-appl
  match protocol sccp
  match protocol tftp
policy-map type inspect p1
  class type inspect c-appl
    inspect
  class class-default
zone security z-in
zone security z-out
zone-pair security in2out source z-in destination z-out
  service-policy type inspect p1
interface gigabitethernet 0/1/5
zone-member security z-in
interface gigabitethernet 0/1/
zone-member security z-out
```

Additional References

Related Documents

Related Topic	Document Title
Cisco IOS commands	Cisco IOS Master Commands List, All Releases
Security commands	Cisco IOS Security Command Reference
Quality of Service commands	Cisco IOS Quality of Service Solutions Command Reference

Standards

Standard	Title
No new or modified standards are supported by this release.	—

MIBs

MIB	MIBs Link
None	To locate and download MIBs for selected platforms, Cisco software releases, and feature sets, use Cisco MIB Locator found at the following URL: http://www.cisco.com/go/mibs

RFCs

RFC	Title
RFC 4511	<i>Lightweight Directory Access Protocol (LDAP): The Protocol</i>

Technical Assistance

Description	Link
The Cisco Support and Documentation website provides online resources to download documentation, software, and tools. Use these resources to install and configure the software and to troubleshoot and resolve technical issues with Cisco products and technologies. Access to most tools on the Cisco Support and Documentation website requires a Cisco.com user ID and password.	http://www.cisco.com/cisco/web/support/index.html

Feature Information for Zone-Based Policy Firewall

Table 1 lists the features in this module and provides links to specific configuration information.

Use Cisco Feature Navigator to find information about platform support and software image support. Cisco Feature Navigator enables you to determine which software images support a specific software release, feature set, or platform. To access Cisco Feature Navigator, go to <http://www.cisco.com/go/cfn>. An account on Cisco.com is not required.


Note

Table 1 lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Table 1 Feature Information for Zone-Based Policy Firewall

Feature Name	Releases	Feature Configuration Information
Firewall—NetMeeting Directory (LDAP) ALG Support	Cisco IOS XE Release 2.4	<p>LDAP is an application protocol that is used for querying and updating information stored on directory servers. This feature enables Cisco Firewalls to support Layer 4 LDAP inspection by default.</p> <p>The following section provides information about this feature:</p> <ul style="list-style-type: none"> • Configuring an LDAP-Enabled Firewall, page 25 • Example: LDAP-Enabled Firewall Configuration, page 33 <p>The following command was modified: match protocol.</p>
Firewall—SCCP Video ALG Support	Cisco IOS XE Release 2.4	<p>SCCP enables voice communication between two Skinny clients through the use of a Cisco Unified Call Manager. This feature enables Cisco firewalls to inspect Skinny control packets that are exchanged between a Skinny client and the Call Manager.</p> <p>The following section provides information about this feature:</p> <ul style="list-style-type: none"> • Configuring an SCCP-Enabled Firewall, page 28 • Example: SCCP-Enabled Firewall Configuration, page 34 <p>The following command was modified: match protocol.</p>

Table 1 **Feature Information for Zone-Based Policy Firewall (continued)**

Feature Name	Releases	Feature Configuration Information
NAT High Speed Logging (HSL) Support	Cisco IOS XE Release 2.1	<p>This feature introduces support for firewall High Speed Logging (HSL) using NetFlow v9 as the export format.</p> <p>The following section provides information about this feature:</p> <ul style="list-style-type: none"> • Configuring NetFlow Event Logging, page 17. <p>The following commands were introduced to support this feature: log dropped-packet, log flow-export v9 udp destination, log flow-export template timeout-rate, parameter-map type inspect global.</p>
Zone-Based Policy Firewall	Cisco IOS XE Release 2.1	<p>This feature provides a Cisco IOS XE software unidirectional firewall policy between groups of interfaces known as zones.</p>
Zone-Based Firewall—Default zone	Cisco IOS XE Release 2.6	<p>A default zone enables a firewall policy to be configured on a zone pair that consist of a zone and a default zone. Any interface without explicit zone membership belongs to a default zone.</p> <p>The following commands were modified: zone-pair security and zone security.</p>

Cisco and the Cisco Logo are trademarks of Cisco Systems, Inc. and/or its affiliates in the U.S. and other countries. A listing of Cisco's trademarks can be found at www.cisco.com/go/trademarks. Third party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1005R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

© 2006–2011 Cisco Systems, Inc. All rights reserved.

