



## Logging Syslog Messages

---

Logging messages via syslog provides centralized error reporting for Cisco Access Registrar. Local logging and syslog logging can be turned on or off at any time by modifying the control flags in the `$INSTALLPATH/conf/aic.conf` file.

Logging syslog messages requires a UNIX host running a *syslog daemon* as a receiver for Cisco Access Registrar messages. Cisco Access Registrar and the syslog daemon can be running on the same host or different hosts.

### syslog Messages

Messages that are sent to the following logs will be forwarded to syslog server in a slightly different format. The logs are:

- `aregcmd_log`
- `config_mcd_[1..n]_log`
- `name_radius_[1..n]_log`
- `agent_server_[1..n]_log`

The messages are in the following format:

```
MMM DD hh:mm:ss hostname %CAR-[severity]-[mnemonic]: [#n], [System|Server]:  
message_description
```

Where:

**MMM DD** is the month and date that the message is received by the syslog server

**hh:mm:ss** is the arrival time of the message

**hostname** is the name of the syslog server

**severity** is one of the following levels:

- 0 - emergency
- 1 - alert
- 2 - critical
- 3 - error
- 4 - warning
- 5 - notification
- 6 - informational

7 - debugging

**mnemonic** can be *aregcmd*, *name\_radius*, *agent\_server* and *config\_mcd* for the identification of AR subsystems that the message relates to.

**#n** is the id for the components: *name\_radius*, *agent\_server*, and *config\_mcd*

**message\_description** provides detailed information of the message

## Example 1

```
May 19 14:28:44 dwlau-ultra2.cisco.com
%CAR-3-name_radius: #1, System: Remote LDAP Server.Unable to bind.
```

## Example 2

```
May 19 14:28:45 dwlau-ultra2.cisco.com
%CAR-6-name_radius: #1, Server: Stopping server
```

# Configuring Message Logging

Message logging is on by default, and all logs are stored in the **\$INSTALL/logs** directory. To turn logging off, or to change the location where logs are stored, you must modify the **\$INSTALLPATH/conf/aic.conf** file.

In **\$INSTALLPATH/conf/aic.conf** file, the following lines control logging.

```
LOCAL_LOGGING [ON|OFF]
LOGDIR full_path
DATADIR full_path
SYSLOG_LOGGING [ON|OFF]
SERVER_IP_ADDRESS [ip_address]
FACILITY_LOCAL_NUMBER [0..7]
```

Where:

**LOCAL\_LOGGING** enables (ON) or disables (OFF) the local logging function. (Local logging is on by default.)

**LOGDIR** specifies a full pathname to a different local log directory.

**DATADIR** specifies a full pathname to a different data directory.

**SYSLOG\_LOGGING** enables (ON) or disables (OFF) the syslog logging function. (syslog logging is on by default.)

**SERVER\_IP\_ADDRESS** specifies the IP address of the host to which AR will send syslog messages.

**FACILITY\_LOCAL\_NUMBER** specifies the facility being used by the syslogd.

The following is an example

```
LOCAL_LOGGING OFF
SYSLOG_LOGGING ON
```

```
SERVER_IP_ADDRESS 209.165.200.224
FACILITY_LOCAL_NUMBER 7
```

**Note**

You must first stop the CAR server prior to changing the **aic.conf** file, then restart the server. If you change the directory location where logs or database data are stored, you should also copy all log files or data files to that same directory before restarting the CAR server.

## Changing Log Directory

You can change the directory where local log messages are stored by adding the following line in the **\$INSTALLPATH/conf/aic.conf** file.

```
LOGDIR full_path
```

Where *full\_path* is a full path to the directory where you want to store the log messages. For example, to store all system logs in **/var/log/AICar1**, add the following line in the **\$INSTALLPATH/conf/aic.conf** file:

```
LOGDIR /var/log/AICar1
```

You must first stop the CAR server prior to changing the **aic.conf** file. After changing the **aic.conf** file, copy all existing log files to the new directory, then restart the server.

**Note**

Specifying a path for local logging does not affect the storage location of syslog messages.

## Configuring syslog Daemon (syslogd)

You must specify the facility from which *syslogd* will receive messages and the file into which the messages will be deposited.

In the syslog server's **/etc/syslog.conf** file, the following line may be needed.

```
localn.info <tab> <tab> <tab> /var/log/filename.log
```

**Note**

Use at least one <tab> as a field separator.

Where:

**local*n***—is the facility being used for **syslogd**; ***n*** must be a value from 0-7 and match the **FACILITY\_LOCAL\_NUMBER** used in AR's **aic.conf** file.

**/var/log/**—is the path to the file that stores **syslogd** messages.

**filename.log**—is the file that stores **syslogd** messages. You may give this file a name of your choice.

### Creating a Log File

To create a syslog log file, complete the following steps:

- 
- Step 1** Log in as user **root**.
- Step 2** Enter the following command, where **filename.log** is a name you choose.
- ```
touch filename.log
```
- Step 3** Change permissions on the syslog log file by entering the following:
- ```
chmod 664 filename.log
```
- 

## Restarting syslogd

To restart the **syslog** daemon, log in as user **root** and enter the following commands:

```
/etc/init.d/syslog stop
/etc/init.d/syslog start
```

# Managing the Syslog File

Left unmanaged, the **syslog** file will grow in size over time and eventually fill all available disk space in its partition. Cisco recommends that you use the **cron** program to manage the syslog files.

The following example **crontab** file performs a weekly archival of the existing **syslog** file (named **ar\_syslog.log** in this example). This scheme keeps the previous two week's worth of **syslog** files.

```
#
# At 02:01am on Sundays:
# Move a weeks worth of 'ar_syslog.log' log messages to 'ar_syslog.log.1'.
# If there was a 'ar_syslog.log.1' move it to 'ar_syslog.log.2'.
# If there was a 'ar_syslog.log.2' then it is lost.
01 02 * * 0 cd /var/log;
if [ -f ar_syslog.log ];
then if [ -f ar_syslog.log.1 ];
then /bin/mv ar_syslog.log.1 ar_syslog.log.2;
fi;
/usr/bin/cp ar_syslog.log ar_syslog.log.1;
>ar_syslog.log;
fi
```




---

**Note** Consider using move (**mv**) or copy (**cp**) commands to store the previous week's syslog files in a different disk partition to reserve space for the current syslog file.

---

To add this **crontab** segment to the existing **cron** facility in **/usr/spool/cron/crontabs** directory, complete the following steps at the syslog server console.

- 
- Step 1** Log in as user **root**.
- Step 2** Enter the following commands:

**crontab -e**

---

## Server Up/Down Status Change Logging

Cisco Access Registrar supports RADIUS server up/down detection and logging. The information messages are saved in the **\$INSTALL/logs/name\_radius\_1\_log** file where **\$INSTALL** is the Cisco Access Registrar installation directory. Each message consists of a header and a message description.

### Header Formats

The format of a header entry is:

*mm/dd/yyyy HH:MM:SS name/radius/n Error Server 0*

### Example Log Messages

Following are the descriptions and types of messages that can be found within the **<AR\_install\_dir>/logs/name\_radius\_1\_log** file.

1. Cisco Access Registrar detects a Remote Server when it responds for the first time or after it is reentered into Cisco Access Registrar's server pool for retry. The format of the message is:

Remote Server *<hostname>* (*<ipaddress>*:*<port>*) is UP!

The following is an example header and message:

```
09/14/1999 17:56:32 name/radius/1 Error Server 0
Remote Server dave-ultra (171.69.237.99:1645) is UP!
```

Cisco Access Registrar detects the Remote Server is not responding to its request. The format of the message is:

Remote Server *<hostname>* (*<ipaddress>*:*<port>*) is DOWN!

The following is an example header and message:

```
09/14/1999 17:57:12 name/radius/1 Error Server 0 Remote
server dave-ultra (171.69.237.99:1645) is DOWN!
```

2. Cisco Access Registrar receives no response from the Remote Server after the server is reentered into Cisco Access Registrar's server pool for retry. The format of the message is:

Remote Server *<hostname>* (*<ipaddress>*:*<port>*) remains DOWN!

The following is an example header and message:

```
09/14/1999 17:56:32 name/radius/1 Error Server 0 Remote
server dave-ultra (171.69.237.99:1645) remains DOWN!
```

3. The Remote Server is responding to the first retry but not the initial request. The format of the message is:

Remote Server *<hostname>* (*<ipaddress>*:*<port>*) is UP but slow!

The following is an example header and message:

```
09/14/1999 17:56:32 name/radius/1 Error Server 0 Remote
server dave-ultra (171.69.237.99:1645) is UP but slow!
```

4. The Remote Server is responding to the second retry request but not the initial request or the first retry request. The format of the message is:

Remote Server <hostname> (<ipaddress>:<port>) is UP but very slow!

The following is an example header and message:

```
09/14/1999 17:56:32 name/radius/1 Error Server 0 Remote
server dave-ultra (171.69.237.99:1645) is UP but very slow!
```

5. The Remote Server has been marked inactive and is being put back into Cisco Access Registrar's server pool for later use. The format of the message is:

Remote Server <hostname> (<ipaddress>:<port>) is being reactivated for later use.

The following is an example header and message:

```
09/14/1999 17:56:32 name/radius/1 Error Server 0 Remote
server dave-ultra (209.165.200.224:1645) is being reactivated for later use.
```