

Administering Clusters on Amazon Web Services (AWS) EKS

Integrating Cisco Container Platform with Amazon Web Services (AWS) allows you to deploy and run containerized applications across both Cisco-based on-prem environments and the AWS cloud.

This chapter contains the following topics:

- Prerequisites for Configuring Clusters on AWS EKS, on page 1
- Amazon IAM Authentication, on page 5
- Configuring Control Plane Proxy for EKS Access, on page 6
- Creating AWS EKS Clusters, on page 6
- Scaling AWS EKS Clusters, on page 8
- Deleting AWS EKS Clusters, on page 8

Prerequisites for Configuring Clusters on AWS EKS

The prerequisites for configuring clusters on AWS EKS are as follows:

See also Adding Amazon Provider Profile.

Amazon Resource Requirements

The following table describes the default limits for the Amazon resources that you may need to increase depending on your Cisco Container Platform deployment requirements.



Note

To increase the limits for a specific resource, you need to contact Amazon support.

| Amazon Resource | Default Limit | Description |
|--|---------------|---|
| Network Address Translation (NAT) gateway for each AWS account | 14 | Each EKS cluster uses three NAT gateways. With the default setting, you are limited to four clusters. |

| Amazon Resource | Default Limit | Description | |
|---|---------------|--|--|
| Amazon Virtual Private Cloud (Amazon VPC) for each AWS account | 3 | Each tenant cluster requires a separate Amazon VPC. | |
| Amazon Elastic Container Service for Kubernetes (Amazon EKS) cluster for each AWS account | 3 | Note Changes to the Amazon EKS cluster limit are updated only on Thursdays. | |
| Elastic IP address for each region | 5 | Each EKS cluster uses three elastic IP addresses. For more information, see Amazon VPC Limits. | |
| Internet gateway for each region | 5 | Each EKS cluster uses one internet gateway. | |

Configuring Storage Class for EKS Clusters

You can configure additional storage classes to allow Kubernetes clusters running on AWS to manage the lifecycle of Amazon EFS file systems by installing the Amazon EFS Container Storage Interface (CSI) driver.



Note Cisco TAC support is not available for the AWS EFS CSI storage.

For more information, see Amazon EFS CSI driver.

Adding AMI Files to your Amazon Account

Cisco Container Platform generates a specific AMI (Amazon Machine Image) file with each product release. The AMI file ensures that compatible packages are available for successful tenant cluster creation.

To make the AMI file available to your Amazon account, you must submit a support case that includes your 12 digit Amazon account ID. You will be notified when the AMI is available within your Amazon account.

Creating AWS Roles

- **Step 1** Log in to the AWS Management Console and open the IAM console at https://console.aws.amazon.com/iam/.
- **Step 2** In the navigation pane of the IAM console, click **Roles**, and then click **Create role**.
- Step 3 Under Select type of trusted entity, click Another AWS account.
- Step 4 In the Account ID field, enter your AWS Account ID, and then click Next.
 The AWS account number must be a trusted entity so that Cisco Container Platform can use the Role ARN during EKS cluster creation.
- **Step 5** Skip the screen to choose permission policies and permission boundary and click **Next**.
- **Step 6** Add metadata to the role by attaching tags of your choice as key–value pairs and click **Next**.

- **Step 7** In the Role name field, enter the name for the role as k8s-ccp-user or any other name of your choice.
- **Step 8** In the **Description** field, enter a description of your choice and click **Create role**.
- **Step 9** After the role is created, navigate to the created role and verify the following details of the role:
 - a) Click the **Permissions** tab to verify that permissions are not set.
 - b) Click the **Trust Relationships** tab to verify that a trust relationship exists for the AWS account that you entered during creation of the Role ARN.

Figure 1: AWS Management Console-Trust Relationships Tab

| Search IAM | Summary | | | | Delete rol |
|--|--|--|---|---|-----------------|
| Dashboard Groups Users Policies Identity providers Account settings Credential report Encryption keys | Creation ti Maximum CLUAPI session durat Give this link to users who can swi roles in the cons Permissions Trust relationships You can view the trusted entities that can | Ion Kubernetes administrat Ns @ ath / me 2018-10-29 17:40 PST Ion 1 hour Edit https://signin.aws.ama. ole Tags Access Advisor | con.com/switchrole?roleNar Revoke sessions | nticator for Kubernetes). Edit me=KubernetesAdmin&account=cisco-conta | aner-platform 🕢 |
| | Edit trust relationship Trusted entities The following trusted entities can assum Trusted entities The account | e this role. | The | nditions following conditions define how and when t are are no conditions associated with this role | |

Configuring Permissions for AWS Account

If the AWS provider account is not a root account, you must ensure that the account has the permissions needed to create the EKS and EC2 resources.

The following Sample aws-provider-policy.json File shows configuring the minimum permissions required for your AWS account. You need to create and import this file to configure the necessary permissions.

Sample aws-provider-policy.json File

{

```
"Version": "2012-10-17",
"Statement": [
    {
        "Effect": "Allow",
        "Action": [
            "cloudformation:*",
            "elasticloadbalancing:*",
            "ec2:*",
            "ecs:*",
            "ecs:*",
            "ecs:*",
            "s3:*"
```

```
],
        "Resource": "*"
    },
    {
        "Effect": "Allow",
        "Action": [
            "iam:List*",
            "iam:Get*",
            "iam:PassRole",
            "iam:AddRoleToInstanceProfile",
            "iam:RemoveRoleFromInstanceProfile",
            "iam:CreateRole",
            "iam:CreateInstanceProfile",
            "iam:DeleteInstanceProfile",
            "iam:DeleteRole",
            "iam:DeleteRolePolicy",
            "iam:AttachRolePolicy",
            "iam:DetachRolePolicy",
            "iam:PutRolePolicy",
            "iam:*AccessKey*",
            "iam:*MFA*"
        ],
        "Resource": "*"
    }
]
```

For more information on user privileges on AWS, see Minimum User Privileges on AWS.

Creating Access Keys

}

Access keys are required to authenticate your requests to the AWS Provider. An access key consists of two parts — an access key ID and a secret access key.

You can use the AWS IAM system in one of the following ways:

Using a single user or personal account

See Creating Access Keys for a Single User Account, on page 4, for creating access keys to allow access to AWS resources.

• Using a federated login account, for enterprises or corporate entities

See Creating Access Keys for Federated Login Accounts, on page 5, for creating access keys to allow programmatic access to AWS resources.

Creating Access Keys for a Single User Account

- Step 1Log in to the AWS Management Console at https://console.aws.amazon.com.
- Step 2From the Username drop-down list on the top-right corner, choose My Security Credentials.
The My Security Credentials page appears.
- **Step 3** Expand the Access keys section.
- Step 4 Click Create New Access Key.

A popup appears displaying the new access key ID and the secret access key.

Step 5 Click **Download Credentials**, and download the CSV file that contains the access keys and save it on your computer.

You can use this access key while adding your Amazon provider profile. For more information, see Adding Amazon Provider Profile.

Creating Access Keys for Federated Login Accounts

| Step 1 | Log in to the AWS Management Console at https://console.aws.amazon.com. |
|--------|---|
| Step 2 | In the left pane, click Add User to create a new user, which Cisco Container Platform will use to login. |
| Step 3 | In the Set user details section, enter a username in the Username field. |
| | For example, ccp-user . |
| Step 4 | In the Select AWS access type section, set Programmatic Access as the Access Type , and then click Next . This setting provides the access key ID and secret access key for the Cisco Container Platform AWS provider. |
| Step 5 | In the Set Permissions table, click Add User to Group , and in the lower section, select the group that you created previously (ccp-user), and then click Next . |
| Step 6 | In the Add tags page, click Next. |
| | In the next screen, the new access key ID and secret access key are displayed. Stay on this screen as it is only shown once. |
| Step 7 | Click Download Credentials , and download the CSV file that contains the access keys and save it on your computer You can use this access key while adding your Amazon provider profile. For more information, see Adding Amazon Provider Profile. |

Amazon IAM Authentication

By default, the AWS IAM identity is used to authenticate and connect with clusters on EKS clusters. Cisco Container Platform uses AWS IAM Authenticator to authenticate on-prem cluster using the AWS IAM identity. This authentication provides a consistent, unified identity scheme across both on-premise and clusters on AWS EKS.

The AWS IAM Authenticator fulfills both a client and server function. On the client side, the authenticator generates, tokenizes and transmits a pre-signed URL to the server-side for identity validation. The client is a Go binary, installed on your workstation, which is transparently invoked by kubectl each time you interact with your Kubernetes cluster. The server-side is a containerized instance of AWS IAM Authenticator running as a DaemonSet on the Kubernetes master nodes. This interacts with the AWS Secure Token Service (STS) to perform identity validation. Cisco Container Platform takes care of the initial server-side configuration and provides a preconfigured Kubeconfig file for admin users to download.



Note

You need to ensure that the AWS IAM Authenticator is available within your \$PATH while using kubectl to interact with the clusters.

Enabling Common Identity

Within the Cisco Container Platform web interface, users are able to select a common identity scheme for clusters. After the clusters are provisioned, you can apply a shared RBAC policy.

Step 1

Note The use of IAM Authentication is implicitly enabled for EKS clusters. Cisco Container Platform can map a user supplied IAM role to the EKS cluster and configuring IAM auth for on-premises clusters.

Configuring Control Plane Proxy for EKS Access

If your Control Plane VMs need proxy configuration to access the internet, specifically AWS API endpoints, you need to configure Cisco Container Platform application deployments with the proxy information.

Step 2 Run the following commands to specify the proxy information:

SSH to the Control Plane cluster master VM.

Note You need to replace *<Proxy_URL_or_IPAddress:Port>* with the URL/IP address of your proxy server and port and the no_proxy list with a list of your internal IP addresses.

Creating AWS EKS Clusters

Before you begin

- Ensure that you have added your Amazon provider profile. For more information, see Adding Amazon Provider Profile.
- Ensure that you have added the required AMI files to your account. For more information, see Adding AMI Files to your Amazon Account, on page 2.
- Ensure that you have created an AWS IAM Role for the Cisco Container Platform usage to create AWS EKS Clusters. For more information, see Creating AWS Roles, on page 2.

Step 1 In the left pane, click **Clusters**, and then click the **AWS** tab.

Step 2 Click NEW CLUSTER.

- **Step 3** In the **Basic Information** screen, enter the following information:
 - a) From the **INFRASTUCTURE PROVIDER** drop-down list, choose the provider related to the appropriate Amazon account.
 - b) From the AWS REGION drop-down list, choose an appropriate AWS region.
 - Note Not all regions support EKS. Ensure that you select a supported region. Currently, Cisco Container Platform supports the ap-northeast-1, ap-northeast-2, ap-southeast-1, ap-southeast-2, eu-central-1, eu-north-1, eu-west-1, eu-west-2, eu-west-3, us-east-1, us-east-2, and us-west-2 regions.
 - c) In the KUBERNETES CLUSTER NAME field, enter a name for your cluster.
 - d) Click NEXT.
- **Step 4** In the **Node Configuration** screen, specify the following information:
 - a) From the INSTANCE TYPE drop-down list, choose an instance type for your cluster.
 - b) From the MACHINE IMAGE drop-down list, choose an appropriate Cisco Container Platform Amazon Machine Image (AMI) file.

To add AMI files to your Amazon account, see Adding AMI Files to your Amazon Account, on page 2.

- c) In the WORKER COUNT field, enter an appropriate number of worker nodes.
- d) In the SSH PUBLIC KEY drop-down field, choose an appropriate authentication key. This field is optional. It is needed if you want to ssh to the worker nodes for troubleshooting purposes. Ensure that you use the Ed25519 or ECDSA format for the public key.

Note: As RSA and DSA are less secure formats, Cisco prevents the use of these formats.

- e) In the IAM ACCESS ROLE ARN field, enter the Amazon Resource Name (ARN) information.
 - Note By default, the AWS credentials specified at the time of Amazon EKS cluster creation, that is the credentials configured in the Infrastructure Provider, are mapped to the Kubernetes cluster-admin ClusterRole. A default ClusterRoleBinding binds the credentials to the system:masters group, thereby granting super-user access to the holders of the IAM identity. The IAM ACCESS ROLE ARN field allows you to specify the ARN of an additional AWS IAM role or IAM user who is also granted administrative control of the cluster.
- f) Click **NEXT**.
- **Step 5** In the **VPC Configuration** screen, specify the following information:
 - a) In the SUBNET CIDR field, enter a value of the overall subnet CIDR for your cluster.
 - b) In the PUBLIC SUBNET CIDR field, enter values for your cluster on separate lines.
 - c) In the **PRIVATE SUBNET CIDR** field, enter values for your cluster on separate lines.

Step 6 In the **Summary** screen, review the cluster information and then click **FINISH**.

Cluster creation can take up to 20 minutes. You can monitor the cluster creation status on the Clusters screen.

Note If you receive the Could not get token: AccessDenied error message, it indicates that the AWS account is not a trusted entity for the Role ARN.

For information on adding your AWS account as a trusted entity, see Creating AWS Roles, on page 2.

Scaling AWS EKS Clusters

You can scale EKS clusters by adding or removing worker nodes to them based on the demands of the workloads you want to run.

| Step 1 | In the right pane, click EDIT . The Edit Cluster dialog box appears. |
|--------|---|
| Step 2 | From the INSTANCE TYPE drop-down list, choose an instance type for your cluster. |
| Step 3 | From the MACHINE IMAGE drop-down list, choose an appropriate Cisco Container Platform Amazon Machine Image (AMI) file. To add AMI files to your Amazon account, see Adding AMI Files to your Amazon Account, on page 2. |
| Step 4 | In the WORKER COUNT field, change the number of work nodes as necessary. |
| Step 5 | Click UPDATE. |

Deleting AWS EKS Clusters

Before you begin

Ensure that the AWS EKS cluster that you want to delete is not currently in use, as deleting a cluster removes the containers and data associated with it.

- **Step 1** In the left pane, click **Clusters**, and then click the **EKS** tab.
- **Step 2** From the drop-down list displayed under the **ACTIONS** column, choose **Delete** for the cluster that you want to delete.
- Step 3Click DELETE in the confirmation dialog box.Upon deleting an AWS EKS cluster, it takes about 10 minutes for the cluster resources to be released.