



CHAPTER 14

Maintaining System Health

This chapter contains the following sections:

- [Monitoring System Health, page 14-1](#)
- [Using System Logs, page 14-1](#)
- [Changing Settings, page 14-3](#)
- [Checking the Status of Prime NCS \(WAN\), page 14-5](#)
- [Stopping Prime NCS \(WAN\), page 14-5](#)
- [Backing Up the Database, page 14-5](#)
- [Uninstalling, page 14-6](#)
- [Managing and Updating Product Licenses, page 14-8](#)

Monitoring System Health

To view the system health dashboards, choose **Administration > Admin Dashboard**. [Table 14-1](#) describes the information displayed on the dashboards.

Table 14-1 Administration > Admin Dashboard Information

Health Information Displayed	Description
System Health	Displays memory and CPU health information over a period of time.
System Events	Displays a list of events, time the event occurred, and the severity of the event.
System Information	Displays general system health information such as the server name, number of jobs scheduled and running, the number of supported MIB variables, number of users logged in, etc.

Using System Logs

Prime NCS (WAN) logs all error, informational, and trace messages generated by all devices that are managed by Prime NCS (WAN).

Prime NCS (WAN) also logs all SNMP messages and Syslogs it receives.

You can download and email the logs to use for troubleshooting Prime NCS (WAN).

-
- Step 1** Choose **Administration > Logging**. The General Logging Options Screen appears.
- Step 2** Choose a Message Level:
- Error
 - Information
 - Trace
- Step 3** Check the check boxes within the Enable Log Module option to enable various administration modules. Check the **Log Modules** option to select all modules.
- Step 4** In the Log File Settings portion, enter the following settings. These settings will be effective after restarting Prime NCS (WAN).
- Maximum file size—Maximum number of MBs allowed per log file.
 - Number of files—Maximum number of log files allowed.
 - File prefix—Log file prefix, which can include the characters “%g” to sequentially number of files.
- Step 5** Click the Download button to download the log file to your local machine.
-  **Note** The logs.zip filename includes a prefix with the host name, date, and time so that you can easily identify the stored log file. Included in the zip file is an html file that documents the log files.
-
- Step 6** Enter the Email ID or Email IDs separated by commas to send the log file.
-  **Note** To send the log file in a mail you must have Email Server Configured.
-
- Step 7** Click **Submit**.
-

Changing SNMP Logging Options

-
- Step 1** Choose **Administration > Logging**, then click SNMP Logging Options.
- Step 2** Check the **Enable SNMP Trace** check box to enable sending SNMP messages (along with traps) between devices and Prime NCS (WAN).
- Step 3** Check the **Display Values** check box to see the SNMP message values.
- Step 4** Configure the IP address or IP addresses to trace the SNMP traps. You can add up to a maximum of 10 IP addresses in the text box.
- Step 5** Specify the maximum SNMP file size and the number of SNMP files.
- Step 6** Click **Save**.
-

Changing Syslog Logging Options

-
- Step 1** Choose **Administration > Logging**, then click Syslog Logging Options.

- Step 2** Check the **Enable Syslog** check box to enable collecting and processing system logs.
 - Step 3** Enter the Syslog Host IP address of the interface from which the message is to be transmitted.
 - Step 4** Choose the **Syslog Facility**. You can choose any of the eight local use facilities for sending syslog messages. The local use facilities are not reserved and are available for general use.
 - Step 5** Click **Save**.
-

Using Logging Options to Enhance Troubleshooting

The logging screen allows you to customize the amount of data Prime NCS (WAN) collects in order to debug an issue. For easily reproduced issues, follow these steps prior to contacting TAC. These steps may create a smoother troubleshooting session:

- Step 1** Choose **Administration > Logging**.
- Step 2** From the Message Level drop-down list, choose **Trace**.
- Step 3** Check each check box to enable all log modules.
- Step 4** Reproduce the current problem.
- Step 5** Return to the Logging Options page.
- Step 6** Click **Download** from the Download Log File section.



Note The logs.zip filename includes a prefix with the host name, date, and time so that you can easily identify the stored log file. Included in the zip file is an html file that documents the log files.

- Step 7** After you have retrieved the logs, choose **Information** from the Message Level drop-down list.



Note Leaving the Message Level at *Trace* can adversely affect performance over a long period of time.

Changing Settings

When you choose **Administration > System**, you can change the Prime NCS (WAN) settings described in [Table 14-2](#).

Table 14-2 Prime NCS (WAN) Settings

Click this Setting ...	To Specify ...
Alarms and events	<p>Which alarms should be deleted, define which alarm types are displayed, specify alarm email options.</p> <p>Note Data cleanup tasks run nightly to delete old alarms. In addition to the data cleanup task, Prime NCS (WAN) has an hourly task to check alarm table size. When the alarm table size exceeds 300 K, the task deletes the oldest cleared alarms until the alarm table size is within 300 K.</p> <p>The Alarm Display Options apply to the Alarm Summary page only. Quick searches or alarms for any entity display all alarms regardless of the acknowledged or assigned state.</p> <p>E-mails are not generated for acknowledged alarms regardless of severity change.</p>
Data retention	<p>How long to retain data for the different data types.</p> <p>Note For the best interactive graph data views, change the default settings to the maximum possible: 90 days for daily aggregated data and 54 weeks for weekly aggregated data. You must also make the appropriate measures to increase RAM and CPU capacity to compensate for these adjustments.</p>
Login disclaimer	The disclaimer text that is displayed at the bottom of the login page for all users.
Mail server configuration	<p>Global e-mail parameters for sending e-mails from Prime NCS (WAN) reports and alarm notifications. You can set the primary and secondary SMTP server host and port, the sender's e-mail address, and the recipient's e-mail addresses.</p> <p>Click the "Configure email notification for individual alarm categories" link to specify the alarm categories and severity levels you want to enable. Email notifications are sent when an alarm occurs that matches categories and the severity levels you select.</p>
Notification receivers	<p>Receivers who will receive notifications from Prime NCS (WAN). Alerts and events are sent as SNMPv2 notifications to configured notification receivers.</p> <p>Note If you are adding a notification receiver with the notification type UDP, the receiver you add should be listening to UDP on the same port on which it is configured.</p> <p>By default only INFO level events are processed for the selected category.</p> <p>Only SNMPV2 traps are considered for northbound notification.</p>
Report	The path where reports are stored and for how long the reports are retained.
Server settings	Whether to enable or disable server ports.
Severity Configuration	The severity level of the alarms.
SNMP Settings	<p>Global SNMP settings such as trace display values such as reachability parameters and backoff algorithm.</p> <p>If you select Exponential (the default value) for the Backoff Algorithm, each SNMP try waits twice as long as the previous try, starting with the specified timeout for the first try. If you choose Constant Timeout, each SNMP try waits the same, specified amount of time.</p> <p>If you select to use reachability parameters, the Prime NCS (WAN) defaults to the global Reachability Retries and Timeout that you configure. If unchecked, Prime NCS (WAN) always uses the timeout and retries specified. The default is selected.</p>
Image Management	Preference parameters for downloading, distributing, and recommending software Images.

Table 14-2 Prime NCS (WAN) Settings

Click this Setting ...	To Specify ...
Configuration	Whether to backup the running configuration, to rollback the configuration, or to get show commands output from cache.
Configuration Archive	Basic configuration archive settings such as protocol, timeout value, number of configuration versions to store, etc.
Audit	Audit log purge settings and where to send purged logs.
Monitoring Settings	Auto monitoring for device and interface health collection and enable deduplication for server health collections.

Checking the Status of Prime NCS (WAN)

To check the status of Prime NCS (WAN) from the CLI, follow these steps:

-
- Step 1** Log into the system as **admin** by entering the following command:
- ```
ssh admin NCS(WAN)_server_IP address or hostname
```
- Step 2** Enter the following CLI:
- ```
# ncs status
```
- The CLI displays messages indicating the status of Prime NCS (WAN).
-

Stopping Prime NCS (WAN)

You can stop Prime NCS (WAN) at any time by following these steps:



Note If any users are logged in when you stop Prime NCS (WAN), their sessions stop functioning.

- Step 1** Log into the system as **admin** by entering the following command:
- ```
ssh admin (WAN)_server_IP address or hostname
```
- Step 2** Enter the following CLI:
- ```
# ncs stop
```
- The CLI displays messages indicating that Prime NCS (WAN) is stopping.
-

Backing Up the Database

This section provides instructions for backing up the Prime NCS (WAN) database. You can schedule regular backups through the Prime NCS (WAN) user interface or manually initiate a backup.

**Note**

Machine specific settings (such as FTP enable and disable, FTP port, FTP root directory, TFTP enable and disable, TFTP port, TFTP root directory, HTTP forward enable and disable, HTTP port, HTTPS port, report repository directory, and all high availability settings) are not included in the backup and restore function if the backup is restored to a different device.

This section contains the following topic:

- [Scheduling Automatic Backups](#)

Scheduling Automatic Backups

To schedule automatic backups of the Prime NCS (WAN) database, follow these steps:

-
- Step 1** Log into the Prime NCS (WAN) user interface.
- Step 2** Click **Tools > Task Manager > Background Tasks** to display the Scheduled Tasks page.
- Step 3** Click the **NCS Server Backup** task to display the **NCS Server Backup** page.
- Step 4** Check the **Enabled** check box.
- Step 5** At the **Backup Repository** parameter, Choose an existing backup repository or click create button to create a new repository.
- Step 6** If you are backing up in remote location, select the FTP Repository check box. You need to enter the FTP location, Username and Password of the remote machine.
- Step 7** In the Interval (Days) text box, enter a number representing the number of days between each backup. For example, 1 = a daily backup, 2 = a backup every other day, 7 = a weekly backup, and so on.
Range: 1 to 360
Default: 7
- Step 8** In the Time of Day text box, enter the time when you want the backup to start. It must be in this format: *hh:mm AM/PM* (for example: 03:00 AM).

**Note**

Backing up a large database affects the performance of the Prime NCS (WAN) server. Therefore, we recommend that you schedule backups to run when the Prime NCS (WAN) server is idle (for example, in the middle of the night).

- Step 9** Click **Submit** to save your settings. The backup file is saved as a .zip file in the *ftp-install-dir/ftp-server/root/NCSBackup* directory using this format: *dd-yyy-mm-ss_hh-mm-ss.zip* (for example, 10-Dec-12_10-15-22.zip).
-

Uninstalling

You can uninstall Prime NCS (WAN) at any time, even while Prime NCS (WAN) is running.

To uninstall Prime NCS (WAN), follow these steps:

-
- Step 1** Log into Prime NCS (WAN) as **root**, then enter the following command:
- ```
ncs stop
```
- Step 2** Using the Linux CLI, navigate to the /opt/NCS1.0.X.X directory (or the directory chosen during installation).
- Step 3** Enter **./UninstallNCS**.
- Step 4** Click **Yes** to continue the uninstall process.
- Step 5** Click **Finish** when the uninstall process is complete.



**Note** If any part of the /opt/NCS1.0.X.X directory remains on the hard drive, manually delete the directory and all of its contents. If you fail to delete the previous Prime NCS (WAN) installation, this error message appears when you attempt to reinstall Prime NCS (WAN): “**Cisco Prime NCS (WAN) is already installed. Please uninstall the older version before installing this version.**”

---

## Recovering the Prime NCS (WAN) Password

You can change the Prime NCS (WAN) application root user or FTP user password. This option provides a safeguard if you lose the root password. An executable was added to the installer /bin directory (passwd.bat for Windows and passwd.sh for Linux). To recover the passwords and regain access to Prime NCS (WAN), follow these steps:



**Note** If you are a Linux user, you must be the root user to run the command.

---



**Note** In Linux, use the *passwd.sh* to change the Prime NCS (WAN) password. The *passwd* is a built-in Linux command to change the OS password.

---

- Step 1** Change to the Prime NCS (WAN) bin folder.
- Step 2** For Linux, use the following command:
- Enter **passwd.sh root-user *newpassword*** to change the Prime NCS (WAN) root password. The new password is the root login password you choose.
- or
- Enter **passwd.sh location-ftp-user *newuser newpassword*** to change the FTP user and password. The *newuser* and *newpassword* are the MSE or Location server user and password.
- Step 3** The following options are available with these commands:
- -q — to quiet the output
  - -pause — to pause before exiting-gui — to switch to the graphical user interface
  - -force — to skip prompting for configuration
- Step 4** Start Prime NCS (WAN).
-

# Managing and Updating Product Licenses

Prime NCS (WAN) licensing is based on the number of network devices for which you want to use Prime NCS (WAN) to manage. An Prime NCS (WAN) device license provides full access to all Prime NCS (WAN) features in order to manage a set number of devices. You purchase a single base license and then purchase additional add-on licenses as necessary to accommodate additional devices.

Prime NCS (WAN) is deployed through physical or virtual appliances. You use the standard License Center Graphical User Interface to add new licenses, which are locked by the standard Cisco Unique Device Identifier (UDI). When Prime NCS (WAN) is deployed on a virtual appliance, the licensing is similar to that on a physical appliance, except instead of using a UDI, you use a Virtual Unique Device Identifier (VUDI).



**Note** To move licenses from one physical appliance to another, you need to call the Licensing TAC and rehost the licenses to a new UDI.

The Prime NCS (WAN) License is recognized by the SKU, which is usually attached to every purchase order to clearly identify which software or package is purchased by a customer.



**Note** If you are using an evaluation license, it is recommended that you add a base license before your evaluation license expires.

You can view license information by clicking **Help > About Prime NCS (WAN)**.



**Caution**

Do not modify your license file; If you make any modifications, your license file will be corrupted.

## Viewing License Details

To view the license type you currently have, the device and interface limits, and the percentage used and remaining on the license:

- 
- Step 1** Choose **Administration > Licenses**.
  - Step 2** Rest your cursor on the icon that appears next to Licenses to view licensing ordering help.
- 

## Adding Licenses

To add a new license:

- 
- Step 1** Choose **Administration > Licenses**.
  - Step 2** Under the Summary folder, click Files.
  - Step 3** Click **License Files**.
  - Step 4** Click **Add**.

**Step 5** Browse to the location of the license file, then click **OK**.



---

**Note** Make sure the license file does not have a .txt extension.

---

## Deleting Licenses

You might need to delete a license when:

- You are currently using an evaluation license and want to apply a base license.
- You are currently using an add-on license and want to apply a new license to accommodate additional devices.

---

**Step 1** Choose **Administration > Licenses**.

**Step 2** Under the Summary folder, click Files.

**Step 3** Click **License Files**.

**Step 4** Select the license file you want to delete, then click **Delete**.

---

