



cnBNG Installation and Configuration

- [Feature Summary and Revision History, on page 1](#)
- [Feature Description, on page 1](#)
- [Installing cnBNG and Accessing BNG Ops Center, on page 3](#)

Feature Summary and Revision History

Summary Data

Table 1: Summary Data

Applicable Product(s) or Functional Area	cnBNG
Applicable Platform(s)	SMI
Feature Default Setting	Disabled - Configuration Required
Related Changes in this Release	Not Applicable
Related Documentation	Not Applicable

Revision History

Table 2: Revision History

Feature Description

This chapter describes cnBNG installation and configuration using the Ultra Cloud Core Subscriber Microservices Infrastructure (SMI) Cluster Manager and the BNG Operations (Ops) Center. The BNG Ops Center is based on the ConfD command line interface (CLI).

To install the SMI Cluster Manager, refer to the "Deploying the SMI Cluster Manager on VMware vCenter" section in the *Ultra Cloud Core Subscriber Microservices Infrastructure - Deployment Guide*.

The SMI Ops Center is the platform to install the cnBNG cluster with the offline or online repository. It is mandatory to install the SMI Ops Center to set up and access the BNG Ops Center.



Note To access the offline or online repository, contact your Cisco Account Manager or representative to get access to the offline or online repository.

BNG Ops Center

The BNG Ops Center is a system-level infrastructure that provides the following functionality:

- A user interface to trigger a deployment of microservices with the flexibility of providing variable helm chart parameters to control the scale and properties of Kubernetes objects (deployment, pod, services, and so on) associated with the deployment.
- A user interface to push application-specific configuration to one or more microservices through Kubernetes configuration maps.
- A user interface to issue application-specific execution commands (such as show and clear commands). These commands:
 - Invoke some APIs in application-specific pods
 - Display the information returned on the user interface application

The following figure shows a sample of the web-based CLI presented to the user.

```

Username: admin
Warning: Permanently added '[localhost]:2024' (RSA) to the list of known hosts.
admin@localhost's password:

Welcome to the bng CLI on unknown
Copyright © 2016–2020, Cisco Systems, Inc.
All rights reserved.

admin connected from 127.0.0.1 using ssh on ops-center-bng-ops-center-68bb45478f-62jvw

Warning!!! Your password will expire in 9 days!

[unknown] bng# show running-config
helm default-repository bng-master
helm repository bng-lac
access-token mgIdutur:AKCpSekcbPUSsIifdwVvxqXjSchQkweH7sD1Xxe9JktjKbpg6Yj9xurfvMn9djkAy8UpZlo
url https://engci-maven-master.cisco.com/artifactory/smi-fuse-internal-snapshot/mobile-cnbt-bng/bng-products/dev-bng-lac/ins/
exit
helm repository bng-master
access-token mgIdutur:AKCpSekcbPUSsIifdwVvxqXjSchQkweH7sD1Xxe9JktjKbpg6Yj9xurfvMn9djkAy8UpZlo
url https://engci-maven-master.cisco.com/artifactory/smi-fuse-internal-snapshot/mobile-cnbt-bng/bng-products/master/
exit
k8s name unknown
k8s namespace bng
k8s nf-name bng
k8s registry dockerhub.cisco.com/smi-fuse-docker-internal
k8s single-node true
k8s use-volume-claims false
k8s ingress-host-name 10.84.102.189.nip.io
aaa authentication users user admin
uid 117
gid 117
password $1sk7Eytecp$MFM3TJHzjNcfmUmHspMb1
ssh_keydir /tmp/admin/.ssh
homedir /tmp/admin
exit
aaa ios level 0
prompt "h> "
exit
aaa ios level 15
prompt "h# "

```

The BNG Ops Center allows you to configure features such as licensing, REST endpoint, and CDL.

Installing cnBNG and Accessing BNG Ops Center

This section describes how to install cnBNG and access the BNG Ops Center.

The Ultra Cloud Core SMI platform is responsible for setting up and managing the Cloud Native Broadband Network Gateway application.



Note The cnBNG installation is tested and qualified on the VMware vCenter 6.7 environment.

Prerequisites

Before installing cnBNG on the SMI layer in an offline environment:

- Ensure that the SMI Cluster Manager all-in-one (AIO) is installed. This helps orchestrate the K8s Cluster and load the image.
- Ensure that all SMI K8s cluster nodes are in Ready state.
- Run the SMI synchronization operation for the BNG Ops Center and Cloud Native Common Execution Environment (CN-CEE).

For CEE installation, refer to the *Ultra Cloud Core Common Execution Environment- Configuration and Administration Guide*.

- Ensure that the local repositories, which host the product offline TAR ball version, is installed.

System Requirements

Feature	Description
Disk Space	2 x 800 GB SSD (RAID 1) or equivalent input/output operations per second (IOPS) and redundancy.
Hardware	<ul style="list-style-type: none"> • High-performance x86 64-bit chipset • CPU performance Passmark benchmark of 13K rating per chip and 1,365 rating per thread, or better • VMware ESXi-compatible

Feature	Description
	<p>Note The following is recommended:</p> <ul style="list-style-type: none"> • Cisco UCSM5 series blade servers to achieve the best performance. • All the host servers should be UCSC-C240-M5SX or UCSC-C220-M5SX. • All the UCS systems should have SSD storage type. • UCS C240M5 servers for better performance and to avoid infrastructure issues.
Platform	<p>VMware ESXi and VMware vCenter versions 6.5 and 6.7</p> <p>Note SMI Cluster Manger support is qualified on the preceding platforms.</p>
Memory	<ul style="list-style-type: none"> • At least DDR3-1600 or better than 1600 MT/s • ECC
Deployment Requirement	<p>Hardware oversubscription, network saturation, or CPU oversubscription reduces application performance and productivity. The Cisco Ultra Cloud Core Subscriber Microservices Infrastructure detects and takes action when infrastructure requirements are not met.</p>

Installing cnBNG in an Offline Environment

Using the SMI Cluster Manager, download the offline TAR ball of the cnBNG, the host and its charts, and corresponding images in the local registries. The SMI Cluster Manager supports the deployment of the BNG Ops Center and all the applications and services associated with it. This section describes the procedures involved in installing cnBNG in an offline environment using the SMI Cluster Manager.

To install cnBNG, complete the following steps:

1. Download the TAR ball from the URL.

```
software-packages download URL
```

Example:

```
SMI Cluster Manager# software-packages download
http://<ipv4address>:<port_number>/packages/bng-2021-02-1.tar
```

2. Verify whether the TAR balls are loaded.

```
software-packages list
```

Example:

```
BNG Cluster Manager# software-packages list
[ bng-2021-02-1 ]
[ sample ]
```

3. Configure the necessary SMI Ops Center parameters in the cluster to install cnBNG.

```

config
  cluster cluster_name
    ops-centers app_name instance_name
      repository url
      netconf-ip ipv4_address
      netconf-port port
      ssh-ip ipv4_address
      ssh-port port
      ingress-hostname <ipv4_address>.<customer_specific_domain_name>
      initial-boot-parameters use-volume-claims true/false
      initial-boot-parameters first-boot-password password
      initial-boot-parameters auto-deploy true/false
      initial-boot-parameters single-node true/false
      initial-boot-parameters image-pull-secrets
    exit
  exit

```

Example:

```

SMI Cluster Manager# config
Entering configuration mode terminal
SMI Cluster Manager(config)# clusters cnbng-smi-cluster-01
SMI Cluster Manager(config-clusters-cnbng-smi-cluster-01)# ops-centers bng bng
SMI Cluster Manager(config-ops-centers-bng/bng)# repository
https://charts.10.10.105.50.nip.io/bng-2021.02.1
SMI Cluster Manager(config-ops-centers-bng/bng)# ingress-hostname 10.10.105.34.nip.io
SMI Cluster Manager(config-ops-centers-bng/bng)# initial-boot-parameters use-volume-claims
true
SMI Cluster Manager(config-ops-centers-bng/bng)# initial-boot-parameters
first-boot-password test123
SMI Cluster Manager(config-ops-centers-bng/bng)# initial-boot-parameters auto-deploy
false
SMI Cluster Manager(config-ops-centers-bng/bng)# initial-boot-parameters single-node
false
SMI Cluster Manager(config-ops-centers-bng/bng)# exit
SMI Cluster Manager(config-clusters-cnbng-smi-cluster-01)# exit
SMI Cluster Manager(config)#

```

4. Configure the secrets, if your local registry contains secrets.

```

config
  cluster cluster_name
    secrets docker-registry secret_name
      docker-server server_name
      docker-username username
      docker-password password
      docker-email email
      namespace k8s namespace
    commit
    exit
  exit

```

Example:

```

SMI Cluster Manager# config
SMI Cluster Manager(config)# clusters test2
SMI Cluster Manager(config-clusters-test2)# secrets docker-registry secl
SMI Cluster Manager(config-docker-registry-secl)# docker-server serv1
SMI Cluster Manager(config-docker-registry-secl)# docker-username user1

```

```

SMI Cluster Manager(config-docker-registry-sec1)# docker-password Cisco@123
SMI Cluster Manager(config-docker-registry-sec1)# docker-email reg@cisco.com
SMI Cluster Manager(config-docker-registry-sec1)# bng bng
SMI Cluster Manager(config-docker-registry-sec1)# exit
SMI Cluster Manager(config-clusters-test2)# exit
SMI Cluster Manager(config)#

```

5. Run the cluster synchronization.

```
clusters cluster_name actions sync run
```

Example:

```
SMI Cluster Manager# clusters cnbng-smi-cluster-01 actions sync run
```

Notes:

- **software-packages download** *url*—Specifies the software packages to be downloaded through HTTP/HTTPS.
- **software-packages list**—Specifies the list of available software packages.
- **ops-centers** *app_name instance_name*—Specifies the BNG Ops Center and instance. *app_name* is the application name. *instance_name* is the name of the instance.
- **repository** *url*—Specifies the local registry URL for downloading the charts.
- **netconf-ip** *ipv4_address*—Specifies the BNG Ops Center netconf IPv4 address.
- **netconf-port** *port*—Specifies the BNG Ops Center netconf port number.
- **ssh-ip** *ipv4_address*—Specifies the SSH IPv4 address for the BNG Ops Center.
- **ssh-port** *port*—Specifies the SSH port number for the BNG Ops Center.
- **ingress-hostname** *<ipv4_address>. <customer_specific_domain_name>*—Specifies the ingress hostname to be set to the BNG Ops Center. *<customer_specific_domain_name>* specifies the domain name of the customer.
- **initial-boot-parameters**—Specifies the initial boot parameters for deploying the helm charts.
 - **use-volume-claims** *true/false*—Specifies the usage of persistent volumes. Set this option to True to use persistent volumes. The default value is true.
 - **first-boot-password** *password*—Specifies the first boot password for the product's Ops Center.
 - **auto-deploy** *true/false*—Auto deploys all the services of the product. Set this option to false to deploy only the product's Ops Center.
 - **single-node** *true/false*— Specifies the product deployment on a single node. Set this option to false for multi node deployments.
 - **image-pull-secrets**—Specifies the docker registry secret name to be used.
- **secrets docker-registry** *secret_name*—Specifies the secret name for your docker registry.
 - **docker-server** *server_name*—Specifies the docker server name.
 - **docker-username** *username*—Specifies the docker registry user name.
 - **docker-password** *password*—Specifies the docker registry password.

- **docker-email** *email*—Specifies the docker registry email.
- **namespace** *namespace*—Specifies the docker registry namespace.

Verifying the cnBNG Installation

Verify the status of the cnBNG installation deployment through the cnBNG CLI. To verify, use the following commands:

1. Log in to the cnBNG product CLI.
2. Verify whether the charts are loaded in the specific instance (verify the namespace).

show helm charts

Example:

```
bng# show helm charts
CHART      INSTANCE  STATUS    VERSION  REVISION  RELEASE  NAMESPACE
-----
infra-charts - DEPLOYED 0.0.6-rel-2021-01-0073-210208130850-fac5207 1 bng-bng-infra-charts
  bng-bng
oam-pod - DEPLOYED 0.1.2-rel-2021-01-0144-210122165946-fcb74ed 1 bng-bng-oam-pod bng-bng
bng-dashboard - DEPLOYED 0.0.1-rel-2021-01-0039-210122165311-0d542be 1
bng-bng-bng-dashboard bng-bng
etcd-cluster - DEPLOYED 0.7.0-0-7-0060-210203074532-f118407 1 bng-bng-etcd-cluster bng-bng
ngn-datastore - DEPLOYED 1.3.0-1-3-0782-210125161812-f50a892 1 bng-bng-ngn-datastore
bng-bng
```

3. Verify the status of the system.

show system status

Example:

```
bng# show system status
system status deployed true
system status percent-ready 100.0
```

Notes:

- **show helm charts**—Displays the helm release details.
- **show system status**—Displays the status of the system.

Accessing BNG Ops Center

You can connect to the BNG Ops Center through SSH or the web-based CLI console.

1. SSH:

```
ssh admin@ops_center_pod_ip -p 2024
```

2. Web-based console:

- a. Log in to the Kubernetes master node.
- b. Run the following command:

```
kubectl get ingress <namespace>
```

The available ingress connections get listed.

- c. Select the appropriate ingress and access the BNG Ops Center.
- d. Access the following URL from your web browser:

```
cli.<namespace>-ops-center.<ip_address>.nip.io
```

By default, the Day 0 configuration is loaded into the cnBNG.

Day 0 Configuration

To view the Day 0 configuration, run the following command.

show running-config

The following is a sample Day 0 configuration:

```
luser@cnbng-smi-cluster-master1:~$ kubectl get svc -n bng-bng | grep
ops-center-bng-bng-ops-center
NAME                                TYPE                CLUSTER-IP          EXTERNAL-IP    PORT(S)
AGE
ops-center-bng-bng-ops-center      ClusterIP           10.96.151.115       <none>
8008/TCP,8080/TCP,2024/TCP,2022/TCP,7681/TCP   7m37s
luser@cnbng-smi-cluster-master1:~$ ssh admin@10.96.151.115 -p 2024
Warning: Permanently added '[10.96.151.115]:2024' (RSA) to the list of known hosts.
admin@10.96.151.115's password:

Welcome to the bng CLI on cnbng-smi-cluster/bng
Copyright © 2016-2020, Cisco Systems, Inc.
All rights reserved.

admin connected from 192.202.0.1 using ssh on ops-center-bng-bng-ops-center-7bddd4cc48-fmb61
[cnbng-smi-cluster/bng] bng# show running-config
system mode running
helm default-repository base-repos
helm repository base-repos
url
https://engci-maven-master.cisco.com/artifactory/smi-fuse-internal-snapshot/mobile-cnat-bng/bng-products/master/
username <username>
password <password>
exit
k8s name                cnbng-smi-cluster
k8s namespace           bng-bng
k8s nf-name             bng
k8s registry            dockerhub.cisco.com/smi-fuse-docker-internal
k8s single-node        false
k8s use-volume-claims  true
k8s ingress-host-name  192.0.2.2.nip.io
aaa authentication users user admin
uid                    1117
gid                    1117
password               $1$EmkQjvc0$08K5tXmUzN1.drQgCL0A2/
ssh_keydir             /tmp/admin/.ssh
homedir                /tmp/admin
exit
aaa ios level 0
prompt "\h> "
exit
aaa ios level 15
prompt "\h# "
exit
aaa ios privilege exec
```



```
level 0
  command action
  exit
  command autowizard
  exit
  command enable
  exit
  command exit
  exit
  command help
  exit
  command startup
  exit
exit
level 15
  command configure
  exit
exit
exit
nacm write-default deny
nacm groups group admin
user-name [ admin ]
exit
nacm rule-list admin
group [ admin ]
rule any-access
  action permit
exit
exit
nacm rule-list confd-api-manager
group [ confd-api-manager ]
rule any-access
  action permit
exit
exit
nacm rule-list ops-center-security
group [ * ]
rule change-self-password
  module-name      ops-center-security
  path              /smiuser/change-self-password
  access-operations exec
  action            permit
exit
rule smiuser
  module-name      ops-center-security
  path              /smiuser
  access-operations exec
  action            deny
exit
exit
deployment
  app-name      BNG
  cluster-name Local
  dc-name       DC
exit
k8 bng
  etcd-endpoint      etcd:2379
  datastore-endpoint datastore-ep-session:8882
  tracing
  enable
  enable-trace-percent 30
  append-messages      true
  endpoint              jaeger-collector:9411
exit
```

```

exit
k8 label protocol-layer key smi.cisco.com/node-type value protocol
exit
k8 label service-layer key smi.cisco.com/node-type value service
exit
k8 label cdl-layer key smi.cisco.com/node-type value session
exit
k8 label oam-layer key smi.cisco.com/node-type value oam
exit
instances instance 1
  system-id DC
  cluster-id Local
  slice-name 1
exit
local-instance instance 1
system mode shutdown
helm default-repository base-repos
helm repository base-repos
  url
https://engci-maven-master.cisco.com/artifactory/smi-fuse-internal-snapshot/mobile-cn-at-bng/bng-products/master/

  username smf-deployer.gen
  password ***
exit
k8s name          svi-cn-bng-tb3
k8s namespace     bng-bng
k8s nf-name       bng
k8s registry      dockerhub.cisco.com/smi-fuse-docker-internal
k8s single-node   false
k8s use-volume-claims true
k8s ingress-host-name 10.81.103.86.nip.io
aaa authentication users user admin
  uid          1117
  gid          1117
  password     $1$vDWeJvJm$v46wiBWqdOj7eWgoPoZZE/
  ssh_keydir   /tmp/admin/.ssh
  homedir      /tmp/admin
exit
aaa ios level 0
  prompt "\h> "
exit
aaa ios level 15
  prompt "\h# "
exit
aaa ios privilege exec
  level 0
  command action
  exit
  command autowizard
  exit
  command enable
  exit
  command exit
  exit
  command help
  exit
  command startup
  exit
exit
level 15
  command configure
  exit
exit
exit

```

```

nacm write-default deny
nacm groups group admin
  user-name [ admin ]
exit
nacm rule-list admin
  group [ admin ]
  rule any-access
  action permit
  exit
exit
nacm rule-list confd-api-manager
  group [ confd-api-manager ]
  rule any-access
  action permit
  exit
exit
nacm rule-list ops-center-security
  group [ * ]
  rule change-self-password
    module-name      ops-center-security
    path              /smiuser/change-self-password
    access-operations exec
    action            permit
  exit
  rule smiuser
    module-name      ops-center-security
    path              /smiuser
    access-operations exec
    action            deny
  exit
exit

```

CP and UP Service Configuration

The CP service requires the basic configuration to process the API calls.



Note For information about the User Plane service configuration, refer to the *Cloud Native BNG User Plane Configuration Guide for Cisco ASR 9000 Series Routers, IOS XR Release 7.3.x*

Configuring the CP

The CP configuration is provided using the Ops Center infrastructure.

The following is a sample CP configuration:

```

ipam
instance 1
  source local
  address-pool POOL_1
  address-quarantine-timer 60
  vrf-name          default
  ipv4
  split-size
  per-cache 32768
  per-dp    32768
  exit
  threshold
  upper-threshold 80

```

```
exit
address-range 11.0.0.2 11.10.255.254
exit
ipv6
address-ranges
  split-size
  per-cache 32768
  per-dp 32768
exit
address-range 2405:1::2 2405:1::ffff
address-range 2405:2::2 2405:2::ffff
address-range 2405:3::2 2405:3::ffff
address-range 2405:4::2 2405:4::ffff
exit
prefix-ranges
  split-size
  per-cache 32768
  per-dp 32768
exit
prefix-range 3405:1:: length 46
prefix-range 3405:2:: length 46
prefix-range 3405:3:: length 46
prefix-range 3405:4:: length 46
exit
exit
address-pool POOL_2
address-quarantine-timer 60
vrf-name VRF-GOLD
ipv4
  split-size
  per-cache 32768
  per-dp 32768
  exit
  threshold
  upper-threshold 80
  exit
  address-range 12.0.0.2 12.10.255.254
  exit
  ipv6
  address-ranges
  split-size
  per-cache 32768
  per-dp 32768
  exit
  address-range 2406:1::2 2406:1::ffff
  address-range 2406:2::2 2406:2::ffff
  address-range 2406:3::2 2406:3::ffff
  address-range 2406:4::2 2406:4::ffff
  exit
  prefix-ranges
  split-size
  per-cache 32768
  per-dp 32768
  exit
  prefix-range 3406:1:: length 46
  prefix-range 3406:2:: length 46
  prefix-range 3406:3:: length 46
  prefix-range 3406:4:: length 46
  exit
  exit
  exit
address-pool POOL_3
address-quarantine-timer 60
```

```
vrf-name                vrf_lps_asr9k
ipv4
  split-size
    per-cache 32768
    per-dp    32768
  exit
  threshold
    upper-threshold 80
  exit
  address-range 13.0.0.1 13.255.255.255
exit
ipv6
  address-ranges
    split-size
      per-cache 16384
      per-dp    16384
    exit
    address-range 2404:1::1 2404:1::ffff
    address-range 2404:2::1 2404:2::ffff
    address-range 2404:3::1 2404:3::ffff
    address-range 2404:4::1 2404:4::ffff
    address-range 2404:5::1 2404:5::ffff
    address-range 2404:6::1 2404:6::ffff
    address-range 2404:7::1 2404:7::ffff
    address-range 2404:8::1 2404:8::ffff
    address-range 2404:9::1 2404:9::ffff
    address-range 2404:10::1 2404:10::ffff
    address-range 2404:11::1 2404:11::ffff
    address-range 2404:12::1 2404:12::ffff
    address-range 2404:13::1 2404:13::ffff
    address-range 2404:14::1 2404:14::ffff
    address-range 2404:15::1 2404:15::ffff
    address-range 2404:16::1 2404:16::ffff
    address-range 2404:17::1 2404:17::ffff
    address-range 2404:18::1 2404:18::ffff
    address-range 2404:19::1 2404:19::ffff
    address-range 2404:20::1 2404:20::ffff
    address-range 2404:21::1 2404:21::ffff
    address-range 2404:22::1 2404:22::ffff
    address-range 2404:23::1 2404:23::ffff
    address-range 2404:24::1 2404:24::ffff
    address-range 2404:25::1 2404:25::ffff
    address-range 2404:26::1 2404:26::ffff
    address-range 2404:27::1 2404:27::ffff
    address-range 2404:28::1 2404:28::ffff
    address-range 2404:29::1 2404:29::ffff
    address-range 2404:30::1 2404:30::ffff
    address-range 2404:31::1 2404:31::ffff
    address-range 2404:32::1 2404:32::ffff
    address-range 2404:33::1 2404:33::ffff
    address-range 2404:34::1 2404:34::ffff
    address-range 2404:35::1 2404:35::ffff
    address-range 2404:36::1 2404:36::ffff
    address-range 2404:37::1 2404:37::ffff
    address-range 2404:38::1 2404:38::ffff
    address-range 2404:39::1 2404:39::ffff
    address-range 2404:40::1 2404:40::ffff
  exit
  prefix-ranges
    split-size
      per-cache 32768
      per-dp    32768
    exit
    prefix-range 2404:db0:: length 42
```

```

    prefix-range 2404:db1:: length 42
    prefix-range 2404:db2:: length 42
    prefix-range 2404:db3:: length 42
    prefix-range 2404:db4:: length 42
    prefix-range 2404:db5:: length 42
    prefix-range 2404:db6:: length 42
    prefix-range 2404:db7:: length 42
    prefix-range 2404:db8:: length 42
    prefix-range 2404:db9:: length 42
    exit
  exit
  exit
exit
cdl node-type session
cdl logging default-log-level error
cdl datastore session
  slice-names [ 1 ]
  endpoint replica 2
  endpoint settings slot-timeout-ms 750
  index replica 2
  index map 1
  slot replica 2
  slot map 2
  slot notification limit 300
exit
cdl kafka replica 1
profile dhcp DHCP_SERVER_1
  ipv4
    mode server
    server
      pool-name          POOL_1
      dns-servers        [ 8.8.8.8 8.8.8.88 8.8.88.88 ]
      netbios-name-server [ 9.9.9.9 9.9.9.99 9.9.99.99 ]
      domain-name        cisco.com
      boot-filename       cisco.cfg
      next-server         7.7.7.7
      netbios-node-type  broadcast-node
      lease days          1
      lease hours         4
      lease minutes       2
    exit
  exit
  ipv6
    mode server
    server
      iana-pool-name     POOL_1
      iapd-pool-name     POOL_1
      dns-servers        [ 2002::1 2002::2 ]
      domain-name        cisco.com
      preference         255
      aftr-name          aftr.cisco.com
      lease days         1
      lease hours        4
      lease minutes      2
    exit
  exit
exit
profile dhcp DHCP_SERVER_2
  ipv4
    mode server
    server
      pool-name          POOL_1
      dns-servers        [ 8.8.8.8 8.8.8.88 8.8.88.88 ]

```

```
netbios-name-server [ 9.9.9.9 9.9.9.99 9.9.99.99 ]
domain-name          cisco.com
boot-filename        cisco.cfg
next-server          7.7.7.7
netbios-node-type    broadcast-node
lease days           1
lease hours          4
lease minutes        2
exit
exit
ipv6
mode server
server
  iana-pool-name     POOL_1
  iapd-pool-name     POOL_1
  lease days         1
  lease hours        4
  lease minutes      2
exit
exit
profile dhcp DHCP_SERVER_3
ipv4
mode server
server
  pool-name          POOL_3
  dns-servers [ 8.8.8.8 ]
  lease hours        6
  lease minutes      1
exit
exit
ipv6
mode server
server
  iana-pool-name     POOL_3
  iapd-pool-name     POOL_3
  lease days         1
  lease hours        4
  lease minutes      2
exit
exit
profile dhcp DHCP_SERVER_4
ipv4
mode server
server
  pool-name          POOL_2
  dns-servers [ 8.8.8.8 ]
  lease hours        6
  lease minutes      1
exit
exit
ipv6
mode server
server
  iana-pool-name     POOL_2
  iapd-pool-name     POOL_2
  lease days         1
  lease hours        4
  lease minutes      2
exit
exit
profile pppoe PPPOE_PROFILE_1
```

```

ctrl-pkt-priority 7
service-name      [ cisco ]
ac-name          123@acname
ac-cookie        123@accookie
exit
profile aaa AAA_PROF_1
authentication
  method-order [ SERVER_GROUP_PROF_1 ]
exit
authorization
  type subscriber method-order [ SERVER_GROUP_PROF_1 ]
  username identifier client-mac-address
  password cisco
exit
accounting
  method-order [ SERVER_GROUP_PROF_1 ]
exit
exit
profile aaa AAA_PROF_2
authentication
  method-order [ SERVER_GROUP_PROF_2 ]
exit
authorization
  type subscriber method-order [ SERVER_GROUP_PROF_2 ]
  username identifier client-mac-address
  password cisco
exit
accounting
  method-order [ SERVER_GROUP_PROF_2 ]
exit
exit
profile server-group SERVER_GROUP_PROF_1
radius-group SERVER_GROUP_1
exit
profile server-group SERVER_GROUP_PROF_2
radius-group SERVER_GROUP_2
exit
profile subscriber SUBS_IPoE_1
dhcp-profile      DHCP_SERVER_1
session-type      ipv4v6
activate-feature-templates [ BASE_TPL_1 ]
aaa authorize AAA_PROF_1
exit
profile subscriber SUBS_IPoE_2
dhcp-profile      DHCP_SERVER_3
session-type      ipv4v6
activate-feature-templates [ BASE_TPL_2 ]
aaa authorize AAA_PROF_2
exit
profile subscriber SUBS_IPoE_3
dhcp-profile      DHCP_SERVER_4
session-type      ipv4v6
activate-feature-templates [ BASE_TPL_3 ]
aaa authorize AAA_PROF_2
exit
profile subscriber SUBS_PPpOE_1
dhcp-profile      DHCP_SERVER_2
pppoe-profile     PPPOE_PROFILE_1
session-type      ipv4v6
class ppp_cls_map
activate-feature-templates [ FT_START_1 ]
matches
  match-type all
  match protocol [ ppp ]

```



```
exit
exit
event session-activate
class ppp_cls_map
  activate-feature-templates [ FT_ACTIVATE_1 ]
  matches
    match-type all
    match protocol [ ppp ]
  exit
  aaa authenticate AAA_PROF_1
exit
exit
profile subscriber SUBS_PPPOE_2
dhcp-profile DHCP_SERVER_3
pppoe-profile PPPOE_PROFILE_1
session-type ipv4v6
class ppp_cls_map
  activate-feature-templates [ FT_START_1 ]
  matches
    match-type all
    match protocol [ ppp ]
  exit
exit
event session-activate
class ppp_cls_map
  activate-feature-templates [ FT_ACTIVATE_2 HSI_100MB ]
  matches
    match-type all
    match protocol [ ppp ]
  exit
  aaa authenticate AAA_PROF_1
exit
exit
profile subscriber SUBS_PPPOE_3
dhcp-profile DHCP_SERVER_4
pppoe-profile PPPOE_PROFILE_1
session-type ipv4v6
class ppp_cls_map
  activate-feature-templates [ FT_START_2 ]
  matches
    match-type all
    match protocol [ ppp ]
  exit
exit
event session-activate
class ppp_cls_map
  activate-feature-templates [ FT_ACTIVATE_3 ]
  matches
    match-type all
    match protocol [ ppp ]
  exit
  aaa authenticate AAA_PROF_1
exit
exit
profile feature-template BASE_TPL_1
vrf-name default
ipv4
  mtu 1492
  disable-unreachables
  verify-unicast-source reachable-via-rx
exit
```

```
ipv6
  mtu 1492
  disable-unreachables
  verify-unicast-source reachable-via-rx
exit
session-accounting
  enable
  aaa-profile AAA_PROF_1
exit
exit
profile feature-template BASE_TPL_2
  vrf-name vrf_lps_asr9k
  ipv4
    mtu 1492
    disable-unreachables
    verify-unicast-source reachable-via-rx
  exit
  ipv6
    mtu 1492
    disable-unreachables
    verify-unicast-source reachable-via-rx
  exit
  qos
    in-policy qos_svcl_in
    out-policy qos_svcl_out
  exit
  session-accounting
    enable
    aaa-profile AAA_PROF_2
  exit
exit
profile feature-template BASE_TPL_3
  vrf-name VRF-GOLD
  ipv4
    mtu 1492
    disable-unreachables
    verify-unicast-source reachable-via-rx
  exit
  ipv6
    mtu 1492
    disable-unreachables
    verify-unicast-source reachable-via-rx
  exit
  session-accounting
    enable
    aaa-profile AAA_PROF_2
  exit
exit
profile feature-template FT_ACTIVATE_1
  vrf-name default
  ipv4
    mtu 1492
    disable-unreachables
    verify-unicast-source reachable-via-rx
  exit
  ipv6
    mtu 1492
    disable-unreachables
    verify-unicast-source reachable-via-rx
  exit
  ppp
    ipcp dns 8.8.8.8 1.2.3.4
    ipcp peer-address-pool POOL_1
    ipcp renegotiation ignore
```

```
    ipcp wins 4.4.4.4 3.3.3.3
    ipv6cp renegotiation ignore
  exit
exit
profile feature-template FT_ACTIVATE_2
vrf-name vrf_lps_asr9k
ipv4
  mtu 1492
  disable-unreachables
  verify-unicast-source reachable-via-rx
exit
ipv6
  mtu 1492
  disable-unreachables
  verify-unicast-source reachable-via-rx
exit
ppp
  ipcp dns 8.8.8.8 1.2.3.4
  ipcp peer-address-pool POOL_3
  ipcp renegotiation ignore
  ipcp wins 4.4.4.4 3.3.3.3
  ipv6cp renegotiation ignore
exit
exit
profile feature-template FT_ACTIVATE_3
vrf-name VRF-GOLD
ipv4
  mtu 1492
  disable-unreachables
  verify-unicast-source reachable-via-rx
exit
ipv6
  mtu 1492
  disable-unreachables
  verify-unicast-source reachable-via-rx
exit
ppp
  ipcp dns 8.8.8.8 1.2.3.4
  ipcp peer-address-pool POOL_2
  ipcp renegotiation ignore
  ipcp wins 4.4.4.4 3.3.3.3
  ipv6cp renegotiation ignore
exit
exit
profile feature-template FT_START_1
session-accounting
  enable
  aaa-profile AAA_PROF_1
exit
ppp
  authentication [ pap chap ]
  lcp delay seconds 1 milliseconds 0
  lcp renegotiation ignore
  max-bad-auth 4
  max-failure 5
  timeout retry 3
  keepalive interval 60 retry 5
exit
exit
profile feature-template FT_START_2
session-accounting
  enable
  aaa-profile AAA_PROF_2
exit
```

```

ppp
 authentication [ pap chap ]
 lcp delay seconds 1 milliseconds 0
 lcp renegotiation ignore
 max-bad-auth 4
 max-failure 5
 timeout retry 3
 keepalive interval 60 retry 5
 exit
exit
profile feature-template HSI_100MB
 qos
 in-policy HSI_UPLOAD_RATE_100MB_IN
 out-policy HSI_DOWNLOAD_RATE_100MB_OUT
 exit
exit
profile feature-template HSI_100MB_NO_Merge
 qos
 in-policy HSI_UPLOAD_RATE_100MB_IN_V4
 out-policy HSI_DOWNLOAD_RATE_100MB_OUT_V4
 exit
exit
profile feature-template HSI_100MB_V4
 qos
 in-policy HSI_UPLOAD_RATE_100MB_IN_V4
 out-policy HSI_DOWNLOAD_RATE_100MB_OUT_V4
 merge-level 40
 exit
service-accounting
 enable
 aaa-profile AAA_PROF_1
 periodic-interval 1200
 exit
exit
profile radius
 algorithm round-robin
 deadtime 1
 detect-dead-server response-timeout 60
 max-retry 1
 timeout 5
 server 203.203.203.12 1812
 type auth
 secret $8$uCC1/Dzxko0TeUFsUIUQoqF1Gbrzt6bo2HWRmUH9Sck=
 exit
 server 203.203.203.12 1813
 type acct
 secret $8$lnsqnr3OZYu6j0+DRGgvic5mOa/wmNw6sAnH4G7BYms=
 exit
 server 203.203.203.13 1812
 type auth
 secret $8$sI2jG0E3TlnPZ6+EpaSKxIYNayfX6pOo3nV8Y6w2R8I=
 exit
 server 203.203.203.13 1813
 type acct
 secret $8$49TVXKEXstB7DyK/r/QuxbzGcQ6avG1A4wrgSukSp9s=
 exit
 server 203.203.203.14 1812
 type auth
 secret $8$qdAzfoAmxVBIX04Xjw//Xywsire0AuNYC8EbKy1lkiQ=
 exit
 server 203.203.203.14 1813
 type acct
 secret $8$Fxs0QXKUmz93ULLuQo6yH6pjR0mB3CgTx7TRYL2U1Ao=
 exit

```

```
server 203.203.203.15 1812
  type auth
  secret $8$j6PMUylUXz9Uggo42Zm2z6xfL0icZ8R5ry7tBP60BYo=
exit
server 203.203.203.15 1813
  type acct
  secret $8$oAbeghiPAJ88qqtjZqYihS39VmycliU85WUo6pHpaAw=
exit
attribute
  nas-identifier CISCO-BNG
  nas-ip 203.203.203.51
exit
server-group SERVER_GROUP_1
  server auth 203.203.203.12 1812
  exit
  server auth 203.203.203.13 1812
  exit
  server acct 203.203.203.12 1813
  exit
  server acct 203.203.203.13 1813
  exit
exit
server-group SERVER_GROUP_2
  server auth 203.203.203.12 1812
  exit
  server auth 203.203.203.13 1812
  exit
  server acct 203.203.203.12 1813
  exit
  server acct 203.203.203.13 1813
  exit
exit
exit
profile coa
  client 203.203.203.11
  server-key $8$l0ZSTRkSki7VIU9Ld31kIFALUH4VipxvUKS01OskSho=
  exit
  client 203.203.203.13
  server-key $8$ViHTNL8bYPDcrTYXO24AJ1TnsnUJRXp6DBfWF/FX1/8=
  exit
exit
user-plane ASR9k-UP-1
  peer-address ipv4 101.101.101.52
  subscriber-profile SUBS_IPoE_1
  port-id Bundle-Ether5011.1
  subscriber-profile SUBS_IPoE_1
  exit
  port-id Bundle-Ether5011.1011015
  subscriber-profile SUBS_PPpOE_1
  exit
  port-id Bundle-Ether5011.1021015
  subscriber-profile SUBS_PPpOE_1
  exit
  port-id Bundle-Ether5011.1031015
  subscriber-profile SUBS_PPpOE_1
  exit
  port-id Bundle-Ether5011.1041015
  subscriber-profile SUBS_PPpOE_1
  exit
  port-id Bundle-Ether5011.2
  subscriber-profile SUBS_IPoE_1
  exit
  port-id Bundle-Ether5011.3
  subscriber-profile SUBS_IPoE_1
```

```
exit
port-id Bundle-Ether5011.4
  subscriber-profile SUBS_IPoE_1
exit
port-id Bundle-Ether5012.1
  subscriber-profile SUBS_IPoE_3
exit
port-id Bundle-Ether5012.1011015
  subscriber-profile SUBS_PPpOE_3
exit
port-id Bundle-Ether5012.1021015
  subscriber-profile SUBS_PPpOE_3
exit
port-id Bundle-Ether5012.1031015
  subscriber-profile SUBS_PPpOE_3
exit
port-id Bundle-Ether5012.1041015
  subscriber-profile SUBS_PPpOE_3
exit
port-id Bundle-Ether5012.2
  subscriber-profile SUBS_IPoE_3
exit
port-id Bundle-Ether5012.3
  subscriber-profile SUBS_IPoE_3
exit
port-id Bundle-Ether5012.4
  subscriber-profile SUBS_IPoE_3
exit
exit
user-plane ASR9k-UP-2
peer-address ipv4 101.101.101.51
subscriber-profile SUBS_IPoE_1
port-id Bundle-Ether1.1011015
  subscriber-profile SUBS_PPpOE_1
exit
port-id Bundle-Ether1.1021015
  subscriber-profile SUBS_PPpOE_1
exit
port-id Bundle-Ether1.1031015
  subscriber-profile SUBS_PPpOE_1
exit
port-id Bundle-Ether1.1041015
  subscriber-profile SUBS_PPpOE_1
exit
exit
user-plane lps_asr9k-1
peer-address ipv4 192.69.1.1
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-10
peer-address ipv4 192.69.1.10
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
```

```
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPPE_2
exit
exit
user-plane lps_asr9k-11
peer-address ipv4 192.69.1.11
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPPE_2
exit
exit
user-plane lps_asr9k-12
peer-address ipv4 192.69.1.12
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPPE_2
exit
exit
user-plane lps_asr9k-13
peer-address ipv4 192.69.1.13
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPPE_2
exit
exit
user-plane lps_asr9k-14
peer-address ipv4 192.69.1.14
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPPE_2
exit
exit
user-plane lps_asr9k-15
peer-address ipv4 192.69.1.15
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPPE_2
exit
```

```
exit
user-plane lps_asr9k-16
peer-address ipv4 192.69.1.16
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-17
peer-address ipv4 192.69.1.17
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-18
peer-address ipv4 192.69.1.18
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-19
peer-address ipv4 192.69.1.19
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-2
peer-address ipv4 192.69.1.2
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-20
peer-address ipv4 192.69.1.20
port-id 8805
```



```
    subscriber-profile SUBS_IPoE_2
  exit
  port-id Bundle-Ether1.1
    subscriber-profile SUBS_IPoE_2
  exit
  port-id Bundle-Ether1.2
    subscriber-profile SUBS_PPPOE_2
  exit
exit
user-plane lps_asr9k-21
  peer-address ipv4 192.69.1.21
  port-id 8805
    subscriber-profile SUBS_IPoE_2
  exit
  port-id Bundle-Ether1.1
    subscriber-profile SUBS_IPoE_2
  exit
  port-id Bundle-Ether1.2
    subscriber-profile SUBS_PPPOE_2
  exit
exit
user-plane lps_asr9k-22
  peer-address ipv4 192.69.1.22
  port-id 8805
    subscriber-profile SUBS_IPoE_2
  exit
  port-id Bundle-Ether1.1
    subscriber-profile SUBS_IPoE_2
  exit
  port-id Bundle-Ether1.2
    subscriber-profile SUBS_PPPOE_2
  exit
exit
user-plane lps_asr9k-23
  peer-address ipv4 192.69.1.23
  port-id 8805
    subscriber-profile SUBS_IPoE_2
  exit
  port-id Bundle-Ether1.1
    subscriber-profile SUBS_IPoE_2
  exit
  port-id Bundle-Ether1.2
    subscriber-profile SUBS_PPPOE_2
  exit
exit
user-plane lps_asr9k-24
  peer-address ipv4 192.69.1.24
  port-id 8805
    subscriber-profile SUBS_IPoE_2
  exit
  port-id Bundle-Ether1.1
    subscriber-profile SUBS_IPoE_2
  exit
  port-id Bundle-Ether1.2
    subscriber-profile SUBS_PPPOE_2
  exit
exit
user-plane lps_asr9k-25
  peer-address ipv4 192.69.1.25
  port-id 8805
    subscriber-profile SUBS_IPoE_2
  exit
  port-id Bundle-Ether1.1
    subscriber-profile SUBS_IPoE_2
```

```
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-26
peer-address ipv4 192.69.1.26
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-27
peer-address ipv4 192.69.1.27
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-28
peer-address ipv4 192.69.1.28
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-29
peer-address ipv4 192.69.1.29
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-3
peer-address ipv4 192.69.1.3
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-30
peer-address ipv4 192.69.1.30
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
```

```
exit
user-plane lps_asr9k-31
peer-address ipv4 192.69.1.31
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-32
peer-address ipv4 192.69.1.32
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-33
peer-address ipv4 192.69.1.33
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-34
peer-address ipv4 192.69.1.34
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-35
peer-address ipv4 192.69.1.35
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-36
peer-address ipv4 192.69.1.36
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-37
peer-address ipv4 192.69.1.37
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
```

```
user-plane lps_asr9k-38
peer-address ipv4 192.69.1.38
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-39
peer-address ipv4 192.69.1.39
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-4
peer-address ipv4 192.69.1.4
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-40
peer-address ipv4 192.69.1.40
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-41
peer-address ipv4 192.69.1.41
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-42
peer-address ipv4 192.69.1.42
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-43
peer-address ipv4 192.69.1.43
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
```

```
exit
exit
user-plane lps_asr9k-44
peer-address ipv4 192.69.1.44
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-45
peer-address ipv4 192.69.1.45
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-46
peer-address ipv4 192.69.1.46
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-47
peer-address ipv4 192.69.1.47
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-48
peer-address ipv4 192.69.1.48
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-49
peer-address ipv4 192.69.1.49
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-5
peer-address ipv4 192.69.1.5
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
```

```
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-50
peer-address ipv4 192.69.1.50
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
exit
user-plane lps_asr9k-6
peer-address ipv4 192.69.1.6
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-7
peer-address ipv4 192.69.1.7
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-8
peer-address ipv4 192.69.1.8
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
user-plane lps_asr9k-9
peer-address ipv4 192.69.1.9
port-id 8805
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.1
  subscriber-profile SUBS_IPoE_2
exit
port-id Bundle-Ether1.2
  subscriber-profile SUBS_PPpOE_2
exit
exit
instance instance-id 1
endpoint sm
exit
```

```

endpoint nodemgr
exit
endpoint n4-protocol
  retransmission timeout 0 max-retry 1
exit
endpoint dhcp
exit
endpoint pppoe
exit
endpoint radius
  replicas 1
  vip-ip 203.203.203.51
  interface coa-nas
    sla response 165000
  vip-ip 203.203.203.51 vip-port 3799
exit
exit
endpoint udp-proxy
  replicas 1
  nodes 2
  vip-ip 203.203.203.51 vip-port 2000
  interface n4
    sla response 165000
  exit
  interface gtpu
    sla response 165000
  exit
exit
exit
logging transaction duplicate disable
logging level application error
logging level transaction error
logging level tracing error
system mode running
exit

```

Configuring the UP

The following is a sample UP configuration:

```

user-plane asr9k-11
peer-address ipv4 10.105.247.124
subscriber-profile subs-default
port-id Bundle-Ether2.10
  subscriber-profile subs-vrf
exit
port-id Bundle-Ether2.20
  subscriber-profile subs-vrf
port-id Bundle-Ether2.10
exit
port-id Bundle-Ether2.30
  subscriber-profile subs-vrf
port-id Bundle-Ether2.10
exit
port-id Bundle-Ether2.40
  subscriber-profile subs-vrf
port-id Bundle-Ether2.10
exit
exit

```

Loading Day1 Configuration

To load the Day 1 configuration for cnBNG, run the following command:

```
ssh admin@ops_center_pod_ip -p 2024 < Day1config.cli
```



Note The **day1config.cli** file contains the necessary parameters required for the Day 1 configuration.

Alternatively, you can copy the configuration and paste it in the BNG Ops Center CLI to load the Day 1 configuration.

config

<Paste the Day 1 configuration here>

commit

exit

Day1config.cli

The **day1config.cli** file contains the Day 1 configuration for cnBNG. For a sample day1 configuration, see [Configuring the CP, on page 11](#).