



# Install the Cisco Dynamic Attributes Connector

This chapter discusses how to install the Cisco Dynamic Attributes Connector on all supported operating systems.

- [Supported Operating Systems and Third-Party Software, on page 1](#)
- [Install Prerequisite Software, on page 2](#)
- [Install the Cisco Secure Dynamic Attributes Connector, on page 6](#)
- [Upgrade the Cisco Secure Dynamic Attributes Connector, on page 9](#)

## Supported Operating Systems and Third-Party Software

The dynamic attributes connector requires the following:

- Ubuntu 18.04 or 20.04
- CentOS 7 Linux
- Red Hat Enterprise Linux (RHEL) 7 or 8
- Python 3.6.x
- Ansible 2.9 or later

Minimum requirements for all operating systems:

- 4 CPUs
- 8GB RAM
- 100GB available disk space

We recommend you size your virtual machines as follows:

- 50 connectors, assuming 5 filters per connector and 20,000 workloads: 4 CPUs; 8GB RAM; 100GB available disk space
- 125 connectors, assuming 5 filters per connector and 50,000 workloads: 8 CPUs, 16 GB RAM, 100GB available disk space



**Note** Failure to size your virtual machines properly can cause the dynamic attributes connector to fail or not to start.

If you wish to use vCenter attributes, we also require:

- vCenter 6.7
- VMware Tools must be installed on the virtual machine

## Install Prerequisite Software

### Before you begin

Make sure you have physical or virtual set up and that the system that can communicate with your the On-Prem Firewall Management Center or Cloud-Delivered Firewall Management Center. For details, see [Supported Operating Systems and Third-Party Software, on page 1](#).

**Step 1** (Optional.) Use a text editor to edit `/etc/environment` to export the following variables to enable communication with the internet if your Ubuntu machine is behind an internet proxy.

Variable	Value
<code>export http_proxy</code>	Use with an HTTP proxy. <i>user:pass@host-or-ip:port</i>
<code>export https_proxy</code>	Use this with an HTTPS proxy. <i>user:pass@host-or-ip:port</i>
<code>export no_proxy</code>	Remove the proxy configuration. <b><code>export no_proxy="localhost,127.0.0.1"</code></b>

Examples:

HTTP proxy without authentication:

```
vi /etc/environment
export http_proxy="myproxy.example.com:8181"
```

HTTPS proxy with authentication:

```
vi /etc/environment
export https_proxy="ben.smith:bens-password@myproxy.example.com:8181"
```

**Step 2** Use a different command window to confirm the settings:

```
env grep | proxy
```

Example result:

```
http_proxy=myproxy.example.com:8181
```

**Step 3** Continue with one of the following sections.

---

**Related Topics**

[Install Prerequisite Software—Ubuntu](#), on page 5

[Install Prerequisite Software—CentOS](#), on page 3

[Install Prerequisite Software—RHEL](#), on page 4

## Install Prerequisite Software—CentOS

**Before you begin**

Do all of the following:

- Make sure your system meets the prerequisites discussed in [Supported Operating Systems and Third-Party Software](#), on page 1.
- (Optional.) If you need proxy access to the dynamic attributes connector, see [Install Prerequisite Software](#), on page 2.

---

**Step 1** Make sure Docker is not installed and uninstall it if it is.

```
docker --version
```

If Docker is installed, uninstall it as discussed in [Uninstall Docker Engine on Ubuntu](#).

**Step 2** Update and upgrade your repositories.

CentOS 7:

```
sudo yum -y update && sudo yum -y upgrade
```

**Step 3** Install the epel repository.

CentOS 7:

```
sudo yum -y install epel-release
```

**Step 4** (CentOS 7 only.) Install Python 3.

```
sudo yum install -y python3 libselenium-python3
```

**Step 5** Install Ansible.

CentOS 7:

```
sudo yum install -y ansible
```

**Step 6** Verify the Ansible version is 2.9 or later.

CentOS 7:

```
ansible --version
ansible 2.9.24
config file = /etc/ansible/ansible.cfg
configured module search path = [u'/home/admin/.ansible/plugins/modules',
u'/usr/share/ansible/plugins/modules']
ansible python module location = /usr/lib/python2.7/site-packages/ansible
```

```
executable location = /usr/bin/ansible
python version = 2.7.5 (default, Apr 2 2020, 13:16:51) [GCC 4.8.5 20150623 (Red Hat 4.8.5-39)]
```

**Note** It's normal for Ansible to reference Python 2.x as the preceding output shows. The connector will still use Python 3.

### What to do next

Install the connector as discussed in [Install the Cisco Secure Dynamic Attributes Connector, on page 6](#).

To optionally stop using a proxy with the dynamic attributes connector, edit `/etc/environment` and remove the proxy configuration.

## Install Prerequisite Software—RHEL

### Before you begin

Do all of the following:

- Make sure your system meets the prerequisites discussed in [Supported Operating Systems and Third-Party Software, on page 1](#).
- (Optional.) If you need proxy access to the dynamic attributes connector, see [Install Prerequisite Software, on page 2](#).

**Step 1** Make sure Docker is not installed and uninstall it if it is.

```
docker --version
```

If Docker is installed, uninstall it as discussed in [Uninstall Docker Engine on Ubuntu](#).

**Step 2** Update your repositories.

RHEL 7:

```
sudo yum -y update && sudo yum -y upgrade
```

RHEL 8:

```
sudo dnf -y update && sudo dnf -y upgrade
```

**Step 3** Install the epel repository.

RHEL 7:

```
sudo yum -y install https://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm
```

RHEL 8:

```
sudo dnf -y install https://dl.fedoraproject.org/pub/epel/epel-release-latest-8.noarch.rpm
```

**Step 4** (RHEL 7 only.) Install Python 3.

```
sudo yum install -y python3 libselenium-python3
```

**Step 5** Install Ansible.

RHEL 7:

```
sudo yum -y install ansible
```

RHEL 8:

```
sudo dnf install -y ansible
```

**Step 6** Verify the Ansible version.

```
ansible --version
```

An example follows.

RHEL 7:

```
ansible 2.9.24
  config file = /etc/ansible/ansible.cfg
  configured module search path = [u'/home/stevej/.ansible/plugins/modules',
u'/usr/share/ansible/plugins/modules']
  ansible python module location = /usr/lib/python2.7/site-packages/ansible
  executable location = /usr/bin/ansible
  python version = 2.7.5 (default, Mar 20 2020, 17:08:22) [GCC 4.8.5 20150623 (Red Hat 4.8.5-39)]
```

**Note** It's normal for Ansible to reference Python 2.x as the preceding output shows. The connector will still use Python 3.

RHEL 8:

```
ansible 2.9.24
  config file = /etc/ansible/ansible.cfg
  configured module search path = ['/home/stevej/.ansible/plugins/modules',
'/usr/share/ansible/plugins/modules']
  ansible python module location = /usr/lib/python3.6/site-packages/ansible
  executable location = /usr/bin/ansible
  python version = 3.6.8 (default, Mar 18 2021, 08:58:41) [GCC 8.4.1 20200928 (Red Hat 8.4.1-1)]
```

---

### What to do next

Install the connector as discussed in [Install the Cisco Secure Dynamic Attributes Connector, on page 6](#).

To optionally stop using a proxy with the dynamic attributes connector, edit `/etc/environment` and remove the proxy configuration.

---

## Install Prerequisite Software—Ubuntu

**Step 1** Make sure Docker is not installed and uninstall it if it is.

```
docker --version
```

If Docker is installed, uninstall it as discussed in [Uninstall Docker Engine on Ubuntu](#).

**Step 2** Update your repositories.

```
sudo apt -y update && sudo apt -y upgrade
```

**Step 3** Confirm your Python version.

```
/usr/bin/python3 --version
```

If the version is earlier than 3.6, you must install version 3.6.x.

**Step 4** Install Python 3.6.

```
sudo apt -y install python3.6
```

**Step 5** Install the common libraries.

```
sudo apt -y install software-properties-common
```

**Step 6** Install Ansible.

```
sudo apt-add-repository -y -u ppa:ansible/ansible && sudo apt -y install ansible
```

**Step 7** Verify the Ansible version.

```
ansible --version
```

An example follows.

```
ansible --version
ansible 2.9.19
  config file = /etc/ansible/ansible.cfg
  configured module search path = [u'/home/admin/.ansible/plugins/modules',
u'/usr/share/ansible/plugins/modules']
  ansible python module location = /usr/lib/python2.7/dist-packages/ansible
  executable location = /usr/bin/ansible
  python version = 2.7.17 (default, Feb 27 2021, 15:10:58) [GCC 7.5.0]
```

**Note** It's normal for Ansible to reference Python 2.x as the preceding output shows. The connector will still use Python 3.6.

---

### What to do next

Install the connector as discussed in [Install the Cisco Secure Dynamic Attributes Connector, on page 6](#).

To optionally stop using a proxy with the dynamic attributes connector, edit `/etc/environment` and remove the proxy configuration.

## Install the Cisco Secure Dynamic Attributes Connector

### About the installation

This topic discusses installing the Cisco Secure Dynamic Attributes Connector. You must install the connector as a user with `sudo` privileges but you can run the connector as a non-privileged user.

### Before you begin

Make sure your system has the following prerequisite software:

- Ubuntu 18.04 or 20.04
- CentOS 7 Linux
- Red Hat Enterprise Linux (RHEL) 7 or 8
- Python 3.6.x

- Ansible 2.9 or later

Minimum requirements for all operating systems:

- 4 CPUs
- 8GB RAM
- 100GB available disk space

We recommend you size your virtual machines as follows:

- 50 connectors, assuming 5 filters per connector and 20,000 workloads: 4 CPUs; 8GB RAM; 100GB available disk space
- 125 connectors, assuming 5 filters per connector and 50,000 workloads: 8 CPUs, 16 GB RAM, 100GB available disk space




---

**Note** Failure to size your virtual machines properly can cause the dynamic attributes connector to fail or not to start.

---

If you wish to use vCenter attributes, we also require:

- vCenter 6.7
- VMware Tools must be installed on the virtual machine

To install prerequisite software, see [Install Prerequisite Software, on page 2](#).

### View the Readme and Release Notes

For the latest installation information, see the following:

Readme: <https://galaxy.ansible.com/cisco/csdac>

Release Notes: [Cisco Secure Dynamic Attributes Connector Release Notes](#)

### Get the Dynamic Attributes Connector software

To get the latest version of the dynamic attributes connector software, run the following command:

```
ansible-galaxy collection install cisco.csdac
```

### Install the muster service

The muster service is another name for the dynamic attributes connector.

Run the following command from the `~/.ansible/collections/ansible_collections/cisco/csdac` directory.

```
ansible-playbook default_playbook.yml [--ask-become-pass] [--extra-vars " vars " ]
```

---

### Syntax Description

`--ask-become-pass` Prompts you to enter the `sudo` password. Required if `sudo` is enabled on your machine.

---

---

**--extra-vars** The following optional extra variables enable the dynamic attributes connector to use a proxy. The value you use must match the value in `/etc/environment`, which you configured as discussed in [Install Prerequisite Software, on page 2](#).

- **csdac\_proxy\_enabled=true**
- **csdac\_http\_proxy\_url=http://PROXY\_URL**  
**csdac\_https\_proxy\_url=PROXY\_URL**

The following optional extra variables create a self-signed certificate you can use to securely connect to the dynamic attributes connector. If you omit these parameters, the dynamic attributes connector uses a default certificate.

- **csdac\_certificate\_domain**  
domain name for autogenerated certificate. Default value is autodetected hostname of the host (detected by ansible)
  - **csdac\_certificate\_country\_name**  
Two-letter country code. (Default is `us`)
  - **csdac\_certificate\_organization\_name**  
Organization name. (Default is `Cisco`)
  - **csdac\_certificate\_organization\_unit\_name**  
Organizational unit name (Default is `Cisco`)
- 

### Example installation with a default certificate

For example, to install the software with default options:

```
ansible-galaxy collection install cisco.csdac
cd ~/.ansible/collections/ansible_collections/cisco/csdac
ansible-playbook default_playbook.yml --ask-become-pass
```

### Example installation with optional certificate

For example, to install the software with an optional certificate:

```
ansible-galaxy collection install cisco.csdac
cd ~/.ansible/collections/ansible_collections/cisco/csdac
ansible-playbook default_playbook.yml --ask-become-pass --extra-vars
"csdac_certificate_domain=domain.example.com csdac_certificate_country_name=US
csdac_certificate_organization_name=Cisco
csdac_certificate_organization_unit_name=Engineering"
```

After you create the certificate, import it into the web browser you'll use to access the connector. The certificate is created in the `~/csdac/app/config/certs` directory.

### View the installation log

The installation log is located as follows:



```
~/ansible/collections/ansible_collections/cisco/csdac/logs/csdac.log
```

### Use your certificate to connect to the dynamic attributes connector

If you have a certificate and key, put them in the `~/csdac/app/config/certs` directory on your virtual machine.

After you perform the preceding task, restart the dynamic attributes connector's Docker container by entering the following command:

```
docker restart muster-ui
```

### Log in to the connector

1. Access the dynamic attributes connector at `https://ip-address`
2. Log in.

The initial login is username `admin`, password `admin`. You are required to change the password the first time you log in.

## Upgrade the Cisco Secure Dynamic Attributes Connector

This topic discusses how to upgrade from any earlier Cisco Secure Dynamic Attributes Connector to the current version. These tasks can be performed regardless of Cisco Secure Dynamic Attributes Connector version or operating system.

---

**Step 1** Log in to the machine you want to upgrade.

**Step 2** Enter the following commands:

```
ansible-galaxy collection install cisco.csdac --force
ansible-playbook default_playbook.yml --ask-become-pass
ansible-playbook default_playbook.yml --ask-become-pass [--extra-vars vars]
```

---

**Syntax Description** `--ask-become-pass` Prompts you to enter the `sudo` password. Required if `sudo` is enabled on your machine.

---

---

**--extra-vars** The following optional extra variables enable the dynamic attributes connector to use a proxy. The value you use must match the value in `/etc/environment`, which you configured as discussed in [Install Prerequisite Software](#), on page 2.

- **csdac\_proxy\_enabled=true**
- **csdac\_http\_proxy\_url=http://PROXY\_URL**  
**csdac\_https\_proxy\_url=PROXY\_URL**

The following optional extra variables create a self-signed certificate you can use to securely connect to the dynamic attributes connector. If you omit these parameters, the dynamic attributes connector uses a default certificate.

- **csdac\_certificate\_domain**  
domain name for autogenerated certificate. Default value is autodetected hostname of the host (detected by ansible)
- **csdac\_certificate\_country\_name**  
Two-letter country code. (Default is `us`)
- **csdac\_certificate\_organization\_name**  
Organization name. (Default is `Cisco`)
- **csdac\_certificate\_organization\_unit\_name**  
Organizational unit name (Default is `Cisco`)

---

**Step 3** Wait for the upgrade to complete.

**Step 4** Upgrade logs are available in the following location:

```
~/.ansible/collections/ansible_collections/cisco/csdac/logs/csdac.log
```

---

### What to do next

See [Create a Connector](#).