



# Modbus Inspector

- [Modbus Inspector Overview, on page 1](#)
- [Best Practices for Configuring the Modbus Inspector, on page 1](#)
- [Modbus Inspector Parameters, on page 2](#)
- [Modbus Inspector Rules, on page 2](#)
- [Modbus Inspector Intrusion Rule Options, on page 3](#)

## Modbus Inspector Overview

Type	Inspector (service)
Usage	Inspect
Instance Type	Multiton
Other Inspectors Required	stream_tcp
Enabled	false

The Modbus protocol defines a communication standard to exchange messages between a Supervisory Control and Data Acquisition (SCADA) system and a Programmable Automation Controller (PLC). The Modbus protocol uses TCP port 502.

The `modbus` inspector detects and analyzes Modbus messages in network traffic. When enabled, the Modbus intrusion rule options provide access to certain Modbus protocol fields.

## Best Practices for Configuring the Modbus Inspector

If your network does not contain an enabled Modbus device, you should not enable the `modbus` inspector in a network analysis policy that you apply to traffic.

# Modbus Inspector Parameters

## Modbus TCP port configuration

The `binder` inspector defines the Modbus TCP port configuration. For more information, see the [Binder Inspector Overview](#).

### Example:

```
[
  {
    "when": {
      "role": "server",
      "proto": "tcp",
      "ports": "502"
    },
    "use": {
      "type": "modbus"
    }
  },
  {
    "when": {
      "role": "any",
      "service": "modbus"
    },
    "use": {
      "type": "modbus"
    }
  }
]
```



**Note** The `modbus` inspector does not provide any parameters.

# Modbus Inspector Rules

Enable the `modbus` inspector rules to generate events and, in an inline deployment, drop offending packets.

**Table 1: Modbus Inspector Rules**

GID:SID	Rule Message
144:1	length in Modbus MBAP header does not match the length needed for the given function
144:2	Modbus protocol ID is non-zero
144:3	reserved Modbus function code in use

# Modbus Inspector Intrusion Rule Options

You can use a `modbus` option alone or in combination with the `content` and `byte_jump` intrusion rule options.

## **modbus\_data**

Sets the data cursor to the beginning of the Modbus `Data` field.

**Syntax:** `modbus_data;`

**Examples:** `modbus_data;`

## **modbus\_func**

Verifies that the Modbus `Function` field matches the specified Modbus function code. You can set a positive integer or string literal to represent a Modbus function code.

**Type:** string

**Syntax:** `modbus_func: <function>;`

**Valid values:**

*Table 2: Modbus Function Code Values*

Code	String
1	read_coils
2	read_discrete_inputs
3	read_holding_registers
4	read_input_registers
5	write_single_coil
6	write_single_register
7	read_exception_status
8	diagnostics
11	get_comm_event_counter
12	get_comm_event_log
15	write_multiple_coils
16	write_multiple_registers
17	report_slave_id
20	read_file_record
21	write_file_record

Code	String
22	mask_write_register
23	read_write_multiple_registers
24	read_fifo_queue
43	encapsulated_interface_transport

**Examples:**

```
modbus_func: read_coils;
```

```
modbus_func: 8;
```

**modbus\_unit**

Verifies that the Modbus Unit ID in the message matches the specified unit ID. You can set a number to represent the Modbus Unit ID.

**Type:** integer

**Syntax:** modbus\_unit: <unit\_id>;

**Valid range:** 0 to 255

**Examples:**

```
modbus_unit: 1;
```