

# GTPV1/V2 Echo Support for Peer MME and SGSN

- Feature Summary and Revision History, on page 1
- Feature Description, on page 2
- Configuring GTPV1/V2 Echo Support for Peer MME and SGSN, on page 2
- Monitoring and Troubleshooting, on page 3

## **Feature Summary and Revision History**

### **Summary Data**

| Applicable Product(s) or Functional Area | MME                               |
|--|-----------------------------------|
| Applicable Platform(s)                   | • ASR 5500                        |
|  | • VPC-DI                          |
|  | • VPC-SI                          |
| Feature Default                          | Disabled - Configuration Required |
| Related Changes in This Release          | Not applicable                    |
| Related Documentation                    | Command Line Interface Reference  |
|  | MME Administration Guide          |
|  | Statistics and Counters Reference |

### **Revision History**

| Revision Details  | Release |
|-------------------|---------|
| First introduced. | 21.17   |

### **Feature Description**

MME supports path management status of MME (S10) and SGSN (Gn/Gp). MME sends and receives GTP V2 Echo Message for Peer Node status in S10 Interface and GTP V1 Echo Message for Peer node status in Gn/Gp Interface. MME sends and receives the Echo message for Configured peer Node in MME regardless of GTP session.

Path failure is detected when there is no response to Echo Request even after max retransmissions. Path failure detection is not done based on "Restart counter value change in echo response".

GTP V1 Echo Message is supported in compliance with the 3GPP 29.060 7.2 Path Management Messages operation and GTP V2 Echo Message is supported in compliance with the 3GPP 29.274, 7.1 Path Management Messages operation.

Existing traps SGSNGtpcPathFailure, SGSNGtpcPathFailureClear, EGTPCPathFail, and EGTPCPathFailClear are used by this feature.

## Configuring GTPV1/V2 Echo Support for Peer MME and SGSN

This section provides information on the CLI commands to configure GTPV1/V2 Echo Support for Peer MME and SGSN feature.

### **Configuring Path Management for Peer MME**

Use the following configuration to configure the path management for Peer MME.

```
configure
  context context_name
  mme-service mme service name
```

peer-mme echo-params interval interval retransmission-timeout
retransmission\_timeout max-retransmissions max-retransmissions reconnect-interval
reconnect interval

no peer-mme echo-params end

#### NOTES:

- no: Removes the path management configuration for peer MME with Gn/Gp capability
- **peer-mme** : Configures a Peer MME for inter-MME relocations.
- echo-params : Configures echo parameters for peer MME with GN/GP Capability.
- interval interval: Configures echo interval in seconds. interval must be an ineteger between 60 and 300.
- retransmission-timeout retransmission\_timeout: Configures echo retransmission timeout in seconds. retransmission timeout must be an ineteger between 1 and 20.
- max-retransmissions max-retransmissions: Configures maximum retries for echo request. max-retransmissions must be an ineteger between 0 and 15.

• **reconnect\_interval** *reconnect\_interval*: Configures echo interval to be used once a peer node is detected to be unreachable. Retransmission is not applicable in this time. *reconnect\_interval* must be an ineteger between 60 and 86400.

### **Configuring Path Management for Peer SGSN**

Use the following configuration to configure the path management for Peer SGSN.

#### **NOTES:**

- no: Removes the path management configuration for peer SGSN with Gn/Gp capability
- echo-params: Configures echo parameters for peer SGSN with GN/GP Capability.
- interval interval: Configures echo interval in seconds. interval must be an ineteger between 60 and 300.
- retransmission-timeout retransmission\_timeout: Configures echo retransmission timeout in seconds. retransmission timeout must be an ineteger between 1 and 20.
- max-retransmissions max-retransmissions: Configures maximum retries for echo request. max-retransmissions must be an ineteger between 0 and 15.
- **reconnect\_interval** reconnect\_interval: Configures echo interval to be used once a peer node is detected to be unreachable. Retransmission is not applicable in this time. reconnect\_interval must be an ineteger between 60 and 86400.

## **Monitoring and Troubleshooting**

This section provides information regarding show commands available to monitor this feature.

### **Show Commands and Outputs**

### show mme-service all name

The output of this command includes the following fields:

- PEER MME Echo Parameters :
  - · interval
  - · retransmission timeout
  - · max retransmissions

- reconnect interval
- PEER GN/GP SGSN Echo Parameters:
  - interval
  - · retransmission timeout
  - · max retransmissions
  - reconnect interval

### show egtpc statistics

The output of this command includes the following fields:

Path Management Messages:

PEER MME Echo Request

- Total TX
- Initial TX
- Retrans TX

PEER MME Echo Response:

• Total RX

### show egtpc peers mme

Total Peers:

### Show sgtpc statistic

Path Management Messages:

#### Echo Request:

```
Total Echo-Req TX: Total Echo-Req RX: Initial Echo-Req TX: Initial Echo-Req RX: Retrans Echo-Req TX:
```

#### Echo Response:

```
Total Echo-Rsp TX: Total Echo-Rsp RX:
```

### show sgtpc peers

```
Path Service Echo Req Echo Req Echo Rsp
Status ID Peer Address Sent Retransmitted Received
```

| GTPV1/V2 Echo Support for Peer MME and SGSN |  |  |
|---|--|--|
|   |  |  |

Show Commands and Outputs

**Show Commands and Outputs**