



Ultra Cloud Core 5G Policy Control Function, Release 2020.05 - CLI Command Reference

First Published: 2020-12-22

Last Modified: 2021-02-02

Americas Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

All printed copies and duplicate soft copies of this document are considered uncontrolled. See the current online version for the latest version.

Cisco has more than 200 offices worldwide. Addresses and phone numbers are listed on the Cisco website at www.cisco.com/go/offices.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: <https://www.cisco.com/c/en/us/about/legal/trademarks.html>. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)

© 2020-2021 Cisco Systems, Inc. All rights reserved.



CONTENTS

PREFACE

About this Guide	xi
Conventions Used	xi
Contacting Customer Support	xii

CHAPTER 1

Mobile Policy Executive Commands	1
aaa authentication	2
cd	3
cdl clear sessions	3
cdl clear sessions filter	4
cdl show indexes	4
cdl show sessions	5
cdl show status	5
commit abort	6
commit confirm	6
commit persist-ID	6
compare	7
config exclusive	7
config shared	7
config terminal	8
deployment add	8
deployment remove-config	9
deployment show-config	9
describe	9
exit	10
help	10
history	10

id	11
idle-timeout	11
ignore-leading-space	11
job	12
leaf-prompting	12
license smart register	12
license smart deregister	13
license smart renew	13
logout session	14
logout user	14
no	14
paginate	14
quit	15
screen-length	15
screen-width	15
send	16
show	16
show-defaults	16
smiuser add-group	17
smiuser add-user	17
smiuser assign-user-group	17
smiuser change-password	18
smiuser change-password-age	19
smiuser change-self-password	19
smiuser delete-group	20
smiuser delete-user	20
smiuser show-user	20
smiuser unassign-user-group	21
smiuser update-password-length	21
subscriber	21
system ops-center	22
system sync	22
system upgrade	23
system uuid-override	23

system ops-center-debug 23

terminal 23

timestamp 24

who 24

CHAPTER 2

Mobile Policy Common Commands 25

cluster 25

cps-license 26

db 26

db balance 27

db global-settings volume-storage-class 28

db global-settings db-replica 28

db global-settings timers 28

db spr 29

debug 30

debug logging 31

debug logging logger 31

debug splunk 31

debug tracing 32

debug tracing jaeger 33

features 34

features activemq 34

features patching 34

show ldap 35

show ldap connection-status 35

ldap server-set 36

ldap server-set add-request-attribute 38

ldap server-set connection 38

ldap server-set health-check 39

ldap server-set search-user 40

testing 40

testing tls-handshake 41

testing zing-memory 42

zing 43

CHAPTER 3**Mobile Policy CDL Client Commands 45**

- datastore external-endpoints 45
- datastore external-endpoints connection-settings 45
- datastore external-endpoints connection-settings channel 46
- datastore external-endpoints connection-settings keep-alive 47
- datastore primary-endpoint 47
- datastore primary-endpoint connection-settings 48
- datastore primary-endpoint connection-settings channel 48
- datastore primary-endpoint connection-settings keep-alive 49

CHAPTER 4**Mobile Policy Diameter Commands 51**

- diameter 51
- diameter application 51
- diameter group 52
- diameter group stack 53
- diameter group stack diameter-engine alt-engines 54
- diameter group stack diameter-engine alt-engines primary 55
- diameter group stack diameter-engine alt-engines secondary 55
- diameter group stack grpc ext-svc 55
- diameter group stack settings timeouts-ms 56
- diameter grpc 57
- diameter grpc channel 57
- diameter next-hop-route next-hop-host 58
- diameter settings timeouts-ms 58

CHAPTER 5**Mobile Policy Infrastructure Commands 61**

- subversion 61

CHAPTER 6**Mobile Policy LDAP Commands 63**

- ldap-server-endpoint connect 63
- ldap-server-endpoint health-check-attributes 64
- ldap-server-endpoint health-check-filter 65
- ldap-server-endpoint input-mapping 65

ldap-server-endpoint ldap-clients	66
ldap-server-endpoint output-mapping	66

CHAPTER 7

Mobile Policy PCF Commands 67

advance-tuning async-threading	67
advance-tuning async-threading threading-config	69
advance-tuning brute-force-recovery	70
advance-tuning overload-control	70
advance-tuning diameter global action	70
advance-tuning diameter global limits	71
advance-tuning http2-threading	71
advance-tuning overload-control	72
advance-tuning n7-stale-session-error-codes	72
advance-tuning overload-control rest	73
advance-tuning overload-control rest global action	73
advance-tuning overload-control rest global limits	73
rest-endpoint	74
rest-endpoint certificate-status	75
rest-endpoint discovered-profiles	76
rest-endpoint discovered-profiles chf	76
rest-endpoint discovered-profiles udr	77
rest-endpoint interface	78
rest-endpoint peer-status	78
rest-endpoint registration-status	79
traffic engine	80
traffic engine rule	80

CHAPTER 8

Mobile Policy Services Repository Commands 83

deployment add config	84
deployment remove-config	85
deployment show-config	85
group nf-mgmt	85
group nf-mgmt failover	86
group nf-mgmt reconnect	86

group nrf discovery	87
group nrf discovery service type nrf	87
group nrf discovery service type nrf endpoint-profile	87
group nrf discovery service type nrf endpoint-profile endpoint-name	89
group nrf discovery service type nrf endpoint-profile endpoint-name primary ip-address	89
group nrf discovery service type nrf endpoint-profile endpoint-name secondary ip-address	90
group nrf discovery service type nrf endpoint-profile endpoint-name tertiary ip-address	91
group nrf discovery service type nrf endpoint-profile version uri-version	92
group nrf mgmt	93
group nrf mgmt service type nrf	93
group nrf mgmt service type nrf endpoint-profile	93
group nrf mgmt service type nrf endpoint-profile endpoint-name	95
group nrf mgmt service type nrf endpoint-profile endpoint-name primary ip-address	95
group nrf mgmt service type nrf endpoint-profile endpoint-name secondary ip-address	96
group nrf mgmt service type nrf endpoint-profile endpoint-name tertiary ip-address	97
group nrf mgmt service type nrf endpoint-profile version uri-version	98
profile nf-client nf-type bsf bsf-profile	99
profile nf-client nf-type bsf bsf-profile locality	99
profile nf-client nf-type bsf bsf-profile locality service name type	100
profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile	100
profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile endpoint-name	101
profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile version uri-version	102
profile nf-client nf-type chf chf-profile	102
profile nf-client nf-type chf chf-profile locality	103
profile nf-client nf-type chf chf-profile locality service name type	103
profile nf-client nf-type chf chf-profile locality service name type endpoint-profile	103
profile nf-client nf-type chf chf-profile locality service name type endpoint-profile endpoint-name	105
profile nf-client nf-type chf chf-profile locality service name type endpoint-profile version uri-version	105
profile nf-client nf-type udr udr-profile locality	106
profile nf-client nf-type udr udr-profile locality service name type	106
profile nf-pair nf-type	107
profile nf-pair nf-type locality	107

service-registration profile	108
service-registration profile allowed-plmns	109
service-registration profile pcf-info	110
service-registration profile pcf-info supi-ranges	111
service-registration profile plmn-list	111
service-registration profile snssais	112
service-registration services	112
service-registration services allowed-nssais	113
service-registration services allowed-plmns	113
show subscriber	114

CHAPTER 9

Mobile Policy TLS Commands 115

pcf-tls ca-certificates	115
pcf-tls certificates	115

CHAPTER 10

Mobile Policy Types Commands 117

api unified	117
engine	118
engine environment	119
engine grpc	119
engine install-features	120
engine patching patch	120
engine properties	121
engine resources limits	121
engine resources requests	122
external-services	122
label cdl-layer	123
label oam-layer	123
label protocol-layer	124
label service-layer	124

CHAPTER 11

Ports and Services Reference Information 125

Ports and Services	125
--------------------	-----



About this Guide

This preface describes the *Ultra Cloud Core 5G Policy Control Function CLI Command Reference*, the document conventions, and the customer support details.

- [Conventions Used, on page xi](#)
- [Contacting Customer Support, on page xii](#)

Conventions Used

The following tables describe the conventions used throughout this documentation.

Notice Type	Description
Information Note	Provides information about important features or instructions.
Caution	Alerts you of potential damage to a program, device, or system.
Warning	Alerts you of potential personal injury or fatality. May also alert you of potential electrical hazards.

Typeface Conventions	Description
Text represented as a screen display	This typeface represents displays that appear on your terminal screen, for example: Login:
Text represented as commands	This typeface represents commands that you enter, for example: show ip access-list This document always gives the full form of a command in lowercase letters. Commands are not case sensitive.

Typeface Conventions	Description
Text represented as a command <i>variable</i>	This typeface represents a variable that is part of a command, for example: show card <i>slot_number</i> <i>slot_number</i> is a variable representing the desired chassis slot number.
Text represented as menu or sub-menu names	This typeface represents menus and sub-menus that you access within a software application, for example: Click the File menu, then click New

Contacting Customer Support

Use the information in this section to contact customer support.

Refer to the support area of <http://www.cisco.com> for up-to-date product documentation or to submit a service request. A valid username and password are required to access this site. Please contact your Cisco sales or service representative for additional information.



CHAPTER 1

Mobile Policy Executive Commands

- [aaa authentication, on page 2](#)
- [cd, on page 3](#)
- [cdl clear sessions, on page 3](#)
- [cdl clear sessions filter, on page 4](#)
- [cdl show indexes, on page 4](#)
- [cdl show sessions, on page 5](#)
- [cdl show status, on page 5](#)
- [commit abort, on page 6](#)
- [commit confirm, on page 6](#)
- [commit persist-ID, on page 6](#)
- [compare, on page 7](#)
- [config exclusive, on page 7](#)
- [config shared, on page 7](#)
- [config terminal, on page 8](#)
- [deployment add, on page 8](#)
- [deployment remove-config , on page 9](#)
- [deployment show-config, on page 9](#)
- [describe, on page 9](#)
- [exit, on page 10](#)
- [help, on page 10](#)
- [history, on page 10](#)
- [id, on page 11](#)
- [idle-timeout, on page 11](#)
- [ignore-leading-space, on page 11](#)
- [job, on page 12](#)
- [leaf-prompting, on page 12](#)
- [license smart register, on page 12](#)
- [license smart deregister, on page 13](#)
- [license smart renew, on page 13](#)
- [logout session, on page 14](#)
- [logout user, on page 14](#)
- [no, on page 14](#)
- [paginate, on page 14](#)

- [quit](#), on page 15
- [screen-length](#), on page 15
- [screen-width](#), on page 15
- [send](#), on page 16
- [show](#), on page 16
- [show-defaults](#), on page 16
- [smiuser add-group](#), on page 17
- [smiuser add-user](#), on page 17
- [smiuser assign-user-group](#), on page 17
- [smiuser change-password](#), on page 18
- [smiuser change-password-age](#), on page 19
- [smiuser change-self-password](#), on page 19
- [smiuser delete-group](#), on page 20
- [smiuser delete-user](#), on page 20
- [smiuser show-user](#), on page 20
- [smiuser unassign-user-group](#), on page 21
- [smiuser update-password-length](#), on page 21
- [subscriber](#), on page 21
- [system ops-center](#), on page 22
- [system sync](#), on page 22
- [system upgrade](#), on page 23
- [system uuid-override](#), on page 23
- [system ops-center-debug](#), on page 23
- [terminal](#), on page 23
- [timestamp](#), on page 24
- [who](#), on page 24

aaa authentication

Configures the AAA-based user management parameters.

Command Modes	Exec
----------------------	------

Syntax Description	aaa authentication users user admin change-password { old-password <i>old_password</i> new-password <i>new_password</i> confirm-password <i>new_password</i> }
---------------------------	---

old-password *old_password*

Specify the old password.

Must be a string.

new-password *new_password*

Specify the new password.

Must be a string.

confirm-password *new_password*

Confirm the new password.

Must be a string.

Usage Guidelines

Use this command to configure the AAA-based user management parameters.

cd

Changes the current working directory.

Command Modes

Exec

Syntax Description

cd *directory* **ssh**

directory

Specify the directory name.

Must be a string.

Usage Guidelines

Use this command to change the current working directory.

cdl clear sessions

Clears the data from the Cisco Data Layer (CDL) datastore.

Command Modes

Exec

Syntax Description

cdl clear sessions [**db-name** *database* | **filter** *filter* | **map-id** *map_id* | **slice-name** *slice_name*]

db-name *database*

Specify the database name to be queried.

Must be a string of minimum one to maximum 16 characters.

filter *filter*

Specify the filter.

map-id *map_id*

Specify the map-id to clear the data for a map.

Must be an integer.

slice-name *slice_name*

Specify the slice name to be queried.

Must be a string of minimum one to maximum 16 characters.

Usage Guidelines Use this command to clear the data from the Cisco Data Layer (CDL) datastore.

cdl clear sessions filter

Clears the Cisco Data Layer (CDL) datastore sessions based on the filter criteria.

Command Modes Exec

Syntax Description `cdl clear sessions filter { condition { ends-with | match | starts-with } | key key_value }`

condition { ends-with | match | starts-with }

Specify the query expression.

key key_value

Specify the key value.

Usage Guidelines Use this command to clear CDL sessions based on the filter criteria.

cdl show indexes

Displays the indexes of the database from the datastore

Command Modes Exec

Syntax Description `cdl show indexes { db-name database | key key_value | limit maximum_indexes | map-id map_id | slice-name slice_name }`

db-name database_name

Specify to database name to be queried.

Must be a string.

key key_value

Specify to query value.

limit maximum_indexes

Specify the maximum number of indexes to be displayed.

Default value is 500.

map-id map_id

Specify the map-id to clear the data for a map.

Must be an integer.

slice-name *slice_name*

Specify the slice name to be queried.

Usage Guidelines Use this command to display the database indexes.

cdl show sessions

Displays the session data from the datastore.

Command Modes Exec

Syntax Description **cdl show sessions** { *count* | *detailed* | *summary* }

count

Specify to display the session count information.

Must be a string.

detailed

Specify to display the session details with data.

Must be a string.

summary

Specify to display the session details without data.

Must be a string.

Usage Guidelines Use this command to display the session data from the datastore.

cdl show status

Displays the status of the database from the datastore

Command Modes Exec

Syntax Description **cdl show status db-name** *database_name*

db-name *database_name*

Specify to display the status of the database.

Must be a string.

Usage Guidelines Use this command to display the status of the database from the datastore.

commit abort

Aborts the commit operation associated to the persist-ID.

Command Modes Exec

Syntax Description `commit { abort persist-id persist_id }`

abort persist-id *persist_id*

Specify to abort commit. Specify the persist-ID.

Must be an integer.

Usage Guidelines Use this command to abort the commit operation.

commit confirm

Confirms the commit operation for the persist-ID.

Command Modes Exec

Syntax Description `commit confirm persist-id persist_id`

persist-id *persist_id*

Specify to persist-ID for which the commit operation must be confirmed.

Must be an integer.

Usage Guidelines Use this command to confirm the commit operation for the persist-ID.

commit persist-ID

Displays the commits associated to the persist-ID.

Command Modes Exec

Syntax Description `commit persist-id persist_id`

persist-id *persist_id*

Specify to confirm the commit operation relevant to the persist-ID.

Must be an integer.

Usage Guidelines Use this command to display the commits associated to the persist-ID.

compare

Compares running configuration to another configuration or a file.

Command Modes

Exec

Syntax Description

compare file { *filename* [.kube | .ssh] | *another_configuration* }

***filename* [.kube | .ssh] |**

Specify the file name.

Must be a string.

another_configuration

another_configuration

Specify the configuration to be compared against.

Must be a string.

Usage Guidelines

Use this command to configure the file that must be compared.

config exclusive

Manipulates the software configuration information to enter the exclusive configuration mode.

Command Modes

Exec

Syntax Description

config exclusive [*no-confirm*]

exclusive

Specify to enter the exclusive configuration mode.

no-confirm

Specify to apply the command without asking for confirmation.

Usage Guidelines

Use this command to manipulate the software configuration information to enter the exclusive configuration mode.

config shared

Manipulates the software configuration information to enter the shared configuration mode.

Command Modes

Exec

Syntax Description **config shared [no-confirm]**

shared

Specify to enter the shared configuration mode.

no-confirm

Specify to apply the command without asking for confirmation.

Usage Guidelines Use this command to manipulate the software configuration information to enter the shared configuration mode.

config terminal

Manipulates the software configuration information to enter the terminal configuration mode.

Command Modes Exec

Syntax Description **config terminal [no-confirm]**

terminal

Specify to enter the terminal configuration mode.

no-confirm

Specify to apply the command without asking for confirmation.

Usage Guidelines Use this command to manipulate the software configuration information to enter the terminal configuration mode.

deployment add

Configures the deployment parameters such as the list of cluster-name, and external IP and port number of the unified-api service.

Command Modes Exec

Syntax Description **deployment add config { cluster-name *cluster_name* | port *port_number* | unified-api-external-ip *external_ip* }**

cluster-name cluster_name

Specify the cluster name.

Must be a string.

port *port_number*

Specify the port number of the unified-api service.

Must be an address.

unified-api-external-ip *external_ip*

Specify the external IP of the unified-api service.

Must be an address.

Usage Guidelines

Use this command to configure the deployment parameters such as the list of cluster-name, and external IP and port number of the unified-api service.

deployment remove-config

Removes the deployment configuration file.

Command Modes

Exec

Syntax Description

deployment remove-config

remove-config

Specify to remove the configuration file.

Must be a string.

Usage Guidelines

Use this command to remove the deployment configuration file.

deployment show-config

Displays the deployment environment parameters.

Command Modes

Exec

Syntax Description

deployment show-config

show-config

Specify to display the deployment parameters.

Must be a string.

Usage Guidelines

Use this command to display the deployment environment parameters.

describe

Displays the command information.

Command Modes	Exec
Syntax Description	describe <i>command</i> <i>command</i> Specify the command name. Must be a string.
Usage Guidelines	Use this command to view command information.

exit

Exits the current configuration mode and returns to the parent configuration mode.

Command Modes	Exec
Syntax Description	exit
Usage Guidelines	Use this command to exit the current configuration mode and return to the parent configuration mode. When used in the Exec mode, exits the session.

help

Displays help information for specified command.

Command Modes	Exec
Syntax Description	help <i>command</i> <i>command</i> Specify the command name to display help information.. Must be a string.
Usage Guidelines	Use this command to view help information for a specified command.

history

Configures the command history cache size.

Command Modes	Exec
Syntax Description	history <i>history_size</i>

history_size

Specify the command history cache size.

Must be an integer.

Usage Guidelines Use this command to configure the command history cache size.

id

Displays user ID information.

Command Modes Exec

Syntax Description `id`

Usage Guidelines Use this command to view user ID information.

idle-timeout

Configures the maximum duration a command can remain idle in seconds after which the system automatically terminates the command.

Command Modes Exec

Syntax Description `idle-timeout idle_timeout`

idle_timeout

Specify the idle timeout duration in seconds.

Usage Guidelines Use this command to configure the maximum duration a command can remain idle.

ignore-leading-space

Configures whether to ignore or consider leading whitespace at the beginning of a command.

Command Modes Exec

Syntax Description `ignore-leading-space { false | true }`

`ignore-leading-space { false | true }`

Specify false to ignore leading whitespace, and true to consider it.

Must be either "false" or "true".

Usage Guidelines Use this command to configure whether to ignore or consider leading whitespace at the beginning of a command.

job

Suspends the jobs that are running in the background.

Command Modes

Exec

Syntax Description

job stop *job_id*

job_id

Specify the job ID.

Must be an integer.

Usage Guidelines

Use this command to suspend the jobs that are running in the background.

leaf-prompting

Enables or disables automatically querying for leaf values.

Command Modes

Exec

Syntax Description

leaf-prompting { false | true }

leaf-prompting { false | true }

Specify false to disable leaf prompting, true to enable.

Must be either "false" or "true".

Usage Guidelines

Use this command to automatically query for leaf values.

license smart register

Registers the VNF for Smart Licensing.

Command Modes

Exec

Syntax Description

license smart register [force] idtoken *idtoken*

register

Specify to register the VNF for Smart Licensing.

Must be a string.

force

Specify to enable the force registration of the agent.

Must be a string.

idtoken

Specify the ID token to register the agent with.

Must be an integer.

Usage Guidelines Use this command to register the VNF for Smart Licensing.

license smart deregister

Deregisters the VNF for Smart Licensing.

Command Modes Exec

Syntax Description `license smart deregister`***deregister***

Specify to deregister the VNF for Smart Licensing.

Must be a string.

Usage Guidelines Use this command to deregister the VNF for Smart Licensing.

license smart renew

Renew smart agent IDs and authentication.

Command Modes Exec

Syntax Description `license smart renew { ID | auth }`***renew***

Specify to renew the smart agent IDs and authentication.

Must be an integer.

ID

Specify the ID to renew smart agent license registration information

auth

Specify to initiate a manual update of the license usage information with Cisco

Usage Guidelines Use this command to configure the license parameters for the NF.

logout session

Logs out a specific session.

Command Modes

Exec

Syntax Description

logout session *session*

session *session*

Specify the session from the possible completion options.

Must be a string.

Usage Guidelines

Use this command to log out of a specific session.

logout user

Logs out a specific user from all sessions.

Command Modes

Exec

Syntax Description

logout user *user*

user *user*

Specify the user from the possible completion options.

Must be a string.

Usage Guidelines

Use this command to log out a specific user from all the sessions.

no

Restores the command history cache size to its default setting. See the history command.

Command Modes

Exec

Syntax Description

no history

Usage Guidelines

Use this command to configure the command history cache size to its default setting. Refer to the history command.

paginate

Configures whether or not to paginate CLI command output.

Command Modes	Exec
Syntax Description	paginate { true false } paginate { true false } Specify false to disable paginating CLI command output, and true to enable. Must be either "false" or "true".
Usage Guidelines	Use this command to paginate the command output.

quit

Exits the management session.

Command Modes	Exec
Syntax Description	quit
Usage Guidelines	Use this command to exit the management session.

screen-length

Configures the number of rows of text that the terminal screen displays.

Command Modes	Exec
Syntax Description	screen-length <i>number_of_rows</i> <i>number_of_rows</i> Specify the number of rows. Must be an integer.
Usage Guidelines	Use this command to configure the number of rows that the terminal screen displays.

screen-width

Configures the number of columns that the terminal screen displays.

Command Modes	Exec
Syntax Description	screen-width <i>number_of_columns</i> <i>number_of_columns</i> Specify the number of columns.

Must be an integer.

Usage Guidelines

Use this command to configure the number of columns that the terminal screen displays.

send

Sends messages to the terminal of a specific user or all users.

Command Modes

Exec

Syntax Description

send *user message*

user

Specify the user to whom the message must be sent.

Must be a string. Select from the possible completions options.

message

Specify the message that must be sent.

Must be a string.

Usage Guidelines

Use this command to send messages to the terminal of a specific user or to all users.

show

Displays the system information.

Command Modes

Exec

Syntax Description

show *system_component*

system_component

Specify the component to view the information.

Must be a string. Select from the possible completion options.

Usage Guidelines

Use this command to view the system information.

show-defaults

Configures whether to display default values when showing the configuration.

Command Modes

Exec

Syntax Description

show-defaults { **false** | **true** }

show-defaults { false | true }

Specify whether to display or hide default values. To hide select false, to display select true.

Must be either "false" or "true".

Usage Guidelines

Use this command to view default values when viewing the configuration commands.

smiuser add-group

Configures the SMI group parameters.

Command Modes

Exec

Syntax Description

smiuser add-group groupname *group_name*

groupname *group_name*

Specify the group name in PAM.

Must be a string.

Usage Guidelines

Use this command to configure the SMI group parameters.

smiuser add-user

Configures the SMI user account parameters.

Command Modes

Exec

Syntax Description

smiuser add-user username *username* **password** *password*

username *username*

Specify the username.

Must be a string.

password *password*

Specify the user password.

Must be a string.

Usage Guidelines

Use this command to configure the smiuser parameters.

smiuser assign-user-group

Assigns the SMI user group.

Command Modes Exec

Syntax Description **smiuser assign-user-group** *groupname* *group_name* **username** *username*

username *username*

Specify the user name in PAM.

Must be a string.

groupname *group_name*

Specify the group name in PAM.

Must be a string.

Usage Guidelines Use this command to assign the SMI user group.

smiuser change-password

Allows resetting the SMI password.

Command Modes Exec

Syntax Description **smiuser change-password** { **username** *username* | **current_password** *current_password* | **new_password** *new_password* | **confirm_password** *new_password* | **password_expire_days** *expire_days* }

username *username*

Specify the username.

Must be a string.

current_password *current_password*

Specify the current password.

Must be a string.

new_password *new_password*

Specify the new password.

Must be a string.

confirm_password *new_password*

Confirm the new password.

Must be a string.

password_expire_days *expire_days*

Specify the number of days before password expires.

Must be an integer.

Usage Guidelines Use this command to reset the SMI password.

smiuser change-password-age

Configures the number of days before which the password expires.

Command Modes Exec

Syntax Description **smiuser change-password-age** [**username***username* | **password_expire_days***expire_days*]

username *username*

Specify the username.

Must be a string.

password_expire_days *expire_days*

Specify the number of days before which the password expires.

Must be an integer.

Usage Guidelines Use this command to configure the number of days before which the password expires.

smiuser change-self-password

Resets the SMI user accounts self-password.

Command Modes Exec

Syntax Description **smiuser change-self-password** { **current_password** *current_password* | **new_password** *new_password* | **confirm_password** *new_password* | **password_expire_days** *expire_days* }

current_password *current_password*

Specify the current password.

Must be a string.

new_password *new_password*

Specify the new password.

Must be a string.

confirm_password *new_password*

Confirm the new password.

Must be a string.

password_expire_days *expire_days*

Specify the number of days before which the password expires.

Must be an integer.

Usage Guidelines Use this command to reset the SMI user accounts self-password.

smiuser delete-group

Deletes the SMI group.

Command Modes Exec

Syntax Description **smiuser delete-group groupname** *group_name*

groupname *group_name*

Specify the group name.

Must be a string.

Usage Guidelines Use this command to delete the SMI user group.

smiuser delete-user

Deletes the SMI user.

Command Modes Exec

Syntax Description **smiuser delete-user username** *username*

username *username*

Specify the username.

Must be a string.

Usage Guidelines Use this command to delete the SMI user.

smiuser show-user

Displays the SMI user details.

Command Modes Exec

Syntax Description **smiuser show-user username** *username*

username *username*

Specify the username.

Must be a string.

Usage Guidelines Use this command to display the SMI user details.

smiuser unassign-user-group

Configures the SMI user's unassign user group.

Command Modes Exec

Syntax Description **smiuser unassign-user-group** **groupname** *groupname_pam* **username** *username_pam*

groupname *groupname_pam*

Specify the groupname in PAM.

Must be a string.

username *username_pam*

Specify the username in PAM.

Must be a string.

Usage Guidelines Use this command to configure the SMI user's unassign user group.

smiuser update-password-length

Configures the minimum password length.

Command Modes Exec

Syntax Description **smiuser update-password-length** **length** *password_length*

length *password_length*

Specify the minimum password length.

Must be an integer.

Usage Guidelines Use this command to configure the minimum password length.

subscriber

Configures the subscriber parameters.

Command Modes	Exec
Syntax Description	subscriber session [imsi <i>imsi_value</i> msisdn <i>msisdn_value</i>] imsi <i>imsi_value</i> Specify the IMSI value. Must be an integer. msisdn <i>msisdn_value</i> Specify the MSISDN value. Must be an integer.
Usage Guidelines	Use this command to configure the subscriber parameters.

system ops-center

Suspends the ops center diagnostics synching process.

Command Modes	Exec
Syntax Description	system ops-center stop ops-center stop Specify to stop the synching process. Must be a string.
Usage Guidelines	Use this command to suspend the ops center diagnostics synching process.

system sync

Configures automatic synching.

Command Modes	Exec
Syntax Description	system ops-center stop synch { start stop } Specify to start or stop the synching process. Must be either "start" or "stop".
Usage Guidelines	Use this command to configure automatic synching.

system upgrade

Enforces the product upgrade.

Command Modes	Exec
---------------	------

Syntax Description	system upgrade
--------------------	-----------------------

Usage Guidelines	Use this command to enforce the product upgrade.
------------------	--

system uuid-override

Enforce the UUID to a new value.

Command Modes	Exec
---------------	------

Syntax Description	system uuid-override new-uuid <i>uid</i>
--------------------	---

new-uuid *uid*

Specify the ID Token to register the agent with.

Must be a string.

Usage Guidelines	Use this command to enforce the UUID to a new value.
------------------	--

system ops-center-debug

Configures the Ops Center debugging process.

Command Modes	Exec
---------------	------

Syntax Description	system ops-center-debug { start stop }
--------------------	---

ops-center-debug { start | stop }

Specify to start or stop the ops-center debugging process.

Must be either "start" or "stop".

Usage Guidelines	Use this command to configure the Ops Center debugging process.
------------------	---

terminal

Configures the terminal parameters.

Command Modes	Exec
---------------	------

Syntax Description **terminal** *terminal_type*

terminal_type

Specify the terminal type.

Must be one of the following:

- ansi
- generic
- linux
- vt100
- xterm

Usage Guidelines Use this command to configure the terminal parameters.

timestamp

Enables or disables the timestamp parameters.

Command Modes Exec

Syntax Description **timestamp { enable | disable }**

timestamp { enable | disable }

Specify the configuration to enable or disable the timestamp display.

Usage Guidelines Use this command to enable or disable the timestamp parameters.

who

Displays information on currently logged on users.

Command Modes Exec

Syntax Description **who**

Usage Guidelines Use this command to view information on currently logged on users. The command output displays the Session, User, Context, From, Protocol, Date, and Mode information.



CHAPTER 2

Mobile Policy Common Commands

- [cluster](#), on page 25
- [cps-license](#), on page 26
- [db](#), on page 26
- [db balance](#), on page 27
- [db global-settings volume-storage-class](#), on page 28
- [db global-settings db-replica](#), on page 28
- [db global-settings timers](#), on page 28
- [db spr](#), on page 29
- [debug](#), on page 30
- [debug logging](#), on page 31
- [debug logging logger](#), on page 31
- [debug splunk](#), on page 31
- [debug tracing](#), on page 32
- [debug tracing jaeger](#), on page 33
- [features](#), on page 34
- [features activemq](#), on page 34
- [features patching](#), on page 34
- [show ldap](#), on page 35
- [show ldap connection-status](#), on page 35
- [ldap server-set](#), on page 36
- [ldap server-set add-request-attribute](#), on page 38
- [ldap server-set connection](#), on page 38
- [ldap server-set health-check](#), on page 39
- [ldap server-set search-user](#), on page 40
- [testing](#), on page 40
- [testing tls-handshake](#), on page 41
- [testing zing-memory](#), on page 42
- [zing](#), on page 43

cluster

Configures the cluster information.

Command Modes	Exec > Global Configuration
Syntax Description	<pre>cluster { cluster-id <i>cluster_id</i> system-id <i>system_id</i> }</pre> cluster-id <i>cluster_id</i> Specify the cluster ID. Must be a string. Default Value: "cluster-1". system-id <i>system_id</i> Specify the system ID. Must be a string. Default Value: "system-1".
Usage Guidelines	Use this command to configure cluster information.

cps-license

Registers the PCF license.

Command Modes	Exec > Global Configuration
Syntax Description	<pre>cps-licence <i>license_name</i> encrypted-key <i>encrypted_key</i></pre> cps-licence <i>license_name</i> Specify the feature name. Must be a string. encrypted-key <i>key</i> Specify the encrypted key. Must be a string.
Usage Guidelines	Use this command to registers the PCF license.

db

Configures the database parameter.

Product	PCF
Privilege	Security Administrator, Administrator

Syntax Description

```
db { balance shard count number_of_shard | global-settings { db-replica
number_of_replica | timers { catchup-timeout-millis catchup_timeout |
election-timeout-millis election_timeout | heartbeat-interval-millis
heartbeat_interval } } | spr shard-count number_of_spr_shards }
```

balance shard count *number_of_shard*

Specify to abort commit. Specify the persist ID.

Must be an integer.

db-replica *number_of_replica*

Specify the number of database replicas.

Must be an integer.

catchup-timeout-millis *catchup_timeout*

Specify the catchup timeout in milliseconds.

Must be an integer.

election-timeout-millis *election_timeout*

Specify the election timeout in milliseconds.

Must be an integer.

heartbeat-interval-millis *heartbeat_interval*

Specify the heartbeat interval in milliseconds.

Must be an integer.

spr shard-count *number_of_spr_shards*

Specify the number of SPR shards.

Must be an integer.

Usage Guidelines

Use this command to configure the database parameter.

db balance

Configures the Balance database.

Command Modes

Exec > Global Configuration

Syntax Description

```
balance shard-count balance_db_shard_count
```

shard-count *balance_db_shard_count*

Specify the Balance database's shard count.

Must be an integer.

Default Value: 1.

Usage Guidelines

Use this command to configure the Balance database.

Example

The following command configures the Balance database's shard count to 1:

```
db balance shard-count 1
```

db global-settings volume-storage-class

Configures the global volume storage settings for DB.

Command Modes

Exec > Global Configuration

Syntax Description

global-settings volume-storage-class [**default** | **local**]

volume-storage-class [**default** | **local**]

If the use-volume-claim is enabled, then specify the volume storage class.

Usage Guidelines

Use this command to configure the volume storage class for database.

db global-settings db-replica

Configures the replica count for the global DB.

Command Modes

Exec > Global Configuration

Syntax Description

global-settings db-replica *replica_count*

db-replica *replica_count*

Specify the global DB replica count.

Must be an integer.

Default Value: 3.

Usage Guidelines

Use this command to configure the replica count for the global DB.

db global-settings timers

Configures global MongoDB timers.

Command Modes

Exec > Global Configuration

Syntax Description

```
global-settings timers { catchup-timeout-millis catchup_timeout |
election-timeout-millis election_timeout | heartbeat-interval-millis
heartbeat_interval }
```

catchup-timeout-millis *catchup_timeout*

Specify the global catchup timeout period, in milliseconds.

Must be an integer.

Default Value: 2000.

election-timeout-millis *election_timeout*

Specify the global election timeout period, in milliseconds.

Must be an integer.

Default Value: 2000.

heartbeat-interval-millis *heartbeat_interval*

Specify the global heartbeat interval period, in milliseconds.

Must be an integer.

Default Value: 300.

Usage Guidelines

Use this command to configure the global MongoDB timers.

db spr

Configures the SPR database.

Command Modes

Exec > Global Configuration

Syntax Description

```
spr shard-count shard_count
```

shard-count *shard_count*

Specify the SPR database's shard count.

Must be an integer.

Default Value: 1.

Usage Guidelines

Use this command to configure the SPR database.

Example

The following command configures the SPR database's shard count to 20:

```
db spr shard-count 20
```

debug

Configures the debug parameters.

Syntax Description

```
debug { logging { default-level logging_level | logger logger_name } | tracing  
{ jaeger agent udp { host host_address | port port_number } | type } }
```

default-level *default_level*

Specify the default level that must be logged.

Must be one of the following:

- trace
- debug
- info
- warn
- error
- off

logger *logger_utility*

Specify the logging utility name.

Must be a string.

debug tracing type *tracing_type*

Specify the tracing type.

Must be one of the following:

- OPENTRACING_JAEGER
- DISABLED

Default Value: DISABLED.

host *host_address*

Specify the host address of the Jaeger agent.

port *port_number*

Specify the port number of the Jaeger agent.

Usage Guidelines

Use this command to configure debug information.

debug logging

Configures the logging parameters.

Command Modes

Exec > Global Configuration

Syntax Description

logging default-level [**debug** | **error** | **info** | **off** | **trace** | **warn**]

default-level *default_level*

Specify the default level that must be logged.

Must be one of the following:

- trace
- debug
- info
- warn
- error
- off

Usage Guidelines

Use this command to configure the logging parameters.

debug logging logger

Configures the logging utility.

Command Modes

Exec > Global Configuration

Syntax Description

logging logger *logger_utility*

logger *logger_utility*

Specify the logging utility name.

Must be a string.

Usage Guidelines

Use this command to configure the logging utility.

debug splunk

Configures the Splunk parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
splunk { batch-count event_count | batch-interval-ms batch_interval |
batch-size-bytes max_batch | hec-token splunk_hec | hec-url port_splunk }
```

batch-count *batch_count*

Specify the maximum number of events to send per batch.

Must be an integer.

Default Value: 10.

batch-interval-ms *batch_interval*

Specify the interval at which to send batched events, in milliseconds.

Must be an integer.

Default Value: 10000.

batch-size-bytes *batch_size*

Specify the maximum size of each batch of events, in bytes.

Must be an integer.

Default Value: 10240.

hec-token *hec_token*

Specify the Splunk HEC token.

Must be a string.

hec-url *hec_url*

Specify the protocol, hostname, and HTTP Event Collector port (8088 by default) of Splunk server.

Must be a string.

Usage Guidelines

Use this command to configure the Splunk parameters.

debug tracing

Configures the tracing parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
tracing [ jaegar agent agent udp [ host host_name | port port_number ] | type
tracing_type ]
```

jaegar agent *agent*

Specify the Jaegar agent's name

host *host_name*

Specify the host name of the Jaegar agent.

port *port_number*

Specify the port number of the Jaegar agent.

debug tracing type *tracing_type*.

Specify the tracing type.

Must be one of the following:

- OPENTRACING_JAEGER
- DISABLED

Default Value: DISABLED.

Usage Guidelines

Use this command to configure the tracing parameters.

debug tracing jaeger

Configures the Jaeger parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
jaeger [ agent host host_name | port port_name ] | type tracing_type ]
```

agent host *host_name*

Specify the host address of the Jaeger agent.

port *port_number*

Specify the port number of the Jaeger agent.

type *tracing_type*

Specify the tracing type.

Must be one of the following:

- OPENTRACING_JAEGER
- DISABLED

Default Value: DISABLED.

Usage Guidelines

Use this command to configure the Jaeger parameters.

features

Configures the control configuration for the application features.

Command Modes

Exec > Global Configuration

Syntax Description

```
features { activemq cluster-ip cluster_ip_address | patching ingress-enabled  
{ false | true } }
```

Usage Guidelines

Use this command configure the control configuration for the application features.

Example

The following command configures the control configuration for the application feature:

```
features { activemq cluster-ip 122.12.122.11 | patching ingress-enabled true }
```

features activemq

Configures the ActiveMQ parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
activemq cluster-ip ip_address
```

cluster-ip *ip_address*

Specify the IP address of the cluster.

Must be an IP address.

Usage Guidelines

Use this command to configure the ActiveMQ parameters.

features patching

Enables or disables the Ingress API.

Command Modes

Exec > Global Configuration

Syntax Description

```
patching ingress-enabled { false | true }
```

ingress-enabled { false | true }

Specify to enable or disable patching ingress, not secured.

Must be either "false" or "true".

Default Value: false.

Usage Guidelines

Use this command to enable or disable the Ingress API.

show ldap

Displays the LDAP connections.

Command Modes

Exec

Syntax Description

show ldap { connection-status { metric *metric_type* | value *metric_value* } | displaylevel *depth_level* }

metric *metric_type*

Specify the metric type.

Must be a string.

value *metric_value*

Specify the metric value.

Must be a string.

displaylevel *depth_level*

Specify the depth level of the LDAP connections.

Usage Guidelines

Use this command to display the LDAP connection information.

Example

The following command displays the LDAP connections:

```
show ldap connection-status
```

show ldap connection-status

Displays the LDAP connections for the SPR lookup.

Command Modes

Exec

Syntax Description

show ldap connection-status { metric *metric_type* | value *metric_value* }

metric *metric_type*

Specify the metric type

Must be a string.

value *metric_value*

Specify the metric value

Must be a string.

Usage Guidelines Use this command to display LDAP connections for the SPR lookup.

ldap server-set

Configures the LDAP server set parameters.

Command Modes Exec > Global Configuration

Syntax Description

```
ldap server-set server_name [ add-child-on-parent-create-failure { false |
true } | add-request-attribute attribute_name attribute_value | binds-per-second
binds_count | connection connection_address port_number {auto-reconnect { false
| true } | bind-timeout-ms bind_timeout_ms | connection-rule FASTEST/ROUND_ROBIN
| priority priority_number | timeout-ms timeout } |
ignore-ldap-error-result-codes result_code | initial-connections
initial_connections | max-connections max_connections |
max-failover-connection-age-ms max_failover_connections |
missing-attribute-result-code attribute_code |
number-consecutive-timeouts-for-bad-connection count_timeout | retry-count
retry_count | retry-timer-ms retry_time | use-asynchronous-operations { false
| true } ]
```

add-child-on-parent-create-failure { false | true }

Specify to enable or disable additions of child on parent creation failure.

Must be either "false" or "true".

Default Value: true.

binds-per-second *binds_count*

Specify the number of binds per second.

Must be of type decimal64, with 2 fraction digits.

Default Value: 0.20.

ignore-ldap-error-result-codes *result_code*

Specify to ignore LDAP error result codes.

Must be an integer.

initial-connections *initial_connections*

Specify the initial connections.

Must be an integer.

Default Value: 1.

max-connections *max_connections*

Specify the maximum number of connections.

Must be an integer.

Default Value: 10.

max-failover-connection-age-ms *max_failover_connections*

Specify the maximum failover connection age in milliseconds.

Must be an integer.

Default Value: 60000.

missing-attribute-result-code *result_code*

Specify missing attribute result code.

Must be an integer.

Default Value: 0.

number-consecutive-timeouts-for-bad-connection *count_timeouts*

Specify the number of consecutive timeouts for bad connection.

Must be an integer.

Default Value: -1.

retry-count *retry_count*

Specify the retry count.

Must be an integer.

Default Value: 3.

retry-timer-ms *retry_timeout*

Specify the retry timer timeout period in milliseconds.

Must be an integer.

Default Value: 50.

server-set *server_name*

Specify the name of the LDAP server set.

Must be a string.

use-asynchronous-operations { false | true }

Specify to enable or disable using LDAP asynchronous operations.

Must be either "false" or "true".

Default Value: true.

Usage Guidelines

Use this command to configure LDAP server set parameters.

ldap server-set add-request-attribute

Configures the request attribute.

Command Modes

Exec > Global Configuration

Syntax Description

add-request-attribute *attribute_name attribute_value*

attribute_name

Specify the request attribute name.

Must be a string.

attribute_value

Specify the request attribute value.

Must be a string.

Usage Guidelines

Use this command to configure the request attribute.

ldap server-set connection

Configure the LDAP connection parameters.

Command Modes

Exec > Global Configuration

Syntax Description

connection *ldap_server_address port_number* { **auto-reconnect** { **false** | **true** } | **bind-timeout-ms** *bind_timeout* | **connection-rule** *connection_rule* | **priority** *priority_number* | **timeout-ms** *timeout* }

auto-reconnect { **false** | **true** }

Specify to enable or disable auto reconnect to LDAP hosts.

Must be either "false" or "true".

Default Value: true.

bind-timeout-ms *bind_timeout*

Specify the timeout period for bind calls to LDAP in milliseconds.

Must be an integer.

Default Value: 2000.

connection-rule *connection_algorithm*

Specify the connection algorithm.

Must be one of the following:

- FASTEST
- ROUND_ROBIN

Default Value: ROUND_ROBIN.

connection *port_number*

Specify the port number of the LDAP server.

Must be an integer.

priority *priority_number*

Specify the priority of the LDAP server set.

Must be an integer.

Default Value: 100.

timeout-ms *timeout*

Specify the timeout period for calls to LDAP in milliseconds.

Must be an integer.

Default Value: 200.

ldap_server_address

Specify the address of the LDAP server.

Must be a string.

Usage Guidelines

Use this command to configure the LDAP connection parameters.

ldap server-set health-check

Configures the health check parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
health-check { attributes attribute_string | dn health_check_dn | filter
filter_string | interval-ms interval_value }
```

attributes health_check_attributes

Specify the health check attributes.

Must be a string.

dn *health_check_dn*

Specify the health check DN.

Must be a string.

filter *health_check_filter*

Specify the health check filter.

Must be a string.

interval-ms *health_check_interval*

Specify the health check interval in milliseconds.

Must be an integer.

Default Value: 5000.

Usage Guidelines Use this command to configure the health check parameters.

ldap server-set search-user

Enables search user for LDAP.

Command Modes Exec > Global Configuration

Syntax Description **search-user** { [**dn** *user_dn*] [**password** *user_password*] }

dn *user_dn*

Specify the user DN.

Must be a string.

password *user_password*

Specify the user password.

Must be an aes-cfb-128-encrypted string.

Usage Guidelines Use this command to enable search user for LDAP.

testing

Configures the parameters for the Testing feature

Command Modes Exec > Global Configuration

Syntax Description **testing** { **external-mongo-access** { **admin** | **balance** | **session** | **spr** } | **subversion-ingress-enabled** | **zing-compiler-options** | **zing-memory** } { **ip** *ip_address* | **port** *port_number* }

code-coverage-enabled { false | true }

Specify to enable or disable code coverage reporting with jacoco.

Must be either "false" or "true".

Default Value: false.

development-mode-enabled { false | true }

Specify to enable or disable development mode.

Must be either "false" or "true".

Default Value: false.

enforce-affinity-rules { false | true }

Specify to enable or disable anti affinity rules for pod scheduling.

Must be either "false" or "true".

Default Value: true.

ldap-grpc-enabled { false | true }

Specify to enable or disable redis IPC communication between ldap-ep to engine.

Must be either "false" or "true".

Default Value: false.

subversion-ingress-enabled { false | true }

Specify if the subversion ingress is enabled.

Must be either "false" or "true".

Default Value: false.

zing-compiler-options *compiler_options*

Specify the compiler options for Zing.

Must be one of the following:

- C2
- Falcon

Default Value: "C2".

Usage Guidelines

Use this command to configure the parameters for the Testing feature.

testing tls-handshake

Configures the TLS/SSL testing parameters.

Command Modes Exec > Global Configuration

Syntax Description **tls-handshake**

alpn-disabled { false | true }

Specify to enable or disable ALPN extension in HTTP2 TLS ClientHello handshake.

Must be either "false" or "true".

Default Value: false.

debug-enabled { false | true }

Specify to enable or disable TLS/SSL debug logs.

Must be either "false" or "true".

Default Value: false.

trust-all { false | true }

Specify to enable or disable Keystore certificate validation for client.

Must be either "false" or "true".

Default Value: false.

Usage Guidelines Use this command to configure the TLS/SSL testing parameters.

testing zing-memory

Configures the storage for preserving the Zing data.

Command Modes Exec > Global Configuration

Syntax Description **zing-memory [datastore *datastore_zing_memory* | diameter *diameter_zing_memory* | engine *engine_zing_memory* | ldap *ldap_zing_memory*]**

datastore *datastore_zing_memory*

Specify the datastore Zing memory. For example, -Xmx4g/-Xmx8g.

Must be a string.

Default Value: "-Xmx8g".

diameter *diameter_zing_memory*

Specify the Diameter Zing memory. For example, -Xmx4g/-Xmx8g.

Must be a string.

Default Value: "-Xmx8g".

engine *engine_zing_memory*

Specify the engine Zing memory. For example -Xmx4g/-Xmx8g.

Must be a string.

Default Value: "-Xmx8g".

ldap *ldap_zing_memory*

Specify the LDAP endpoint. For example, -Xmx4g/-Xmx8g.

Must be a string.

Default Value: "-Xmx8g".

Usage Guidelines

Use this command to preserve the Zing data.

Example

The following command configures the storage for Zing data:

```
testing zing-memory [ datastore -Xmx8g | diameter -Xmx4g | engine -Xmx8g | ldap -Xmx4g ]
```

zing

Enables or disables the Zing feature for the engine.

Command Modes

Exec > Global Configuration

Syntax Description

zing enable { false | true }

enable { false | true }

Specify to enable or disable Zing Java Virtual Machine.

Must be either "false" or "true".

Default Value: false.

Usage Guidelines

Use this command to enable or disable the Zing feature for the engine.

Example

The following command configures Zing for the engine:

```
zing enable true
```




CHAPTER 3

Mobile Policy CDL Client Commands

- [datastore external-endpoints](#), on page 45
- [datastore external-endpoints connection-settings](#), on page 45
- [datastore external-endpoints connection-settings channel](#), on page 46
- [datastore external-endpoints connection-settings keep-alive](#), on page 47
- [datastore primary-endpoint](#), on page 47
- [datastore primary-endpoint connection-settings](#), on page 48
- [datastore primary-endpoint connection-settings channel](#), on page 48
- [datastore primary-endpoint connection-settings keep-alive](#), on page 49

datastore external-endpoints

Configures the list of external datastore endpoints.

Command Modes	Exec > Global Configuration
Syntax Description	datastore external-endpoints <i>external_endpoint</i> external-endpoints <i>external_endpoints</i> Specify the external datastore endpoints.
Usage Guidelines	Use this command to configure the list of external datastore endpoints.

datastore external-endpoints connection-settings

Configures the connection setting parameters.

Command Modes	Exec > Global Configuration
Syntax Description	connection-settings { channel <i>channel_count</i> keep-alive { keep-alive-time-ms <i>keep_alive_time</i> keep-alive-timeout-ms <i>keep_alive_timeout</i> } timeout-ms <i>timeout_in_ms</i> port <i>port_number</i> rating <i>rating</i> }

timeout-ms *timeout_ms*

Specify the timeout period in milliseconds.

Must be an integer.

channel *channel_count*

Specify the number of parallel gRPC channels to open towards each datastore endpoint.

Must be an integer.

keep-alive-time-ms *keep_alive_time*

Specify the idle timeout in milliseconds, after which keepalive notification is sent.

Must be an integer.

keep-alive-timeout-ms *keep_alive_timeout*

Specify the idle timeout period in milliseconds, after which keepalive probe is initiated.

Must be an integer.

timeout-ms *timeout_ms*

Specify the timeout period in milliseconds.

Must be an integer.

port *port_number*

Specify the port number.

Must be an integer.

rating *rating*

Specify the rating for the datastore endpoint (higher the better).

Must be an integer.

Default Value: 0.

Usage Guidelines Use this command to configure connection settings.

datastore external-endpoints connection-settings channel

Configures the number of parallel gRPC channels to open towards each datastore endpoint.

Command Modes Exec > Global Configuration

Syntax Description **connection-settings channel count** *channel_count*

count *channel_count*

Specify the number of parallel gRPC channels to open towards each datastore endpoint.

Must be an integer.

Usage Guidelines

Use this command to configure the number of parallel gRPC channels to open towards each datastore endpoint.

Example

The following command configures the channel count to 10:

```
datastore external-endpoints sample1 connection-settings channel count 10
```

datastore external-endpoints connection-settings keep-alive

Configures keep-alive parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
connection-settings keep-alive { keep-alive-time-ms keep_alive_time |  
keep-alive-timeout-ms keep_alive_timeout }
```

keep-alive-time-ms *keep_alive_time*

Specify the idle timeout in milliseconds, after which keepalive notification is sent.

Must be an integer.

keep-alive-timeout-ms *keep_alive_timeout*

Specify the idle timeout period in milliseconds, after which keepalive probe is initiated.

Must be an integer.

Usage Guidelines

Use this command to configure the keep-alive parameters.

datastore primary-endpoint

Configures the primary (cluster local) datastore parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
primary-endpoint connection-settings { channel channel_count | keep-alive {  
keep-alive-time-ms keep_alive_time | keep-alive-timeout-ms keep_alive_timeout |  
timeout-ms } | timeout-ms timeout_in_ms }
```

channel *channel_count*

Specify the number of parallel gRPC channels to open towards each datastore endpoint.

Must be an integer.

keep-alive-time-ms *keep_alive_time*

Specify the idle timeout in milliseconds, after which keepalive notification is sent.

Must be an integer.

keep-alive-timeout-ms *keep_alive_timeout*

Specify the idle timeout period in milliseconds, after which keepalive probe is initiated.

Must be an integer.

timeout-ms *timeout_ms*

Specify the timeout period in milliseconds.

Must be an integer.

Usage Guidelines

Use this command to configure the primary datastore configuration.

datastore primary-endpoint connection-settings

Configures the datastore connection settings.

Command Modes

Exec > Global Configuration

Syntax Description

connection-settings { **channel** *channel_count* | **keep-alive** | **timeout-ms** *timeout_ms* }

channel *channel_count*

Specify the number of parallel gRPC channels to open towards each datastore endpoint.

Must be an integer.

timeout-ms *timeout_ms*

Specify the timeout period in milliseconds.

Must be an integer.

Usage Guidelines

Use this command to configure the datastore connection settings.

datastore primary-endpoint connection-settings channel

Configures the number of parallel gRPC channels to open towards each datastore endpoint.

Command Modes

Exec > Global Configuration

Syntax Description

connection-settings channel count *channel_count*

count *channel_count*

Specify the number of parallel gRPC channels to open towards each datastore endpoint.

Must be an integer.

Usage Guidelines

Use this command to configure the number of parallel gRPC channels to open towards each datastore endpoint.

Example

The following command configures the channel count to 10:

```
datastore external-endpoints sample1 connection-settings channel count 10
```

datastore primary-endpoint connection-settings keep-alive

Configures keep-alive parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
keep-alive { keep-alive-time-ms keep_alive_time | keep-alive-timeout-ms keep_alive_timeout }
```

keep-alive-time-ms *keep_alive_time*

Specify the idle timeout in milliseconds, after which keepalive notification is sent.

Must be an integer.

keep-alive-timeout-ms *keep_alive_timeout*

Specify the idle timeout period in milliseconds, after which keepalive probe is initiated.

Must be an integer.

Usage Guidelines

Use this command to configure the keep-alive parameters.

datastore primary-endpoint connection-settings keep-alive



CHAPTER 4

Mobile Policy Diameter Commands

- [diameter, on page 51](#)
- [diameter application, on page 51](#)
- [diameter group, on page 52](#)
- [diameter group stack, on page 53](#)
- [diameter group stack diameter-engine alt-engines, on page 54](#)
- [diameter group stack diameter-engine alt-engines primary, on page 55](#)
- [diameter group stack diameter-engine alt-engines secondary, on page 55](#)
- [diameter group stack grpc ext-svc, on page 55](#)
- [diameter group stack settings timeouts-ms, on page 56](#)
- [diameter grpc, on page 57](#)
- [diameter grpc channel, on page 57](#)
- [diameter next-hop-route next-hop-host, on page 58](#)
- [diameter settings timeouts-ms, on page 58](#)

diameter

Displays the configured Diameter stack definition.

Command Modes

Exec

Syntax Description

show diameter

Usage Guidelines

Use this command to view the configured Diameter stack definition.

Example

The following command displays the configured Diameter stack definition:

```
show diameter peer-status
```

diameter application

Configures the Diameter application definition.

Command Modes	Exec > Global Configuration
Syntax Description	application <i>application_name</i> { application-id <i>application_id</i> tgpp-application { false true } vendor <i>vendor_id</i> } application-id <i>application_id</i> Specify the application ID. Must be an integer. application <i>application_name</i> Specify the application abbreviation. For example, gx. Must be a string. tgpp-application { false true } Specify whether the application is a 3GPP application. Must be either "false" or "true". Default Value: false. vendor <i>vendor_id</i> Specify the vendor IDs. Must be an integer.
Usage Guidelines	Use this command to configure the Diameter application definition.

diameter group

Configures the Diameter stack group parameters.

Command Modes	Exec > Global Configuration
Syntax Description	group [group <i>group_name</i> mode <i>mode</i> repository <i>repository_name</i> stack <i>stack_name</i>] group <i>group_name</i> Specify the group and stack name. Must be a string in the pattern [a-zA-Z][a-zA-Z0-9-]*. mode <i>mode</i> Specify the mode in which the Diameter stack must run. Must be one of the following: • client

- server

Default Value: client.

repository *repository_name*

Specify the Helm repository.

Usage Guidelines

Use this command to configure the Diameter stack group.

diameter group stack

Configures the Diameter stack definition.

Command Modes

Exec > Global Configuration

Syntax Description

```
group group_name stack stack_name { application application_name | bind-ip
bind_ip_address | bind-port bind_port_number | fqdn fqdn_name | realm realm |
peer-host peer_host_name | peer-port peer_port_number | peer-realm peer_realm |
node-host node_host }
```

application *application_name*

Specify the Diameter application.

bind-ip *bind_ip_address*

Specify the IP address to use in the CER or CEA message.

Must be an IP address.

bind-port *bind_port_number*

Specify the port number to bind the server.

Must be a port number.

Default Value: 3868.

fqdn *fqdn*

Specify the fully qualified domain name (FQDN) to use in CER or CEA messages.

Must be a string.

node-host *node_host*

Specify the node host to start the stack on.

Must be a string.

peer-host *peer_host_name*

Specify the remote peer host address or FQDN.

Must be a string.

peer-port *peer_port_number*

Specify the peer port number.

Must be a port number.

Default Value: 3868.

peer-realm *peer_realm*

Specify the remote peer realm.

Must be a string.

realm *realm*

Specify the realm to use in CER or CEA messages.

Must be a string.

replicas *replica_count*

Specify the replica count.

Must be an integer.

Default Value: 1.

stack *stack_name*

Specify the stack name.

Must be a string.

Usage Guidelines

Use this command to configure the Diameter stack definition.

diameter group stack diameter-engine alt-engines

Configures the alternate Diameter engine parameters.

Command Modes

Exec > Global Configuration > Diameter Group Configuration > Stack Configuration

Syntax Description

alt-engines check-session-exists { false | true }

check-session-exists { false | true }

Specify whether to check if the session exists on the alternate-engines before forwarding requests.

Must be either "false" or "true".

Default Value: false.

Usage Guidelines

Use this command to configure the alternate Diameter engine parameters.

diameter group stack diameter-engine alt-engines primary

Configures the primary Diameter Engine parameters.

Command Modes Exec > Global Configuration > Diameter Group Configuration > Stack Configuration

Syntax Description **primary** **svc-name** *service_name* **port** *port_number*

port *port_number*

Specify the port number exposed by the external service.

Must be a port number.

Default Value: 8884.

svc-name *service_name*

Specify the external service name that represents the Diameter engine.

Usage Guidelines Use this command to configure the primary Diameter Engine parameters.

diameter group stack diameter-engine alt-engines secondary

Configures the secondary Diameter Engine parameters.

Command Modes Exec > Global Configuration > Diameter Group Configuration > Stack Configuration

Syntax Description **secondary** **svc-name** *service_name* **port** *port_number*

port *port_number*

Specify the port number exposed by the external service.

Must be a port number.

Default Value: 8884.

svc-name *service_name*

Specify the external service name that represents the Diameter engine.

Usage Guidelines Use this command to configure the secondary Diameter Engine parameters.

diameter group stack grpc ext-svc

Configures the external gRPC service parameters for the Diameter interface.

Command Modes Exec > Global Configuration

Syntax Description **ext-svc** { **port** *port_number* | **ip** *ip_address* }

ip *ip_address*

Specify the gRPC server's IP address.

Must be an IP address.

port *port_number*

Specify the port number to bind the server.

Must be a port number.

Default Value: 8868.

Usage Guidelines Use this command to configure the external gRPC service parameters for the Diameter interface.

diameter group stack settings timeouts-ms

Configures the timeout parameters for the Diameter interface.

Command Modes Exec > Global Configuration

Syntax Description **timeout-ms** [**cea** *cea_timeout* | **dpa** *dpa_timeout* | **dwa** *dwa_timeout* | **iac** *inactivity_timeout* | **request** *request_timeout* | **stop** *timeout_stop_diameter*]

cea *cea_exchange_timeout*

Specify the timeout duration for completing the CEA exchange in milliseconds.

Must be an integer.

Default Value: 10000.

dpa *dpa_timeout*

Specify the DPA timeout duration in milliseconds.

Must be an integer.

Default Value: 10000.

dwa *dwa_timeout*

Specify the DWA timeout duration in milliseconds.

Must be an integer.

Default Value: 10000.

iac *inactivity_timeout*

Specify the inactivity timeout duration in milliseconds.

Must be an integer.

Default Value: 5000.

request *request_timeout*

Specify the request timeout duration in milliseconds.

Must be an integer.

Default Value: 1750.

stop *stop_timeout*

Specify the timeout duration for stopping the Diameter interface in milliseconds.

Must be an integer.

Default Value: 9000.

Usage Guidelines

Use this command to configure the timeout duration for the Diameter interface.

Example

The following command configures the timeout duration for the Diameter interface:

```
diameter settings timeout-ms [ cea 10000 | dpa 10000 | dwa 10000 | iac 5000 | request 1750
| stop 9000 ]
```

diameter grpc

Configures the global gRPC settings.

Command Modes

Exec > Global Configuration

Syntax Description

grpc

Usage Guidelines

Use this command to configure the global gRPC settings.

Example

The following command configures the global gRPC settings:

```
diameter grpc channel count 100
```

diameter grpc channel

Configures the gRPC channels to open towards the server.

Command Modes

Exec > Global Configuration

Syntax Description

grpc channel count *channel_count*

channel *channel_count*

Specify the number of channel to open towards the server.

Must be an integer.

Default Value: 10.

Usage Guidelines

Use this command to configure the gRPC channels to open towards the server.

diameter next-hop-route next-hop-host

Configures the next-hop host name.

Command Modes

Exec > Global Configuration

Syntax Description

next_hop_realm rating *rating*

next-hop-host-name *hostname_list*

Specify the DRA hosts name list as received in the Origin-Host AVP in CER or CEA message.

Must be a string.

rating *rating*

Specify the rating that determines the priority.

Must be an integer.

Default Value: 0.

Usage Guidelines

Use this command to configure the next-hop host name.

Example

The following command configures the next-hop host name:

```
next_hop_realm rating 2
```

diameter settings timeouts-ms

Configures the timeout parameters for the Diameter interface.

Command Modes

Exec > Global Configuration

Syntax Description

timeout-ms [cea cea_timeout | dpa dpa_timeout | dwa dwa_timeout | iac inactivity_timeout | request request_timeout | stop timeout_stop_diameter]

cea *cea_exchange_timeout*

Specify the timeout duration for completing the CEA exchange in milliseconds.

Must be an integer.

Default Value: 10000.

dpa dpa_timeout

Specify the DPA timeout duration in milliseconds.

Must be an integer.

Default Value: 10000.

dwa dwa_timeout

Specify the DWA timeout duration in milliseconds.

Must be an integer.

Default Value: 10000.

iac inactivity_timeout

Specify the inactivity timeout duration in milliseconds.

Must be an integer.

Default Value: 5000.

request request_timeout

Specify the request timeout duration in milliseconds.

Must be an integer.

Default Value: 1750.

stop stop_timeout

Specify the timeout duration for stopping the Diameter interface in milliseconds.

Must be an integer.

Default Value: 9000.

Usage Guidelines

Use this command to configure the timeout duration for the Diameter interface.

Example

The following command configures the timeout duration for the Diameter interface:

```
diameter settings timeout-ms [ cea 10000 | dpa 10000 | dwa 10000 | iac 5000 | request 1750  
| stop 9000 ]
```

diameter settings timeouts-ms



CHAPTER 5

Mobile Policy Infrastructure Commands

- [subversion](#), on page 61

subversion

Configures Subversion parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
subversion { polling-interval-secs monitor_svn_thread_polling_interval |  
max-data-chunk-size max_data_chunk_size }
```

max-data-chunk-size *max_data_chunk_size*

Specify the maximum chunk size, in bytes, to store in configmap.

Must be an integer in the range of 300000-550000.

Default Value: 550000.

polling-interval-secs *monitor_svn_thread_polling_interval*

Specify the monitor-svn thread polling interval in seconds.

Must be an integer.

Default Value: 120.

Usage Guidelines

Use this command to configure the Subversion parameters.



CHAPTER 6

Mobile Policy LDAP Commands

- [ldap-server-endpoint connect](#), on page 63
- [ldap-server-endpoint health-check-attributes](#), on page 64
- [ldap-server-endpoint health-check-filter](#), on page 65
- [ldap-server-endpoint input-mapping](#), on page 65
- [ldap-server-endpoint ldap-clients](#), on page 66
- [ldap-server-endpoint output-mapping](#), on page 66

ldap-server-endpoint connect

Configures the LDAP Server connection parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
ldap-server-endpoint connect [ bind-ip bind_ip_address | binddn bind_dn |  
max-transactions max_tps | password password | port port_number | request-timeout  
request_timeout | replica replica_count ]
```

bind-ip *bind_ip_address*

Specify the IP address to connect to the LDAP server.

Must be an IP address.

binddn *bind_dn*

Specify the binding user to bind to the LDAP server.

Must be a string.

max-transactions *max_tps*

Specify the maximum TPS allowed.

Must be an integer.

Default Value: 200.

password *password*

Specify the binding user's password in plain text format.

Must be an aes-cfb-128-encrypted string.

port *port_number*

Specify the destination LDAP port to connect to the LDAP server.

Must be a port number.

Default Value: 9389.

replica *replica_count*

Specify the replica count.

Must be an integer.

Default Value: 1.

request-timeout *request_timeout*

Specify the request time out duration in milliseconds.

Must be an integer.

Default Value: 2000.

Usage Guidelines

Use this command to configure the LDAP Server connection parameters.

ldap-server-endpoint health-check-attributes

Configures the response attributes and values for the health-check request.

Command Modes

Exec > Global Configuration

Syntax Description

ldap-server-endpoint health-check-attributes *attribute_name* **value** *value*

value *value*

Specify the LDAP attribute filter value.

Must be a string.

attribute_name

Specify the LDAP attribute filter name.

Must be a string.

Usage Guidelines

Use this command to configure the response attributes and values for health-check request.

ldap-server-endpoint health-check-filter

Configures the health check filter parameters for the LDAP server endpoint.

Command Modes

Exec > Global Configuration

Syntax Description

health-check-filter *attribute_name* **value** *value*

value *value*

Specify the LDAP attribute filter value.

Must be a string.

attribute_name

Specify the LDAP attribute filter name.

Must be a string.

Usage Guidelines

Use this command to configure the health check filter parameters.

ldap-server-endpoint input-mapping

Configures mapping for the LDAP search query filter name to Session lookup attribute.

Command Modes

Exec > Global Configuration

Syntax Description

input-mapping *filter_name* **internal-lookup-key** *lookup_key*

internal-lookup-key *lookup_key*

Specify the session lookup key.

Must be one of the following:

- IMSI
- MSISDN
- IP_ADDRESS

filter_name

Specify the LDAP query filter name.

Must be a string.

Usage Guidelines

Use this command to configure the mapping for the LDAP search query filter name to Session lookup attribute.

ldap-server-endpoint ldap-clients

Configures the LDAP client credentials to bind to the server.

Command Modes

Exec > Global Configuration

Syntax Description

ldap-clients *client* **password** *password*

binddn *bind_dn*

Specify the binding user to bind to the LDAP server.

Must be a string.

password *password*

Specify the binding user's password in plain text format.

Must be an aes-cfb-128-encrypted string.

Usage Guidelines

Use this command to configure the LDAP client credentials to bind to the server.

ldap-server-endpoint output-mapping

Configures the mapping for session lookup attributes to LDAP search response attributes.

Command Modes

Exec > Global Configuration

Syntax Description

output-mapping *attribute_name* **input** *lookup_key*

input *lookup_key*

Specify the session lookup key.

Must be a string.

output-mapping *attribute_name*

Specify the LDAP response attribute name.

Must be a string.

Usage Guidelines

Use this command to configure the mapping for session lookup attributes to LDAP search response attributes.



CHAPTER 7

Mobile Policy PCF Commands

- [advance-tuning async-threading](#), on page 67
- [advance-tuning async-threading threading-config](#), on page 69
- [advance-tuning brute-force-recovery](#), on page 70
- [advance-tuning overload-control](#), on page 70
- [advance-tuning diameter global action](#), on page 70
- [advance-tuning diameter global limits](#), on page 71
- [advance-tuning http2-threading](#), on page 71
- [advance-tuning overload-control](#), on page 72
- [advance-tuning n7-stale-session-error-codes](#), on page 72
- [advance-tuning overload-control rest](#), on page 73
- [advance-tuning overload-control rest global action](#), on page 73
- [advance-tuning overload-control rest global limits](#), on page 73
- [rest-endpoint](#), on page 74
- [rest-endpoint certificate-status](#), on page 75
- [rest-endpoint discovered-profiles](#), on page 76
- [rest-endpoint discovered-profiles chf](#), on page 76
- [rest-endpoint discovered-profiles udr](#), on page 77
- [rest-endpoint interface](#), on page 78
- [rest-endpoint peer-status](#), on page 78
- [rest-endpoint registration-status](#), on page 79
- [traffic engine](#), on page 80
- [traffic engine rule](#), on page 80

advance-tuning async-threading

Configures threading configuration for HTTP outgoing request from PCF.

Command Modes

Exec > Global Configuration

Syntax Description

```
advance-tuning async-threading { default-drop-oldest-when-full { false | true } | default-priority default_priority | default-processing-threads processing_thread_number | default-queue-size default_queue_size | default-worker-threads default_number_worker_threads | request-timeout-ms request_timeout | thread-configuration service_name drop-oldest-when-full {
```

```
false | true } | priority thread_priority | queue-size queue_size | threads
thread_number }
```

default-drop-oldest-when-full { false | true }

Specify to drop the oldest packet when queue is full.

Must be either "false" or "true".

Default Value: false.

default-priority *default_priority*

Specify the default priority of thread.

Must be an integer.

Default Value: 5.

default-processing-threads *processing_thread_number*

Specify the default number of processing threads.

Must be an integer.

Default Value: 10.

default-queue-size *default_queue_size*

Specify the default size of the queue.

Must be an integer.

Default Value: 100.

default-worker-threads *default_number_worker_threads*

Specify the default number of worker threads.

Must be an integer.

Default Value: 20.

http2-connect-timeout-ms *http2_connect_timeout*

Specify the request timeout period in milliseconds.

Must be an integer.

Default Value: 100.

http2-idle-connection-timeout-sec *http2_client_idle_connect_timeout*

Specify the idle connection timeout for HTTP2 client.

Must be an integer.

Default Value: 60.

max-timeouts-to-reconnect *max_requests_timeouts_http2_connection*

Specify the maximum request timeouts to reconnect HTTP2 connection.

Must be an integer.

Default Value: 0.

Usage Guidelines

Use this command to configure threading configuration for HTTP outgoing request from PCF.

Example

The following command configures the threading configuration for HTTP outgoing request from PCF with default priority of 5:

```
advance-tuning async-threading default-priority 5
```

advance-tuning async-threading threading-config

Configures service threading.

Command Modes

Exec > Global Configuration

Syntax Description

```
threading-config service_name{ drop-oldest-when-full { false | true } |  
prioritythread_priority |queue-sizequeue_size |threadsthread_number }
```

drop-oldest-when-full { false | true }

Specify to drop the oldest packet when the queue is full.

Must be either "false" or "true".

priority *thread_priority*

Specify the threading priority.

Must be an integer.

queue-size *queue_size*

Specify the size of the queue.

Must be an integer.

service-name *service_name*

Specify the service name.

Must be a string.

threads *thread_number*

Specify the number of threads.

Must be an integer.

Usage Guidelines Use this command to configure threading service.

advance-tuning brute-force-recovery

Enables HTTP2 connection recovery parameters via closing connection.

Command Modes Exec > Global Configuration

Syntax Description **brute-force-recovery** { **max-reconnects** *max_http2_reconnects* | **time-interval-mins** *time_interval* }

max-reconnects *max_http2_reconnects*

Specify the maximum number of HTTP2 reconnect attempts to be allowed before restarting REST endpoint for recovery. Counter for previous reconnect attempts gets reset as per time-interval-mins. When set to 0, restart of rest endpoint is not performed even on reaching configured count and system continues attempting reconnect for recovery.

Must be an integer.

Default Value: 0.

time-interval-mins *time_interval*

Specify the time interval in minutes. If there is no HTTP2 reconnect triggered due to timeout for specified duration plus 1 minute then counter for previous reconnect attempts is reset to 0.

Must be an integer.

Default Value: 0.

Usage Guidelines Use this command to enable HTTP2 connection recovery parameters via closing connection.

advance-tuning overload-control

Configures Overload Control configuration for all Diameter interfaces.

Command Modes Exec > Global Configuration

Syntax Description **diameter** *global*

Usage Guidelines Use this command to configure Overload Control configuration for all Diameter traffic.

advance-tuning diameter global action

Configures the action to take on overload detection.

Command Modes Exec > Global Configuration

Syntax Description `action throttle-action throttle_action`

action throttle-action *throttle_action*

Specify the action to take when overload traffic is detected.

Must be one of the following:

- REJECT
- DROP

Usage Guidelines Use this command to configure the action that must be taken on overload detection.

advance-tuning diameter global limits

Configures the limits for the overload handling parameters for the REST or Diameter interface.

Command Modes Exec > Global Configuration

Syntax Description `limits max-requests-per-sec maximum_requests`

max-requests-per-sec *maximum_requests*

Specify the maximum number of requests that are allowed per second before throttling is applied.

Must be an integer.

Usage Guidelines Use this command to configure the limits for overload handling parameters for the REST or Diameter interface.

advance-tuning http2-threading

Configures threading configuration for HTTP incoming request to PCF.

Command Modes Exec > Global Configuration

Syntax Description `disable-validation { false | true } { idle-thread-timeout-ms idle_thread_timeout | max-queue-capacity max_packet_capacity | max-thread-pool-size max_thread_pool_size | min-thread-pool-size min_thread_pool_size | request-timeout-ms request_timeout }`

disable-validation { false | true }

Specify to enable or disable validation.

Must be either "false" or "true".

Default Value: false.

idle-thread-timeout-ms *idle_thread_timeout*

Specify the thread idle timeout in milliseconds.

Must be an integer.

Default Value: 60000.

max-queue-capacity *max_packet_capacity*

Specify the maximum packet capacity of the queue.

Must be an integer.

Default Value: 5000.

max-thread-pool-size *max_thread_pool_size*

Specify the maximum size of pool of threads.

Must be an integer.

Default Value: 20.

min-thread-pool-size *min_thread_pool_size*

Specify the minimum size of pool of threads.

Must be an integer.

Default Value: 5.

Usage Guidelines

Use this command to configure threading configuration for HTTP incoming request to PCF.

Example

The following command configures the threading configuration for HTTP incoming request to PCF with maximum queue capacity of 500:

```
advance-tuning http2-threading max-queue-capacity 500
```

advance-tuning overload-control

Configures threading configuration for HTTP incoming request to PCF.

Command Modes

Exec > Global Configuration

Syntax Description

overload-control

Usage Guidelines

Use this command to configure threading configuration for HTTP incoming request to PCF.

advance-tuning n7-stale-session-error-codes

Configures the N7Notify error code values for the N7 sessions for which the session expiration time must be reverted to the previous value. This indicates the value that was set before the N7Notify request was generated.

Command Modes	Exec > Global Configuration
Syntax Description	n7-stale-session-error-codes <i>error_codes</i>

n7-stale-session-error-codes *error_codes*

Specifies the N7Notify error code values for the N7 sessions. The session expiration time should be reverted to the previous value for these sessions, which indicates the value before the N7Notify request was generated.

You can specify multiple error codes using comma-separated values.

Default Value: Empty string.

Usage Guidelines	Use this command to configure the N7Notify error code values for the N7 sessions.
-------------------------	---

advance-tuning overload-control rest

Configures Overload Control configuration for all REST traffic.

Command Modes	Exec > Global Configuration
Syntax Description	global

Usage Guidelines	Use this command to configure threading configuration for HTTP incoming request to PCF.
-------------------------	---

advance-tuning overload-control rest global action

Configures the action to take on overload detection.

Command Modes	Exec > Global Configuration
Syntax Description	throttle-action <i>throttle_action</i>

throttle-action *throttle_action*

Specify the action to take when overload traffic is detected.

Must be one of the following:

- REJECT
- DROP

Usage Guidelines	Use this command to configure the action that must be taken on overload detection.
-------------------------	--

advance-tuning overload-control rest global limits

Configures the limits for the overload handling parameters for the REST or Diameter interface.

Command Modes Exec > Global Configuration

Syntax Description **limits max-requests-per-sec** *maximum_requests*

max-requests-per-sec *maximum_requests*

Specify the maximum number of requests that are allowed per second before throttling is applied.

Must be an integer.

Usage Guidelines Use this command to configure the limits for overload handling parameters for the REST or Diameter interface.

rest-endpoint

Configures the REST endpoint parameters.

Command Modes Exec > Global Configuration

Syntax Description **rest-endpoint** { **ips** *ip_address* | **port** *port_number* | **replicas** *replica_count* | **tracing-service-name** *service_name* }

certificate-name *certificate_name*

Specify the alias name for the certificate.

http-connection-limit *max_inbound_http_connections*

Specify the maximum number of allowed inbound HTTP connections.

Must be an integer.

Default Value: 200.

inbound-request-timeout-ms *inbound_requests_timeout*

Specify the timeout period for inbound requests in milliseconds.

Must be an integer.

Default Value: 2000.

ips *ip_address*

Specify the IP addresses for the REST service.

Must be an IP address.

outbound-request-timeout-ms *outbound_requests_timeout*

Specify the timeout period for outbound requests in milliseconds.

Must be an integer.

Default Value: 200.

port *port_number*

Specify port number of the REST service.

Must be an integer.

replicas *replica_count*

Specify the replica count.

Must be an integer.

Default Value: 1.

repository *repository_name*

Specify to override the Helm repository.

tracing-service-name *tracing_service_name*

Specify the tracing service name for REST endpoint.

Must be a string.

uri-scheme *uri_scheme*

Specify the URI scheme.

Must be one of the following:

- http
- https

Default Value: http.

Usage Guidelines

Use this command to configure the REST endpoint.

Example

The following command configures the REST endpoint tracing service name as nPcf-pcf-rest-ep:

```
rest-endpoint tracing-service-name nPcf-pcf-rest-ep
```

rest-endpoint certificate-status

Displays certificate status.

Command Modes

Exec > Global Configuration

Syntax Description

show **certificate-status**

certificateName

Displays the certificate name.

Must be a string.

timeToExpire

Displays the time to expire.

Must be a string.

Usage Guidelines Use this command to view certificate status.

rest-endpoint discovered-profiles

Displays the PCF discovered and cached NFs.

Command Modes Exec > Global Configuration

Syntax Description **show discovered-profiles**

Usage Guidelines Use this command to view the PCF discovered and cached NFs.

rest-endpoint discovered-profiles chf

Displays PCF Discover cache for CHF.

Command Modes Exec > Global Configuration

Syntax Description **show discovered-profiles chf**

expiry

The expiration time in seconds.

Must be a string.

ipv4Address

The NF IPv4 address.

Must be a string.

nflInstanceId

The NF Instance ID.

Must be a string.

nfStatus

Is the PCF instance registered to NRF.

Must be a string.

nfType

The NF type.

Must be a string.

port

The NF port number.

Must be a port number.

Usage Guidelines

Use this command to view PCF Discover cache for CHF.

rest-endpoint discovered-profiles udr

Displays PCF Discover cache for UDR.

Command Modes

Exec > Global Configuration

Syntax Description

show discovered-profiles udr

expiry

The expiration time in seconds.

Must be a string.

ipv4Address

The NF IPv4 address.

Must be a string.

nfInstanceld

The NF Instance ID.

Must be a string.

nfStatus

Is the PCF instance registered to NRF.

Must be a string.

nfType

The NF type.

Must be a string.

port

The NF port number.

Must be a port number.

Usage Guidelines Use this command to view PCF Discover cache for UDR.

rest-endpoint interface

Configures the NF interfaces.

Command Modes Exec > Global Configuration

Syntax Description **interface** *interface_type* **ip** *ip_address* [**outbound-request-timeout-ms** *outbound_request_timeout* | **notify-update-retry-count** *notify_update_retry_count*]

interface *interface_type*

Specify the NF interface type.

ip *ip_address*

Specify the NF interface IP address.

Must be an IP address.

outbound-request-timeout-ms *outbound_request_timeout*

Specify the timeout period for outbound requests in milliseconds.

Must be an integer.

notify-update-retry-count *notify_update_retry_count*

Specify retry count in case of timeout for N7_NotifyUpdate requests. The retry is attempted from the same rest-ep pod to the same peer.

Must be an integer.

Default value is 0.

Usage Guidelines Use this command to configure NF interfaces.

Example

The following command configures the NF interface to restEndpoint with the IP address 11.11.11.11:

```
rest-endpoint interface restEndpoint ip 11.11.11.11
```

rest-endpoint peer-status

Displays the NFs peer status.

Command Modes Exec > Global Configuration

Syntax Description **show peer-status****connectionDuration**

Displays the NF connection uptime duration.

Must be a string.

nfName

Displays the PCF Discover cache for UDR.

Must be a string.

peerIp

Displays the NF peer IP address.

Must be a string.

peerPort

Displays the NF peer port number.

Must be a string.

podIp

Displays the PCF pod IP address.

Must be a string.

Usage Guidelines Use this command to view the NFs peer status.

rest-endpoint registration-status

Displays NRF registration details.

Command Modes Exec > Global Configuration

Syntax Description **show registration-status****nrfUri**

Displays the registered NRF URI.

Must be a string.

podId

Displays the PCF pod ID.

Must be a string.

registered

Displays whether Is PCF instance is registered to NRF.

Must be a string.

Usage Guidelines

Use this command to view NRF registration details.

traffic engine

Configures the default engine group to receive traffic.

Command Modes

Exec > Global Configuration

Syntax Description

default-destination *default_destination*

default-destination *default_destination*

Specify the default engine group to receive the traffic.

Usage Guidelines

Use this command to configure the default engine group to receive traffic. Make sure to run this command on the machine with the appropriate product configured.

Example

The following command configures the default engine group as /policy-test:engine/test-test1:group:

```
traffic engine default-destination /policy-test:engine/test-test1:group
```

traffic engine rule

Configures the traffic routing rule parameters.

Command Modes

Exec > Global Configuration

Syntax Description

rule *rule_name* { **dnn** *dnn_route* | **supi** *supi_route* | **gpsi** *gpsi_route* | **hash-prefix** *hash_prefix_route* | **intf** *interface_route* | **destination** *engine_group* }

destination *engine_group*

Specify the engine group to receive traffic.

dnn *dnn_route*

Specify the route on DNN - regex.

Must be a string.

gpsi *gpsi_route*

Specify the route on GPSI - regex.

Must be a string.

hash-prefix *hash_prefix_route*

Specify the route on 2-digit hash - prefix.

Must be a string.

intf *interface_route*

Specify the route on interface type - exact.

Must be a string.

supi *supi_route*

Specify the route on SUPI - regex.

Must be a string.

rule_name

Specify the rule name.

Must be a string.

Usage Guidelines

Use this command to configure the traffic routing rule parameters.



CHAPTER 8

Mobile Policy Services Repository Commands

- deployment add config, on page 84
- deployment remove-config, on page 85
- deployment show-config, on page 85
- group nf-mgmt, on page 85
- group nf-mgmt failover, on page 86
- group nf-mgmt reconnect, on page 86
- group nrf discovery, on page 87
- group nrf discovery service type nrf, on page 87
- group nrf discovery service type nrf endpoint-profile, on page 87
- group nrf discovery service type nrf endpoint-profile endpoint-name, on page 89
- group nrf discovery service type nrf endpoint-profile endpoint-name primary ip-address, on page 89
- group nrf discovery service type nrf endpoint-profile endpoint-name secondary ip-address, on page 90
- group nrf discovery service type nrf endpoint-profile endpoint-name tertiary ip-address, on page 91
- group nrf discovery service type nrf endpoint-profile version uri-version, on page 92
- group nrf mgmt, on page 93
- group nrf mgmt service type nrf, on page 93
- group nrf mgmt service type nrf endpoint-profile, on page 93
- group nrf mgmt service type nrf endpoint-profile endpoint-name, on page 95
- group nrf mgmt service type nrf endpoint-profile endpoint-name primary ip-address, on page 95
- group nrf mgmt service type nrf endpoint-profile endpoint-name secondary ip-address, on page 96
- group nrf mgmt service type nrf endpoint-profile endpoint-name tertiary ip-address, on page 97
- group nrf mgmt service type nrf endpoint-profile version uri-version, on page 98
- profile nf-client nf-type bsf bsf-profile, on page 99
- profile nf-client nf-type bsf bsf-profile locality, on page 99
- profile nf-client nf-type bsf bsf-profile locality service name type, on page 100
- profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile, on page 100
- profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile endpoint-name, on page 101
- profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile version uri-version, on page 102
- profile nf-client nf-type chf chf-profile, on page 102
- profile nf-client nf-type chf chf-profile locality, on page 103
- profile nf-client nf-type chf chf-profile locality service name type, on page 103
- profile nf-client nf-type chf chf-profile locality service name type endpoint-profile, on page 103

- [profile nf-client nf-type chf chf-profile locality service name type endpoint-profile endpoint-name](#), on page 105
- [profile nf-client nf-type chf chf-profile locality service name type endpoint-profile version uri-version](#), on page 105
- [profile nf-client nf-type udr udr-profile locality](#), on page 106
- [profile nf-client nf-type udr udr-profile locality service name type](#), on page 106
- [profile nf-pair nf-type](#), on page 107
- [profile nf-pair nf-type locality](#), on page 107
- [service-registration profile](#), on page 108
- [service-registration profile allowed-plmns](#), on page 109
- [service-registration profile pcf-info](#), on page 110
- [service-registration profile pcf-info supi-ranges](#), on page 111
- [service-registration profile plmn-list](#), on page 111
- [service-registration profile snssais](#), on page 112
- [service-registration services](#), on page 112
- [service-registration services allowed-nssais](#), on page 113
- [service-registration services allowed-plmns](#), on page 113
- [show subscriber](#), on page 114

deployment add config

Configures the cluster name and unified API external IP parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
add config { cluster-name cluster_name | port port_number |  
unified-api-external-ip ip_address }
```

cluster-name *cluster_name*

Specify the cluster name.

Must be a string.

port *port_number*

Specify the port number of the unified API service.

Must be a port number.

unified-api-external-ip *ip_address*

Specify the external IP address of the unified API service.

Must be an IP address.

Usage Guidelines

Use this command to configure the cluster name and unified API external IP parameters.

deployment remove-config

Removes the deployment configuration file.

Command Modes	Exec
----------------------	------

Syntax Description	remove-config
---------------------------	----------------------

Usage Guidelines	Use this command to remove the deployment configuration file.
-------------------------	---

deployment show-config

Displays configuration information.

Command Modes	Exec
----------------------	------

Syntax Description	show-config
---------------------------	--------------------

Usage Guidelines	Use this command to view the configuration information.
-------------------------	---

group nf-mgmt

Configures the NF management group parameters.

Command Modes	Exec > Global Configuration
----------------------	-----------------------------

Syntax Description	group nf-mgmt <i>group_name</i> nrf-mgmt-group registerGroup { nrf-mgmt-group <i>mgmt_group_name</i> api-version <i>api_version</i> locality <i>group_locality</i> }
---------------------------	--

api-version *api_version*

Specify the NF Management Service API version supported by the NRF.

Must be one of the following:

- 1.0.0
- 1.0.2

Default Value: 1.0.0.

load-report-enabled { **false** | **true** }

Specify to enable or disable sending cluster load in NRF heartbeat requests.

Must be either "false" or "true".

Default Value: true.

locality *group_locality*

Specify the NRF group locality.

Must be a string.

nrf-mgmt-group *mgmt_group_name*

Specify the NRF management group name.

group_name

Specify the group name.

Must be a string.

Usage Guidelines

Use this command to enter the NRF management group configuration.

group nf-mgmt failover

Configures the failover SLA parameters.

Command Modes

Exec > Global Configuration

Syntax Description

failover group nf-mgmt *group_name* **failover sla** *failover_sla*

failover_sla

Specify the failover SLA value in milliseconds.

Must be an integer.

Usage Guidelines

Use this command to configure the failover SLA parameters.

group nf-mgmt reconnect

Configures the reconnect interval.

Command Modes

Exec > Global Configuration

Syntax Description

reconnect interval *reconnect_interval*

reconnect_interval

Specify the reconnect interval in milliseconds.

Must be an integer.

Usage Guidelines

Use this command to configure the reconnect interval.

group nrf discovery

Configures NRF discovery group parameters.

Syntax Description

discovery *group_name*

group_name

Specify the discovery group name.

Must be a string.

Usage Guidelines

Use this command to configure NRF discovery group parameters. Enters the NRF Discovery Configuration mode.

group nrf discovery service type nrf

Configures the NRF discovery service type.

Syntax Description

nrf nnrf-disc *service_type*

service_type

Specify the NRF discovery service type.

Must be nnrf-disc.

Usage Guidelines

Use this command to configure the NRF discovery service type.

group nrf discovery service type nrf endpoint-profile

Configures the endpoint profile parameters.

Command Modes

Exec > Global Configuration

Syntax Description

endpoint-profile *endpoint_profile_name* { **capacity** *endpoint_capacity* | **priority** *endpoint_priority* | **api-uri-prefix** *api_uri_prefix* | **api-root** *api_string* | **api-root** *api_string* | **uri-scheme** *uri_scheme* }

api-root *api_string*

Specify the deployment-specific service API prefix that is used within the { apiRoot }.

Must be a string.

api-uri-prefix *api_uri_prefix*

Specify the API URI prefix. If not configured, it takes the standard API name for the service as per the specification.

Must be a string.

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

Default Value: 10.

certificate-name *certificate_name*

Specify the alias name for client certificate.

Must be a string.

client-certificate *client_certificate*

Specify the client certificate in PEM format.

Must be an aes-cfb-128-encrypted string.

client-key *client_key*

Specify the client private key in PEM format.

Must be an aes-cfb-128-encrypted string.

name *endpoint_profile_name*

Specify the endpoint profile name.

Must be a string.

priority *endpoint_priority*

Specify the endpoint's priority.

Must be an integer.

Default Value: 1.

uri-scheme *uri_scheme*

Specify the URI scheme.

Must be one of the following:

- http
- https

Default Value: http.

Usage Guidelines

Use this command to configure the endpoint profile parameters.

group nrf discovery service type nrf endpoint-profile endpoint-name

Configures endpoint name.

Command Modes Exec > Global Configuration

Syntax Description **group nrf discovery** *discovery_group* **service type nrf nnrf-disc endpoint-profile** *endpoint_profile_name* { **priority** *endpoint_priority* | **capacity** *endpoint_capacity* }

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

name *endpoint_name*

Specify the endpoint name.

Must be a string.

priority *endpoint_priority*

Specify the priority for the service to select the appropriate profile using the load-balancing logic.

Must be an integer.

Usage Guidelines Use this command to configure the endpoint name.

group nrf discovery service type nrf endpoint-profile endpoint-name primary ip-address

Configures the IP address and port parameters.

Command Modes Exec > Global Configuration

Syntax Description **primary ip-address** [**ipv4** *ipv4_address* | **ipv6** *ipv6_address* | **port** *port_number*] | **secondary ip-address** [**ipv4** *ipv4_address* | **ipv6** *ipv6_address* | **port** *port_number*] | **tertiary ip-address** [**ipv4** *ipv4_address* | **ipv6** *ipv6_address* | **port** *port_number*]

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

group nrf discovery service type nrf endpoint-profile endpoint-name secondary ip-address

ipv4 *ipv4_address*

Specify the IPv4 address.

Must be an IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

Must be an IPv6 address.

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

Must be an IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

Must be an IPv6 address.

port *port_number*

Specify the port number.

Must be a port number.

Usage Guidelines

Use this command to configure the IP address and port parameters.

group nrf discovery service type nrf endpoint-profile endpoint-name secondary ip-address

Configures the IP address and port parameters.

Command Modes

Exec > Global Configuration

Syntax Description

secondary ip-address [**ipv4** *ipv4_address* | **ipv6** *ipv6_address* | **port** *port_number*] | **tertiary ip-address** [**ipv4** *ipv4_address* | **ipv6** *ipv6_address* | **port** *port_number*]

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

Must be an IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

Must be an IPv6 address.

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

Must be an IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

Must be an IPv6 address.

port *port_number*

Specify the port number.

Must be a port number.

Usage Guidelines

Use this command to configure the IP address and port parameters.

group nrf discovery service type nrf endpoint-profile endpoint-name tertiary ip-address

Configures the IP address and port parameters.

Command Modes

Exec > Global Configuration

Syntax Description

tertiary ip-address [**ipv4** *ipv4_address* | **ipv6** *ipv6_address* | **port** *port_number*]

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

Must be an IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

Must be an IPv6 address.

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

Must be an IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

Must be an IPv6 address.

port *port_number*

Specify the port number.

Must be a port number.

Usage Guidelines

Use this command to configure the IP address and port parameters.

group nrf discovery service type nrf endpoint-profile version uri-version

Configures the URI version.

Command Modes

Exec > Global Configuration

Syntax Description

version *uri_version* **full-version** *full_version*

full-version *full_version*

Specify the full URI version in the format *major-version.minor-version.patch-version.[alpha-draft-number]*.

Must be a string.

uri_version

Specify the URI version.

Must be a string in the pattern v\d.

Usage Guidelines

Use this command to configure the URI version.

group nrf mgmt

Configures the NRF management group parameters.

Syntax Description

mgmt *mgmt_group_name*

mgmt_group_name

Specify the management group name.

Must be a string.

Usage Guidelines

Use this command to configure the NRF management group parameters.

group nrf mgmt service type nrf

Configures the NRF management service type.

Syntax Description

service type nrf *service_name*

service_name

Specify the service name.

Must be nnrf-nfm.

Usage Guidelines

Use this command to configure the NRF management service type.

group nrf mgmt service type nrf endpoint-profile

Configures the endpoint profile parameters.

Command Modes

Exec > Global Configuration

Syntax Description

endpoint-profile *endpoint_profile_name* { **capacity** *endpoint_capacity* | **priority** *endpoint_priority* | **api-uri-prefix** *api_uri_prefix* | **api-root** *api_string* | **api-root** *api_string* | **uri-scheme** *uri_scheme* }

api-root api_string

Specify the deployment-specific service API prefix that is used within the { apiRoot }.

Must be a string.

api-uri-prefix *api_uri_prefix*

Specify the API URI prefix. If not configured, it takes the standard API name for the service as per the specification.

Must be a string.

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

Default Value: 10.

certificate-name *certificate_name*

Specify the alias name for client certificate.

Must be a string.

client-certificate *client_certificate*

Specify the client certificate in PEM format.

Must be an aes-cfb-128-encrypted string.

client-key *client_key*

Specify the client private key in PEM format.

Must be an aes-cfb-128-encrypted string.

name *endpoint_profile_name*

Specify the endpoint profile name.

Must be a string.

priority *endpoint_priority*

Specify the endpoint's priority.

Must be an integer.

Default Value: 1.

uri-scheme *uri_scheme*

Specify the URI scheme.

Must be one of the following:

- http
- https

Default Value: http.

Usage Guidelines

Use this command to configure the endpoint profile parameters.

group nrf mgmt service type nrf endpoint-profile endpoint-name

Configures endpoint name.

Command Modes

Exec > Global Configuration

Syntax Description

endpoint-profile *endpoint_profile_name* { **priority** *endpoint_priority* | **capacity** *endpoint_capacity* }

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

endpoint_profile_name

Specify the endpoint name.

Must be a string.

priority *endpoint_priority*

Specify the priority for the service to select the appropriate profile using the load-balancing logic.

Must be an integer.

Usage Guidelines

Use this command to configure the endpoint name.

group nrf mgmt service type nrf endpoint-profile endpoint-name primary ip-address

Configures the IP address and port parameters.

Command Modes

Exec > Global Configuration

Syntax Description

primary ip-address [**fqdn** *fqdn* [**ipv4** *ipv4_address* | **ipv6** *ipv6_address* | **port** *port_number*]

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

group nrf mgmt service type nrf endpoint-profile endpoint-name secondary ip-address

ipv4 *ipv4_address*

Specify the IPv4 address.

Must be an IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

Must be an IPv6 address.

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

Must be an IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

Must be an IPv6 address.

port *port_number*

Specify the port number.

Must be a port number.

Usage Guidelines

Use this command to configure the IP address and port parameters.

group nrf mgmt service type nrf endpoint-profile endpoint-name secondary ip-address

Configures the IP address and port parameters.

Command Modes

Exec > Global Configuration

Syntax Description

secondary ip-address [**fqdn** *fqdn* | **ipv4** *ipv4_address* | **ipv6** *ipv6_address* | **port** *port_number*]

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

Must be an IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

Must be an IPv6 address.

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

Must be an IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

Must be an IPv6 address.

port *port_number*

Specify the port number.

Must be a port number.

Usage Guidelines

Use this command to configure the IP address and port parameters.

group nrf mgmt service type nrf endpoint-profile endpoint-name tertiary ip-address

Configures the IP address and port parameters.

Command Modes

Exec > Global Configuration

Syntax Description

tertiary ip-address [**fqdn***fqdn* | **ipv4***ipv4_address* | **ipv6** *ipv6_address* | **port** *port_number*]

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

Must be an IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

Must be an IPv6 address.

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

Must be an IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

Must be an IPv6 address.

port *port_number*

Specify the port number.

Must be a port number.

Usage Guidelines

Use this command to configure the IP address and port parameters.

group nrf mgmt service type nrf endpoint-profile version uri-version

Configures the URI version.

Command Modes

Exec > Global Configuration

Syntax Description

uri_version **full-version** *full_version*

full-version *full_version*

Specify the full URI version in the format *major-version.minor-version.patch-version.[alpha-draft-number]*.

Must be a string.

uri_version

Specify the URI version.

Must be a string in the pattern v\d.

Usage Guidelines

Use this command to configure the URI version.

profile nf-client nf-type bsf bsf-profile

Configures the BSF profile parameters.

Command Modes

Exec > Global Configuration

Syntax Description

bsf-profile *bsf_profile_name*

bsf_profile_name

Specify the BSF profile name.

Must be a string.

Usage Guidelines

Use this command to configure the BSF profile parameters.

profile nf-client nf-type bsf bsf-profile locality

Configures the locality parameters.

Command Modes

Exec > Global Configuration

Syntax Description

locality *locality_name* **priority** *locality_priority*

priority locality_priority

Specify the locality priority.

Must be an integer.

Default Value: 65535.

locality_name

Specify the locality name.

Must be a string.

Usage Guidelines

Use this command to configure the locality parameters.

profile nf-client nf-type bsf bsf-profile locality service name type

Configures the BSF service type.

Command Modes Exec > Global Configuration

Syntax Description **service** *service_name* **type** *service_type*

type *service_type*

Specify the service type.

Must be nbsf-management.

Usage Guidelines Use this command to configure the BSF service type.

profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile

Configures the endpoint profile parameters.

Command Modes Exec > Global Configuration

Syntax Description **endpoint-profile** *endpoint_profile_name* { **capacity** *endpoint_capacity* | **priority** *endpoint_priority* | **api-uri-prefix** *api_uri_prefix* | **api-root** *api_string* | **api-root** *api_string* | **uri-scheme** *uri_scheme* }

api-root *api_string*

Specify the deployment-specific service API prefix that is used within the { apiRoot }.

Must be a string.

api-uri-prefix *api_uri_prefix*

Specify the API URI prefix. If not configured, it takes the standard API name for the service as per the specification.

Must be a string.

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

Default Value: 10.

certificate-name *certificate_name*

Specify the alias name for client certificate.

Must be a string.

client-certificate *client_certificate*

Specify the client certificate in PEM format.

Must be an aes-cfb-128-encrypted string.

client-key *client_key*

Specify the client private key in PEM format.

Must be an aes-cfb-128-encrypted string.

name *endpoint_profile_name*

Specify the endpoint profile name.

Must be a string.

priority *endpoint_priority*

Specify the endpoint's priority.

Must be an integer.

Default Value: 1.

uri-scheme *uri_scheme*

Specify the URI scheme.

Must be one of the following:

- http
- https

Default Value: http.

Usage Guidelines

Use this command to configure the endpoint profile parameters.

profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile endpoint-name

Configures endpoint name.

Command Modes

Exec > Global Configuration

Syntax Description

```
endpoint-profile endpoint_profile_name { priority endpoint_priority | capacity
endpoint_capacity }
```

profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile version uri-version

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

name *endpoint_name*

Specify the endpoint name.

Must be a string.

priority *endpoint_priority*

Specify the priority for the service to select the appropriate profile using the load-balancing logic.

Must be an integer.

Usage Guidelines

Use this command to configure the endpoint name.

profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile version uri-version

Configures the URI version.

Command Modes

Exec > Global Configuration

Syntax Description

version *uri_version* **full-version** *full_version*

full-version *full_version*

Specify the full URI version in the format *major-version.minor-version.patch-version.[alpha-draft-number]*.

Must be a string.

uri_version

Specify the URI version.

Must be a string in the pattern v\d.

Usage Guidelines

Use this command to configure the URI version.

profile nf-client nf-type chf chf-profile

Configures the locality for the UDR profile.

Syntax Description

chf-profile *chf_profile*

chf_profile_name

Specify the CHF profile name.

Must be a string.

Usage Guidelines

Use this command to configure the locality for the CHF profile.

profile nf-client nf-type chf chf-profile locality

Configures the locality for the CHF profile.

Syntax Description

locality *locality_name*

locality_name

Specify the locality name.

Must be a string.

Usage Guidelines

Use this command to configure the locality for the CHF profile.

profile nf-client nf-type chf chf-profile locality service name type

Configures the CHF service type.

Command Modes

Exec > Global Configuration

Syntax Description

type *service_type*

type *service_type*

Specify the CHF service type.

Must be one of the following:

- nchf-spendinglimitcontrol

Usage Guidelines

Use this command to configure the CHF service type.

profile nf-client nf-type chf chf-profile locality service name type endpoint-profile

Configures the endpoint profile parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
endpoint-profile endpoint_profile_name { capacity endpoint_capacity | priority
endpoint_priority | api-uri-prefix api_uri_prefix | api-root api_string | api-root
api_string | uri-scheme uri_scheme }
```

api-root *api_string*

Specify the deployment-specific service API prefix that is used within the { apiRoot }.

Must be a string.

api-uri-prefix *api_uri_prefix*

Specify the API URI prefix. If not configured, it takes the standard API name for the service as per the specification.

Must be a string.

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

Default Value: 10.

certificate-name *certificate_name*

Specify the alias name for client certificate.

Must be a string.

client-certificate *client_certificate*

Specify the client certificate in PEM format.

Must be an aes-cfb-128-encrypted string.

client-key *client_key*

Specify the client private key in PEM format.

Must be an aes-cfb-128-encrypted string.

name *endpoint_profile_name*

Specify the endpoint profile name.

Must be a string.

priority *endpoint_priority*

Specify the endpoint's priority.

Must be an integer.

Default Value: 1.

uri-scheme *uri_scheme*

Specify the URI scheme.

Must be one of the following:

- http
- https

Default Value: http.

Usage Guidelines

Use this command to configure the endpoint profile parameters.

profile nf-client nf-type chf chf-profile locality service name type endpoint-profile endpoint-name

Configures endpoint name.

Command Modes

Exec > Global Configuration

Syntax Description

endpoint-profile *endpoint_profile_name* { **priority** *endpoint_priority* | **capacity** *endpoint_capacity* }

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

name *endpoint_name*

Specify the endpoint name.

Must be a string.

priority *endpoint_priority*

Specify the priority for the service to select the appropriate profile using the load-balancing logic.

Must be an integer.

Usage Guidelines

Use this command to configure the endpoint name.

profile nf-client nf-type chf chf-profile locality service name type endpoint-profile version uri-version

Configures the URI version.

Command Modes

Exec > Global Configuration

Syntax Description

version *uri_version* **full-version** *full_version*

full-version *full_version*

Specify the full URI version in the format *major-version.minor-version.patch-version.[alpha-draft-number]*.

Must be a string.

uri_version

Specify the URI version.

Must be a string in the pattern v\d.

Usage Guidelines

Use this command to configure the URI version.

profile nf-client nf-type udr udr-profile locality

Configures the locality for the UDR profile.

Syntax Description

locality *locality* [**priority** *priority* | **service** *udr_service*]

priority *priority*

Specify the priority for the UDR local configuration."

Must be an integer.

udr-profile *udr_profile_name*

Specify the UDR profile name."

Must be a string.

Usage Guidelines

Use this command to configure the locality for the UDR profile.

profile nf-client nf-type udr udr-profile locality service name type

Configures UDR service type.

Command Modes

Exec > Global Configuration

Syntax Description

service_name **type** *service_type*

type *service_type*

Specify the service type.

Must be nudr-dr.

Usage Guidelines Use this command to configure the UDR service type.

profile nf-pair nf-type

Configures the NF type for the NF client pair configuration.

Syntax Description `nf_type nrf-discovery-group group_name { subscription-enabled { false | true } | subscription-enabled { false | true } | subscription-extension extension_duration }`

nrf-discovery-group group_name

Specify the NRF discovery group name.

subscription-enabled { false | true }

Specify to enable or disable the subscription to NRF for NF change.

Must be either "false" or "true".

Default Value: false.

subscription-extension extension_duration

Specify the duration for which the subscription must be extended in minutes.

Must be an integer.

Default Value: 60.

nf_type

Specify the NF type.

Must be one of the following:

- UDR
- CHF
- BSF

Usage Guidelines Use this command to configure the NF type for the NF client pair configuration.

profile nf-pair nf-type locality

Configures the locality parameters.

Command Modes Exec > Global Configuration

Syntax Description `locality [ client client_locality | preferred-server preferred_server | geo-server geo_server ]`

client *client_locality*

Specify the locality of the client.

geo-server *geo_service_locality*

Specify the geo-server locality information.

Must be a string.

preferred-server *preferred_server_locality*

Specify the preferred server locality information.

Must be a string.

Usage Guidelines

Use this command to configure the locality parameters.

service-registration profile

Configures the network function profile parameters to enable discovery of the registered NFs, and when the discovery fails, the discovery is attempted on the local configuration.

Command Modes

Exec > Global Configuration

Syntax Description

```
profile { allowed-plmns { mobile_country_code | mobile_network_code } | capacity
profile_capacity | instance-id instance_id_pcf | locality pcf_location | nf-status
nf_service_status | pcf-info { dnn-list | supi-ranges } | plmn-list {
mobile_country_code | mobile_network_code } | priority profile_priority | snssais {
slice_service_type | sd service_differentiator } }
```

capacity *profile_capacity*

Specify the PCFs profile's capacity.

Must be an integer.

fqdn *fqdn*

Specify the fully qualified domain name of the PCF. For example, pcf.5gc.mnc123.mcc089.pub.3gppnetwork.org.

Must be a string.

instance-id *pcf_instance_id*

Specify the PCF instance ID.

Must be a string.

locality *pcf_location*

Specify the location of the PCF.

Must be a string.

capacity *profile_capacity*

Specify the PCFs profile's capacity.

Must be an integer.

fqdn *fqdn*

Specify the fully qualified domain name of the PCF. For example, pcf.5gc.mnc123.mcc089.pub.3gppnetwork.org.

Must be a string.

instance-id *pcf_instance_id*

Specify the PCF instance ID.

Must be a string.

locality *pcf_location*

Specify the location of the PCF.

Must be a string.

priority *profile_priority*

Specify the PCF profile's priority.

Must be an integer.

nf_service_status

Specify the PCF service status.

Must be one of the following:

- REGISTERED
- UNDISCOVERABLE

Default Value: REGISTERED.

Usage Guidelines

Use this command to configure the network function profile.

service-registration profile allowed-plmns

Configures PLMNs allowed to access the network function.

Command Modes

Exec > Global Configuration

Syntax Description

allowed-plmns { *mobile_country_code* | *mobile_network_code* }

mobile_country_code

Specify the Mobile Country Code.

Must be a string in the pattern `\d{3}`.

mobile_network_code

Specify the Mobile Network Code.

Must be a string in the pattern `\d{2,3}`.

Usage Guidelines Use this command to configure PLMNs allowed to access the network function.

service-registration profile pcf-info

Configures the PCF parameters.

Command Modes Exec > Global Configuration

Syntax Description **pcf-info** { **dnn-list** *dnn_list_name* | **supi-ranges** *supi_range_id* [**start** *start_value* | **pattern** *range_pattern* | **end** *end_value*] }

dnn-list dnn_list_name

Specify the DNNs supported by the PCF.

Must be a string.

supi-ranges supi_range_id

Specify the SUPI range identifier.

Must be a string.

start start_value

Specify the first value of the SUPI range.

Must be a string in the pattern `[0-9]+`.

pattern range_pattern

Specify the regular expression according to the ECMA-262 dialect that represents the set of SUPIs belonging to the specified range.

Must be a string.

end end_value

Specify the last value of the SUPI range.

Must be a string in the pattern `[0-9]+`.

Usage Guidelines Use this command to configure PCF parameters.

service-registration profile pcf-info supi-ranges

Configures the list of SUPI ranges, which the PCF instance serves.

Command Modes	Exec > Global Configuration
Syntax Description	supi-ranges <i>supi_range_id</i> [start <i>start_value</i> pattern <i>range_pattern</i> end <i>end_value</i>] end <i>end_value</i> Specify the last value of the SUPI range. Must be a string in the pattern [0-9]+. pattern <i>range_pattern</i> Specify the regular expression according to the ECMA-262 dialect that represents the set of SUPIs belonging to the specified range. Must be a string. start <i>start_value</i> Specify the first value of the SUPI range. Must be a string in the pattern [0-9]+. supi_range_id Specify the SUPI range identifier. Must be a string.

Usage Guidelines Use this command to configure the list of SUPI ranges, which the PCF instance serves.

service-registration profile plmn-list

Configures the PLMNs of the network function.

Command Modes	Exec > Global Configuration
Syntax Description	plmn-list { <i>mobile_country_code</i> <i>mobile_network_code</i> } mobile_country_code Specify the Mobile Country Code. Must be a string in the pattern \d{3}.

mobile_network_code

Specify the Mobile Network Code.

Must be a string in the pattern `\d{2,3}`.

Usage Guidelines

Use this command to configure the PLMNs of the network function.

service-registration profile snssais

Configures the S-NSSAIs of the network function.

Command Modes

Exec > Global Configuration

Syntax Description

snssais { *slice_service_type* | **sd** *service_differentiator* }

sd slice_differentiator

Specify the Slice Differentiator value.

Must be a string.

slice_service_type

Specify the Slice or Service Types value.

Must be an integer in the range of 0-255.

Usage Guidelines

Use this command to configure the S-NSSAIs of the network function.

service-registration services

Configures the service parameters.

Command Modes

Exec > Global Configuration

Syntax Description

services *services_name* **api-version** *api_version*

api-version api_version

Specify the API version.

Must be one of the following:

- 1.0.0
- 1.0.2

Default Value: 1.0.0.

service_name

Specify the service name.

Must be one of the following:

- amfService
- smfService

Usage Guidelines Use this command to configure the service parameters.

service-registration services allowed-nssais

Command Modes Exec > Global Configuration

Syntax Description **allowed-nssais** { *slice_service_type* | **sd** *service_differentiator* }

sd slice_differentiator

Specify the Slice Differentiator value.

Must be a string.

slice_service_type

Specify the Slice or Service Types value.

Must be an integer in the range of 0-255.

Usage Guidelines Use this command to configure the S-NSSAIs allowed of the NF service instance.

service-registration services allowed-plmns

Configures the PLMNs allowed to access the NF service instance.

Command Modes Exec > Global Configuration

Syntax Description **allowed-plmns** { *mobile_country_code* | *mobile_network_code* }

mobile_country_code

Specify the Mobile Country Code.

Must be a string in the pattern \d{3}.

mobile_network_code

Specify the Mobile Network Code.

Must be a string in the pattern \d{2,3}.

Usage Guidelines Use this command to configure the PLMNs allowed to access the NF service instance.

show subscriber

Displays subscriber session information.

Command Modes

Exec

Syntax Description

show subscriber [**imsi** *imsi* | **msisdn** *msisdn*]

imsi *imsi*

Specify the IMSI.

Must be a string.

msisdn *msisdn*

Specify the MSISDN.

Must be a string.

Usage Guidelines

Use this command to view subscriber session information.



CHAPTER 9

Mobile Policy TLS Commands

- [pcf-tls ca-certificates](#), on page 115
- [pcf-tls certificates](#), on page 115

pcf-tls ca-certificates

Configures the certificate name and data configuration.

Command Modes	Exec > Global Configuration
Syntax Description	pcf-tls ca-certificates <i>certificate_alias_name</i> cert-data <i>certificate_data</i> cert-data <i>certificate_data</i> Specify the certificate data in PEM format. Must be a string. certificate_alias_name Specify the alias name for the certificate. Must be a string.

Usage Guidelines	Use this command to configure the certificate name and data configuration.
------------------	--

pcf-tls certificates

Configures the certificate name, data, and key parameters.

Command Modes	Exec > Global Configuration
Syntax Description	pcf-tls certificates <i>certificate_alias_name</i> cert-data <i>certificate_data</i> private-key <i>certificate_private_key</i> cert-data <i>certificate_data</i> Specify the certificate data in PEM format.

Must be a string.

private-key certificate_private_key

Specify the certificate private key in PEM format.

Must be a string.

certificate_alias_name

Specify the alias name for the certificate.

Must be a string.

Usage Guidelines

Use this command to configure the certificate name, data, and key parameters.



CHAPTER 10

Mobile Policy Types Commands

- [api unified](#), on page 117
- [engine](#), on page 118
- [engine environment](#), on page 119
- [engine grpc](#), on page 119
- [engine install-features](#), on page 120
- [engine patching patch](#), on page 120
- [engine properties](#), on page 121
- [engine resources limits](#), on page 121
- [engine resources requests](#), on page 122
- [external-services](#), on page 122
- [label cdl-layer](#), on page 123
- [label oam-layer](#), on page 123
- [label protocol-layer](#), on page 124
- [label service-layer](#), on page 124

api unified

Configures the Engine API parameters.

Command Modes

Exec > Global Configuration

Syntax Description

api unified { **engine-group** *engine_group* | **externalIPs** *ip_address* }

engine-group *engine_group*

Specify the default engine group to receive API traffic.

external-port *port_number*

Specify the API service port number.

Must be an integer.

externalIPs *ip_address*

Specify external IP address for the API service.

Must be an IP address.

Usage Guidelines

Use this command to configure the Engine API parameters.

engine

Configures the engine parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
engine engine_name [ boot-config engine_name | config-lock { false | true } |
environment environment_variables | grpc grpc_configuration_options |
install-features application_features | patching patching_jars | properties
system_properties | release-train release_train_image | replicas replica_count |
repository helm_repository | subversion-config-url subversion_config_url |
subversion-run-url subversion_run_url | tracing-service-name tracing_server |
unified-api-replicas unified_api_count ]
```

boot-config *engine_name*

Specify the engine name to boot the initial engine group.

config-lock { **false** | **true** }

Specify to enable or disable the configuration lock.

Must be either "false" or "true".

Default Value: false.

grouping *engine_group_name*

Specify the engine group's name.

Must be a string in the pattern [a-zA-Z][a-zA-Z0-9-]*.

release-train *release_train_image*

Specify the release train image.

Must be a string.

replicas *replica_count*

Specify the replica count.

Must be an integer.

Default Value: 1.

repository *helm_repository*

Specify the Helm repository.

subversion-config-url *subversion_config_url*

Specify the subversion configuration URL.

Must be a string.

subversion-run-url *subversion_run_url*

Specify the subversion run URL.

Must be a string.

tracing-service-name *tracing_server_name*

Specify the tracing server name used for Policy Engine.

Must be a string.

Usage Guidelines

Use this command to configure the engine parameters.

engine environment

Configures the environment variables exposed to engine-app pods.

Command Modes

Exec > Global Configuration

Syntax Description

engine_name **environment** *environment_name* **value** *value*

environment_name

Specify the environment name.

Must be a string.

value value

Specify the value for the environment.

Must be a string.

Usage Guidelines

Use this command to configure the environment variables exposed to engine-app pods.

engine grpc

Configures the gRPC parameters.

Command Modes

Exec > Global Configuration

Syntax Description

grpc [**externalIPs** *external_ip_address* | **port** *grpc_port_number*]

externalIPs external_ip_address

Specify the external IP address.

Must be an IP address.

port *grpc_port_number*

Specify the gRPC port number.

Must be an integer.

Usage Guidelines Use this command to configure the gRPC parameters.

engine install-features

Configures the installation feature parameters.

Command Modes Exec > Global Configuration

Syntax Description **install-features** { **policy-builder** *policy_builder_name* | **policy-server** *policy_server_name* }

policy-builder *policy_builder_name*

Specify the policy builder feature to be installed.

Must be a string.

policy-server *policy_server_name*

Specify the policy server feature feature to be installed.

Must be a string.

Usage Guidelines Use this command to configure the installation feature parameters.

engine patching patch

Configures the patching parameters.

Command Modes Exec > Global Configuration

Syntax Description **patching patch** *patch_id* [**jar** *jar_to_patch* | **version** *jar_version_number*]

patch_id

Specify the ID of the patch to apply.

Must be a string.

jar *jar_to_patch*

Specify the jar to patch.

Must be a string.

version *jar_version_number*

Specify the version number of jar. Changes every time a new patch is uploaded.

Must be an integer.

Default Value: 1.

Usage Guidelines

Use this command to configure the patching parameters.

engine properties

Configures the system properties passed to the application.

Command Modes

Exec > Global Configuration

Syntax Description

properties *system_properties* **value** *value*

properties *system_properties*

Specify the environment name.

Must be a string.

value *value*

Specify the value for the environment.

Must be a string.

Usage Guidelines

Use this command to configure the system properties passed to the application.

engine resources limits

Configures the resource request parameters.

Command Modes

Exec > Global Configuration

Syntax Description

resources limits { **cpu** *cpu_limit* | **memory** *memory_limit* }

cpu *cpu_limit*

Specify the CPU limit. If not specified, the default value is set to 18.

Must be an integer in the range of 5-16.

Default Value: 14.

memory *memory_limit*

Specify the memory limit. If not specified, the default value is set to 20Gi.

Must be a string.

Default Value: 20Gi.

Usage Guidelines Use this command to configure the resource request parameters.

engine resources requests

Configures the resource request parameters.

Command Modes Exec > Global Configuration

Syntax Description **resources requests** { **cpu** *cpu_request* | **memory** *memory_request* }

cpu *cpu_request*

Specify the CPU request.

Must be an integer in the range of 1-5.

Default Value: 5.

memory *memory_request*

Specify the memory request.

Must be a string.

Default Value: 10Gi.

Usage Guidelines Use this command to configure the resource request parameters.

external-services

Configures access to external services.

Command Modes Exec > Global Configuration

Syntax Description **external-services K8 service name** *service_name* [**ips** *ip_address* | **port** *port_number*]

K8 Service name *service_name*

Specify the Kubernetes or the external service name.

Must be a string in the pattern [a-z]([-a-z0-9]*[a-z0-9])?.

ips *ip_address*

Specify the IP address of the external service.

Must be an IP address.

port *port_number*

Specify the port number of the external service.

Must be a port number.

Usage Guidelines Use this command to configure the access to external services.

label cdl-layer

Configures the CDL pods node affinity label.

Command Modes Exec > Global Configuration

Syntax Description **cdl-layer** { **key** *label_key* | **value** *label_value* }**key** *label_key*

Specify the label key.

Must be a string.

value *label_value*

Specify the label value.

Must be a string.

Usage Guidelines Use this command to configure the CDL.

label oam-layer

Configures the OAM pods node affinity label.

Command Modes Exec > Global Configuration

Syntax Description **oam-layer** { **key** *label_key* | **value** *label_value* }**key** *label_key*

Specify the label key.

Must be a string.

value *label_value*

Specify the label value.

Must be a string.

Usage Guidelines Use this command to configure the OAM pods node affinity label.

label protocol-layer

Configures the protocol layer pod node affinity label.

Command Modes

Exec > Global Configuration

Syntax Description

protocol-layer { **key** *label_key* | **value** *label_value* }

key *label_key*

Specify the label key.

Must be a string.

value *label_value*

Specify the label value.

Must be a string.

Usage Guidelines

Use this command to configure the protocol layer pod node affinity label.

label service-layer

Configures the service pods node affinity label.

Command Modes

Exec > Global Configuration

Syntax Description

service-layer { **key** *label_key* | **value** *label_value* }

key *label_key*

Specify the label key.

Must be a string.

value *label_value*

Specify the label value.

Must be a string.

Usage Guidelines

Use this command to configure the service pods node affinity label.



CHAPTER 11

Ports and Services Reference Information

- [Ports and Services, on page 125](#)

Ports and Services

PCF uses different ports for communication purposes. The following table describes the default ports and the associated services.

Table 1: Ports and Services

Port	Service	Usage
22	SSH	SMI uses this port to communicate with the virtual machines.
80	HTTP	SMI uses this port for providing Web access to CLI, Documentation, and TAC.
443	SSL/HTTP	SMI uses this port for providing Web access to CLI, Documentation, and TAC.
2024	SSH	SMI accesses the Confdd CLI through this port.
3868	TCP	PCF uses this port as the default Diameter Endpoint on a public port.
6443	HTTP	SMI uses this port to communicate with the Kubernetes API server.
8080	HTTP	PCF uses this port to communicate with the Keep Alive API Interface on a public network.
9082	HTTP	PCF uses this port to access the SBI Interface on a public network. The Keepalive monitors the health of the container on this port. If the port is not accessible, then the kubectrl restarts the container to restore the service.
9299	HTTP	SMI uses this port to communicate with the Prometheus Service.
9885	TCP	Default port that operates as the PCF Service gRPC endpoint on a private network.
10250	SSL/HTTP	SMI uses this port to communicate with Kubelet.

Port	Service	Usage
10256	HTTP	SMI uses this port to interact with the Kube proxy.