



Ultra Cloud Core 5G Policy Control Function, Release 2021.02 - CLI Command Reference

First Published: 2021-05-03

Americas Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

All printed copies and duplicate soft copies of this document are considered uncontrolled. See the current online version for the latest version.

Cisco has more than 200 offices worldwide. Addresses and phone numbers are listed on the Cisco website at www.cisco.com/go/offices.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: <https://www.cisco.com/c/en/us/about/legal/trademarks.html>. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)

© 2021 Cisco Systems, Inc. All rights reserved.



CONTENTS

PREFACE

About this Guide	xi
Conventions Used	xi
Contacting Customer Support	xii

CHAPTER 1

Mobile Policy Executive Commands	1
aaa authentication	2
cd	3
cdl clear sessions	3
cdl clear sessions filter	4
cdl show indexes	4
cdl show sessions	5
cdl show status	5
commit abort	6
commit confirm	6
commit persist-ID	6
compare	7
config exclusive	7
config shared	7
config terminal	8
deployment add	8
deployment remove-config	9
deployment show-config	9
describe	9
exit	10
help	10
history	10

id	11
idle-timeout	11
ignore-leading-space	11
job	12
leaf-prompting	12
license smart register	12
license smart deregister	13
license smart renew	13
logout session	14
logout user	14
no	14
paginate	14
quit	15
screen-length	15
screen-width	15
send	16
show	16
show-defaults	16
smiuser add-group	17
smiuser add-user	17
smiuser assign-user-group	17
smiuser change-password	18
smiuser change-password-age	19
smiuser change-self-password	19
smiuser delete-group	20
smiuser delete-user	20
smiuser show-user	20
smiuser unassign-user-group	21
smiuser update-password-length	21
subscriber	21
system ops-center	22
system sync	22
system upgrade	23
system uuid-override	23

system ops-center-debug 23

terminal 23

timestamp 24

who 24

CHAPTER 2 **Mobile Policy Common Commands** 25

cluster 25

cps-license 26

db 26

db balance 27

db global-settings 27

db global-settings timers 28

db spr 28

debug 29

debug logging 29

debug splunk 29

debug tracing 29

features 30

features activemq 30

features patching 30

ldap 31

ldap connection-status 31

ldap server-set 32

ldap server-set add-request-attribute 34

ldap server-set connection 34

ldap server-set health-check 36

ldap server-set search-user 36

testing 37

testing tls-handshake 38

testing zing-memory 39

zing 40

CHAPTER 3 **Mobile Policy CDL Client Commands** 41

datastore external-endpoints 41

- datastore external-endpoints connection-settings 42
- datastore external-endpoints connection-settings channel 42
- datastore external-endpoints connection-settings keep-alive 42
- datastore primary-endpoint 43
- datastore primary-endpoint connection-settings 43
- datastore primary-endpoint connection-settings channel 44
- datastore primary-endpoint connection-settings keep-alive 44

CHAPTER 4 Mobile Policy Diameter Commands 45

- diameter 45
- diameter application 45
- diameter group 46
- diameter group stack 47
- diameter group stack diameter-engine alt-engines 48
- diameter group stack diameter-engine alt-engines primary 49
- diameter group stack diameter-engine alt-engines secondary 49
- diameter group stack grpc ext-svc 49
- diameter group stack settings timeouts-ms 50
- diameter grpc 51
- diameter grpc channel 51
- diameter next-hop-route next-hop-host 52
- diameter settings timeouts-ms 52

CHAPTER 5 Mobile Policy Infrastructure Commands 55

- subversion 55

CHAPTER 6 Mobile Policy LDAP Commands 57

- ldap-server-endpoint connect 57
- ldap-server-endpoint health-check-attributes 58
- ldap-server-endpoint health-check-filter 58
- ldap-server-endpoint input-mapping 59
- ldap-server-endpoint ldap-clients 59
- ldap-server-endpoint output-mapping 60

CHAPTER 7**Mobile Policy PCF Commands 61**

- advance-tuning 61
- advance-tuning async-threading 62
- advance-tuning async-threading threading-config 63
- advance-tuning brute-force-recovery 64
- advance-tuning http2-threading 65
- advance-tuning overload-control 66
- advance-tuning overload-control diameter global 66
- advance-tuning overload-control diameter global action 66
- advance-tuning overload-control diameter global limits 67
- advance-tuning overload-control rest global 67
- advance-tuning overload-control rest global action 67
- advance-tuning overload-control rest global limits 68
- rest-endpoint 68
- rest-endpoint certificate-status 70
- rest-endpoint discovered-profiles 70
- rest-endpoint discovered-profiles chf 70
- rest-endpoint discovered-profiles udr 71
- rest-endpoint interface 72
- rest-endpoint peer-status 73
- rest-endpoint registration-status 73
- traffic engine 74
- traffic engine rule 74

CHAPTER 8**Mobile Policy Services Repository Commands 77**

- clear subscriber 78
- deployment add config 78
- deployment remove-config 79
- deployment show-config 79
- group nf-mgmt 79
- group nf-mgmt failover 80
- group nf-mgmt reconnect 81
- group nrf discovery 81

group nrf discovery service type nrf 81

group nrf discovery service type nrf endpoint-profile 82

group nrf discovery service type nrf endpoint-profile endpoint-name 83

group nrf discovery service type nrf endpoint-profile endpoint-name primary ip-address 84

group nrf discovery service type nrf endpoint-profile endpoint-name secondary ip-address 85

group nrf discovery service type nrf endpoint-profile endpoint-name tertiary ip-address 86

group nrf discovery service type nrf endpoint-profile version uri-version 87

group nrf mgmt 87

group nrf mgmt service type nrf 87

group nrf mgmt service type nrf endpoint-profile 88

group nrf mgmt service type nrf endpoint-profile endpoint-name 89

group nrf mgmt service type nrf endpoint-profile endpoint-name primary ip-address 90

group nrf mgmt service type nrf endpoint-profile endpoint-name secondary ip-address 91

group nrf mgmt service type nrf endpoint-profile endpoint-name tertiary ip-address 92

group nrf mgmt service type nrf endpoint-profile version uri-version 93

profile nf-client nf-type bsf bsf-profile 93

profile nf-client nf-type bsf bsf-profile locality 93

profile nf-client nf-type bsf bsf-profile locality service name type 94

profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile 94

profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile endpoint-name 96

profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile version uri-version 96

profile nf-client nf-type chf chf-profile 97

profile nf-client nf-type chf chf-profile locality 97

profile nf-client nf-type chf chf-profile locality service name type 98

profile nf-client nf-type chf chf-profile locality service name type endpoint-profile 98

profile nf-client nf-type chf chf-profile locality service name type endpoint-profile endpoint-name 99

profile nf-client nf-type chf chf-profile locality service name type endpoint-profile version uri-version 100

profile nf-client nf-type udr udr-profile locality 100

profile nf-client nf-type udr udr-profile locality service name type 101

profile nf-pair nf-type 101

profile nf-pair nf-type locality 102

service-registration profile 103

service-registration profile allowed-plmns	104
service-registration profile pcf-info	105
service-registration profile pcf-info supi-ranges	105
service-registration profile plmn-list	106
service-registration profile snssais	106
service-registration services	107
service-registration services allowed-nssais	107
service-registration services allowed-plmns	108
show subscriber	108

CHAPTER 9 **Mobile Policy TLS Commands** 109

pcf-tls ca-certificates	109
pcf-tls certificates	109

CHAPTER 10 **Mobile Policy Types Commands** 111

api unified	111
engine	112
engine environment	113
engine grpc	113
engine install-features	114
engine n7	114
engine patching patch	115
engine properties	115
engine resources limits	116
engine resources requests	116
external-services	117
label cdl-layer	117
label oam-layer	118
label protocol-layer	118
label service-layer	119

CHAPTER 11 **Ports and Services Reference Information** 121

Ports and Services	121
--------------------	-----



About this Guide

This preface describes the *Ultra Cloud Core 5G Policy Control Function CLI Command Reference*, the document conventions, and the customer support details.

- [Conventions Used, on page xi](#)
- [Contacting Customer Support, on page xii](#)

Conventions Used

The following tables describe the conventions used throughout this documentation.

Notice Type	Description
Information Note	Provides information about important features or instructions.
Caution	Alerts you of potential damage to a program, device, or system.
Warning	Alerts you of potential personal injury or fatality. May also alert you of potential electrical hazards.

Typeface Conventions	Description
Text represented as a screen display	This typeface represents displays that appear on your terminal screen, for example: <code>Login:</code>
Text represented as commands	This typeface represents commands that you enter, for example: show ip access-list This document always gives the full form of a command in lowercase letters. Commands are not case sensitive.

Typeface Conventions	Description
Text represented as a command <i>variable</i>	This typeface represents a variable that is part of a command, for example: show card <i>slot_number</i> <i>slot_number</i> is a variable representing the desired chassis slot number.
Text represented as menu or sub-menu names	This typeface represents menus and sub-menus that you access within a software application, for example: Click the File menu, then click New

Contacting Customer Support

Use the information in this section to contact customer support.

Refer to the support area of <http://www.cisco.com> for up-to-date product documentation or to submit a service request. A valid username and password are required to access this site. Please contact your Cisco sales or service representative for additional information.



CHAPTER 1

Mobile Policy Executive Commands

- [aaa authentication](#), on page 2
- [cd](#), on page 3
- [cdl clear sessions](#), on page 3
- [cdl clear sessions filter](#), on page 4
- [cdl show indexes](#), on page 4
- [cdl show sessions](#), on page 5
- [cdl show status](#), on page 5
- [commit abort](#), on page 6
- [commit confirm](#), on page 6
- [commit persist-ID](#), on page 6
- [compare](#), on page 7
- [config exclusive](#), on page 7
- [config shared](#), on page 7
- [config terminal](#), on page 8
- [deployment add](#), on page 8
- [deployment remove-config](#), on page 9
- [deployment show-config](#), on page 9
- [describe](#), on page 9
- [exit](#), on page 10
- [help](#), on page 10
- [history](#), on page 10
- [id](#), on page 11
- [idle-timeout](#), on page 11
- [ignore-leading-space](#), on page 11
- [job](#), on page 12
- [leaf-prompting](#), on page 12
- [license smart register](#), on page 12
- [license smart deregister](#), on page 13
- [license smart renew](#), on page 13
- [logout session](#), on page 14
- [logout user](#), on page 14
- [no](#), on page 14
- [paginate](#), on page 14

- [quit](#), on page 15
- [screen-length](#), on page 15
- [screen-width](#), on page 15
- [send](#), on page 16
- [show](#), on page 16
- [show-defaults](#), on page 16
- [smiuser add-group](#), on page 17
- [smiuser add-user](#), on page 17
- [smiuser assign-user-group](#), on page 17
- [smiuser change-password](#), on page 18
- [smiuser change-password-age](#), on page 19
- [smiuser change-self-password](#), on page 19
- [smiuser delete-group](#), on page 20
- [smiuser delete-user](#), on page 20
- [smiuser show-user](#), on page 20
- [smiuser unassign-user-group](#), on page 21
- [smiuser update-password-length](#), on page 21
- [subscriber](#), on page 21
- [system ops-center](#), on page 22
- [system sync](#), on page 22
- [system upgrade](#), on page 23
- [system uuid-override](#), on page 23
- [system ops-center-debug](#), on page 23
- [terminal](#), on page 23
- [timestamp](#), on page 24
- [who](#), on page 24

aaa authentication

Configures the AAA-based user management parameters.

Command Modes

Exec

Syntax Description

```
aaa authentication users user admin change-password { old-password  
old_password | new-password new_password | confirm-password new_password }
```

old-password *old_password*

Specify the old password.

Must be a string.

new-password *new_password*

Specify the new password.

Must be a string.

confirm-password *new_password*

Confirm the new password.

Must be a string.

Usage Guidelines

Use this command to configure the AAA-based user management parameters.

cd

Changes the current working directory.

Command Modes

Exec

Syntax Description

cd *directory*.ssh

directory

Specify the directory name.

Must be a string.

Usage Guidelines

Use this command to change the current working directory.

cdl clear sessions

Clears the data from the Cisco Data Layer (CDL) datastore.

Command Modes

Exec

Syntax Description

cdl clear sessions [**db-name** *database* | **filter** *filter* | **map-id** *map_id* | **slice-name** *slice_name*]

db-name *database*

Specify the database name to be queried.

Must be a string of minimum one to maximum 16 characters.

filter *filter*

Specify the filter.

map-id *map_id*

Specify the map-id to clear the data for a map.

Must be an integer.

slice-name *slice_name*

Specify the slice name to be queried.

Must be a string of minimum one to maximum 16 characters.

Usage Guidelines Use this command to clear the data from the Cisco Data Layer (CDL) datastore.

cdl clear sessions filter

Clears the Cisco Data Layer (CDL) datastore sessions based on the filter criteria.

Command Modes Exec

Syntax Description `cdl clear sessions filter { condition { ends-with | match | starts-with } | key key_value }`

condition { ends-with | match | starts-with }

Specify the query expression.

key *key_value*

Specify the key value.

Usage Guidelines Use this command to clear CDL sessions based on the filter criteria.

cdl show indexes

Displays the indexes of the database from the datastore

Command Modes Exec

Syntax Description `cdl show indexes { db-name database | key key_value | limit maximum_indexes | map-id map_id | slice-name slice_name }`

db-name *database_name*

Specify to database name to be queried.

Must be a string.

key *key_value*

Specify to query value.

limit *maximum_indexes*

Specify the maximum number of indexes to be displayed.

Default value is 500.

map-id *map_id*

Specify the map-id to clear the data for a map.

Must be an integer.

slice-name *slice_name*

Specify the slice name to be queried.

Usage Guidelines Use this command to display the database indexes.

cdl show sessions

Displays the session data from the datastore.

Command Modes Exec

Syntax Description **cdl show sessions** { *count* | *detailed* | *summary* }

count

Specify to display the session count information.

Must be a string.

detailed

Specify to display the session details with data.

Must be a string.

summary

Specify to display the session details without data.

Must be a string.

Usage Guidelines Use this command to display the session data from the datastore.

cdl show status

Displays the status of the database from the datastore

Command Modes Exec

Syntax Description **cdl show status db-name** *database_name*

db-name *database_name*

Specify to display the status of the database.

Must be a string.

Usage Guidelines Use this command to display the status of the database from the datastore.

commit abort

Aborts the commit operation associated to the persist-ID.

Command Modes Exec

Syntax Description `commit { abort persist-id persist_id }`

abort persist-id *persist_id*

Specify to abort commit. Specify the persist-ID.

Must be an integer.

Usage Guidelines Use this command to abort the commit operation.

commit confirm

Confirms the commit operation for the persist-ID.

Command Modes Exec

Syntax Description `commit confirm persist-id persist_id`

persist-id *persist_id*

Specify to persist-ID for which the commit operation must be confirmed.

Must be an integer.

Usage Guidelines Use this command to confirm the commit operation for the persist-ID.

commit persist-ID

Displays the commits associated to the persist-ID.

Command Modes Exec

Syntax Description `commit persist-id persist_id`

persist-id *persist_id*

Specify to confirm the commit operation relevant to the persist-ID.

Must be an integer.

Usage Guidelines Use this command to display the commits associated to the persist-ID.

compare

Compares running configuration to another configuration or a file.

Command Modes

Exec

Syntax Description

```
compare file { filename [.kube | .ssh] | another_configuration }
```

filename [.kube | .ssh] |

Specify the file name.

Must be a string.

another_configuration

another_configuration

Specify the configuration to be compared against.

Must be a string.

Usage Guidelines

Use this command to configure the file that must be compared.

config exclusive

Manipulates the software configuration information to enter the exclusive configuration mode.

Command Modes

Exec

Syntax Description

```
config exclusive [ no-confirm ]
```

exclusive

Specify to enter the exclusive configuration mode.

no-confirm

Specify to apply the command without asking for confirmation.

Usage Guidelines

Use this command to manipulate the software configuration information to enter the exclusive configuration mode.

config shared

Manipulates the software configuration information to enter the shared configuration mode.

Command Modes

Exec

Syntax Description `config shared [no-confirm]`

shared

Specify to enter the shared configuration mode.

no-confirm

Specify to apply the command without asking for confirmation.

Usage Guidelines Use this command to manipulate the software configuration information to enter the shared configuration mode.

config terminal

Manipulates the software configuration information to enter the terminal configuration mode.

Command Modes Exec

Syntax Description `config terminal [no-confirm]`

terminal

Specify to enter the terminal configuration mode.

no-confirm

Specify to apply the command without asking for confirmation.

Usage Guidelines Use this command to manipulate the software configuration information to enter the terminal configuration mode.

deployment add

Configures the deployment parameters such as the list of cluster-name, and external IP and port number of the unified-api service.

Command Modes Exec

Syntax Description `deployment add config { cluster-name cluster_name | port port_number | unified-api-external-ip external_ip }`

cluster-name cluster_name

Specify the cluster name.

Must be a string.

port *port_number*

Specify the port number of the unified-api service.

Must be an address.

unified-api-external-ip *external_ip*

Specify the external IP of the unified-api service.

Must be an address.

Usage Guidelines

Use this command to configure the deployment parameters such as the list of cluster-name, and external IP and port number of the unified-api service.

deployment remove-config

Removes the deployment configuration file.

Command Modes

Exec

Syntax Description

deployment remove-config

remove-config

Specify to remove the configuration file.

Must be a string.

Usage Guidelines

Use this command to remove the deployment configuration file.

deployment show-config

Displays the deployment environment parameters.

Command Modes

Exec

Syntax Description

deployment show-config

show-config

Specify to display the deployment parameters.

Must be a string.

Usage Guidelines

Use this command to display the deployment environment parameters.

describe

Displays the command information.

Command Modes Exec

Syntax Description **describe** *command*

command

Specify the command name.

Must be a string.

Usage Guidelines Use this command to view command information.

exit

Exits the current configuration mode and returns to the parent configuration mode.

Command Modes Exec

Syntax Description **exit**

Usage Guidelines Use this command to exit the current configuration mode and return to the parent configuration mode. When used in the Exec mode, exits the session.

help

Displays help information for specified command.

Command Modes Exec

Syntax Description **help** *command*

command

Specify the command name to display help information..

Must be a string.

Usage Guidelines Use this command to view help information for a specified command.

history

Configures the command history cache size.

Command Modes Exec

Syntax Description **history** *history_size*

history_size

Specify the command history cache size.

Must be an integer.

Usage Guidelines

Use this command to configure the command history cache size.

id

Displays user ID information.

Command Modes

Exec

Syntax Description

id

Usage Guidelines

Use this command to view user ID information.

idle-timeout

Configures the maximum duration a command can remain idle in seconds after which the system automatically terminates the command.

Command Modes

Exec

Syntax Description

idle-timeout *idle_timeout*

idle_timeout

Specify the idle timeout duration in seconds.

Usage Guidelines

Use this command to configure the maximum duration a command can remain idle.

ignore-leading-space

Configures whether to ignore or consider leading whitespace at the beginning of a command.

Command Modes

Exec

Syntax Description

ignore-leading-space { false | true }

ignore-leading-space { false | true }

Specify false to ignore leading whitespace, and true to consider it.

Must be either "false" or "true".

Usage Guidelines

Use this command to configure whether to ignore or consider leading whitespace at the beginning of a command.

job

Suspends the jobs that are running in the background.

Command Modes Exec

Syntax Description `job stop job_id`

job_id

Specify the job ID.

Must be an integer.

Usage Guidelines Use this command to suspend the jobs that are running in the background.

leaf-prompting

Enables or disables automatically querying for leaf values.

Command Modes Exec

Syntax Description `leaf-prompting { false | true }`

leaf-prompting { false | true }

Specify false to disable leaf prompting, true to enable.

Must be either "false" or "true".

Usage Guidelines Use this command to automatically query for leaf values.

license smart register

Registers the VNF for Smart Licensing.

Command Modes Exec

Syntax Description `license smart register [force] idtoken idtoken`

register

Specify to register the VNF for Smart Licensing.

Must be a string.

force

Specify to enable the force registration of the agent.

Must be a string.

idtoken

Specify the ID token to register the agent with.

Must be an integer.

Usage Guidelines Use this command to register the VNF for Smart Licensing.

license smart deregister

Deregisters the VNF for Smart Licensing.

Command Modes Exec

Syntax Description `license smart deregister`

deregister

Specify to deregister the VNF for Smart Licensing.

Must be a string.

Usage Guidelines Use this command to deregister the VNF for Smart Licensing.

license smart renew

Renew smart agent IDs and authentication.

Command Modes Exec

Syntax Description `license smart renew { ID | auth }`

renew

Specify to renew the smart agent IDs and authentication.

Must be an integer.

ID

Specify the ID to renew smart agent license registration information

auth

Specify to initiate a manual update of the license usage information with Cisco

Usage Guidelines Use this command to configure the license parameters for the NF.

logout session

Logs out a specific session.

Command Modes Exec

Syntax Description `logout session session`

session session

Specify the session from the possible completion options.

Must be a string.

Usage Guidelines Use this command to log out of a specific session.

logout user

Logs out a specific user from all sessions.

Command Modes Exec

Syntax Description `logout user user`

user user

Specify the user from the possible completion options.

Must be a string.

Usage Guidelines Use this command to log out a specific user from all the sessions.

no

Restores the command history cache size to its default setting. See the history command.

Command Modes Exec

Syntax Description `no history`

Usage Guidelines Use this command to configure the command history cache size to its default setting. Refer to the history command.

paginate

Configures whether or not to paginate CLI command output.

Command Modes	Exec
Syntax Description	paginate { true false } paginate { true false } Specify false to disable paginating CLI command output, and true to enable. Must be either "false" or "true".
Usage Guidelines	Use this command to paginate the command output.

quit

Exits the management session.

Command Modes	Exec
Syntax Description	quit
Usage Guidelines	Use this command to exit the management session.

screen-length

Configures the number of rows of text that the terminal screen displays.

Command Modes	Exec
Syntax Description	screen-length <i>number_of_rows</i> number_of_rows Specify the number of rows. Must be an integer.
Usage Guidelines	Use this command to configure the number of rows that the terminal screen displays.

screen-width

Configures the number of columns that the terminal screen displays.

Command Modes	Exec
Syntax Description	screen-width <i>number_of_columns</i> number_of_columns Specify the number of columns.

Must be an integer.

Usage Guidelines Use this command to configure the number of columns that the terminal screen displays.

send

Sends messages to the terminal of a specific user or all users.

Command Modes Exec

Syntax Description `send user message`

user

Specify the user to whom the message must be sent.

Must be a string. Select from the possible completions options.

message

Specify the message that must be sent.

Must be a string.

Usage Guidelines Use this command to send messages to the terminal of a specific user or to all users.

show

Displays the system information.

Command Modes Exec

Syntax Description `show system_component`

system_component

Specify the component to view the information.

Must be a string. Select from the possible completion options.

Usage Guidelines Use this command to view the system information.

show-defaults

Configures whether to display default values when showing the configuration.

Command Modes Exec

Syntax Description `show-defaults { false | true }`

show-defaults { false | true }

Specify whether to display or hide default values. To hide select false, to display select true.

Must be either "false" or "true".

Usage Guidelines

Use this command to view default values when viewing the configuration commands.

smiuser add-group

Configures the SMI group parameters.

Command Modes

Exec

Syntax Description

smiuser add-group groupname *group_name*

groupname *group_name*

Specify the group name in PAM.

Must be a string.

Usage Guidelines

Use this command to configure the SMI group parameters.

smiuser add-user

Configures the SMI user account parameters.

Command Modes

Exec

Syntax Description

smiuser add-user username *username* **password** *password*

username *username*

Specify the username.

Must be a string.

password *password*

Specify the user password.

Must be a string.

Usage Guidelines

Use this command to configure the smiuser parameters.

smiuser assign-user-group

Assigns the SMI user group.

Command Modes Exec

Syntax Description **smiuser assign-user-group** *groupname* *group_name* **username** *username*

username *username*

Specify the user name in PAM.

Must be a string.

groupname *group_name*

Specify the group name in PAM.

Must be a string.

Usage Guidelines Use this command to assign the SMI user group.

smiuser change-password

Allows resetting the SMI password.

Command Modes Exec

Syntax Description **smiuser change-password** { **username** *username* | **current_password** *current_password* | **new_password** *new_password* | **confirm_password** *new_password* | **password_expire_days** *expire_days* }

username *username*

Specify the username.

Must be a string.

current_password *current_password*

Specify the current password.

Must be a string.

new_password *new_password*

Specify the new password.

Must be a string.

confirm_password *new_password*

Confirm the new password.

Must be a string.

password_expire_days *expire_days*

Specify the number of days before password expires.

Must be an integer.

Usage Guidelines Use this command to reset the SMI password.

smiuser change-password-age

Configures the number of days before which the password expires.

Command Modes Exec

Syntax Description `smiuser change-password-age [username username | password_expire_days expire_days]`

username *username*

Specify the username.

Must be a string.

password_expire_days *expire_days*

Specify the number of days before which the password expires.

Must be an integer.

Usage Guidelines Use this command to configure the number of days before which the password expires.

smiuser change-self-password

Resets the SMI user accounts self-password.

Command Modes Exec

Syntax Description `smiuser change-self-password { current_password current_password | new_password new_password | confirm_password new_password | password_expire_days expire_days }`

current_password *current_password*

Specify the current password.

Must be a string.

new_password *new_password*

Specify the new password.

Must be a string.

confirm_password *new_password*

Confirm the new password.

Must be a string.

password_expire_days *expire_days*

Specify the number of days before which the password expires.

Must be an integer.

Usage Guidelines Use this command to reset the SMI user accounts self-password.

smiuser delete-group

Deletes the SMI group.

Command Modes Exec

Syntax Description `smiuser delete-group groupname` *group_name*

groupname *group_name*

Specify the group name.

Must be a string.

Usage Guidelines Use this command to delete the SMI user group.

smiuser delete-user

Deletes the SMI user.

Command Modes Exec

Syntax Description `smiuser delete-user username` *username*

username *username*

Specify the username.

Must be a string.

Usage Guidelines Use this command to delete the SMI user.

smiuser show-user

Displays the SMI user details.

Command Modes Exec

Syntax Description `smiuser show-user username` *username*

username *username*

Specify the username.

Must be a string.

Usage Guidelines Use this command to display the SMI user details.

smiuser unassign-user-group

Configures the SMI user's unassign user group.

Command Modes Exec

Syntax Description **smiuser unassign-user-group** **groupname** *groupname_pam* **username** *username_pam*

groupname *groupname_pam*

Specify the groupname in PAM.

Must be a string.

username *username_pam*

Specify the username in PAM.

Must be a string.

Usage Guidelines Use this command to configure the SMI user's unassign user group.

smiuser update-password-length

Configures the minimum password length.

Command Modes Exec

Syntax Description **smiuser update-password-length** **length** *password_length*

length *password_length*

Specify the minimum password length.

Must be an integer.

Usage Guidelines Use this command to configure the minimum password length.

subscriber

Configures the subscriber parameters.

Command Modes	Exec
Syntax Description	<p>subscriber session [imsi <i>imsi_value</i> msisdn <i>msisdn_value</i>]</p> <p>imsi <i>imsi_value</i> Specify the IMSI value. Must be an integer.</p> <p>msisdn <i>msisdn_value</i> Specify the MSISDN value. Must be an integer.</p>
Usage Guidelines	Use this command to configure the subscriber parameters.

system ops-center

Suspends the ops center diagnostics synching process.

Command Modes	Exec
Syntax Description	<p>system ops-center stop</p> <p>ops-center stop Specify to stop the synching process. Must be a string.</p>
Usage Guidelines	Use this command to suspend the ops center diagnostics synching process.

system sync

Configures automatic synching.

Command Modes	Exec
Syntax Description	<p>system ops-center stop</p> <p>synch { start stop } Specify to start or stop the synching process. Must be either "start" or "stop".</p>
Usage Guidelines	Use this command to configure automatic synching.

system upgrade

Enforces the product upgrade.

Command Modes Exec

Syntax Description `system upgrade`

Usage Guidelines Use this command to enforce the product upgrade.

system uuid-override

Enforce the UUID to a new value.

Command Modes Exec

Syntax Description `system uuid-override new-uuid uid`

new-uuid *uid*

Specify the ID Token to register the agent with.

Must be a string.

Usage Guidelines Use this command to enforce the UUID to a new value.

system ops-center-debug

Configures the Ops Center debugging process.

Command Modes Exec

Syntax Description `system ops-center-debug { start | stop }`

ops-center-debug { start | stop }

Specify to start or stop the ops-center debugging process.

Must be either "start" or "stop".

Usage Guidelines Use this command to configure the Ops Center debugging process.

terminal

Configures the terminal parameters.

Command Modes Exec

Syntax Description `terminal terminal_type`

terminal_type

Specify the terminal type.

Must be one of the following:

- ansi
- generic
- linux
- vt100
- xterm

Usage Guidelines Use this command to configure the terminal parameters.

timestamp

Enables or disables the timestamp parameters.

Command Modes Exec

Syntax Description `timestamp { enable | disable }`

`timestamp { enable | disable }`

Specify the configuration to enable or disable the timestamp display.

Usage Guidelines Use this command to enable or disable the timestamp parameters.

who

Displays information on currently logged on users.

Command Modes Exec

Syntax Description `who`

Usage Guidelines Use this command to view information on currently logged on users. The command output displays the Session, User, Context, From, Protocol, Date, and Mode information.



CHAPTER 2

Mobile Policy Common Commands

- [cluster](#), on page 25
- [cps-license](#), on page 26
- [db](#), on page 26
- [db balance](#), on page 27
- [db global-settings](#), on page 27
- [db global-settings timers](#), on page 28
- [db spr](#), on page 28
- [debug](#), on page 29
- [debug logging](#), on page 29
- [debug splunk](#), on page 29
- [debug tracing](#), on page 29
- [features](#), on page 30
- [features activemq](#), on page 30
- [features patching](#), on page 30
- [ldap](#), on page 31
- [ldap connection-status](#), on page 31
- [ldap server-set](#), on page 32
- [ldap server-set add-request-attribute](#), on page 34
- [ldap server-set connection](#), on page 34
- [ldap server-set health-check](#), on page 36
- [ldap server-set search-user](#), on page 36
- [testing](#), on page 37
- [testing tls-handshake](#), on page 38
- [testing zing-memory](#), on page 39
- [zing](#), on page 40

cluster

Configures the cluster information.

Command Modes

Exec > Global Configuration

Syntax Description

```
cluster { cluster-id cluster_id | system-id system_id}
```

cluster-id *cluster_id*

Specify the cluster ID.

Must be a string.

Default Value: cluster-1.

system-id *system_id*

Specify the system ID.

Must be a string.

Default Value: system-1.

Usage Guidelines Use this command to configure cluster information.

cps-license

Configures CPS licensing.

Command Modes Exec > Global Configuration

Syntax Description **cps-licence** *license_name* **encrypted-key** *encrypted_key*

encrypted-key *key*

Specify the encrypted key.

Must be a string.

feature-name *feature_name*

Specify the feature name.

Must be a string.

Usage Guidelines Use this command to configure PCF license.

db

Configures database setup.

Command Modes Exec > Global Configuration

Syntax Description **db** { **balance shard count** *shard_count* | **global-settings** { **db-replica** *replica_count* | **timers** { **catchup-timeout-millis** *catchup_timeout_in_ms* | **election-timeout-millis** *election_timeout_in_ms* | **heartbeat-interval-millis** *heartbeat_interval_in_ms* } } | **spr shard-count** *shard_count*}

Usage Guidelines Use this command to configure the database setup.

db balance

Configures the Balance database.

Command Modes Exec > Global Configuration

Syntax Description **db balance shard-count** *balance_db_shard_count*

shard-count *balance_db_shard_count*

Specify the Balance database's shard count.

Must be an integer.

Default Value: 1.

Usage Guidelines Use this command to configure the Balance database.

Example

The following command configures the Balance database's shard count to 1:

```
db balance shard-count 1
```

db global-settings

Configures global DB settings.

Command Modes Exec > Global Configuration

Syntax Description **global-settings db-replica** *replica_count*

db-replica *replica_count*

Specify the global DB replica count.

Must be an integer.

Default Value: 3.

volume-storage-class *volume_storage_class*

Specify the volume storage class if use-volume-claims enabled is enabled.

Must be one of the following:

- **default**
- **local**

Default Value: default.

Usage Guidelines Use this command to configure the global DB settings.

db global-settings timers

Configures global MongoDB timers.

Command Modes Exec > Global Configuration

Syntax Description `db global-settings timers { catchup-timeout-millis catchup_timeout | election-timeout-millis election_timeout | heartbeat-interval-millis heartbeat_interval }`

catchup-timeout-millis *catchup_timeout*

Specify the global catchup timeout period, in milliseconds.

Must be an integer.

Default Value: 2000.

election-timeout-millis *election_timeout*

Specify the global election timeout period, in milliseconds.

Must be an integer.

Default Value: 2000.

heartbeat-interval-millis *heartbeat_interval*

Specify the global heartbeat interval period, in milliseconds.

Must be an integer.

Default Value: 300.

Usage Guidelines Use this command to configure the global MongoDB timers.

db spr

Configures the SPR database.

Command Modes Exec > Global Configuration

Syntax Description `db spr shard-count shard_count`

shard-count *shard_count*

Specify the SPR database's shard count.

Must be an integer.

Default Value: 1.

Usage Guidelines Use this command to configure the SPR database.

Example

The following command configures the SPR database's shard count to 20:

```
db spr shard-count 20
```

debug

Configures the debug parameters.

Syntax Description `debug { logging { default-level logging_level | logger logger_name } | tracing { jaeger agent udp { host host_address | port port_number } | type }`

Usage Guidelines Use this command to configure debug information.

debug logging

Configures the logging parameters.

Command Modes Exec > Global Configuration

Syntax Description `default-level [debug debug | error error | info info | off off | trace trace | warn warn]`

Usage Guidelines Use this command to configure the logging parameters.

debug splunk

Configures the Splunk parameters.

Command Modes Exec > Global Configuration

Syntax Description `debug splunk { batch-count event_count | batch-interval-ms batch_interval | batch-size-bytes max_batch | hec-token splunk_hec | hec-url port_splunk }`

Usage Guidelines Use this command to configure the Splunk parameters.

debug tracing

Configures the tracing parameters.

Command Modes Exec > Global Configuration

Syntax Description `debug tracing [jaegar agent agent udp [host host_name port_number] | type tracing_type]`

Usage Guidelines Use this command to configure the tracing parameters.

features

Configures the control configuration for the application features.

Command Modes Exec > Global Configuration

Syntax Description `features { activemq cluster-ip cluster_ip_address | patching ingress-enabled { false | true } }`

Usage Guidelines Use this command configure the control configuration for the application features.

Example

The following command configures the control configuration for the application feature:

```
features { activemq cluster-ip 122.12.122.11 | patching ingress-enabled true }
```

features activemq

Configures the ActiveMQ parameters.

Command Modes Exec > Global Configuration

Syntax Description `features activemq cluster-ip ip_address`

cluster-ip ip_address

Specify the IP address of the cluster.

Usage Guidelines Use this command to configure the ActiveMQ parameters.

features patching

Configures the Ingress API.

Command Modes Exec > Global Configuration

Syntax Description `features patching ingress-enabled { false | true }`

ingress-enabled { false | true }

Specify to enable or disable patching ingress, not secured.

Must be one of the following:

- **false**
- **true**

Default Value: false.

Usage Guidelines Use this command to enable or disable Ingress API.

ldap

Displays the LDAP connections.

Command Modes Exec

Syntax Description `show ldap connection-status`

replicas *replica_count*

Specify the replica count.

Must be an integer.

Default Value: 1.

repository *helm_repository*

Specify to override Helm repository.

Usage Guidelines Use this command to view LDAP connection information.

Example

The following command displays the LDAP connections:

```
show ldap connection-status
```

ldap connection-status

Displays the LDAP connections for the SPR lookup.

Command Modes Exec

Syntax Description `show ldap connection-status server-set { metric metric_type | value metric_value { timestamp timestamp_value } }`

metric *metric_type*

Specify the metric type

Must be a string.

serverset *server_set_name*

Specify the LDAP server set name.

Must be a string.

value *metric_value*

Specify the metric value

Must be a string.

Usage Guidelines Use this command to display LDAP connections for the SPR lookup.

ldap server-set

Configures the LDAP server set parameters.

Command Modes Exec > Global Configuration

Syntax Description

```
ldap server-set server_name [ add-child-on-parent-create-failure { false | true } | add-request-attribute attribute_name attribute_value | binds-per-second binds_count | connection connection_address port_number {auto-reconnect { false | true } | bind-timeout-ms bind_timeout_ms | connection-rule FASTEST/ROUND_ROBIN | priority priority_number | timeout-ms timeout } | ignore-ldap-error-result-codes result_code | initial-connections initial_connections | max-connections max_connections | max-failover-connection-age-ms max_failover_connections | missing-attribute-result-code attribute_code | number-consecutive-timeouts-for-bad-connection count_timeout | retry-count retry_count | retry-timer-ms retry_time | use-asynchronous-operations { false | true } ]
```

add-child-on-parent-create-failure { false | true}

Specify to enable or disable additions of child on parent creation failure.

Must be one of the following:

- false
- true

Default Value: true.

binds-per-second *binds_count*

Specify the number of binds per second.

Must be of type decimal64, with 2 fraction digits.

Default Value: 0.20.

ignore-ldap-error-result-codes *result_code*

Specify to ignore LDAP error result codes.

Must be an integer.

initial-connections *initial_connections*

Specify the initial connections.

Must be an integer.

Default Value: 1.

max-connections *max_connections*

Specify the maximum number of connections.

Must be an integer.

Default Value: 10.

max-failover-connection-age-ms *max_failover_connections*

Specify the maximum failover connection age in milliseconds.

Must be an integer.

Default Value: 60000.

missing-attribute-result-code *result_code*

Specify missing attribute result code.

Must be an integer.

Default Value: 0.

number-consecutive-timeouts-for-bad-connection *count_timeouts*

Specify the number of consecutive timeouts for bad connection.

Must be an integer.

Default Value: -1.

retry-count *retry_count*

Specify the retry count.

Must be an integer.

Default Value: 3.

retry-timer-ms *retry_timeout*

Specify the retry timer timeout period in milliseconds.

Must be an integer.

Default Value: 50.

server-set *server_name*

Specify the name of the LDAP server set.

Must be a string.

use-asynchronous-operations { false | true }

Specify to enable or disable using LDAP asynchronous operations.

Must be one of the following:

- false
- true

Default Value: true.

Usage Guidelines Use this command to configure LDAP server set parameters.

ldap server-set add-request-attribute

Configures the request attribute.

Command Modes Exec > Global Configuration

Syntax Description **add-request-attribute** *attribute_name* *attribute_value*

attribute_name

Specify the request attribute name.

Must be a string.

attribute_value

Specify the request attribute value.

Must be a string.

Usage Guidelines Use this command to configure the request attribute.

ldap server-set connection

Configure the LDAP connection parameters.

Command Modes Exec > Global Configuration

Syntax Description **connection** *ldap_server_address* *port_number* { **auto-reconnect** { false | true } | **bind-timeout-ms** *bind_timeout* | **connection-rule** *connection_rule* | **priority** *priority_number* | **timeout-ms** *timeout*}

auto-reconnect { false | true}

Specify to enable or disable auto reconnect to LDAP hosts.

Must be one of the following:

- **false**
- **true**

Default Value: true.

bind-timeout-ms *bind_timeout*

Specify the timeout period for bind calls to LDAP in milliseconds.

Must be an integer.

Default Value: 2000.

connection-rule *connection_algorithm*

Specify the connection algorithm.

Must be one of the following:

- **FASTEST**
- **ROUND_ROBIN**

Default Value: ROUND_ROBIN.

connection *port_number*

Specify the port number of the LDAP server.

Must be an integer.

priority *priority_number*

Specify the priority of the LDAP server set.

Must be an integer.

Default Value: 100.

timeout-ms *timeout*

Specify the timeout period for calls to LDAP in milliseconds.

Must be an integer.

Default Value: 200.

ldap_server_address

Specify the address of the LDAP server.

Must be a string.

Usage Guidelines Use this command to configure the LDAP connection parameters.

Idap server-set health-check

Configures the health check parameters.

Command Modes Exec > Global Configuration

Syntax Description `health-check { attributes attribute_string | dn health_check_dn | filter filter_string | interval-ms interval_value }`

attributes *health_check_attributes*

Specify the health check attributes.

Must be a string.

dn *health_check_dn*

Specify the health check DN.

Must be a string.

filter *health_check_filter*

Specify the health check filter.

Must be a string.

interval-ms *health_check_interval*

Specify the health check interval in milliseconds.

Must be an integer.

Default Value: 5000.

Usage Guidelines Use this command to configure the health check parameters.

Idap server-set search-user

Enables search user for LDAP.

Command Modes Exec > Global Configuration

Syntax Description `search-user { [dn user_dn] [password user_password] }`

dn *user_dn*

Specify the user DN.

Must be a string.

password *user_password*

Specify the user password.

Usage Guidelines

Use this command to enable search user for LDAP.

testing

Configures the testing feature.

Command Modes

Exec > Global Configuration

Syntax Description

```
testing { external-mongo-access { admin | balance | session | spr } |
subversion-ingress-enabled | zing-compiler-options | zing-memory } { ip
ip_address | port port_number}
```

code-coverage-enabled { false | true }

Specify to enable or disable code coverage reporting with jacoco.

Must be one of the following:

- **false**
- **true**

Default Value: false.

development-mode-enabled { false | true }

Specify to enable or disable development mode.

Must be one of the following:

- **false**
- **true**

Default Value: false.

enforce-affinity-rules { false | true }

Specify to enable or disable anti affinity rules for pod scheduling.

Must be one of the following:

- **false**
- **true**

Default Value: true.

ldap-grpc-enabled { false | true }

Specify to enable or disable redis IPC communication between ldap-ep to engine.

Must be one of the following:

- **false**
- **true**

Default Value: false.

subversion-ingress-enabled { false | true}

Specify if the subversion ingress is enabled.

Must be one of the following:

- **false**
- **true**

Default Value: false.

zing-compiler-options *compiler_options*

Specify the compiler options for Zing.

Must be one of the following:

- **C2**
- **Falcon**

Default Value: C2.

Usage Guidelines Use this command to configure the testing feature.

testing tls-handshake

Configures the TLS/SSL testing configuration.

Command Modes Exec > Global Configuration

Syntax Description **tls-handshake**

alpn-disabled { false | true}

Specify to enable or disable ALPN extension in HTTP2 TLS ClientHello handshake.

Must be one of the following:

- **false**
- **true**

Default Value: false.

debug-enabled { false | true}

Specify to enable or disable TLS/SSL debug logs.

Must be one of the following:

- **false**
- **true**

Default Value: false.

trust-all { false | true}

Specify to enable or disable Keystore certificate validation for client.

Must be one of the following:

- **false**
- **true**

Default Value: false.

Usage Guidelines Use this command to configure the TLS/SSL testing configuration.

testing zing-memory

Configures the storage for Zing data.

Command Modes Exec > Global Configuration

Syntax Description **testing zing-memory** [**datastore** *datastore_zing_memory* | **diameter** *diameter_zing_memory* | **engine** *engine_zing_memory* | **ldap** *ldap_zing_memory*]

datastore *datastore_zing_memory*

Specify the datastore Zing memory. For example, -Xmx4g/-Xmx8g.

Must be a string.

Default Value: -Xmx8g.

diameter *diameter_zing_memory*

Specify the Diameter Zing memory. For example, -Xmx4g/-Xmx8g.

Must be a string.

Default Value: -Xmx8g.

engine *engine_zing_memory*

Specify the engine Zing memory. For example -Xmx4g/-Xmx8g.

Must be a string.

Default Value: -Xmx8g.

ldap ldap_zing_memory

Specify the LDAP endpoint. For example, -Xmx4g/-Xmx8g.

Must be a string.

Default Value: -Xmx8g.

Usage Guidelines

Use this command to configure the storage for Zing data.

zing

Configures Zing for the engine.

Command Modes

Exec > Global Configuration

Syntax Description

zing enable { false | true}

enable { false | true}

Specify to enable or disable Zing Java Virtual Machine.

Must be one of the following:

- **false**
- **true**

Default Value: false.

Usage Guidelines

Use this command to configure Zing for the engine.

Example

The following command configures Zing for the engine:

```
zing enable true
```



CHAPTER 3

Mobile Policy CDL Client Commands

- [datastore external-endpoints](#), on page 41
- [datastore external-endpoints connection-settings](#), on page 42
- [datastore external-endpoints connection-settings channel](#), on page 42
- [datastore external-endpoints connection-settings keep-alive](#), on page 42
- [datastore primary-endpoint](#), on page 43
- [datastore primary-endpoint connection-settings](#), on page 43
- [datastore primary-endpoint connection-settings channel](#), on page 44
- [datastore primary-endpoint connection-settings keep-alive](#), on page 44

datastore external-endpoints

Configures the list of external datastore endpoints.

Command Modes

Exec > Global Configuration

Syntax Description

datastore external-endpoints *external_endpoint*

external-endpoints *external_endpoints*

Specify the external datastore endpoints.

port *port_number*

Specify the port number.

rating *rating*

Specify the rating for the datastore endpoint (higher the better).

Must be an integer.

Default Value: 0.

Usage Guidelines

Use this command to configure the list of external datastore endpoints.

datastore external-endpoints connection-settings

Configures the connection setting parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
datastore external-endpoints external_endpoints connection-settings { channel
channel_count | keep-alive { keep-alive-time-ms keep_alive_time |
keep-alive-timeout-ms keep_alive_timeout } | timeout-ms timeout_in_ms | port
port_number | rating rating}
```

timeout-ms *timeout_ms*

Specify the timeout period in milliseconds.

Must be an integer.

Usage Guidelines

Use this command to configure connection settings.

datastore external-endpoints connection-settings channel

Configures the number of parallel gRPC channels to open towards each datastore endpoint.

Command Modes

Exec > Global Configuration

Syntax Description

```
datastore { external-endpoints external_endpoints | primary_enpoint
primary_endpoint } connection-settings channel count channel_count
```

count *channel_count*

Specify the number of parallel gRPC channels to open towards each datastore endpoint.

Must be an integer.

Usage Guidelines

Use this command to configure the number of parallel gRPC channels to open towards each datastore endpoint.

Example

The following command configures the channel count to 10:

```
datastore external-endpoints sample1 connection-settings channel count 10
```

datastore external-endpoints connection-settings keep-alive

Configures keep-alive parameters.

Command Modes

Exec > Global Configuration

Syntax Description `datastore { external-endpoints external_endpoints | primary_endpoint primary_endpoint } connection-settings keep-alive { keep-alive-time-ms keep_alive_time | keep-alive-timeout-ms keep_alive_timeout }`

keep-alive-time-ms *keep_alive_time*

Specify the idle timeout in milliseconds, after which keepalive notification is sent.

Must be an integer.

keep-alive-timeout-ms *keep_alive_timeout*

Specify the idle timeout period in milliseconds, after which keepalive probe is initiated.

Must be an integer.

Usage Guidelines Use this command to configure the keep-alive parameters.

datastore primary-endpoint

Configures the primary (cluster local) datastore parameters.

Command Modes Exec > Global Configuration

Syntax Description `datastore primary-endpoint connection-settings { channel channel_count | keep-alive { keep-alive-time-ms keep_alive_time | keep-alive-timeout-ms keep_alive_timeout | timeout-ms } | timeout-ms timeout_in_ms }`

Usage Guidelines Use this command to configure the primary datastore configuration.

datastore primary-endpoint connection-settings

Configures the datastore connection settings.

Command Modes Exec > Global Configuration

Syntax Description `datastore { external-endpoints external_endpoints | primary_endpoint primary_endpoint } connection-settings`

timeout-ms *timeout_ms*

Specify the timeout period in milliseconds.

Must be an integer.

Usage Guidelines Use this command to configure the datastore connection settings.

datastore primary-endpoint connection-settings channel

Configures the number of parallel gRPC channels to open towards each datastore endpoint.

Command Modes Exec > Global Configuration

Syntax Description `datastore { external-endpoints external_endpoints | primary_endpoint primary_endpoint } connection-settings channel count channel_count`

count *channel_count*

Specify the number of parallel gRPC channels to open towards each datastore endpoint.

Must be an integer.

Usage Guidelines Use this command to configure the number of parallel gRPC channels to open towards each datastore endpoint.

Example

The following command configures the channel count to 10:

```
datastore external-endpoints sample1 connection-settings channel count 10
```

datastore primary-endpoint connection-settings keep-alive

Configures keep-alive parameters.

Command Modes Exec > Global Configuration

Syntax Description `datastore { external-endpoints external_endpoints | primary_endpoint primary_endpoint } connection-settings keep-alive { keep-alive-time-ms keep_alive_time | keep-alive-timeout-ms keep_alive_timeout}`

keep-alive-time-ms *keep_alive_time*

Specify the idle timeout in milliseconds, after which keepalive notification is sent.

Must be an integer.

keep-alive-timeout-ms *keep_alive_timeout*

Specify the idle timeout period in milliseconds, after which keepalive probe is initiated.

Must be an integer.

Usage Guidelines Use this command to configure the keep-alive parameters.



CHAPTER 4

Mobile Policy Diameter Commands

- [diameter](#), on page 45
- [diameter application](#), on page 45
- [diameter group](#), on page 46
- [diameter group stack](#), on page 47
- [diameter group stack diameter-engine alt-engines](#), on page 48
- [diameter group stack diameter-engine alt-engines primary](#), on page 49
- [diameter group stack diameter-engine alt-engines secondary](#), on page 49
- [diameter group stack grpc ext-svc](#), on page 49
- [diameter group stack settings timeouts-ms](#), on page 50
- [diameter grpc](#), on page 51
- [diameter grpc channel](#), on page 51
- [diameter next-hop-route next-hop-host](#), on page 52
- [diameter settings timeouts-ms](#), on page 52

diameter

Displays the configured Diameter stack definition.

Command Modes Exec

Syntax Description `show diameter`

Usage Guidelines Use this command to view the configured Diameter stack definition.

Example

The following command displays the configured Diameter stack definition:

```
show diameter peer-status
```

diameter application

Configures the Diameter application definition.

Command Modes	Exec > Global Configuration
Syntax Description	<pre>diameter application <i>application_name</i> { application-id <i>application_id</i> tgpp-application { false true } vendor <i>vendor_id</i>}</pre> <p>application-id <i>application_id</i> Specify the application ID. Must be an integer.</p> <p>application <i>application_name</i> Specify the application abbreviation. For example, gx. Must be a string.</p> <p>tgpp-application { false true} Specify whether the application is a 3GPP application. Must be one of the following:</p> <ul style="list-style-type: none"> • false • true <p>Default Value: false.</p> <p>vendor <i>vendor_id</i> Specify the vendor IDs. Must be an integer.</p>

Usage Guidelines Use this command to configure the Diameter application definition.

diameter group

Configures the Diameter stack group parameters.

Command Modes	Exec > Global Configuration
Syntax Description	<pre>diameter group [group <i>group_name</i> mode <i>mode</i> repository <i>repository_name</i> stack <i>stack_name</i>]</pre> <p>group <i>group_name</i> Specify the group and stack name. Must be a string in the pattern [a-zA-Z][a-zA-Z0-9]*.</p> <p>mode <i>mode</i> Specify the mode in which the Diameter stack must run.</p>

Must be one of the following:

- **client**
- **server**

Default Value: client.

repository *repository_name*

Specify the helm repository.

Usage Guidelines

Use this command to configure the Diameter stack group.

diameter group stack

Configures the Diameter stack definition.

Command Modes

Exec > Global Configuration

Syntax Description

```
diameter group group_name stack stack_name { application application_name | bind-ip
bind_ip_address | bind-port bind_port_number | fqdn fqdn_name | realm realm |
peer-host peer_host_name | peer-port peer_port_number | peer-realm peer_realm |
node-host node_host}
```

application *application_name*

Specify the Diameter application.

bind-ip *bind_ip_address*

Specify the IP address to use in the CER or CEA message.

bind-port *bind_port_number*

Specify the port number to bind the server.

Default Value: 3868.

fqdn *fqdn*

Specify the fully qualified domain name (FQDN) to use in CER or CEA messages.

Must be a string.

node-host *node_host*

Specify the node host to start the stack on.

Must be a string.

peer-host *peer_host_name*

Specify the remote peer host address or FQDN.

Must be a string.

peer-port *peer_port_number*

Specify the peer port number.

Default Value: 3868.

peer-realm *peer_realm*

Specify the remote peer realm.

Must be a string.

realm *realm*

Specify the realm to use in CER or CEA messages.

Must be a string.

replicas *replica_count*

Specify the replica count.

Must be an integer.

Default Value: 1.

stack *stack_name*

Specify the stack name.

Must be a string.

Usage Guidelines

Use this command to configure the Diameter stack definition.

diameter group stack diameter-engine alt-engines

Configures the alternate Diameter engine parameters.

Command Modes

Exec > Global Configuration > Diameter Group Configuration > Stack Configuration

Syntax Description

diameter-engine alt-engines check-session-exists { false | true }

check-session-exists { false | true }

Specify whether to check if the session exists on the alternate-engines before forwarding requests.

Must be one of the following:

- **false**
- **true**

Default Value: false.

Usage Guidelines Use this command to configure the alternate Diameter engine parameters.

diameter group stack diameter-engine alt-engines primary

Configures the primary Diameter Engine parameters.

Command Modes Exec > Global Configuration > Diameter Group Configuration > Stack Configuration

Syntax Description **primary** **svc-name** *service_name* **port** *port_number*

port *port_number*

Specify the port number exposed by the external service.

Default Value: 8884.

svc-name *service_name*

Specify the external service name that represents the Diameter engine.

Usage Guidelines Use this command to configure the primary Diameter Engine parameters.

diameter group stack diameter-engine alt-engines secondary

Configures the secondary Diameter Engine parameters.

Command Modes Exec > Global Configuration > Diameter Group Configuration > Stack Configuration

Syntax Description **secondary** **svc-name** *service_name* **port** *port_number*

port *port_number*

Specify the port number exposed by the external service.

Default Value: 8884.

svc-name *service_name*

Specify the external service name that represents the Diameter engine.

Usage Guidelines Use this command to configure the secondary Diameter Engine parameters.

diameter group stack grpc ext-svc

Configures the external gRPC service parameters for the Diameter interface.

Command Modes Exec > Global Configuration

Syntax Description **diameter grpc** [**port** *port_number* | **ip** *ip_address*]

ip ip_address

Specify the gRPC server's IP address.

port port_number

Specify the port number to bind the server.

Default Value: 8868.

Usage Guidelines

Use this command to configure the external gRPC service parameters for the Diameter interface.

diameter group stack settings timeouts-ms

Configures the timeout parameters for the Diameter interface.

Command Modes

Exec > Global Configuration

Syntax Description

```
diameter settings timeout-ms [ cea cea_timeout | dpa dpa_timeout | dwa dwa_timeout
| iac inactivity_timeout | request request_timeout | stop timeout_stop_diameter ]
```

cea cea_exchange_timeout

Specify the timeout duration for completing the CEA exchange in milliseconds.

Must be an integer.

Default Value: 10000.

dpa dpa_timeout

Specify the DPA timeout duration in milliseconds.

Must be an integer.

Default Value: 10000.

dwa dwa_timeout

Specify the DWA timeout duration in milliseconds.

Must be an integer.

Default Value: 10000.

iac inactivity_timeout

Specify the inactivity timeout duration in milliseconds.

Must be an integer.

Default Value: 5000.

request request_timeout

Specify the request timeout duration in milliseconds.

Must be an integer.

Default Value: 1750.

stop *stop_timeout*

Specify the timeout duration for stopping the Diameter interface in milliseconds.

Must be an integer.

Default Value: 9000.

Usage Guidelines

Use this command to configure the timeout duration for the Diameter interface.

Example

The following command configures the timeout duration for the Diameter interface:

```
diameter settings timeout-ms [ cea 10000 | dpa 10000 | dwa 10000 | iac 5000 | request 1750
| stop 9000 ]
```

diameter grpc

Configures the global gRPC settings.

Command Modes

Exec > Global Configuration

Syntax Description

diameter grpc channel count *count*

Usage Guidelines

Use this command to configure the global gRPC settings.

Example

The following command configures the global gRPC settings:

```
diameter grpc channel count 100
```

diameter grpc channel

Configures the gRPC channels to open towards the server.

Command Modes

Exec > Global Configuration

Syntax Description

diameter grpc channel count *channel_count*

channel *channel_count*

Specify the number of channel to open towards the server.

Must be an integer.

Default Value: 10.

Usage Guidelines Use this command to configure the gRPC channels to open towards the server.

diameter next-hop-route next-hop-host

Configures the next-hop host name.

Command Modes Exec > Global Configuration

Syntax Description `next_hop_realm rating rating`

next-hop-host-name *hostname_list*

Specify the DRA hosts name list as received in the Origin-Host AVP in CER or CEA message.

Must be a string.

rating *rating*

Specify the rating that determines the priority.

Must be an integer.

Default Value: 0.

Usage Guidelines Use this command to configure the next-hop host name.

Example

The following command configures the next-hop host name:

```
next_hop_realm rating 2
```

diameter settings timeouts-ms

Configures the timeout parameters for the Diameter interface.

Command Modes Exec > Global Configuration

Syntax Description `diameter settings timeout-ms [cea cea_timeout | dpa dpa_timeout | dwa dwa_timeout | iac inactivity_timeout | request request_timeout | stop timeout_stop_diameter]`

cea *cea_exchange_timeout*

Specify the timeout duration for completing the CEA exchange in milliseconds.

Must be an integer.

Default Value: 10000.

dpa *dpa_timeout*

Specify the DPA timeout duration in milliseconds.

Must be an integer.

Default Value: 10000.

dwa *dwa_timeout*

Specify the DWA timeout duration in milliseconds.

Must be an integer.

Default Value: 10000.

iac *inactivity_timeout*

Specify the inactivity timeout duration in milliseconds.

Must be an integer.

Default Value: 5000.

request *request_timeout*

Specify the request timeout duration in milliseconds.

Must be an integer.

Default Value: 1750.

stop *stop_timeout*

Specify the timeout duration for stopping the Diameter interface in milliseconds.

Must be an integer.

Default Value: 9000.

Usage Guidelines

Use this command to configure the timeout duration for the Diameter interface.

Example

The following command configures the timeout duration for the Diameter interface:

```
diameter settings timeout-ms [ cea 10000 | dpa 10000 | dwa 10000 | iac 5000 | request 1750  
| stop 9000 ]
```




CHAPTER 5

Mobile Policy Infrastructure Commands

- [subversion](#), on page 55

subversion

Configures Subversion parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
subversion { polling-interval-secs monitor_svn_thread_polling_interval |  
max-data-chunk-size max_data_chunk_size}
```

max-data-chunk-size *max_data_chunk_size*

Specify the maximum chunk size, in bytes, to store in configmap.

Must be an integer in the range of 300000-550000.

Default Value: 550000.

polling-interval-secs *monitor_svn_thread_polling_interval*

Specify the monitor-svn thread polling interval in seconds.

Must be an integer.

Default Value: 120.

Usage Guidelines

Use this command to configure the Subversion parameters.



CHAPTER 6

Mobile Policy LDAP Commands

- [ldap-server-endpoint connect](#), on page 57
- [ldap-server-endpoint health-check-attributes](#), on page 58
- [ldap-server-endpoint health-check-filter](#), on page 58
- [ldap-server-endpoint input-mapping](#), on page 59
- [ldap-server-endpoint ldap-clients](#), on page 59
- [ldap-server-endpoint output-mapping](#), on page 60

ldap-server-endpoint connect

Configures the LDAP Server connection parameters.

Command Modes Exec > Global Configuration

Syntax Description `ldap-server-endpoint connect [bind-ip bind_ip_address | binddn bind_dn | max-transactions max_tps | password password | port port_number | request-timeout request_timeout | replica replica_count]`

bind-ip *bind_ip_address*

Specify the IP address to connect to the LDAP server.

binddn *bind_dn*

Specify the binding user to bind to the LDAP server.

Must be a string.

max-transactions *max_tps*

Specify the maximum TPS allowed.

Must be an integer.

Default Value: 200.

password *password*

Specify the binding user's password in plain text format.

port *port_number*

Specify the destination LDAP port to connect to the LDAP server.

Default Value: 9389.

replica *replica_count*

Specify the replica count.

Must be an integer.

Default Value: 1.

request-timeout *request_timeout*

Specify the request time out duration in milliseconds.

Must be an integer.

Default Value: 2000.

Usage Guidelines

Use this command to configure the LDAP Server connection parameters.

ldap-server-endpoint health-check-attributes

Configures the response attributes and values for the health-check request.

Command Modes

Exec > Global Configuration

Syntax Description

ldap-server-endpoint health-check-attributes *attribute_name* **value** *value*

value *value*

Specify the LDAP attribute filter value.

Must be a string.

attribute_name

Specify the LDAP attribute filter name.

Must be a string.

Usage Guidelines

Use this command to configure the response attributes and values for health-check request.

ldap-server-endpoint health-check-filter

Configures the health check filter parameters for the LDAP server endpoint.

Command Modes

Exec > Global Configuration

Syntax Description

ldap-server-endpoint health-check-filter *attribute_name* **value** *value*

value *value*

Specify the LDAP attribute filter value.

Must be a string.

attribute_name

Specify the LDAP attribute filter name.

Must be a string.

Usage Guidelines Use this command to configure the health check filter parameters.

ldap-server-endpoint input-mapping

Configures mapping for the LDAP search query filter name to Session lookup attribute.

Command Modes Exec > Global Configuration

Syntax Description `ldap-server-endpoint input-mapping filter_name internal-lookup-key lookup_key`

internal-lookup-key *lookup_key*

Specify the session lookup key.

Must be one of the following:

- IMSI
- IP_ADDRESS
- MSISDN

filter_name

Specify the LDAP query filter name.

Must be a string.

Usage Guidelines Use this command to configure the mapping for the LDAP search query filter name to Session lookup attribute.

ldap-server-endpoint ldap-clients

Configures the LDAP client credentials to bind to the server.

Command Modes Exec > Global Configuration

Syntax Description `ldap-server-endpoint ldap-clients client password password`

binddn *bind_dn*

Specify the binding user to bind to the LDAP server.

Must be a string.

password *password*

Specify the binding user's password in plain text format.

Usage Guidelines Use this command to configure the LDAP client credentials to bind to the server.

ldap-server-endpoint output-mapping

Configures the mapping for session lookup attributes to LDAP search response attributes.

Command Modes Exec > Global Configuration

Syntax Description `ldap-server-endpoint output-mapping attribute_name input lookup_key`

input *lookup_key*

Specify the session lookup key.

Must be a string.

ouput-mapping *attribute_name*

Specify the LDAP response attribute name.

Must be a string.

Usage Guidelines Use this command to configure the mapping for session lookup attributes to LDAP search response attributes.



CHAPTER 7

Mobile Policy PCF Commands

- [advance-tuning](#), on page 61
- [advance-tuning async-threading](#), on page 62
- [advance-tuning async-threading threading-config](#), on page 63
- [advance-tuning brute-force-recovery](#), on page 64
- [advance-tuning http2-threading](#), on page 65
- [advance-tuning overload-control](#), on page 66
- [advance-tuning overload-control diameter global](#), on page 66
- [advance-tuning overload-control diameter global action](#), on page 66
- [advance-tuning overload-control diameter global limits](#), on page 67
- [advance-tuning overload-control rest global](#), on page 67
- [advance-tuning overload-control rest global action](#), on page 67
- [advance-tuning overload-control rest global limits](#), on page 68
- [rest-endpoint](#), on page 68
- [rest-endpoint certificate-status](#), on page 70
- [rest-endpoint discovered-profiles](#), on page 70
- [rest-endpoint discovered-profiles chf](#), on page 70
- [rest-endpoint discovered-profiles udr](#), on page 71
- [rest-endpoint interface](#), on page 72
- [rest-endpoint peer-status](#), on page 73
- [rest-endpoint registration-status](#), on page 73
- [traffic engine](#), on page 74
- [traffic engine rule](#), on page 74

advance-tuning

Configures advanced tuning parameters.

Command Modes Exec > Global Configuration

Syntax Description `advance-tuning { n7-stale-session-error-codes error_codes | redis-password redis_password}`

n7-stale-session-error-codes *error_codes*

Specify the comma-separated list of N7Notify stale session error codes.

Must be a string.

redis-password *redis_password*

Specify the Redis password.

Usage Guidelines

Use this command to configure advanced tuning parameters.

advance-tuning async-threading

Configures threading configuration for HTTP outgoing request from PCF.

Command Modes

Exec > Global Configuration

Syntax Description

```
advance-tuning async-threading { default-drop-oldest-when-full { false | true } | default-priority default_priority | default-processing-threads processing_thread_number | default-queue-size default_queue_size | default-worker-threads default_number_worker_threads | request-timeout-ms request_timeout | thread-configuration service_name drop-oldest-when-full { false | true } | priority thread_priority | queue-size queue_size | threads thread_number}
```

default-drop-oldest-when-full { **false** | **true**}

Specify to drop the oldest packet when queue is full.

Must be one of the following:

- **false**
- **true**

Default Value: false.

default-priority *default_priority*

Specify the default priority of thread.

Must be an integer.

Default Value: 5.

default-processing-threads *processing_thread_number*

Specify the default number of processing threads.

Must be an integer.

Default Value: 10.

default-queue-size *default_queue_size*

Specify the default size of the queue.

Must be an integer.

Default Value: 100.

default-worker-threads *default_number_worker_threads*

Specify the default number of worker threads.

Must be an integer.

Default Value: 20.

http2-connect-timeout-ms *http2_connect_timeout*

Specify the request timeout period in milliseconds.

Must be an integer.

Default Value: 100.

http2-idle-connection-timeout-sec *http2_client_idle_connect_timeout*

Specify the idle connection timeout for HTTP2 client.

Must be an integer.

Default Value: 60.

max-timeouts-to-reconnect *max_requests_timeouts*

Specify the maximum request timeouts to reconnect HTTP2 connection.

Must be an integer.

Default Value: 0.

Usage Guidelines

Use this command to configure threading configuration for HTTP outgoing request from PCF.

Example

The following command configures the threading configuration for HTTP outgoing request from PCF with default priority of 5:

```
advance-tuning async-threading default-priority 5
```

advance-tuning async-threading threading-config

Configures threading configuration of servicethreading.

Command Modes

Exec > Global Configuration

Syntax Description

threading-config *service_name*

drop-oldest-when-full { false | true}

Specify to drop the oldest packet when the queue is full.

Must be one of the following:

- false
- true

priority *thread_priority*

Specify the threading priority.

Must be an integer.

queue-size *queue_size*

Specify the size of the queue.

Must be an integer.

service-name *service_name*

Specify the service name.

Must be a string.

threads *thread_number*

Specify the number of threads.

Must be an integer.

Usage Guidelines

Use this command to configure threading configuration of service.

advance-tuning brute-force-recovery

Enables HTTP2 connection recovery parameters via closing connection.

Command Modes

Exec > Global Configuration

Syntax Description

```
brute-force-recovery { max-reconnects max_http2_reconnects | time-interval-mins
time_interval}
```

max-reconnects *max_http2_reconnects*

Specify the maximum number of HTTP2 reconnect attempts to be allowed before restarting REST endpoint for recovery. Counter for previous reconnect attempts gets reset as per time-interval-mins. When set to 0, restart of rest endpoint is not performed even on reaching configured count and system continues attempting reconnect for recovery.

Must be an integer.

Default Value: 0.

time-interval-mins *time_interval*

Specify the time interval in minutes. If there is no HTTP2 reconnect triggered due to timeout for specified duration plus 1 minute then counter for previous reconnect attempts is reset to 0.

Must be an integer.

Default Value: 0.

Usage Guidelines

Use this command to enable HTTP2 connection recovery parameters via closing connection.

advance-tuning http2-threading

Configures threading configuration for HTTP incoming request to PCF.

Command Modes

Exec > Global Configuration

Syntax Description

```
advance-tuning http2-threading { disable-validation { false | true } |
idle-thread-timeout-ms idle_thread_timeout | max-queue-capacity max_packet_capacity
| max-thread-pool-size max_thread_pool_size | min-thread-pool-size
min_thread_pool_size | request-timeout-ms request_timeout}
```

disable-validation { false | true }

Specify to enable or disable validation.

Must be one of the following:

- false
- true

Default Value: false.

idle-thread-timeout-ms *idle_thread_timeout*

Specify the thread idle timeout in milliseconds.

Must be an integer.

Default Value: 60000.

max-queue-capacity *max_packet_capacity*

Specify the maximum packet capacity of the queue.

Must be an integer.

Default Value: 5000.

max-thread-pool-size *max_thread_pool_size*

Specify the maximum size of pool of threads.

Must be an integer.

Default Value: 20.

min-thread-pool-size *min_thread_pool_size*

Specify the minimum size of pool of threads.

Must be an integer.

Default Value: 5.

Usage Guidelines

Use this command to configure threading configuration for HTTP incoming request to PCF.

Example

The following command configures the threading configuration for HTTP incoming request to PCF with maximum queue capacity of 500:

```
advance-tuning http2-threading max-queue-capacity 500
```

advance-tuning overload-control

Configures threading configuration for HTTP incoming request to PCF.

Command Modes

Exec > Global Configuration

Syntax Description

advance-tuning overload-control

Usage Guidelines

Use this command to configure threading configuration for HTTP incoming request to PCF.

advance-tuning overload-control diameter global

Configures Overload Control configuration for all Diameter interfaces.

Command Modes

Exec > Global Configuration

Syntax Description

advance-tuning overload-control diameter global

Usage Guidelines

Use this command to configure Overload Control configuration for all Diameter traffic.

advance-tuning overload-control diameter global action

Configures the action to take on overload detection.

Command Modes

Exec > Global Configuration

Syntax Description

action throttle-action *throttle_action*

action throttle-action *throttle_action*

Specify the action to take when overload traffic is detected.

Must be one of the following:

- **DROP**
- **REJECT**

Usage Guidelines Use this command to configure the action that must be taken on overload detection.

advance-tuning overload-control diameter global limits

Configures the limits for the overload handling parameters for the REST or Diameter interface.

Command Modes Exec > Global Configuration

Syntax Description `limits max-requests-per-sec maximum_requests`

`max-requests-per-sec maximum_requests`

Specify the maximum number of requests that are allowed per second before throttling is applied.

Must be an integer.

Usage Guidelines Use this command to configure the limits for overload handling parameters for the REST or Diameter interface.

advance-tuning overload-control rest global

Configures Overload Control configuration for all REST traffic.

Command Modes Exec > Global Configuration

Syntax Description `advance-tuning overload-control rest global`

Usage Guidelines Use this command to configure threading configuration for HTTP incoming request to PCF.

advance-tuning overload-control rest global action

Configures the action to take on overload detection.

Command Modes Exec > Global Configuration

Syntax Description `action throttle-action throttle_action`

`action throttle-action throttle_action`

Specify the action to take when overload traffic is detected.

Must be one of the following:

- **DROP**

- REJECT

Usage Guidelines Use this command to configure the action that must be taken on overload detection.

advance-tuning overload-control rest global limits

Configures the limits for the overload handling parameters for the REST or Diameter interface.

Command Modes Exec > Global Configuration

Syntax Description **limits max-requests-per-sec** *maximum_requests*

max-requests-per-sec *maximum_requests*

Specify the maximum number of requests that are allowed per second before throttling is applied.

Must be an integer.

Usage Guidelines Use this command to configure the limits for overload handling parameters for the REST or Diameter interface.

rest-endpoint

Configures the REST endpoint.

Command Modes Exec > Global Configuration

Syntax Description **rest-endpoint** { **ips** *ip_address* | **port** *port_number* | **replicas** *replica_count* | **tracing-service-name** *service_name*}

certificate-name *certificate_name*

Specify the alias name for the certificate.

http-connection-limit *max_inbound_https_connections*

Specify the maximum number of allowed inbound HTTPS connections.

Must be an integer.

Default Value: 200.

http-idle-connection-timeout-on-server-seconds *connection_timeout*

Specify the server side idle connection timeout period in seconds.

Must be an integer.

Default Value: 60.

inbound-request-timeout-ms *inbound_requests_timeout*

Specify the timeout period for inbound requests in milliseconds.

Must be an integer.

Default Value: 2000.

ips *ip_address*

Specify the IP addresses for the REST service.

outbound-request-timeout-ms *outbound_requests_timeout*

Specify the timeout period for outbound requests in milliseconds.

Must be an integer.

Default Value: 200.

port *port_number*

Specify port number of the REST service.

Must be an integer.

replicas *replica_count*

Specify the replica count.

Must be an integer.

Default Value: 1.

repository *repository_name*

Specify to override the Helm repository.

tracing-service-name *tracing_service_name*

Specify the tracing service name for REST endpoint.

Must be a string.

uri-scheme *uri_scheme*

Specify the URI scheme.

Must be one of the following:

- **http**
- **https**

Default Value: http.

Usage Guidelines

Use this command to configure the REST endpoint.

Example

The following command configures the REST endpoint tracing service name as nPcf-pcf-rest-ep:

```
rest-endpoint tracing-service-name nPcf-pcf-rest-ep
```

rest-endpoint certificate-status

Displays certificate status.

Command Modes Exec > Global Configuration

Syntax Description `show certificate-status`

certificateName

Displays the certificate name.

Must be a string.

timeToExpire

Displays the time to expire.

Must be a string.

Usage Guidelines Use this command to view certificate status.

rest-endpoint discovered-profiles

Displays the PCF discovered and cached NFs.

Command Modes Exec > Global Configuration

Syntax Description `show discovered-profiles`

Usage Guidelines Use this command to view the PCF discovered and cached NFs.

rest-endpoint discovered-profiles chf

Displays PCF Discover cache for CHF.

Command Modes Exec > Global Configuration

Syntax Description `show discovered-profiles chf`

expiry

The expiration time in seconds.

Must be a string.

ipv4Address

The NF IPv4 address.

Must be a string.

nfnstanceld

The NF Instance ID.

Must be a string.

nfStatus

Is the PCF instance registered to NRF.

Must be a string.

nfType

The NF type.

Must be a string.

port

The NF port number.

Usage Guidelines

Use this command to view PCF Discover cache for CHF.

rest-endpoint discovered-profiles udr

Displays PCF Discover cache for UDR.

Command Modes

Exec > Global Configuration

Syntax Description

show discovered-profiles udr

expiry

The expiration time in seconds.

Must be a string.

ipv4Address

The NF IPv4 address.

Must be a string.

nfnstanceld

The NF Instance ID.

Must be a string.

nfStatus

Is the PCF instance registered to NRF.

Must be a string.

nfType

The NF type.

Must be a string.

port

The NF port number.

Usage Guidelines Use this command to view PCF Discover cache for UDR.

rest-endpoint interface

Configures the NF interfaces.

Command Modes Exec > Global Configuration

Syntax Description `rest-endpoint interface interface_type { ip ip_address | notify-update-retry-count notify_update_retry_count | outbound-request-timeout-ms outbound_request_timeout | port port_number}`

interface interface_type

Specify the NF interface type.

ip ip_address

Specify the NF interface IP address.

notify-update-retry-count notify_update_retry_count

Specify the retry count for N7 NotifyUpdate outbound requests in case of timeout.

Must be an integer.

Default Value: 0.

outbound-request-timeout-ms outbound_request_timeout

Specify the timeout period for outbound requests in milliseconds.

Must be an integer.

port port_number

Specify the port number for NF interface.

Must be an integer.

Usage Guidelines Use this command to configure NF interfaces.

Example

The following command configures the NF interface to restEndpoint with the IP address 11.11.11.11:

```
rest-endpoint interface restEndpoint ip 11.11.11.11
```

rest-endpoint peer-status

Displays the NF's peer status.

Command Modes Exec > Global Configuration

Syntax Description `show peer-status`

connectionDuration

Displays the NF connection uptime duration.

Must be a string.

nfName

Displays the PCF Discover cache for UDR.

Must be a string.

peerIp

Displays the NF peer IP address.

Must be a string.

peerPort

Displays the NF peer port number.

Must be a string.

podIp

Displays the PCF pod IP address.

Must be a string.

Usage Guidelines Use this command to view the NF's peer status.

rest-endpoint registration-status

Displays NRF registration details.

Command Modes	Exec > Global Configuration
Syntax Description	<p>show registration-status</p> <p>nrfUri Displays the registered NRF URI. Must be a string.</p> <p>podIp Displays the PCF pod ID. Must be a string.</p> <p>registered Displays whether Is PCF instance is registered to NRF. Must be a string.</p>
Usage Guidelines	Use this command to view NRF registration details.

traffic engine

Configures the default engine group to receive traffic.

Command Modes	Exec > Global Configuration
Syntax Description	<p>traffic engine default-destination <i>default_destination</i></p> <p>default-destination <i>default_destination</i></p> <p>Specify the default engine group to receive the traffic.</p>
Usage Guidelines	Use this command to configure the default engine group to receive traffic. Note that a similar command is available for PCRF.

Example

The following command configures the default engine group as /policy-test:engine/test-test1:group:

```
traffic engine default-destination /policy-test:engine/test-test1:group
```

traffic engine rule

Configures traffic routing rule parameters.

Command Modes	Exec > Global Configuration
----------------------	-----------------------------

Syntax Description

```
traffic engine rule rule_name { dnn dnn_route | supi supi_route | gpsi gpsi_route  
| hash-prefix hash_prefix_route | intf interface_route | destination engine_group}
```

destination *engine_group*

Specify the engine group to receive traffic.

dnn *dnn_route*

Specify the route on DNN - regex.

Must be a string.

gpsi *gpsi_route*

Specify the route on GPSI - regex.

Must be a string.

hash-prefix *hash_prefix_route*

Specify the route on 2-digit hash - prefix.

Must be a string.

intf *interface_route*

Specify the route on interface type - exact.

Must be a string.

supi *supi_route*

Specify the route on SUPI - regex.

Must be a string.

rule_name

Specify the rule name.

Must be a string.

Usage Guidelines

Use this command to configure the traffic routing rule parameters.



CHAPTER 8

Mobile Policy Services Repository Commands

- [clear subscriber](#), on page 78
- [deployment add config](#), on page 78
- [deployment remove-config](#), on page 79
- [deployment show-config](#), on page 79
- [group nf-mgmt](#), on page 79
- [group nf-mgmt failover](#), on page 80
- [group nf-mgmt reconnect](#), on page 81
- [group nrf discovery](#), on page 81
- [group nrf discovery service type nrf](#), on page 81
- [group nrf discovery service type nrf endpoint-profile](#), on page 82
- [group nrf discovery service type nrf endpoint-profile endpoint-name](#), on page 83
- [group nrf discovery service type nrf endpoint-profile endpoint-name primary ip-address](#), on page 84
- [group nrf discovery service type nrf endpoint-profile endpoint-name secondary ip-address](#), on page 85
- [group nrf discovery service type nrf endpoint-profile endpoint-name tertiary ip-address](#), on page 86
- [group nrf discovery service type nrf endpoint-profile version uri-version](#), on page 87
- [group nrf mgmt](#), on page 87
- [group nrf mgmt service type nrf](#), on page 87
- [group nrf mgmt service type nrf endpoint-profile](#), on page 88
- [group nrf mgmt service type nrf endpoint-profile endpoint-name](#), on page 89
- [group nrf mgmt service type nrf endpoint-profile endpoint-name primary ip-address](#), on page 90
- [group nrf mgmt service type nrf endpoint-profile endpoint-name secondary ip-address](#), on page 91
- [group nrf mgmt service type nrf endpoint-profile endpoint-name tertiary ip-address](#), on page 92
- [group nrf mgmt service type nrf endpoint-profile version uri-version](#), on page 93
- [profile nf-client nf-type bsf bsf-profile](#), on page 93
- [profile nf-client nf-type bsf bsf-profile locality](#), on page 93
- [profile nf-client nf-type bsf bsf-profile locality service name type](#), on page 94
- [profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile](#), on page 94
- [profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile endpoint-name](#), on page 96
- [profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile version uri-version](#), on page 96
- [profile nf-client nf-type chf chf-profile](#), on page 97
- [profile nf-client nf-type chf chf-profile locality](#), on page 97
- [profile nf-client nf-type chf chf-profile locality service name type](#), on page 98

- [profile nf-client nf-type chf chf-profile locality service name type endpoint-profile](#), on page 98
- [profile nf-client nf-type chf chf-profile locality service name type endpoint-profile endpoint-name](#), on page 99
- [profile nf-client nf-type chf chf-profile locality service name type endpoint-profile version uri-version](#), on page 100
- [profile nf-client nf-type udr udr-profile locality](#), on page 100
- [profile nf-client nf-type udr udr-profile locality service name type](#), on page 101
- [profile nf-pair nf-type](#), on page 101
- [profile nf-pair nf-type locality](#), on page 102
- [service-registration profile](#), on page 103
- [service-registration profile allowed-plmns](#), on page 104
- [service-registration profile pcf-info](#), on page 105
- [service-registration profile pcf-info supi-ranges](#), on page 105
- [service-registration profile plmn-list](#), on page 106
- [service-registration profile snssais](#), on page 106
- [service-registration services](#), on page 107
- [service-registration services allowed-nssais](#), on page 107
- [service-registration services allowed-plmns](#), on page 108
- [show subscriber](#), on page 108

clear subscriber

Clears subscriber session information.

Command Modes Exec

Syntax Description `clear subscriber [imsi imsi | msisdn msisdn]`

imsi *imsi*

Specify the IMSI.

Must be a string.

msisdn *msisdn*

Specify the MSISDN.

Must be a string.

Usage Guidelines Use this command to clear subscriber session information.

deployment add config

Configures the cluster name and unified API external IP parameters.

Command Modes Exec > Global Configuration

Syntax Description `deployment add config { cluster-name cluster_name | port port_number | unified-api-external-ip ip_address}`

cluster-name *cluster_name*

Specify the cluster name.

Must be a string.

port *port_number*

Specify the port number of the unified API service.

unified-api-external-ip *ip_address*

Specify the external IP address of the unified API service.

Usage Guidelines Use this command to configure the cluster name and unified API external IP parameters.

deployment remove-config

Removes the deployment configuration file.

Command Modes Exec

Syntax Description `deployment remove-config`

Usage Guidelines Use this command to remove the deployment configuration file.

deployment show-config

Displays configuration information.

Command Modes Exec

Syntax Description `deployment show-config`

Usage Guidelines Use this command to view the configuration information.

group nf-mgmt

Configures the NF management group parameters.

Command Modes Exec > Global Configuration

Syntax Description `group nf-mgmt group_name nrf-mgmt-group registerGroup { nrf-mgmt-group mgmt_group_name | api-version api_version | locality group_locality}`

api-version *api_version*

Specify the NF Management Service API version supported by the NRF.

Must be one of the following:

- 1.0.0
- 1.0.2

Default Value: 1.0.0.

load-report-enabled { false | true }

Specify to enable or disable sending cluster load in NRF heartbeat requests.

Must be one of the following:

- false
- true

Default Value: true.

locality *group_locality*

Specify the NRF group locality.

Must be a string.

nrf-mgmt-group *mgmt_group_name*

Specify the NRF management group name.

group_name

Specify the group name.

Must be a string.

Usage Guidelines

Use this command to enter the NRF management group configuration.

group nf-mgmt failover

Configures the failover SLA parameters.

Command Modes

Exec > Global Configuration

Syntax Description

failover group nf-mgmt *group_name* **failover sla** *failover_sla*

failover_sla

Specify the failover SLA value in milliseconds.

Must be an integer.

Usage Guidelines Use this command to configure the failover SLA parameters.

group nf-mgmt reconnect

Configures the reconnect interval.

Command Modes Exec > Global Configuration

Syntax Description `reconnect interval reconnect_interval`

reconnect_interval

Specify the reconnect interval in milliseconds.

Must be an integer.

Usage Guidelines Use this command to configure the reconnect interval.

group nrf discovery

Configures NRF discovery group parameters.

Syntax Description `group nrf discovery group_name`

group_name

Specify the discovery group name.

Must be a string.

Usage Guidelines Use this command to configure NRF discovery group parameters. Enters the NRF Discovery Configuration mode.

group nrf discovery service type nrf

Configures the NRF discovery service type.

Syntax Description `group nrf discovery group_name service type nrf nrf-disc service_type`

service_type

Specify the NRF discovery service type.

Must be one of the following:

- **nrf-disc**

Usage Guidelines Use this command to configure the NRF discovery service type.

group nrf discovery service type nrf endpoint-profile

Configures the endpoint profile parameters.

Command Modes Exec > Global Configuration

Syntax Description `group nrf discovery discovery_group service type nrf nrf-disc endpoint-profile endpoint_profile_name { capacity endpoint_capacity | priority endpoint_priority | api-uri-prefix api_uri_prefix | api-root api_string | api-root api_string | uri-scheme uri_scheme}`

api-root *api_string*

Specify the deployment-specific service API prefix that is used within the { apiRoot }.

Must be a string.

api-uri-prefix *api_uri_prefix*

Specify the API URI prefix. If not configured, it takes the standard API name for the service as per the specification.

Must be a string.

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

Default Value: 10.

certificate-name *certificate_name*

Specify the alias name for client certificate.

Must be a string.

client-certificate *client_certificate*

Specify the client certificate in PEM format.

client-key *client_key*

Specify the client private key in PEM format.

name *endpoint_profile_name*

Specify the endpoint profile name.

Must be a string.

priority *endpoint_priority*

Specify the endpoint's priority.

Must be an integer.

Default Value: 1.

uri-scheme *uri_scheme*

Specify the URI scheme.

Must be one of the following:

- http
- https

Default Value: http.

Usage Guidelines

Use this command to configure the endpoint profile parameters.

group nrf discovery service type nrf endpoint-profile endpoint-name

Configures endpoint name.

Command Modes

Exec > Global Configuration

Syntax Description

```
group nrf discovery discovery_group service type nrf nrf-disc
endpoint-profile endpoint_profile_name { priority endpoint_priority | capacity
endpoint_capacity}
```

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

name *endpoint_name*

Specify the endpoint name.

Must be a string.

priority *endpoint_priority*

Specify the priority for the service to select the appropriate profile using the load-balancing logic.

Must be an integer.

Usage Guidelines

Use this command to configure the endpoint name.

group nrf discovery service type nrf endpoint-profile endpoint-name primary ip-address

Configures the IP address and port parameters.

Command Modes Exec > Global Configuration

Syntax Description `group nrf discovery discovery_group service type nrf nrf-disc endpoint-profile endpoint_profile endpoint-name endpoint_name { primary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number] | secondary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number] | tertiary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number]}`

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

port *port_number*

Specify the port number.

Usage Guidelines Use this command to configure the IP address and port parameters.

group nrf discovery service type nrf endpoint-profile endpoint-name secondary ip-address

Configures the IP address and port parameters.

Command Modes Exec > Global Configuration

Syntax Description `group nrf discovery discovery_group service type nrf nrf-disc endpoint-profile endpoint_profile endpoint-name endpoint_name { primary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number] | secondary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number] | tertiary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number]}`

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

port *port_number*

Specify the port number.

Usage Guidelines Use this command to configure the IP address and port parameters.

group nrf discovery service type nrf endpoint-profile endpoint-name tertiary ip-address

Configures the IP address and port parameters.

Command Modes Exec > Global Configuration

Syntax Description `group nrf discovery discovery_group service type nrf nrf-disc endpoint-profile endpoint_profile endpoint-name endpoint_name { primary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number] | secondary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number] | tertiary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number]}`

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

port *port_number*

Specify the port number.

Usage Guidelines Use this command to configure the IP address and port parameters.

group nrf discovery service type nrf endpoint-profile version uri-version

Configures the URI version.

Command Modes Exec > Global Configuration

Syntax Description `group nrf discovery discovery_group service type nrf nrf-disc endpoint-profile endpoint_profile_name version uri_version full-version full_version`

full-version *full_version*

Specify the full URI version in the format *major-version.minor-version.patch-version.[alpha-draft-number]*.

Must be a string.

uri_version

Specify the URI version.

Must be a string in the pattern `v\d`.

Usage Guidelines Use this command to configure the URI version.

group nrf mgmt

Configures the NRF management group parameters.

Syntax Description `group nrf mgmt mgmt_group_name`

mgmt_group_name

Specify the management group name.

Must be a string.

Usage Guidelines Use this command to configure the NRF management group parameters.

group nrf mgmt service type nrf

Configures the NRF management service type.

Syntax Description `group nrf mgmt group_name service type nrf service_name`

service_name

Specify the service name.

Must be one of the following:

- **nnrf-nfm**

Usage Guidelines Use this command to configure the NRF management service type.

group nrf mgmt service type nrf endpoint-profile

Configures the endpoint profile parameters.

Command Modes Exec > Global Configuration

Syntax Description `group nrf discovery discovery_group service type nrf nnrf-disc endpoint-profile endpoint_profile_name { capacity endpoint_capacity | priority endpoint_priority | api-uri-prefix api_uri_prefix | api-root api_string | api-root api_string | uri-scheme uri_scheme }`

api-root *api_string*

Specify the deployment-specific service API prefix that is used within the { apiRoot }.

Must be a string.

api-uri-prefix *api_uri_prefix*

Specify the API URI prefix. If not configured, it takes the standard API name for the service as per the specification.

Must be a string.

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

Default Value: 10.

certificate-name *certificate_name*

Specify the alias name for client certificate.

Must be a string.

client-certificate *client_certificate*

Specify the client certificate in PEM format.

client-key *client_key*

Specify the client private key in PEM format.

name *endpoint_profile_name*

Specify the endpoint profile name.

Must be a string.

priority *endpoint_priority*

Specify the endpoint's priority.

Must be an integer.

Default Value: 1.

uri-scheme *uri_scheme*

Specify the URI scheme.

Must be one of the following:

- http
- https

Default Value: http.

Usage Guidelines

Use this command to configure the endpoint profile parameters.

group nrf mgmt service type nrf endpoint-profile endpoint-name

Configures endpoint name.

Command Modes

Exec > Global Configuration

Syntax Description

```
group nrf discovery discovery_group service type nrf nnrf-disc
endpoint-profile endpoint_profile_name { priority endpoint_priority | capacity
endpoint_capacity}
```

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

name *endpoint_name*

Specify the endpoint name.

Must be a string.

priority *endpoint_priority*

Specify the priority for the service to select the appropriate profile using the load-balancing logic.

Must be an integer.

Usage Guidelines

Use this command to configure the endpoint name.

group nrf mgmt service type nrf endpoint-profile endpoint-name primary ip-address

Configures the IP address and port parameters.

Command Modes Exec > Global Configuration

Syntax Description `group nrf discovery discovery_group service type nrf nrf-disc endpoint-profile endpoint_profile endpoint-name endpoint_name { primary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number] | secondary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number] | tertiary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number]}`

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

port *port_number*

Specify the port number.

Usage Guidelines Use this command to configure the IP address and port parameters.

group nrf mgmt service type nrf endpoint-profile endpoint-name secondary ip-address

Configures the IP address and port parameters.

Command Modes Exec > Global Configuration

Syntax Description `group nrf discovery discovery_group service type nrf nrf-disc endpoint-profile endpoint_profile endpoint-name endpoint_name { primary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number] | secondary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number] | tertiary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number]}`

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

port *port_number*

Specify the port number.

Usage Guidelines Use this command to configure the IP address and port parameters.

group nrf mgmt service type nrf endpoint-profile endpoint-name tertiary ip-address

Configures the IP address and port parameters.

Command Modes Exec > Global Configuration

Syntax Description `group nrf discovery discovery_group service type nrf nrf-disc endpoint-profile endpoint_profile endpoint-name endpoint_name { primary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number] | secondary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number] | tertiary ip-address [ipv4 ipv4_address | ipv6 ipv6_address | port port_number]}`

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

fqdn *fqdn*

Specify the fully qualified domain name.

Must be a string.

ipv4 *ipv4_address*

Specify the IPv4 address.

ipv6 *ipv6_address*

Specify the IPv6 address.

port *port_number*

Specify the port number.

Usage Guidelines Use this command to configure the IP address and port parameters.

group nrf mgmt service type nrf endpoint-profile version uri-version

Configures the URI version.

Command Modes Exec > Global Configuration

Syntax Description `group nrf discovery discovery_group service type nrf nnrf-disc endpoint-profile endpoint_profile_name version uri_version full-version full_version`

full-version *full_version*

Specify the full URI version in the format *major-version.minor-version.patch-version.[alpha-draft-number]*.

Must be a string.

uri_version

Specify the URI version.

Must be a string in the pattern \vd.

Usage Guidelines Use this command to configure the URI version.

profile nf-client nf-type bsf bsf-profile

Configures the BSF profile parameters.

Command Modes Exec > Global Configuration

Syntax Description `profile nf-client nf-type bsf bsf-profile bsf_profile`

bsf_profile_name

Specify the BSF profile name.

Must be a string.

Usage Guidelines Use this command to configure the BSF profile parameters.

profile nf-client nf-type bsf bsf-profile locality

Configures the locality parameters.

Command Modes Exec > Global Configuration

Syntax Description `nf-client nf-type bsf profile nf-client nf-type bsf bsh-profile bsf_profile locality locality`

priority *locality_priority*

Specify the locality priority.

Must be an integer.

Default Value: 65535.

locality_name

Specify the locality name.

Must be a string.

Usage Guidelines Use this command to configure the locality parameters.

profile nf-client nf-type bsf bsf-profile locality service name type

Configures the BSF service type.

Command Modes Exec > Global Configuration

Syntax Description `profile nf-client nf-type bsf chf-profile profile_name locality locality { priority priority | service service_name type service_type}`

type *service_type*

Specify the service type.

Must be one of the following:

- **nbsf-management**

Usage Guidelines Use this command to configure the BSF service type.

profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile

Configures the endpoint profile parameters.

Command Modes Exec > Global Configuration

Syntax Description `group nrf discovery discovery_group service type nrf nnrf-disc endpoint-profile endpoint_profile_name { capacity endpoint_capacity | priority endpoint_priority | api-uri-prefix api_uri_prefix | api-root api_string | api-root api_string | uri-scheme uri_scheme}`

api-root *api_string*

Specify the deployment-specific service API prefix that is used within the { apiRoot }.

Must be a string.

api-uri-prefix *api_uri_prefix*

Specify the API URI prefix. If not configured, it takes the standard API name for the service as per the specification.

Must be a string.

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

Default Value: 10.

certificate-name *certificate_name*

Specify the alias name for client certificate.

Must be a string.

client-certificate *client_certificate*

Specify the client certificate in PEM format.

client-key *client_key*

Specify the client private key in PEM format.

name *endpoint_profile_name*

Specify the endpoint profile name.

Must be a string.

priority *endpoint_priority*

Specify the endpoint's priority.

Must be an integer.

Default Value: 1.

uri-scheme *uri_scheme*

Specify the URI scheme.

Must be one of the following:

- **http**
- **https**

profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile endpoint-name

Default Value: http.

Usage Guidelines Use this command to configure the endpoint profile parameters.

profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile endpoint-name

Configures endpoint name.

Command Modes Exec > Global Configuration

Syntax Description **group nrf discovery** *discovery_group* **service type nrf nnrf-disc endpoint-profile** *endpoint_profile_name* { **priority** *endpoint_priority* | **capacity** *endpoint_capacity* }

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

name *endpoint_name*

Specify the endpoint name.

Must be a string.

priority *endpoint_priority*

Specify the priority for the service to select the appropriate profile using the load-balancing logic.

Must be an integer.

Usage Guidelines Use this command to configure the endpoint name.

profile nf-client nf-type bsf bsf-profile locality service name type endpoint-profile version uri-version

Configures the URI version.

Command Modes Exec > Global Configuration

Syntax Description **group nrf discovery** *discovery_group* **service type nrf nnrf-disc endpoint-profile** *endpoint_profile_name* **version** *uri_version* **full-version** *full_version*

full-version *full_version*

Specify the full URI version in the format *major-version.minor-version.patch-version.[alpha-draft-number]*.

Must be a string.

uri_version

Specify the URI version.

Must be a string in the pattern \d.

Usage Guidelines Use this command to configure the URI version.

profile nf-client nf-type chf chf-profile

Configures the locality for the UDR profile.

Syntax Description `profile nf-client nf-type chf chf-profile chf_profile`

chf_profile_name

Specify the CHF profile name.

Must be a string.

Usage Guidelines Use this command to configure the locality for the CHF profile.

profile nf-client nf-type chf chf-profile locality

Configures the locality for the CHF profile.

Syntax Description `nf-client nf-type chf profile nf-client nf-type chf chf-profile chf_profile
locality locality`

priority priority

Specify the priority for the CHF local configuration."

Must be an integer.

Default Value: 65535.

locality_name

Specify the locality name.

Must be a string.

Usage Guidelines Use this command to configure the locality for the CHF profile.

```
profile nf-client nf-type chf chf-profile locality service name type
```

profile nf-client nf-type chf chf-profile locality service name type

Configures the CHF service type.

Command Modes Exec > Global Configuration

Syntax Description `profile nf-client nf-type chf chf-profile profile_name locality locality { priority priority | service service_name type service_type}`

type service_type

Specify the CHF service type.

Must be one of the following:

- **nchf-spendinglimitcontrol**

Usage Guidelines Use this command to configure the CHF service type.

profile nf-client nf-type chf chf-profile locality service name type endpoint-profile

Configures the endpoint profile parameters.

Command Modes Exec > Global Configuration

Syntax Description `group nrf discovery discovery_group service type nrf nnrf-disc endpoint-profile endpoint_profile_name { capacity endpoint_capacity | priority endpoint_priority | api-uri-prefix api_uri_prefix | api-root api_string | api-root api_string | uri-scheme uri_scheme}`

api-root api_string

Specify the deployment-specific service API prefix that is used within the { apiRoot }.

Must be a string.

api-uri-prefix api_uri_prefix

Specify the API URI prefix. If not configured, it takes the standard API name for the service as per the specification.

Must be a string.

capacity endpoint_capacity

Specify the node capacity for the endpoint.

Must be an integer.

Default Value: 10.

certificate-name *certificate_name*

Specify the alias name for client certificate.

Must be a string.

client-certificate *client_certificate*

Specify the client certificate in PEM format.

client-key *client_key*

Specify the client private key in PEM format.

name *endpoint_profile_name*

Specify the endpoint profile name.

Must be a string.

priority *endpoint_priority*

Specify the endpoint's priority.

Must be an integer.

Default Value: 1.

uri-scheme *uri_scheme*

Specify the URI scheme.

Must be one of the following:

- **http**
- **https**

Default Value: http.

Usage Guidelines

Use this command to configure the endpoint profile parameters.

profile nf-client nf-type chf chf-profile locality service name type endpoint-profile endpoint-name

Configures endpoint name.

Command Modes

Exec > Global Configuration

```
profile nf-client nf-type chf chf-profile locality service name type endpoint-profile version uri-version
```

Syntax Description

```
group nrf discovery discovery_group service type nrf nnrf-disc
endpoint-profile endpoint_profile_name { priority endpoint_priority | capacity
endpoint_capacity}
```

capacity *endpoint_capacity*

Specify the node capacity for the endpoint.

Must be an integer.

name *endpoint_name*

Specify the endpoint name.

Must be a string.

priority *endpoint_priority*

Specify the priority for the service to select the appropriate profile using the load-balancing logic.

Must be an integer.

Usage Guidelines

Use this command to configure the endpoint name.

profile nf-client nf-type chf chf-profile locality service name type endpoint-profile version uri-version

Configures the URI version.

Command Modes

Exec > Global Configuration

Syntax Description

```
group nrf discovery discovery_group service type nrf nnrf-disc
endpoint-profile endpoint_profile_name version uri_version full-version full_version
```

full-version *full_version*

Specify the full URI version in the format *major-version.minor-version.patch-version.[alpha-draft-number]*.

Must be a string.

uri_version

Specify the URI version.

Must be a string in the pattern v\d.

Usage Guidelines

Use this command to configure the URI version.

profile nf-client nf-type udr udr-profile locality

Configures the locality for the UDR profile.

Syntax Description `profile nf-client nf-type udr udr-profile udr_profile locality locality [priority priority | service udr_service]`

priority *priority*

Specify the priority for the UDR local configuration."

Must be an integer.

udr-profile *udr_profile_name*

Specify the UDR profile name."

Must be a string.

Usage Guidelines Use this command to configure the locality for the UDR profile.

profile nf-client nf-type udr udr-profile locality service name type

Configures UDR service type.

Command Modes Exec > Global Configuration

Syntax Description `profile nf-client nf-type udr udr-profile profile_name locality locality { priority priority | service service_name type service_type}`

type *service_type*

Specify the service type.

Must be one of the following:

- **nudr-dr**

Usage Guidelines Use this command to configure the UDR service type.

profile nf-pair nf-type

Configures the NF type for the NF client pair configuration.

Syntax Description `profile nf-pair nf-type nf_type nrf-discovery-group group_name { subscription-enabled { false | true } | subscription-enabled { false | true } | subscription-extension extension_duration}`

nrf-discovery-group *group_name*

Specify the NRF discovery group name.

subscription-enabled { false | true}

Specify to enable or disable the subscription to NRF for NF change.

Must be one of the following:

- false
- true

Default Value: false.

subscription-extension *extension_duration*

Specify the duration for which the subscription must be extended in minutes.

Must be an integer.

Default Value: 60.

nf_type

Specify the NF type.

Must be one of the following:

- BSF
- CHF
- UDR

Usage Guidelines

Use this command to configure the NF type for the NF client pair configuration.

profile nf-pair nf-type locality

Configures the locality parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
profile nf-pair nf-type nf_type nrf-discovery-group group_name locality [
client client_locality | preferred-server preferred_server | geo-server geo_server
]
```

client *client_locality*

Specify the locality of the client.

geo-server *geo_service_locality*

Specify the geo-server locality information.

Must be a string.

preferred-server *preferred_server_locality*

Specify the preferred server locality information.

Must be a string.

Usage Guidelines

Use this command to configure the locality parameters.

service-registration profile

Configures the network function profile parameters to enable discovery of the registered NFs, and when the discovery fails, the discovery is attempted on the local configuration.

Command Modes

Exec > Global Configuration

Syntax Description

```
service-registration profile { allowed-plmns { mobile_country_code | mobile_network_code } | capacity profile_capacity | instance-id instance_id_pcf | locality pcf_location | nf-status nf_service_status | pcf-info { dnn-list | supi-ranges } | plmn-list { mobile_country_code | mobile_network_code } | priority profile_priority | snssais { slice_service_type | sd service_differentiator } }
```

capacity *profile_capacity*

Specify the PCFs profile's capacity.

Must be an integer.

fqdn *fqdn*

Specify the fully qualified domain name of the PCF. For example, pcf.5gc.mnc123.mcc089.pub.3gppnetwork.org.

Must be a string.

instance-id *pcf_instance_id*

Specify the PCF instance ID.

Must be a string.

locality *pcf_location*

Specify the location of the PCF.

Must be a string.

capacity *profile_capacity*

Specify the PCFs profile's capacity.

Must be an integer.

fqdn fqdn

Specify the fully qualified domain name of the PCF. For example, pcf.5gc.mnc123.mcc089.pub.3gppnetwork.org.

Must be a string.

instance-id pcf_instance_id

Specify the PCF instance ID.

Must be a string.

locality pcf_location

Specify the location of the PCF.

Must be a string.

priority profile_priority

Specify the PCF profile's priority.

Must be an integer.

nf_service_status

Specify the PCF service status.

Must be one of the following:

- REGISTERED
- UNDISCOVERABLE

Default Value: REGISTERED.

Usage Guidelines Use this command to configure the network function profile.

service-registration profile allowed-plmns

Configures PLMNs allowed to access the network function.

Command Modes Exec > Global Configuration

Syntax Description `service-registration profile allowed-plmns { mobile_country_code | mobile_network_code }`

mobile_country_code

Specify the Mobile Country Code.

Must be a string in the pattern `\d{3}`.

mobile_network_code

Specify the Mobile Network Code.

Must be a string in the pattern `\d{2,3}`.

Usage Guidelines

Use this command to configure PLMNs allowed to access the network function.

service-registration profile pcf-info

Configures the PCF parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
service-registration profile pcf-info { dnn-list dnn_list_name | supi-ranges
supi_range_id [ start start_value | pattern range_pattern | end end_value ] }
```

dnn_list

Specify the DNNs supported by the PCF.

Must be a string.

Usage Guidelines

Use this command to configure PCF parameters.

service-registration profile pcf-info supi-ranges

Configures the list of SUPI ranges, which the PCF instance serves.

Command Modes

Exec > Global Configuration

Syntax Description

```
service-registration profile pcf-info supi-ranges supi_range_id [ start
start_value | pattern range_pattern | end end_value ]
```

end end_value

Specify the last value of the SUPI range.

Must be a string in the pattern `[0-9]+`.

pattern range_pattern

Specify the regular expression according to the ECMA-262 dialect that represents the set of SUPIs belonging to the specified range.

Must be a string.

start start_value

Specify the first value of the SUPI range.

Must be a string in the pattern `[0-9]+`.

supi_range_id

Specify the SUPI range identifier.

Must be a string.

Usage Guidelines Use this command to configure the list of SUPI ranges, which the PCF instance serves.

service-registration profile plmn-list

Configures the PLMNs of the network function.

Command Modes Exec > Global Configuration

Syntax Description `service-registration profile plmn-list { mobile_country_code | mobile_network_code }`

mobile_country_code

Specify the Mobile Country Code.

Must be a string in the pattern `\d{3}`.

mobile_network_code

Specify the Mobile Network Code.

Must be a string in the pattern `\d{2,3}`.

Usage Guidelines Use this command to configure the PLMNs of the network function.

service-registration profile snssais

Configures the S-NSSAIs of the network function.

Command Modes Exec > Global Configuration

Syntax Description `service-registration profile snssais { slice_service_type | sd service_differentiator }`

sd slice_differentiator

Specify the Slice Differentiator value.

Must be a string.

slice_service_type

Specify the Slice or Service Types value.

Must be an integer in the range of 0-255.

Usage Guidelines Use this command to configure the S-NSSAIs of the network function.

service-registration services

Configures the service parameters.

Command Modes Exec > Global Configuration

Syntax Description `service-registration services services_name`

api-version *api_version*

Specify the API version.

Must be one of the following:

- 1.0.0
- 1.0.2

Default Value: 1.0.0.

service_name

Specify the service name.

Must be one of the following:

- amfService
- smfService

Usage Guidelines Use this command to configure the service parameters.

service-registration services allowed-nssais

Command Modes Exec > Global Configuration

Syntax Description `service-registration services service_name allowed-nssais { slice_service_type | sd service_differentiator }`

sd slice_differentiator

Specify the Slice Differentiator value.

Must be a string.

slice_service_type

Specify the Slice or Service Types value.

Must be an integer in the range of 0-255.

Usage Guidelines Use this command to configure the S-NSSAIs allowed of the NF service instance.

service-registration services allowed-plmns

Configures the PLMNs allowed to access the NF service instance.

Command Modes

Exec > Global Configuration

Syntax Description

service-registration services *service_name* **allowed-plmns** { *mobile_country_code* | *mobile_network_code* }

mobile_country_code

Specify the Mobile Country Code.

Must be a string in the pattern `\d{3}`.

mobile_network_code

Specify the Mobile Network Code.

Must be a string in the pattern `\d{2,3}`.

Usage Guidelines

Use this command to configure the PLMNs allowed to access the NF service instance.

show subscriber

Displays subscriber session information.

Command Modes

Exec

Syntax Description

show subscriber [**imsi** *imsi* | **msisdn** *msisdn*]

imsi *imsi*

Specify the IMSI.

Must be a string.

msisdn *msisdn*

Specify the MSISDN.

Must be a string.

Usage Guidelines

Use this command to view subscriber session information.



CHAPTER 9

Mobile Policy TLS Commands

- [pcf-tls ca-certificates](#), on page 109
- [pcf-tls certificates](#), on page 109

pcf-tls ca-certificates

Configures the certificate name and data configuration.

Command Modes Exec > Global Configuration

Syntax Description **ca-certificates** *certificate_alias_name* **cert-data** *certificate_data*

cert-data *certificate_data*

Specify the certificate data in PEM format.

Must be a string.

certificate_alias_name

Specify the alias name for the certificate.

Must be a string.

Usage Guidelines Use this command to configure the certificate name and data configuration.

pcf-tls certificates

Configures the certificate name, data, and key parameters.

Command Modes Exec > Global Configuration

Syntax Description **certificates** *certificate_alias_name* **cert-data** *certificate_data* **private-key** *certificate_private_key*

cert-data *certificate_data*

Specify the certificate data in PEM format.

Must be a string.

private-key certificate_private_key

Specify the certificate private key in PEM format.

Must be a string.

certificate_alias_name

Specify the alias name for the certificate.

Must be a string.

Usage Guidelines

Use this command to configure the certificate name, data, and key parameters.



CHAPTER 10

Mobile Policy Types Commands

- [api unified](#), on page 111
- [engine](#), on page 112
- [engine environment](#), on page 113
- [engine grpc](#), on page 113
- [engine install-features](#), on page 114
- [engine n7](#), on page 114
- [engine patching patch](#), on page 115
- [engine properties](#), on page 115
- [engine resources limits](#), on page 116
- [engine resources requests](#), on page 116
- [external-services](#), on page 117
- [label cdl-layer](#), on page 117
- [label oam-layer](#), on page 118
- [label protocol-layer](#), on page 118
- [label service-layer](#), on page 119

api unified

Configures Engine API parameters.

Command Modes Exec > Global Configuration

Syntax Description `api unified { [engine-group engine_group] [externalIPs ip_address] }`

engine-group *engine_group*

Specify the default engine group to receive API traffic.

external-port *port_number*

Specify the API service port number.

Must be an integer.

externalIPs *ip_address*

Specify external IP address for the API service.

Usage Guidelines

Use this command to configure Engine API parameters.

engine

Configures the engine parameters.

Command Modes

Exec > Global Configuration

Syntax Description

```
engine engine_name [ boot-config engine_name | config-lock { false | true } |
environment environment_variables | grpc grpc_configuration_options |
install-features application_features | patching patching_jars | properties
system_properties | release-train release_train_image | replicas replica_count |
repository helm_repository | subversion-config-url subversion_config_url |
subversion-run-url subversion_run_url | tracing-service-name tracing_server |
unified-api-replicas unified_api_count ]
```

boot-config *engine_name*

Specify the engine name to boot the initial engine group.

config-lock { false | true }

Specify to enable or disable the configuration lock.

Must be one of the following:

- **false**
- **true**

Default Value: false.

grouping *engine_group_name*

Specify the engine group's name.

Must be a string in the pattern [a-zA-Z][a-zA-Z0-9]*.

release-train *release_train_image*

Specify the release train image.

Must be a string.

replicas *replica_count*

Specify the replica count.

Must be an integer.

Default Value: 1.

repository *helm_repository*

Specify the Helm repository.

subversion-config-url *subversion_config_url*

Specify the subversion configuration URL.

Must be a string.

subversion-run-url *subversion_run_url*

Specify the subversion run URL.

Must be a string.

tracing-service-name *tracing_server_name*

Specify the tracing server name used for Policy Engine.

Must be a string.

Usage Guidelines Use this command to configure the engine parameters.

engine environment

Configures the environment variables exposed to engine-app pods.

Command Modes Exec > Global Configuration

Syntax Description **engine** *engine_name* **environment** *name* **value** *value*

name

Specify the property/environment name.

Must be a string.

value value

Specify the value for the environment.

Must be a string.

Usage Guidelines Use this command to configure the environment variables exposed to engine-app pods.

engine grpc

Configures the gRPC parameters.

Command Modes Exec > Global Configuration

Syntax Description `engine engine_name grpc [externalIPs external_ip_address | port grpc_port_number]`

externalIPs external_ip_address

Specify the external IP address.

port grpc_port_number

Specify the gRPC port number.

Must be an integer.

Usage Guidelines Use this command to configure the gRPC parameters.

engine install-features

Configures the installation feature parameters.

Command Modes Exec > Global Configuration

Syntax Description `engine engine_name install-features { policy-builder policy_builder_name | policy-server policy_server_name }`

policy-builder policy_builder_name

Specify the policy builder feature to be installed.

Must be a string.

policy-server policy_server_name

Specify the policy server feature feature to be installed.

Must be a string.

Usage Guidelines Use this command to configure the feature parameters.

engine n7

Configures the n7 interface engine configuration parameters.

Command Modes Exec > Global Configuration

Syntax Description `n7 defaultBearerUpliftAllowed defaultBearer_uplift_allowed disableCombinedN7Notify { false | true }`

defaultBearerUpliftAllowed defaultBearer_uplift_allowed

Specify the number of times defaultbearer uplift must be allowed during the course of Rx session.

Must be an integer.

Default Value: 1.

disableCombinedN7Notify { false | true}

Specify whether to send combined n7 notify request having default and dedicated bearer detail, or to send separate n7 notify requests for default and dedicated bearer.

Must be one of the following:

- **false**
- **true**

Default Value: false.

Usage Guidelines Use this command to configure the n7 interface engine configuration parameters.

engine patching patch

Configures the patching parameters.

Command Modes Exec > Global Configuration

Syntax Description **engine** *engine_name* **patching patch** *patch_id* [[**jar** *jar_to_patch*] [**version** *jar_version_number*]]

jar *jar_to_patch*

Specify the jar to patch.

Must be a string.

version *jar_version_number*

Specify the version number of jar. Changes every time a new patch is uploaded.

Must be an integer.

Default Value: 1.

patch_id

Specify the ID of the patch to apply.

Must be a string.

Usage Guidelines Use this command to configure the patching parameters.

engine properties

Configures the system properties passed to the application.

Command Modes Exec > Global Configuration

Syntax Description **engine** *engine_name* **properties** *name* **value** *value*

name *name*

Specify the property/environment name.

Must be a string.

value *value*

Specify the value for the environment.

Must be a string.

Usage Guidelines Use this command to configure the system properties passed to the application.

engine resources limits

Configures the resource request parameters.

Command Modes Exec > Global Configuration

Syntax Description **engine** *engine_name* **resources limits** { [**cpu** *cpu_limit*] [**memory** *memory_limit*] }

cpu *cpu_limit*

Specify the CPU limit. If not specified, the default value is set to 18.

Must be an integer in the range of 5-16.

Default Value: 14.

memory *memory_limit*

Specify the memory limit. If not specified, the default value is set to 20Gi.

Must be a string.

Default Value: 20Gi.

Usage Guidelines Use this command to configure the resource request parameters.

engine resources requests

Configures the resource request parameters.

Command Modes Exec > Global Configuration

Syntax Description **engine** *engine_name* **resources requests** { [**cpu** *cpu_request*] [**memory** *memory_request*] }

cpu *cpu_request*

Specify the CPU request.

Must be an integer in the range of 1-5.

Default Value: 5.

memory *memory_request*

Specify the memory request.

Must be a string.

Default Value: 10Gi.

Usage Guidelines Use this command to configure the resource request parameters.

external-services

Configures access to external services.

Command Modes Exec > Global Configuration

Syntax Description **external-services K8 service name** *service_name* [**ips** *ip_address* | **port** *port_number*]

K8 Service name *service_name*

Specify the Kubernetes or the external service name.

Must be a string of 1-63 characters in the k8-svc-name pattern. For information on the k8-svc-name pattern, see the Input Pattern Types section.

ips *ip_address*

Specify the IP address of the external service.

port *port_number*

Specify the port number of the external service.

Usage Guidelines Use this command to configure the access to external services.

label cdl-layer

Configures the CDL pods node affinity label.

Command Modes Exec > Global Configuration

Syntax Description **cdl-layer** { **key** *label_key* | **value** *label_value* }

key *label_key*

Specify the label key.

Must be a string.

value *label_value*

Specify the label value.

Must be a string.

Usage Guidelines Use this command to configure the CDL.

label oam-layer

Configures the OAM pods node affinity label.

Command Modes Exec > Global Configuration

Syntax Description `oam-layer { key label_key | value label_value}`

key *label_key*

Specify the label key.

Must be a string.

value *label_value*

Specify the label value.

Must be a string.

Usage Guidelines Use this command to configure the OAM pods node affinity label.

label protocol-layer

Configures the protocol layer pod node affinity label.

Command Modes Exec > Global Configuration

Syntax Description `protocol-layer { key label_key | value label_value}`

key *label_key*

Specify the label key.

Must be a string.

value *label_value*

Specify the label value.

Must be a string.

Usage Guidelines Use this command to configure the protocol layer pod node affinity label.

label service-layer

Configures the service pods node affinity label.

Command Modes Exec > Global Configuration

Syntax Description `service-layer { key label_key | value label_value}`

key *label_key*

Specify the label key.

Must be a string.

value *label_value*

Specify the label value.

Must be a string.

Usage Guidelines Use this command to configure the service pods node affinity label.

label service-layer



CHAPTER 11

Ports and Services Reference Information

- [Ports and Services, on page 121](#)

Ports and Services

PCF uses different ports for communication purposes. The following table describes the default ports and the associated services.

Table 1: Ports and Services

Port	Service	Usage
22	SSH	SMI uses this port to communicate with the virtual machines.
80	HTTP	SMI uses this port for providing Web access to CLI, Documentation, and TAC.
443	SSL/HTTP	SMI uses this port for providing Web access to CLI, Documentation, and TAC.
2024	SSH	SMI accesses the Confdd CLI through this port.
3868	TCP	PCF uses this port as the default Diameter Endpoint on a public port.
6443	HTTP	SMI uses this port to communicate with the Kubernetes API server.
8080	HTTP	PCF uses this port to communicate with the Keep Alive API Interface on a public network.
9082	HTTP	PCF uses this port to access the SBI Interface on a public network. The Keepalive monitors the health of the container on this port. If the port is not accessible, then the kubectl restarts the container to restore the service.
9299	HTTP	SMI uses this port to communicate with the Prometheus Service.
9885	TCP	Default port that operates as the PCF Service gRPC endpoint on a private network.
10250	SSL/HTTP	SMI uses this port to communicate with Kubelet.

Port	Service	Usage
10256	HTTP	SMI uses this port to interact with the Kube proxy.