



Diameter Endpoint

- [Feature Summary and Revision History, on page 1](#)
- [Feature Description, on page 1](#)
- [Configuring the Node for the Diameter Endpoint Pod, on page 2](#)

Feature Summary and Revision History

Summary Data

Table 1: Summary Data

Applicable Products or Functional Area	5G-PCF
Applicable Platform(s)	SMI
Feature Default Setting	Enabled – Always-On
Related Changes in this Release	Not Applicable
Related Documentation	Not Applicable

Revision History

Table 2: Revision History

Revision Details	Release
First Introduced.	Pre 2020.01.0

Feature Description

You can enable the Diameter endpoint to dynamically create pods on a designated node or host. This feature might be a requirement when you want to ensure that the nodes are meeting specific security and regulatory parameters, or the node is closer to the datacenter in terms of geographical proximity. The node affinity determines the node where PCF created the Diameter endpoint pods, which are based on the affinity towards

a node or group of nodes. Node affinity is a set of rules that allows you to define the custom labels on nodes and specify the label selectors within the pods. Based on these rules, the scheduler determines the location where the pod can be placed.



Note If you do not specify a node, then the Kubernetes scheduler determines the node where the Diameter endpoint creates a pod.

Configuring the Node for the Diameter Endpoint Pod

This section describes how to specify the node or host where the Diameter endpoint must spawn the pod. To specify the node where you want Diameter endpoint to spawn the pod, use the following configuration:

```
config
  diameter group diameter_group_name
  mode server server_name
  stack stack_name
  application application_name
  bind-ip host_address
  fqdn fqdn_address
  realm realm_address
  node-host node_host_address
end
```

NOTES:

- **diameter group** *diameter_group_name* – Specifies the Diameter group name.
- **mode server** *server_name* – Specifies the server name that operates as the mode server.
- **stack** *stack_name* – Specifies the stack name.
- **application** *application_name* – Specifies the application name.
- **bind-ip** *host_address* – Specifies the host address of the binding database.
- **fqdn** *fqdn_address* – Specifies the FQDN address.
- **realm** *realm_address* – Specifies the realm address.
- **node-host** *node_host_address* – Specifies the host IP address of the node.

Sample Configuration

The following is a sample configuration of the node configuration.

```
mode server
  stack cicdsite
  application rx
  bind-ip 192.0.2.18
  realm cisco.com
  node-host for-node-2a-worker39e1587354h
exit
```