Cisco Prime License Manager CLI Commands

- Introduction, page 1
- license file, page 1
- license management change user name, page 2
- license management reset user password, page 2
- license management list users, page 3
- license management product re-register all, page 3
- license management reset, page 4
- license management security update, page 4
- license management service, page 4
- license management show system, page 5
- license management system remove, page 5

Introduction

The commands in this section are specific to Cisco Prime License Manager. For platform-specific commands, see the Command Line Interface Guide for Cisco Unified Communications Solutions.

license file

This command asks to select a license file from a list.

license file {**diagnose**| **get**}

Syntax Description

Parameters	Description
diagnose	Prints diagnostic information of the selected file.

Parameters	Description
get	Creates a TAR file of the license file(s) on the system and transfers the TAR file to a remote area.

Command Modes Administrator (admin:)

Requirements

Command privilege level: 1

Allowed during upgrade: Yes

Applies to: Enterprise License Manager, Cisco Prime License Manager

license management change user name

This command takes parameters interactively and changes the username of the administrator.

license management change user {**name**}

Syntax Description

Parameters	Description
name	Specifies the administrator username.

Command Modes Administrator (admin:)

Requirements

Command privilege level: 1

Allowed during upgrade: Yes

Applies to: Enterprise License Manager, Cisco Prime License Manager

license management reset user password

This command takes parameters interactively and changes the username of the administrator.

license management reset user {**password**}

Syntax Description

Parameters	Description
password	Specifies the administrator password.

Command Modes Administrator (admin:)

Requirements

Command privilege level: 1

Allowed during upgrade: Yes

Applies to: Cisco Prime License Manager

license management list users

This command lists the administrative users.

license management list users

Command Modes Administrator (admin:)

Requirements

Command privilege level: 1

Allowed during upgrade: Yes

Applies to: Enterprise License Manager, Cisco Prime License Manager

license management product re-register all

This command forces re-registration of all product instances associated with this Enterprise License Manager/Cisco Prime License Manager server. This command may take some time for re-registration and synchronization with all product instances to complete.

license management product re-register all

Command Modes Administrator (admin:)

Requirements

Command privilege level: 1

Allowed during upgrade: Yes

Applies to: Enterprise License Manager, Cisco Prime License Manager

license management reset

This command resets the identity, store data, and essentially removes all the installed licenses. It also restarts the Cisco Prime License Manager server process to make the changes effective.

license management reset {**identity**| **registration**}

Syntax Description

Parameters	Description
identity	Resets the identity
registration	Resets the registration

Command Modes

Administrator (admin:)

Requirements

Command privilege level: 1

Allowed during upgrade: Yes

Applies to: Enterprise License Manager, Cisco Prime License Manager

license management security update

This command downloads Cisco Prime License Manager security update from the specified remote server location and installs the contents of the specified security update file.

license management security update

Requirements

Command privilege level: 1

Allowed during upgrade: Yes

Applies to: Enterprise License Manager, Cisco Prime License Manager

license management service

This command activates or deactivates a given service on the Cisco Prime License Manager server.

license management service {**activate**| **deactivate**}

Syntax Description

Parameters	Description
activate	Activates a given service on the Cisco Prime License Manager server.
deactivate	Deactivates a given service on the Cisco Prime License Manager server.

Command Modes Administrator (admin:)

Requirements

Command privilege level: 1

Allowed during upgrade: Yes

Applies to: Enterprise License Manager, Cisco Prime License Manager

license management show system

This command lists the administrative users.

license management show system

Command Modes Administrator (admin:)

Requirements

Command privilege level: 1

Allowed during upgrade: Yes

Applies to: Enterprise License Manager, Cisco Prime License Manager

license management system remove

This command allows you to remove an unused Cisco Prime License Manager instance from a coresident deployment.

license management system remove

Command Modes Administrator (admin:)

Requirements

Command privilege level: 0

Allowed during upgrade: Yes

Applies to: Cisco Prime License Manager