



Partition

Partitions divide the route plan into logical subsets. These subsets include organization, location, and type of call.

Use the following procedures to add, update, copy, or delete a partition:

- Adding a Partition, page 18-1
- Deleting a Partition, page 18-2

Adding a Partition

The following procedure describes how to add a partition.

Procedure

- Step 1** Open Cisco CallManager Administration.
- Step 2** Select **Route Plan > Partition** in the menu bar.
- Step 3** Enter a name in the Partition Name field. The name can consist of up to 50 alphanumeric characters, and can contain any combination of spaces, periods (.), hyphens (-), and underscore characters (_). Each partition name must be unique to the route plan.

**Timesaver**

Use concise and descriptive names for your partitions. The CompanynameLocationCalltype format usually provides a sufficient level of detail and is short enough to enable you to quickly and easily identify a partition. For example, CiscoDallasMetroPT identifies a partition for toll free inter-LATA (Local Access and Transport Area) calls from the Cisco office in Dallas.

- Step 4** Enter a description in the Description field. The description can consist of up to 50 alphanumeric characters, and can contain any combination of spaces, periods (.), hyphens (-), and underscore characters (_). If you do not enter a description, the partition name is automatically entered in this field.
- Step 5** Click **Insert** to add the new partition. The new partition name is added to the partition list on the left side of the page, and the message “Status: Insert completed” is displayed.
- Step 6** To add more partitions, click **New** and repeat Steps 3 through 5.
-

Related Procedures

- Deleting a Partition, page 18-2

Deleting a Partition

The following procedure describes how to delete a partition.

Procedure

- Step 1** Open Cisco CallManager Administration.
- Step 2** Select **Route Plan > Partition** in the menu bar.
- Step 3** Select a name in the partition list on the left side of the page.
- Step 4** Click **Delete** to remove the partition.

**Caution**

Check carefully to ensure that you are deleting the correct partition before initiating this action. Deleted partitions cannot be recovered. If a partition is accidentally deleted, it must be rebuilt.

- Step 5** A dialog box appears warning you that deleting this partition cannot be undone.
- Step 6** Click **OK** to delete the partition, or click **Cancel** to cancel the action. If you click **OK**, the partition is deleted and the message “Status: Ready” is displayed.
- Step 7** Repeat Steps 3 through 7 to delete other partitions.
-

Related Procedures

- Adding a Partition, page 18-1

