



CHAPTER 30

Deleting Managers/Assistants

You can use Cisco Unified Communications Manager Bulk Administration (BAT) to delete a specific manager-assistant association from the Cisco Unified Communications Manager database. For example, the assistant with the user ID, *jmorgan*, is assigned to two managers with user IDs, *rcraig* and *dbaker*. If you want to change the manager-assistant association, so the assistant, *jmorgan* is only assigned to *rcraig*, you can delete the *jmorgan-dbaker* association by creating a CSV data file with the following entry:

Example

```
jmorgan,dbaker
```

Deleting Manager-Assistant Associations from Cisco Unified Communications Manager

If you want to delete a manager or an assistant from all manager-assistant associations, see the following sections:

- [Deleting Managers from Cisco Unified Communications Manager, page 31-1](#)
- [Deleting Assistants from Cisco Unified Communications Manager, page 32-1](#)

To delete specific manager-assistant associations from Cisco Unified Communications Manager, use this procedure.

Before You Begin

You must have a CSV data file that contains the user IDs for the specific managers and assistants associations that you want to delete. See [Chapter 28, “Working with Cisco Unified Communications Manager Assistant”](#).

Procedure

-
- Step 1** Choose **Bulk Administration > Managers/Assistants > Delete Managers/Assistants**. The Delete Managers/Assistants Configuration window displays.
 - Step 2** In the **File Name** field, choose the CSV file that you created for this type of bulk transaction.
 - Step 3** Choose the type of deletion:
 - **Delete associated assistants for one manager**
 - **Delete associated managers for one assistant**

- Step 4** In the Job Information area, enter the Job description.
- Step 5** To delete the managers/assistants immediately, click the **Run Immediately** radio button or, to delete the managers/assistants at a later time, click Run Late.
- Step 6** Click **Submit** to create a job for deleting the required managers/assistants associations.
- Step 7** To schedule and/or activate this job, use the Job Scheduler option in the Bulk Administration main menu.
For more information on jobs, see the [Chapter 63, “Scheduling Jobs.”](#)
For information on log files, see [“BAT Log Files” section on page 64-3.](#)
-

Additional Topics

See the [“Related Topics” section on page 30-2.](#)

Related Topics

- [Deleting Managers from Cisco Unified Communications Manager, page 31-1](#)
- [Deleting Assistants from Cisco Unified Communications Manager, page 32-1](#)