



# CHAPTER 17

## TLS Peer Subjects

---

TLS peer subject configuration enables you to create and modify peer subjects that you can associate to a transport listener.

### Finding TLS Peer Subjects

Because you might have several TLS peer subjects in your network, Cisco Unified Presence lets you locate specific TLS peer subjects on the basis of specific criteria. Use the following procedure to locate TLS peer subjects.

**Note**

During your work in a browser session, the cookies on the client machine store your find/list search preferences. If you navigate to other menu items and return to this menu item, or if you close the browser and then open a new browser window, the system retains your Cisco Unified Presence search preferences until you modify your search.

---

**Procedure**

---

**Step 1** Choose Cisco Unified Presence > **Security** > **TLS Peer Subjects**.

The Find and List TLS Peer Subjects window displays. Records from an active (prior) query may also display in the window.

**Step 2** To find all records in the database, ensure the dialog box is empty; go to [Step 3](#).

To filter or search records

- From the drop-down list box, choose a search pattern.
- Specify the appropriate search text, if applicable.

**Note**

To add additional search criteria, click the + button. When you add criteria, the system searches for a record that matches all criteria that you specify. To remove criteria, click the – button to remove the last added criterion or click the **Clear Filter** button to remove all added search criteria.

---

**Step 3** Click **Find**.

All matching records display. You can change the number of items that display on each window by choosing a different value from the Rows per Page drop-down list box.




---

**Note** You can delete multiple records from the database by checking the check boxes next to the appropriate record and clicking **Delete Selected**. You can delete all configurable records for this selection by clicking **Select All** and then clicking **Delete Selected**.

---

**Step 4** From the list of records that display, click the link for the record that you want to view.




---

**Note** To reverse the sort order, click the up or down arrow, if available, in the list header.

---

The window displays the item that you choose.

---

#### Additional Information

See the [“Related Topics”](#) section on page 17-3.

## Configuring a TLS Peer Subject

This section describes how to add or update TLS peer subjects in the Cisco Unified Presence database.

#### Procedure

---

**Step 1** Perform one of the following tasks:

- To add a TLS peer subject, choose Cisco Unified Presence > **Security** > **TLS Peer Subjects** and click **Add New**.
- To update a TLS peer subject, find the TLS peer subject by using the procedure in the [“Finding TLS Peer Subjects”](#) section on page 17-1.

The TLS Peer Subject Configuration window displays.

**Step 2** Enter the appropriate settings as described in [Table 17-1](#).




---

**Note** You must restart the SIP proxy server before any changes that you make to TLS peer subjects take effect. To restart the proxy server, choose Cisco Unified Presence > **Proxy Server** > **Settings**. For more information, see [Proxy Server Settings](#).

---

**Step 3** To save the data, click the **Save** icon that displays in the tool bar in the upper, left corner of the window (or click the **Save button** that displays at the bottom of the window).

---

#### Additional Information

See the [“Related Topics”](#) section on page 17-3.

# TLS Peer Subject Configuration Settings

Table 17-1 describes the TLS peer subject configuration settings. For related procedures, see the “Related Topics” section on page 17-3.

**Table 17-1** TLS Peer Subject Configuration Settings

Field	Description
Peer Subject Name	This parameter specifies the unique name of the TLS peer subject.
Description	This parameter specifies a description of this TLS peer subject.

## Deleting a TLS Peer Subject

This section describes how to delete a TLS peer subject.

### Procedure

**Step 1** Find the TLS peer subject by using the procedure in the “Finding TLS Peer Subjects” section on page 17-1.

**Step 2** From list of matching records, choose the TLS peer subject that you want to delete.



**Note** You must restart the SIP proxy server before any changes that you make to TLS peer subjects take effect. To restart the proxy server, choose Cisco Unified Presence > **Proxy Server** > **Settings**. For more information, see [Proxy Server Settings](#).

**Step 3** To delete the TLS peer subject, click the **Delete Selected Item** icon that displays in the tool bar in the upper, left corner of the window (or click the **Delete Selected** button that displays at the bottom of the window).

If the TLS peer subject is not in use, Cisco Unified Presence deletes it. If it is in use, a message displays.

### Additional Information

See the “Related Topics” section on page 17-3.

## Related Topics

- [Finding TLS Peer Subjects](#), page 17-1
- [Configuring a TLS Peer Subject](#), page 17-2
- [Deleting a TLS Peer Subject](#), page 17-3

