



Plug-in Configuration

Application plug-ins extend the functionality of Cisco Unified Presence.

This section contains the following topics:

- [Installing Plug-ins, page 38-1](#)
- [Updating the Plug-in URL, page 38-2](#)
- [Update Plug-in URL Configuration Settings, page 38-2](#)

Installing Plug-ins



Tip

Before you install any plug-ins, disable all intrusion detection or antivirus services that run on the server where you plan to install the plug-in.

Perform the following procedure to install any plug-in.

Procedure

Step 1 Choose **Application > Plugins**.

The Find and List Plugins window displays. Records from an active (prior) query may also display in the window.

Step 2 To find all records in the database, ensure the dialog box is empty; go to [Step 3](#).

To filter or search records

- From the first drop-down list box, choose a search parameter.
- From the second drop-down list box, choose a search pattern.
- Specify the appropriate search text, if applicable.



Note

To add additional search criteria, click the + button. When you add criteria, the system searches for a record that matches all criteria that you specify. To remove criteria, click the – button to remove the last added criterion or click the **Clear Filter** button to remove all added search criteria.

- Step 3** Click **Find**.
 - Step 4** Click the plug-in name that you want to install.
 - Step 5** To download the plug-in, click the **Download** link.
 - Step 6** Follow the instructions in the installation wizard to complete the installation.
-

Related Topics

- [Plug-in Configuration, page 38-1](#)
- [Updating the Plug-in URL, page 38-2](#)

Updating the Plug-in URL

During the Cisco Unified Presence install process, records that are added to the Plugins table specify the URLs that the Administration applications use to build the Application drop-down menu. The domain name server (DNS) provides the basis for the URL that is constructed at installation time. If the DNS changes, the URL does not get updated.

Perform the following procedure to update the URL of the Plug-in URL.

Procedure

-
- Step 1** Choose **Application > Plugins**.
The Find and List Plugins window displays.
 - Step 2** From the drop-down list boxes, choose the Plugin name and the Plugin type.
 - Step 3** Click the Plugin name that you want to update.
The Update Plugin URL window displays.
 - Step 4** Enter the URL in the Custom URL field.
 - Step 5** To update and save the URL, click the **Save** icon that displays in the tool bar in the upper, left corner of the window (or click the **Save button** that displays at the bottom of the window).
-

Related Topics

- [Plug-in Configuration, page 38-1](#)
- [Installing Plug-ins, page 38-1](#)

Update Plug-in URL Configuration Settings

[Table 38-1](#) describes the update plug-in URL configuration settings.

Table 38-1 Update Plug-in URL Configuration Settings

Field	Description
Plugin Name	From the drop-down list box, choose the Plugin Name for which you are changing the URL.
Plugin Type	From the drop-down list box, choose the Plugin Type for which you are changing the URL; for example, application or installation.
URL	The URL automatically displays.
Custom URL	Use only alphanumeric characters for the custom URL.
Show Plugin on User Option Pages	Check this check box to show the plug-in on the user option window.

