ılıılı cısco.

Release Notes for the Ultra Cloud Serving Gateway Control Plane Function Version 2023.01.4

First Published: January 25, 2023 Last Updated: April 25, 2023

Introduction

This Release Notes identifies changes and issues related to this software release.

Release Lifecycle Milestones

Release Lifecycle Milestone	Milestone	Date
First Customer Ship	FCS	31-Jan-2023
End of Life	EoL	31-Jan-2023
End of Software Maintenance	EoSM	31-Jul-2024
End of Vulnerability and Security Support	EoVSS	31-Jul-2024
Last Date of Support	LDoS	31-Jul-2025

These milestones and the intervals between them are defined in the <u>Cisco Ultra Cloud Core (UCC) Software Release Lifecycle Product</u> <u>Bulletin</u> available on cisco.com.

Release Package Version Information

Software Packages	Version
ccg.2023.01.3.SPA.tgz	2023.01.3
NED package	ncs-5.6.1-ccg-nc-2023.01.4
NSO	5.6.1

Descriptions for the various packages provided with this release are available in the <u>Release Package Descriptions</u> section.

NOTE: The ccg.version>.SPA.tgz software package is common to both the cnSGWc and SMF 5G Network Functions (NF). The deployment and configuration procedure determines the NF deployment.

Verified Compatibility

Products	Version
Ultra Cloud Core SMI	2023.01.1.18
Ultra Cloud Core SMF	2023.01.0

Related Documentation

For the complete list of documentation available for this release, go to:

https://www.cisco.com/c/en/us/support/wireless/ultra-cloud-core-serving-gateway-function/products-installation-and-configuration-guides-list.html

Installation and Upgrade Notes

This Release Notes does not contain general installation and upgrade instructions. Refer to the existing installation documentation for specific installation and upgrade considerations.

NOTE: In this software release, you must deploy SMF in merged mode only. For more information on this mode, see the UCC SMF Configuration and Administration Guide and UCC cnSGWc Configuration and Administration Guide.

Software Integrity Verification

To verify the integrity of the software image you have from Cisco, you can validate the SHA512 checksum information against the checksum identified by Cisco for the software.

Image checksum information is available through **Cisco.com Software Download Details.** To find the checksum, hover the mouse pointer over the software image you have downloaded.

Details	×		
Description :	SMF offline signature package	Related Links and Documentation	
Release :	3099.01.0	- No related links or documentation -	
Release Date :	29-Jan-2020		
FileName :	smf.3099.1.0.SPA.tgz		
Size :	2414.57 MB (2531857999 bytes)		
MD5 Checksun	1 : 99e8c8605cc7cd9eeedd820ac07787e6		
	a		
		Release Date Size	
SM	offline signature package	29-Jan-2020 2414.57 MB	Ļ
	3099.1.0.SPA.tgz		-
	SMF offline sig	nature package	

At the bottom you find the SHA512 checksum, if you do not see the whole checksum you can expand it by pressing the "..." at the end.

To validate the information, calculate a SHA512 checksum using the information in <u>Table 1</u> and verify that it matches the one provided on the software download page.

To calculate a SHA512 checksum on your local desktop please see the table below.

Operating System	SHA512 checksum calculation command examples	
Microsoft Windows	Open a command line window and type the following command	
	<pre>> certutil.exe -hashfile <filename>. <extension> SHA512</extension></filename></pre>	
Apple MAC	Open a terminal window and type the following command	
	\$ shasum -a 512 <filename>.<extension></extension></filename>	
Linux	Open a terminal window and type the following command	
	\$ sha512sum <filename>.<extension></extension></filename>	
Or		
\$ shasum -a 512 <filename>.<extension></extension></filename>		
NOTES:		
<filename> is the name of the file.</filename>		
<pre><extension>is the file extension (e.gzip or .tgz).</extension></pre>		

Table 1 – Checksum Calculations per Operating System

If the SHA512 checksum matches, you can be sure that no one has tampered with the software image or the image has not been corrupted during download.

If the SHA512 checksum does not match, we advise you to not attempt upgrading any systems with the corrupted software image. Download the software again and verify the SHA512 checksum again. If there is a constant mismatch, please open a case with the Cisco Technical Assistance Center.

Certificate Validation

The software images are signed via x509 certificates. For information and instructions on how to validate the certificates, refer to the .README file packaged with the software.

Open Bugs for this Release

There are no open bugs in this software release.

Resolved Bugs for this Release

There are no resolved defects in this software release.

Obtaining Documentation and Submitting a Service Request

Cloud Native Product Version Numbering System

The show helm list command displays detailed information about the version of the cloud native product currently deployed.

Versioning: Format & Field Description

YYYY.RN.MN[.TTN] [.dN] [.MR][.iBN]

 YYYY → 4 Digit year. Mandatory Field Starts with 2020. Incremented after the last planned release of year. Mandatory Field Starts with 1. Starts with 0. Does not support preceding 0. Reset to 0 at the beginning of every maintenance release. Precedes with "4" which represents the word "throttle" cases. MR → Maior Release for TOT and DEV branches. Starts with 0. Does not support preceding 0. Preceded by 'm' for builds from main branch. 	Where,	
 Reset for every throttle of throttle. 	 Mandatory Field Starts with 2020. Incremented after the last planned release of year. RN → Major Release Number. Mandatory Field Starts with 1. Support preceding 0. Reset to 1 after the last planned release of a year(YYYY) MN → Maintenance Number. Mandatory Field Starts with 0. Does not support preceding 0. Reset to 0 at the beginning of every major release for that release. Incremented for every maintenance release. 	 Optional Field, Starts with 1. Precedes with "t" which represents the word "throttle of throttle." Applicable only in "Throttle of Throttle" cases. Reset to 1 at the beginning of every major release for that release. DN → DEV branch Number. Same as TTN, except Used for DEV branches Precedes with "d" which represents "dev branch". MR → Major Release for TOT and DEV branches. Starts with 0 for every new TOT and DEV branches. Starts with 0 for every new TOT and DEV branches. BN → Build Number Optional Field, Starts with 1. Precedes with "f" which represents the word "interim". Does not support preceding 0. Reset at the beginning of every major release for that release

The appropriate version number field increments after a version has been released. The new version numbering format is a contiguous sequential number that represents incremental changes between releases. This format facilitates identifying the changes between releases when using Bug Search Tool to research software releases.

Release Package Descriptions

Table 2 lists provide descriptions for the packages that are available with this release.

Table 2 - Release Package Information

Software Packages	Description
ccg. <version>.SPA.tgz</version>	The offline release signature package. This package contains the CCG deployment software, NED package, as well as the release signature, certificate, and verification information.
ncs- <nso_version>-ccg-nc-<version>.tar.gz</version></nso_version>	The NETCONF NED package. This package includes all the yang files that are used for NF configuration. Note that NSO is used for the NED file creation.

NOTE: The ccg./VPA.tgz software package is common to both the cnSGWc and SMF 5G Network Functions (NF). The deployment and configuration procedure determines the NF deployment.

Obtaining Documentation and Submitting a Service Request

For information on obtaining documentation, using the Cisco Bug Search Tool (BST), submitting a service request, and gathering additional information, refer to <u>https://www.cisco.com/c/en/us/support/index.html</u>.

Obtaining Documentation and Submitting a Service Request

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANYKIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITHTHE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSEOR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright ©1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

All printed copies and duplicate soft copies of this document are considered uncontrolled. See the current online version for the latest version.

Cisco has more than 200 offices worldwide. Addresses and phone numbers are listed on the Cisco website at www.cisco.com/go/offices.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: http://www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)

© 2023 Cisco Systems, Inc. All rights reserved.