



## Exporting and Importing Configuration

---

You can import and export the Operations Hub configuration using the Cisco Operations Hub UI or RESTful APIs.

- **Export** - Enables you to store the exported configuration at a secure location.
- **Import** - Enables you to import the configuration during disaster recovery to restore the Cisco Operations Hub to its original configuration.

**Note:** Only Administrators can perform the import and export configuration.

From Cisco Operations Hub cluster, you can import and export data for the following components:

- User management data
- LDAP configuration
- Tag information
- Login banner content
- User created Grafana and Kibana dashboards
- [Importing Configuration Using Cisco Operations Hub, on page 1](#)
- [Exporting Configuration Using Cisco Operations Hub, on page 2](#)
- [Importing Configuration Using RESTful API, on page 2](#)
- [Exporting Configuration Using RESTful API, on page 2](#)

## Importing Configuration Using Cisco Operations Hub

This procedure imports the Cisco Operations Hub configuration.

---

- Step 1** At the main menu, select **System > Import & Export**.  
The **Import & Export** page appears.
- Step 2** In the **Import Configuration** area, browse and choose an Operations Hub configuration file or drag and drop the file.  
The Operations Hub configuration file must be in the *tar.gz* format.
- Step 3** click **Import**.

**Note** User passwords are not exported when you export the Cisco Operations Hub configuration. Therefore you have to provide a password before importing any configuration file. Otherwise the user management data cannot be imported.

To update the user password in the user management file, complete the following steps:

- a. Extract the exported Cisco Operations Hub configuration files.
- b. Add a password in the user management JSON file.
- c. Repack the files.

---

## Exporting Configuration Using Cisco Operations Hub

This procedure exports the Cisco Operations Hub configuration.

- 
- Step 1** At the main menu, select **System > Import & Export**.  
The **Import & Export** page appears.
  - Step 2** In the **Export Configuration** area, click **Export** to download the file containing the Operations Hub configuration.
  - Step 3** Rename the file and save it to a secure location.
- 

## Importing Configuration Using RESTful API

You can import the Cisco Operations Hub configuration and check the status of the import operation using the following APIs:

```
https://<HostName>/utility/v1/config/import  
https://<HostName>/utility/v1/config/operation/status
```

## Exporting Configuration Using RESTful API

You can export the Cisco Operations Hub configuration and check the status of the export operation using the following APIs:

```
https://<HostName>/utility/v1/config/export  
https://<HostName>/utility/v1/config/operation/status
```