



Migrating from Older MSO/ND0 Releases to Latest ND Release

[New and Changed Information](#) 2

[Introduction](#) 2

[Migration Paths](#) 2

New and Changed Information

The following table provides an overview of the significant changes to the organization and features in this guide up to this current release. The table does not provide an exhaustive list of all changes made to the guide or of the new features up to this release.

Table 1: New Features and Changed Behavior

Feature or Change	Description	Where Documented
Initial release of document	Initial release of document.	

Introduction

This document provides the necessary information to migrate from older Multi-Site Orchestrator (MSO) or Nexus Dashboard Orchestrator (NDO) releases to the latest Nexus Dashboard (ND) release.

Migration Paths

These are the supported paths to migrate from older MSO or NDO releases to the ND release.

From Older MSO/NDO Release	To New ND Release	Detailed Upgrade Path	Upgrade Procedure Links
• Cisco Nexus Dashboard Versions 3.0.1 • Cisco Nexus Dashboard Orchestrator Versions 4.2.x, 4.3.1 • Cisco Nexus Dashboard Orchestrator Versions 3.7(1l), 3.7(1k), 3.7(1j), 3.7(1g), 3.7(1d), 3.7(2d), 3.7(2e), 3.7(2f), 3.7(2g), 3.7(2h), 3.7(2i) • Cisco Nexus Dashboard Orchestrator Versions 4.0(x) and 4.1(1) • Cisco Nexus Dashboard Orchestrator Versions 3.2(x), 3.3(x), 3.4(x), 3.5(x), 3.6(x) • Cisco Multi-Site Orchestrator Versions 3.1(x) • Cisco Multi-Site Orchestrator Versions 2.1(xx), 2.2(xx), 3.0(xx) • Cisco Multi-Site Orchestrator Version 1.1(xx), 1.2(xx), 2.0(xx)	ND 4.3.1.175 / NDO 5.2.1	1. Upgrade to ND-3.2.2m (NDO-4.4.3). 2. Upgrade to Unified ND 4.3.1.	• Cisco Nexus Dashboard Orchestrator Deployment Guide, Release 3.7(x) - Migrating Existing MSO Cluster to Nexus Dashboard • Upgrading a Nexus Dashboard 3.2.2 Cluster to This Release
ND 3.2.2m / NDO 4.4.x	ND 4.3.1.175 / NDO 5.2.1	Upgrade to ND 4.3.1 / NDO 5.2.1	Upgrading a Nexus Dashboard 3.2.2 Cluster to This Release



Americas Headquarters
Cisco Systems, Inc.
San Jose, CA 95134-1706
USA

Asia Pacific Headquarters
CiscoSystems(USA)Pte.Ltd.
Singapore

Europe Headquarters
CiscoSystemsInternationalBV
Amsterdam, The Netherlands

Cisco has more than 200 offices worldwide. Addresses, phone numbers, and fax numbers are listed on the Cisco Website at www.cisco.com/go/offices.