



show pcc-af

This chapter describes the output of the **show pcc-af** command.

- [show pcc-af service all, on page 1](#)
- [show pcc-af service statistics, on page 2](#)

show pcc-af service all

Table 1: show pcc-af service all Command Output Description

| Variables | Description |
|------------------------|--|
| Service Name | The name of the PCC-AF service for which statistics are collected or displayed. |
| Context | The name of the context in which PCC-AF service is configured. |
| Service State | Indicates the state of PCC-AF service. |
| Diameter | This group indicates the Diameter endpoint configuration information for Rx interface. |
| Origin | Indicates the name of the Diameter origin endpoint configured for PCC-AF service. |
| Dictionary | Indicates the name of the Diameter dictionary configured for Rx interface in PCC-AF service. By default it is "Standard" dictionary. |
| Associated PCC-Service | Indicates the name of the PCC-Service associated with PCC-AF service. |
| Max Charging Sessions | Indicates the maximum number of charging sessions allowed in this PCC-AF service instance. By default it is 10000. |
| Newcall Policy | Indicates the new call policy configured to manage the congestion control on a PCC-AF service. |

show pcc-af service statistics

Table 2: show pcc-af service statistics Command Output Description

| Variables | Description |
|-----------------------|---|
| Service Name | The name of the PCC-AF service for which statistics are collected or displayed. |
| Inbound Messages | Indicates the total number of Rx messages received. |
| AAR Messages | Indicates the total number of Rx AAR messages received. |
| STR Messages | Indicates the total number of Rx STR messages received. |
| RAR Messages | Indicates the total number of Rx RAR request received. |
| ASR Messages | Indicates the total number of Rx ASR request received. |
| Outbound Messages | Indicates the total number of Rx messages sent. |
| Accepted AAR Messages | Indicates the total number of Rx AAR-Accepted messages sent. |
| Accepted STR Messages | Indicates the total number of Rx STR-Accepted messages sent. |
| RAA Messages | Indicates the total number of Rx RAA messages sent. |
| ASA Messages | Indicates the total number of Rx ASA sent. |
| Unknown Messages | Indicates the total number of unknown type of Rx messages received. |