



# Security Configuration Mode Commands

The Security configuration mode is a sub-mode of the Global Configuration mode. This sub-mode enables you to define or modify the connection with the Talos Intelligence content-filtering server and configure URL categorization parameters.

---

## Command Modes

Exec > Global Configuration > Security Configuration

**configure > security**

Entering the above command sequence results in the following prompt:

```
[local]host_name(config-security) #
```



---

## Important

The commands or keywords/variables that are available are dependent on platform type, product version, and installed license(s).

- [category, on page 1](#)
- [end, on page 2](#)
- [exit, on page 2](#)
- [server, on page 2](#)

## category

Adds or removes a URL categorization server.



---

## Important

This is a license-controlled feature. For more information, contact your Cisco account or support representative.

---

## Product

All

---

## Privilege

Security Administrator, Administrator

---

## Command Modes

Exec > Global Configuration > Security Configuration

**configure > security**

Entering the above command sequence results in the following prompt:

**end**

```
[local]host_name(config-security)#
```

---

**Syntax Description**    **[ no ] category server server\_name**

**no**

Removes the specified URL categorization server.

**server\_name**

Specifies the name of the URL categorization server. *server\_name* must be an alpha and/or numeric string from 1 through 31 characters that is case sensitive.

---

**Usage Guidelines**    Use this command to create or remove a URL categorization server from the Security configuration mode.

## end

Exits the current configuration mode and returns to the Exec mode.

---

**Product**    All

---

**Privilege**    Security Administrator, Administrator

---

**Syntax Description**    **end**

---

**Usage Guidelines**    Use this command to return to the Exec mode.

## exit

Exits the current mode and returns to the parent configuration mode.

---

**Product**    All

---

**Privilege**    Security Administrator, Administrator

---

**Syntax Description**    **exit**

---

**Usage Guidelines**    Use this command to return to the parent configuration mode.

## server

This command creates or specifies a Talos Security Intelligence (TSI) server entry and enters the TSI Server Configuration mode.




---

**Important**

This is a license-controlled feature. For more information, contact your Cisco account or support representative.

---

<b>Product</b>	All
<b>Privilege</b>	Security Administrator, Administrator
<b>Command Modes</b>	Exec > Global Configuration > Security Configuration <b>configure &gt; security</b> Entering the above command sequence results in the following prompt: <code>[local]host_name(config-security)#</code>
<b>Syntax Description</b>	<b>[ no ] server talos-intelligence</b> <i>server_name</i>  <b>no</b> Removes the specified Talos Security Intelligence server.  <b><i>server_name</i></b> Specifies the name of the Talos Security Intelligence server to create, configure, or remove. <i>server_name</i> must be an alpha and/or numeric string from 1 through 31 characters that is case sensitive.
<b>Usage Guidelines</b>	Use this command to create, configure, or remove a Talos Security Intelligence server from the Security configuration mode. Entering this command results in the following prompt: <code>[local]host_name(config-server-tsi)#</code> The various parameters available for configuration of a TSI server entry are defined in the <i>TSI Server Configuration Mode Commands</i> chapter.

