



# Mobile Policy LDAP Commands

---

- [ldap-server-endpoint connect, on page 1](#)
- [ldap-server-endpoint health-check-attributes, on page 2](#)
- [ldap-server-endpoint health-check-filter, on page 2](#)
- [ldap-server-endpoint input-mapping, on page 3](#)
- [ldap-server-endpoint ldap-clients, on page 3](#)
- [ldap-server-endpoint output-mapping, on page 4](#)

## ldap-server-endpoint connect

Configures the LDAP Server connection parameters.

**Command Modes** Exec > Global Configuration

**Syntax Description** `ldap-server-endpoint connect [ bind-ip bind_ip_address | binddn bind_dn | max-transactions max_tps | password password | port port_number | request-timeout request_timeout | replica replica_count ]`

**bind-ip *bind\_ip\_address***

Specify the IP address to connect to the LDAP server.

**binddn *bind\_dn***

Specify the binding user to bind to the LDAP server.

Must be a string.

**max-transactions *max\_tps***

Specify the maximum TPS allowed.

Must be an integer.

Default Value: 200.

**password *password***

Specify the binding user's password in plain text format.

**ldap-server-endpoint health-check-attributes*****port port\_number***

Specify the destination LDAP port to connect to the LDAP server.

Default Value: 9389.

***replica replica\_count***

Specify the replica count.

Must be an integer.

Default Value: 1.

***request-timeout request\_timeout***

Specify the request time out duration in milliseconds.

Must be an integer.

Default Value: 2000.

**Usage Guidelines**

Use this command to configure the LDAP Server connection parameters.

## ldap-server-endpoint health-check-attributes

Configures the response attributes and values for the health-check request.

**Command Modes**

Exec > Global Configuration

**Syntax Description**

**ldap-server-endpoint health-check-attributes attribute\_name value value**

***value value***

Specify the LDAP attribute filter value.

Must be a string.

***attribute\_name***

Specify the LDAP attribute filter name.

Must be a string.

**Usage Guidelines**

Use this command to configure the response attributes and values for health-check request.

## ldap-server-endpoint health-check-filter

Configures the health check filter parameters for the LDAP server endpoint.

**Command Modes**

Exec > Global Configuration

**Syntax Description**

**ldap-server-endpoint health-check-filter attribute\_name value value**

***value value***

Specify the LDAP attribute filter value.

Must be a string.

***attribute\_name***

Specify the LDAP attribute filter name.

Must be a string.

---

<b>Usage Guidelines</b>	Use this command to configure the health check filter parameters.
-------------------------	---

## ldap-server-endpoint input-mapping

Configures mapping for the LDAP search query filter name to Session lookup attribute.

---

<b>Command Modes</b>	Exec > Global Configuration
----------------------	-----------------------------

<b>Syntax Description</b>	<b>ldap-server-endpoint input-mapping <i>filter_name internal-lookup-key lookup_key</i></b>
---------------------------	---

***internal-lookup-key lookup\_key***

Specify the session lookup key.

Must be one of the following:

- IMSI
- IP\_ADDRESS
- MSISDN

***filter\_name***

Specify the LDAP query filter name.

Must be a string.

---

<b>Usage Guidelines</b>	Use this command to configure the mapping for the LDAP search query filter name to Session lookup attribute.
-------------------------	--

## ldap-server-endpoint ldap-clients

Configures the LDAP client credentials to bind to the server.

---

<b>Command Modes</b>	Exec > Global Configuration
----------------------	-----------------------------

<b>Syntax Description</b>	<b>ldap-server-endpoint ldap-clients <i>client password password</i></b>
---------------------------	--

***binddn bind\_dn***

Specify the binding user to bind to the LDAP server.

**ldap-server-endpoint output-mapping**

Must be a string.

***password password***

Specify the binding user's password in plain text format.

**Usage Guidelines**

Use this command to configure the LDAP client credentials to bind to the server.

## ldap-server-endpoint output-mapping

Configures the mapping for session lookup attributes to LDAP search response attributes.

**Command Modes**

Exec > Global Configuration

**Syntax Description**

**ldap-server-endpoint output-mapping *attribute\_name input lookup\_key***

***input lookup\_key***

Specify the session lookup key.

Must be a string.

***output-mapping *attribute\_name****

Specify the LDAP response attribute name.

Must be a string.

**Usage Guidelines**

Use this command to configure the mapping for session lookup attributes to LDAP search response attributes.