

Microsoft Windows で pscp を使用する方法を教えてください。

目次

[質問](#)

[環境](#)

[解決策](#)

質問

Microsoft Windows で pscp を使用する方法を教えてください。

環境

Cisco E メール セキュリティ アプライアンス (ESA)、Web セキュリティ アプライアンス (WSA)、セキュリティ管理アプライアンス (SMA)、AsyncOS のすべてのバージョン

解決策

このナレッジ ベース記事では、シスコによる保守およびサポートの対象でないソフトウェアを参照しています。情報は、利便性のために無償で提供されています。さらにサポートが必要な場合は、ソフトウェアベンダーに連絡してください。

<http://www.chiark.greenend.org.uk/~sgtatham/putty/download.html> から pscp.exe をダウンロードして下さい。

ディスクに保存します。

Windows CLI を開きます。[Start] -> [Run] の順に選択し、[Open] フィールドに「command」と入力して [OK] をクリックします。

「pscp.exe」を Windows CLI にドラッグし、CLI にコマンドのフルパスを入力します。

特定のファイルをアップロードします。

```
pscp file user@host: file
```

特定のファイルをダウンロードします。

```
pscp user@host: file file
```

フォルダ内のすべてのファイルをダウンロードします。

```
pscp -unsafe user@host: folder/*.* folder/
```

使用方法 : *pscp [options] [user@]host: source target*

pscp [options] source [source...] [[user@]host: target

pscp [options] -ls [user@]host: filespec

Options:

--V print version information and exit

--pgpfp print PGP key fingerprints and exit

--p preserve file attributes

--q quiet, don't show statistics

--r copy directories recursively

--v show verbose messages

--load sessname Load settings from saved session

--P port connect to specified port

--l user connect with specified username

--pw passw login with specified password

--1 -2 force use of particular SSH protocol version

--4 -6 force use of IPv4 or IPv6

--C enable compression

--i key private key file for authentication

--batch disable all interactive prompts

--unsafe allow server-side wildcards (DANGEROUS)

--sftp force use of SFTP protocol

--scp force use of SCP protocol