



# ACS Group-of-Objects Configuration Mode Commands

The ACS Group-of-Objects Configuration Mode is used to configure groups of Active Charging Service (ACS) objects.



---

**Important** This configuration mode is available only in 10.2 and later releases.

---

## Command Modes

Exec > ACS Configuration > ACS Group-of-Objects Configuration

**active-charging service** *service\_name* > **group-of-objects** *object\_name* [ **type string** ]

Entering the above command sequence results in the following prompt:

```
[local]host_name(config-acs-group-of-objects) #
```



---

**Important** The commands or keywords/variables that are available are dependent on platform type, product version, and installed license(s).

---

- [end, on page 1](#)
- [exit, on page 2](#)
- [member-object, on page 2](#)

## end

Exits the current configuration mode and returns to the Exec mode.

---

**Product** All

---

**Privilege** Security Administrator, Administrator

---

**Syntax Description** **end**

---

**Usage Guidelines** Use this command to return to the Exec mode.

## exit

Exits the current mode and returns to the parent configuration mode.

---

**Product**

All

---

**Privilege**

Security Administrator, Administrator

---

**Syntax Description**

**exit**

---

**Usage Guidelines**

Use this command to return to the parent configuration mode.

## member-object

This command allows you to add or remove objects from the current group-of-objects.




---

**Important**

A maximum of 128 objects can be added to a group-of-objects.

---



---

**Product**

ACS

---

**Privilege**

Security Administrator, Administrator

---

**Command Modes**

Exec > ACS Configuration > ACS Group-of-Objects Configuration

**active-charging service** *service\_name* > **group-of-objects** *object\_name* [ **type string** ]

Entering the above command sequence results in the following prompt:

```
[local]host_name(config-acs-group-of-objects)#
```

---

**Syntax Description**

[ **no** ] **member-object** *object*

**no**

If previously added, removes the specified member object from the current group-of-objects.

**object**

Specifies the member object to add to or remove from the current group-of-objects.

*object* must be an alpha and/or numeric string of 1 through 63 characters.

---

**Usage Guidelines**

Use this command to add or remove member objects from a group-of-objects.

**Example**

The following command adds the object *test* to the current group-of-objects:

```
member-object test
```