



## User Inputs for the Installation

---

This appendix provides information on the user inputs for CiscoWorks Common Services installation. It contains:

- [User Inputs for Express Installation](#)
- [User Inputs for Typical Installation](#)
- [User Inputs for Custom Installation](#)

### User Inputs for Express Installation

CiscoWorks Common Services and the dependent applications are installed in `/opt/CSCOpX/`. In Express mode, you must provide the following information during installation:

**Table D-1** *User Inputs for Express Installation*

Settings	Value
Password for <i>admin</i> user	No default values. Enter the admin password. For more information on passwords see <a href="#">“Password Information”</a>

## User Inputs for Typical Installation

Enter the following information during installation in Typical mode:

**Table D-2** *User Inputs for Typical Installation*

Settings	Value
Destination folder	The default location is /opt/CSCOpX. Select another location if you want to install in a specific location.
Components to install	Select the components you want to install.
Password for <i>admin</i> user	No default values. Enter the admin password. For more information on passwords see <a href="#">“Password Information”</a>

## User Inputs for Custom Installation

Enter the following information during installation in Custom mode:

**Table D-3** *User Inputs for Custom Installation*

Settings	Value
Destination folder	The default location is /opt/CSCOpX. Select another location if you want to install in a specific location.
Components to install	Select the components you want to install.
Password for users <i>admin</i> and <i>guest</i>	No default values. Enter the admin and guest password. For more information on passwords see <a href="#">“Password Information”</a>

**Table D-3 User Inputs for Custom Installation (continued)**

Settings	Value
Password for the CiscoWorks Common Services database	By default, the value is generated randomly. For more information on passwords see <a href="#">“Password Information”</a>
<p>Select one of the User Management modes:</p> <ul style="list-style-type: none"> <li>• Manage locally by CiscoWorks Common Services.</li> <li style="text-align: center;">or</li> <li>• Manage by Access Control Server (ACS).</li> </ul> <p>If ACS mode is selected, enter the following server data:</p> <ul style="list-style-type: none"> <li>• ACS Name</li> <li>• ACS Port</li> <li>• Admin User Name and Password</li> <li>• Shared device key</li> </ul>	<p>By default, the User Management mode is set to local, and ACS server data is empty.</p> <p>If ACS mode is selected and if you leave the fields blank, the server name is set to <i>tacacs.company.com</i> and port is set to 49.</p>

*Table D-3 User Inputs for Custom Installation (continued)*

Settings	Value
Apache certificate settings: <ul style="list-style-type: none"> <li>• SMTP server</li> <li>• Host name</li> <li>• Administrator's e-mail address</li> <li>• Country</li> <li>• State</li> <li>• City</li> <li>• Company</li> <li>• Organization</li> </ul>	Host name is mandatory.
Password for the Licensing database	By default, the value is randomly generated. For more information on passwords, see <a href="#">“Password Information”</a>