



User Inputs for the Installation

This appendix provides information on the user inputs for CiscoWorks Common Services installation. It contains:

- [User Inputs for Express Installation](#)
- [User Inputs for Typical Installation](#)
- [User Inputs for Custom Installation](#)

User Inputs for Express Installation

CiscoWorks Common Services and all dependent components are installed in `%System drive%\Program Files\CSCOp\`. In Express Mode, you must provide the following information during installation:

Table C-1 *User Inputs for Express Installation*

Settings	Value
Password for <i>admin</i> user	No default values. Enter the admin password. For more information on passwords refer “ Password Information ”

User Inputs for Typical Installation

Enter the following information during installation in Typical mode:

Table C-2 *User Inputs for Typical Installation*

Settings	Value
Destination folder	The default location is <i>%System drive%:\Program Files\CSCOPx\</i> . Select another location if you want to install in a specific location.
Components to install	Select the components you want to install.
Password for <i>admin</i> user	No default values. Enter the admin password. For more information on passwords, see “Password Information”

User Inputs for Custom Installation

Enter the following information during installation in Custom mode:

Table C-3 *User Inputs for Custom Installation*

Setting	Value
Destination folder	The default location is <i>%System drive%:\Program Files\CSCOPx\</i> . Select another location if you want to install in a specific location.
Components to install	Select the components you want to install.

Table C-3 User Inputs for Custom Installation (continued)

Setting	Value
Password for users <i>admin</i> and <i>guest</i>	No default values. Enter the admin and guest password. For more information on passwords, see “Password Information”
Password for user <i>casuser</i>	The password is generated randomly if you leave the field blank.
<p>Select one of the User Management modes:</p> <ul style="list-style-type: none"> • Manage locally by CiscoWorks Common Services. <p>or</p> <ul style="list-style-type: none"> • Manage by Access Control Server (ACS). <p>If ACS mode is selected, enter the following server data:</p> <ul style="list-style-type: none"> • ACS Name • ACS Port • Admin User Name and Password • Shared device key 	<p>By default, the User Management mode is set to local, and ACS server data is empty.</p> <p>If ACS mode is selected and if you leave the fields blank, the server name is set to <i>tacacs.company.com</i> and port is set to 49.</p>
Password for the CiscoWorks Common Services database	By default, a random password is generated. For more information on passwords, see “Password Information”
Password and port for the Licensing database	The default port is 10033. Leave the password field empty to generate a random password. For more information on passwords, see “Password Information”

Table C-3 User Inputs for Custom Installation (continued)

Setting	Value
Web server settings: <ul style="list-style-type: none"> • HTTPS port • Administrator's e-mail address • SMTP server name 	The default values are: Port number 443 <i>admin@domain.com</i> <i>localhost name</i>
Data for the Self-signed Certificate: <ul style="list-style-type: none"> • Country Code • State • City • Company • Organization • Hostname 	By default, the self-signed certificate is generated using the organization that Windows is registered to, and the host name.