



Admin Utility Web Interface For Cisco Emergency Responder

These topics describe the fields on the pages of the Cisco Emergency Responder (Cisco ER) Admin Utility web interface.

- [Point to a New Publisher, page E-1](#)
- [Update CCM Version, page E-2](#)
- [Update Cluster DB Host, page E-3](#)

Point to a New Publisher

The Point to a New Publisher page appears when you select **Update > Publisher**.

Authorization Requirements

You must have system administrator authority to access this page.

Description

Use the Point to a New Publisher page to point the subscriber to a different publisher.



Caution


Choosing to change the publisher will delete all the current associations with the existing publisher.

[Table E-1](#) describes the Point to a New Publisher page.

Table E-1 *Point to a New Publisher Page*

Field	Description
Status	Displays the current Publisher host
Publisher Details	
HostName	Name of the new Publisher host
IP Address	IP address of the new Publisher host
Security Password	Password used to gain access to the Publisher host

Table E-1 Point to a New Publisher Page (continued)

Field	Description
Go button	Click Go to change the Publisher host
	 Caution Change the publisher deletes all the current associations with the existing publisher.
Cancel button	Cancels the Point to a New Publisher operation.

Related Topics

- [Before You Install or Upgrade, page 2-1](#)
- [Pointing Subscriber Servers to a Different Publisher, page 9-1](#)

Update CCM Version

The Update CCM Version page appears when you select **Update > CCM**.

Authorization Requirements

You must have system administrator authority to access this page.

Description

Use the Upgrade CCM Version page to upgrade to a different version of Cisco Unified Communications Manager.

[Table E-2](#) describes the Upgrade CCM Version page.

Table E-2 Upgrade CCM Version Page

Field	Description
Status	Displays the current Cisco Unified Communications Manager version.
CCM Version Details	
Choose the Cisco Unified Communications Manager Version to Upgrade	Use the pulldown menu to select the Cisco Unified Communications Manager version to which you want to upgrade
Go button	Click Go to initiate the upgrade process. Note Change the CCM version separately on the Publisher and Subscriber nodes.
Cancel button	Cancels the Cisco Unified Communications Manager upgrade.

Related Topics

- [Changing the Cisco Unified Communications Manager Version, page 9-2](#)

Update Cluster DB Host

The Update Cluster DB Host page appears when you select **Update>Cluster DB Host**.

Authorization Requirements

You must have system administrator authority to access this page.

Description

Use the Update Cluster DB Host page to designate a new server as the Cisco ER cluster's database host server.

[Table E-3](#) describes the Update Cluster DB Host page.

Table E-3 Update Cluster DB Host Page

Field	Description
Status	Displays the name of the current cluster database host
Cluster DB Host Details	
ClusterDBHostname/IP Address	Enter the hostname (if DNS is configured) or the IP address of the new cluster database host. Note If the cluster is spread across domains, then enter a fully qualified hostname.
Password	Enter the password for the new cluster database host
Confirm Password	Re-enter the password for the new cluster database host.
Go button	Click the Go button to designate the new server as the new cluster database host. Note The Cisco ER Cluster DB host details will be updated. Cisco ER services will have to be restarted for this change to take effect. This will update Cisco ER Cluster DB host details for this server group only. Other servers in this Cisco ER cluster will NOT be updated automatically. For further details, see the “Updating the Cisco ER Cluster Database Host Details” section on page 9-3.
Cancel button	Cancels the Update Cluster DB Host operation.

Related Topics

- [Configuring the Cisco Emergency Responder Cluster and Cluster DB Host](#), page 5-23
- [Updating the Cisco ER Cluster Database Host Details](#), page 9-3

