



## Configuring Partitions

---

A partition is a list of route patterns. Partitions facilitate call routing by dividing the route plan into logical subsets based on organization, location, and call type.

Use the following procedures to add or delete route partitions:

- Adding a Partition, page 21-1
- Deleting a Partition, page 21-2

### Adding a Partition

The following procedure describes how to add a partition.

#### Procedure

---

- Step 1** Open Cisco CallManager Administration.
- Step 2** Select **Route Plan > Partition** in the menu bar.
- Step 3** Enter a name in the Partition Name field. The name can consist of up to 50 alphanumeric characters, and can contain any combination of spaces, periods (.), hyphens (-), and underscore characters (\_). Each partition name must be unique to the route plan.

**Timesaver**

---

Use concise and descriptive names for your partitions. The CompanynameLocationCalltype format usually provides a sufficient level of detail and is short enough to enable you to quickly and easily identify a partition. For example, CiscoDallasMetroPT identifies a partition for toll free inter-LATA (Local Access and Transport Area) calls from the Cisco office in Dallas.

---

- Step 4** Enter a description in the Description field. The description can consist of up to 50 alphanumeric characters, and can contain any combination of spaces, periods (.), hyphens (-), and underscore characters (\_). If you do not enter a description, the partition name is automatically entered in this field.
- Step 5** Click **Insert** to add the new partition. The new partition name is added to the partition list on the left side of the page, and the message “Status: Insert completed” is displayed.
- Step 6** To add more partitions, click **New** and repeat Steps 3 through 5.
- 

**Related Topics**

- Deleting a Partition, page 21-2

## Deleting a Partition

The following procedure describes how to delete a partition.

**Procedure**

---

- Step 1** Open Cisco CallManager Administration.
- Step 2** Select **Route Plan > Partition** in the menu bar.
- Step 3** Select a name in the partition list on the left side of the page.
- Step 4** Click **Delete** to remove the partition.

**Caution**

---

Check carefully to ensure that you are deleting the correct partition before initiating this action. Deleted partitions cannot be recovered. If a partition is accidentally deleted, it must be rebuilt.

---

- Step 5** A dialog box appears warning you that deleting this partition cannot be undone.
- Step 6** Click **OK** to delete the partition, or click **Cancel** to cancel the action. If you click **OK**, the partition is deleted and the message “Status: Ready” is displayed.
- Step 7** Repeat Steps 3 through 7 to delete other partitions.
- 

**Related Topics**

- Adding a Partition, page 21-1

■ Deleting a Partition