



Cisco Voice Pilot Configuration

The voice mail pilot number designates the directory number that you dial to access your voice messages. Cisco CallManager automatically dials the voice-messaging number when you press the Messages button on your phone. Each pilot number can belong to a different voice-mail messaging system.

The following topics provide information on voice mail pilot configuration:

- [Configuring the Voice Mail Pilot Number, page 39-1](#)
- [Voice Mail Pilot Configuration Settings, page 39-2](#)
- [Voice Mail Connectivity to the Cisco CallManager, *Cisco CallManager System Guide*](#)
- [Cisco uOne Configuration Checklist, *Cisco CallManager System Guide*](#)
- [Cisco Unity Configuration Checklist, *Cisco CallManager System Guide*](#)

Configuring the Voice Mail Pilot Number

Follow these procedures to configure the voice mail pilot number.

Procedure

- Step 1** Choose **Feature > Voice Mail > Voice Mail Pilot**.
The Voice Mail Pilot Configuration window displays.
- Step 2** Choose a Cisco voice-mail pilot number, or click the **Add a New Voice Mail Pilot Number** link.

- Step 3** Configure the appropriate settings as described in [Table 39-1](#).
- Step 4** Click **Insert** to add the new voice mail pilot number, or click **Update** to update the settings for an existing voice mail pilot number.

Related Topics

- [Voice Mail Pilot Configuration Settings, page 39-2](#)
- [Message Waiting Configuration, page 40-1](#)
- [Voice Mail Profile Configuration, page 41-1](#)
- [Voice Mail Connectivity to the Cisco CallManager, Cisco CallManager System Guide](#)
- [Cisco uOne Configuration Checklist, Cisco CallManager System Guide](#)
- [Cisco Unity Configuration Checklist, Cisco CallManager System Guide](#)

Voice Mail Pilot Configuration Settings

[Table 39-1](#) describes the voice mail pilot configuration settings.

Table 39-1 Voice Mail Pilot Configuration Settings

Field	Description
Voice Mail Pilot Number	Enter a number to identify the voice-mail pilot number.
Description	Enter the description of the pilot number.
Calling Search Space	Choose the appropriate calling search space. A calling search space comprises a collection of partitions that are searched for numbers called from this pilot number.
Make this the default Voice Mail Pilot for the system	<p>Check the box to make this pilot number the default Voice Mail Pilot for the system.</p> <p>Note If you check the Default box, this voice mail pilot number will replace your current default pilot number.</p>

Related Topics

- [Configuring the Voice Mail Pilot Number, page 39-1](#)
- [Message Waiting Configuration, page 40-1](#)
- [Voice Mail Profile Configuration, page 41-1](#)
- [Voice Mail Connectivity to the Cisco CallManager, *Cisco CallManager System Guide*](#)
- [Cisco uOne Configuration Checklist, *Cisco CallManager System Guide*](#)
- [Cisco Unity Configuration Checklist, *Cisco CallManager System Guide*](#)

