



Proxy Profile

Use proxy profile settings to configure settings that are related to the SIP proxy server, including primary servers, standby servers, and the users that are associated with the profile. You can use this window to search for specific profiles and change individual settings.

Finding a Proxy Profile

Because you might have several proxy profiles in your network, Cisco Unified Presence Server lets you locate specific proxy profiles on the basis of specific criteria. Use the following procedure to locate specific proxy profiles.



Note

During your work in a browser session, the cookies on the client machine store your find/list search preferences. If you navigate to other menu items and return to this menu item, or if you close the browser and then open a new browser window, the system retains your Cisco Unified Presence Server search preferences until you modify your search.

Procedure

- Step 1** Choose **Application > Unified Personal Communicator > Proxy Profile**.
- The Find and List Proxy Profiles window displays. Use the drop-down list boxes to search for proxy profiles.
- Step 2** From the first drop-down box, choose one of the following criteria:
- Name
 - Description
- Step 3** From the second drop-down list box, choose one of the following criteria:
- begins with
 - contains
 - is exactly
 - ends with
 - is empty
 - is not empty
- Step 4** Specify the appropriate search text, if applicable, and click **Find**.

**Tip**

To find all proxy profiles that are registered in the database, click **Find** without entering any search text.

A list of discovered proxy profiles displays.

- Step 5** From the list of records, click the proxy profile that matches your search criteria.
The window displays the proxy profile that you choose.

Additional Information

See the [“Related Topics”](#) section on page 33-4.

Configuring a Proxy Profile

This section describes how to add or update a proxy profile in the Cisco Unified Presence Server database.

Procedure

- Step 1** Perform one of the following tasks:
- To add a proxy profile, choose **Application > Unified Personal Communicator > Proxy Profile** and click **Add New**.
 - To update a proxy profile, find the profile by using the procedure in the [“Finding a Proxy Profile”](#) section on page 33-1.
- The Proxy Profile Configuration window displays.
- Step 2** Enter the appropriate settings as described in [Table 33-1](#).
- Step 3** To associate users with the proxy profile, click **Add Users to Profile**.
The Find and List Users window displays.
- Step 4** From the first drop-down list box, choose one of the following criteria:
- First name
 - Middle name
 - Last name
 - User ID
 - Department
- Step 5** From the second drop-down list box, choose one of the following criteria:
- begins with
 - contains
 - is exactly
 - ends with

- is empty
- is not empty

Step 6 Specify the appropriate search text, if applicable, and click **Find**.



Tip To find all users that are registered in the database, click **Find** without entering any search text.

A list of discovered users displays.

Step 7 From the list of records, click the users that you want to add to the proxy profile or click **Select All**.

Step 8 To add the users to the proxy profile, click **Add Selected**.

Step 9 To exit the Find and List Users window, click **Close**.

Step 10 To save the data and to add the proxy profile to the database, click the **Save** icon that displays in the tool bar in the upper, left corner of the window (or click the **Save** button that displays at the bottom of the window).

Additional Information

See the [“Related Topics” section on page 33-4](#).

Proxy Profile Configuration Settings

[Table 33-1](#) describes the proxy profile configuration parameters. For related procedures, see the [“Related Topics” section on page 33-4](#).

Table 33-1 *proxy Profile Configuration Parameters*

Field	Description
Name	This parameter specifies the name of the proxy profile.
Description	This parameter provides a general description of the proxy profile.
Primary Proxy Server	This parameter specifies the primary proxy server. From the dropdown list, you can choose from the proxy servers that you already defined on the system.
Backup Proxy Server	This parameter specifies the backup proxy server. From the dropdown list, you can choose from the proxy servers that you already defined on the system. You can specify two backup proxy servers.

Deleting a Proxy Profile

This section describes how to delete a proxy profile.

Procedure

- Step 1** Find the proxy profile by using the procedure in the [“Finding a Proxy Profile” section on page 33-1](#).
- Step 2** From list of matching records, choose the proxy profile that you want to delete.
- Step 3** To delete the profile, click the **Delete Selected Item** icon that displays in the tool bar in the upper, left corner of the window (or click the **Delete Selected** button that displays at the bottom of the window).

If the proxy profile is not in use, Cisco Unified Presence Server deletes it. If it is in use, a message displays.

Additional Information

See the [“Related Topics” section on page 33-4](#).

Related Topics

- [Finding a Proxy Profile, page 33-1](#)
- [Configuring a Proxy Profile, page 33-2](#)
- [Deleting a Proxy Profile, page 33-4](#)