



Proxy Server Settings

Use proxy server settings to configure settings for the SIP proxy server.

Configuring Proxy Server Settings

This section describes how to configure proxy server settings for the Cisco Unified Presence.

Procedure

- Step 1** Choose Cisco Unified Presence > **Proxy Server** > **Settings**.
The Proxy Configuration Settings window displays.
 - Step 2** For the Method/Event Routing Status, choose **On** or **Off**.
 - Step 3** Choose the appropriate Preferred Proxy Listener, as described in [Table 11-1](#).
 - Step 4** To save your settings, click the **Save** icon that displays in the tool bar in the upper, left corner of the window (or click the **Save button** that displays at the bottom of the window).
-

Additional Information

See the “[Related Topics](#)” section on page 11-2.

Proxy Server Configuration Settings

[Table 11-1](#) describes the proxy server configuration settings. For related procedures, see the “[Related Topics](#)” section on page 11-2.

Table 11-1 Proxy Server Configuration Settings

Field	Description
Method/Event Routing Status	This parameter specifies whether the method/event routing module is enabled or disabled in the SIP proxy server.
Preferred Proxy Listener	This parameter specifies which SIP proxy listener is considered the preferred listener. The dropdown list contains SIP proxy server listeners that you defined in the Transport Listeners window.

Restart Proxy Services

Some changes that you make in Cisco Unified Presence Administration require that you restart SIP proxy services before the change takes effect. The following changes require that you to restart SIP proxy services:

- Adding, deleting, or modifying the system server
- Modifying the SIP proxy server settings
- Adding, deleting, or modifying transport listeners
- Adding, deleting, or modifying TLS context and TLS peer subjects

To restart proxy services, use the following procedure:

**Warning**

While the proxy services are restarting, the Cisco Enterprise SIP proxy services drop any existing transactions and do not accept any new requests.

Procedure

-
- Step 1** Choose Cisco Unified Presence > **Proxy Server** > **Settings**.
The Proxy Configuration Settings window displays.
- Step 2** Click **Restart All Proxy Services**.
- Step 3** When the confirmation window displays, click **OK**.
-

Related Topics

- [Configuring Proxy Server Settings, page 11-1](#)
- [Proxy Server Configuration Settings, page 11-1](#)