



CHAPTER 8

Cisco Unified Presence Settings

Use Cisco Unified Presence settings to configure global parameters that affect all Cisco Unified Presence services and applications.

Configuring Cisco Unified Presence Settings

This section describes how to configure Cisco Unified Presence settings.

Procedure

-
- Step 1** Choose Cisco Unified Presence > **Settings**.
The Cisco Unified Presence Settings window displays.
 - Step 2** Configure the Cisco Unified Presence settings, as shown in [Table 8-1](#).
 - Step 3** To save your settings, click the **Save** icon that displays in the tool bar in the upper, left corner of the window (or click the **Save** button that displays at the bottom of the window).
-

Cisco Unified Presence Configuration Settings

Table 2-1 describes the server configuration settings. For related procedures, see the [“Related Topics” section on page 8-2](#).

Table 8-1 Cisco Unified Presence Settings

Field	Description
Enable Instant Messaging check box	Check this check box to enable instant messaging on this Cisco Unified Presence cluster. This setting affects the Cisco IP Phone Messenger service, the SIP Proxy, and Cisco Unified Personal Communicator. Default setting: Enabled

Table 8-1 Cisco Unified Presence Settings (continued)

Field	Description
Enable Publish to Cisco Unified Communications Manager check box Note This field only displays when you connect to Cisco Unified Communications Manager Release 6.0 or higher.	Check this check box to enable PUBLISH to the associated Cisco Unified Communications Manager. This setting affects the IP Phone Messenger service, the SIP Proxy, and Cisco Unified Personal Communicator. Default setting: Disabled
Cisco Unified Communications Manager SIP Publish Trunk Note This field only displays when you connect to Cisco Unified Communications Manager Release 6.0 or higher.	From the drop-down list, choose the appropriate SIP PUBLISH trunk to allow Cisco Unified Presence to monitor phone status from Cisco Unified Communications Manager. Note You must check the Enable Publish to Cisco Unified Communications Manager check box to enable this parameter. Note This parameter changes the SIP Publish Trunk on Cisco Unified Communications Manager. In addition, if you change the SIP Publish Trunk parameter on Cisco Unified Communications Manager, this also changes this setting because they are connected. Default setting: Current Cisco Unified Communications Manager SIP Publish Trunk, as read from AXL

Additional Information

See the [“Related Topics”](#) section on page 8-2.

Related Topics

- [Configuring Cisco Unified Presence Settings, page 8-1](#)
- [Cisco Unified Presence Configuration Settings, page 8-1](#)