

Configure group-role mapping using Radius class attribute on Security Management Appliance (SMA)

Document ID: 200258

TAC

Contributed by Zack Shaikh Cisco TAC Engineer.

Nov 16, 2015

Contents

Introduction

- Requirements
- Components Used

Introduction

This document describes how to configure group-role mapping using Radius class attribute on Security Management Appliance (SMA)

Requirements

Cisco recommends that you have a basic knowledge of SMA and Radius configuration.

Components Used

The information in this document is based on these software and hardware versions:

- AsyncOS 7.2.x and later
- Security Management Appliance
- Radius server

Q. How to configure group-role mapping using Radius class attribute on Security Management Appliance?

A. Radius authentication on the SMA allows administrators to provide users with access to the Web Graphic User Interface (GUI) of the SMA. In addition, it provides the ability to map different user groups, based on the RADIUS class attribute, to different roles like Operator for the SMA.

Steps to configure group-role based mapping using Radius on SMA are as following:

From SMA GUI:

1. Navigate to the **System Administration > Users** (under Management Appliance tab)
2. Click the **Edit Global Setting** under **External Authentication**.
3. Under **Group Mapping**: field : **???RADIUS CLASS Attribute???**.
4. Enter Correspondence value of **??? IETF Attribute type 25 - Class Attribute???** from Radius server.
5. Enter **Role** from the drop down bar.
6. Submit and commit.

The RADIUS server can be configured for many attributes based on user groups. Once a user is authenticated via Radius, the SMA can check the group attributes and assign different role mappings. SMA will match the Radius Attribute class value configured on the Radius Server (Standard **RADIUS attribute #25**).

To configure Class Attribute on radius server, you would need to login to radius server as **Administrator**.

For example:

- Consider "**IETF Attribute type 25 - Class Attribute**" shows value of '**Domain Admin**' for users with administrator privilege.
- On radius server On SMA, Under "**RADIUS CLASS Attribute???**" type Domain Admin and Under Role type Administrator
- You may add multiple '**Group Mapping**' rows by clicking 'Add Row'

Note: Radius server MUST have same class attribute value configured. The value is case-sensitive.

