

Change Language in CUAC Advanced Client

Contents

[Introduction](#)

[Prerequisites](#)

[Requirements](#)

[Components Used](#)

[Background Information](#)

[Configuration](#)

Introduction

This document describes how to change the display language in Cisco Unified Attendant Console Advanced Client.

Prerequisites

Requirements

Cisco recommends that you have knowledge of these topics:

- Cisco Unified Attendant Console Advanced

Components Used

- Cisco Unified Attendant Console Advanced Client 14.0.2

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, ensure that you understand the potential impact of any command.

Background Information


The Cisco Unified Attendant Console Advanced Client supports multiple display languages to accommodate operators working in different regions or language environments.

Once the application is installed, there are two different methods to change the display language:


1. Modify the application files.
2. Reinstall the application and select the desired language.

Configuration


Step 1. Exit from **Attendant Console Client**.



Step 2. Open **Windows File Explorer** and navigate to the path "**%ProgramData%\Cisco\CUACA**". ProgramData use to be a hidden folder by default.



Step 3. Open the **OPR.cfg** file in a text editor.



Step 4. Modify the **DefaultLanguage="English"** to the desired language value and **save** the changes. Languages information is listed in this table:

Operator CFG File	Language (Locale)
Arabic	Arabic (Saudi Arabia)
Chinese Simplified	Chinese (PRC) [Simplified Chinese]
Chinese Traditional	Chinese (Taiwan) [Traditional Chinese]
Danish	Danish
Dutch	Dutch (Netherlands)
English	English
French	French (Parisian)
German	German
Italian	Italian
Japanese	Japanese
Korean	Korean
Portuguese	Portuguese (Portugal)
Russian	Russian
Spanish	Spanish (Traditional)
Swedish	Swedish

Step 5. Open the **Attendant Console Client**.

Cisco Unified Attendant Console - (تسجيل) تقييم

تعليمات خيارات ملف

تسجيل الدخول

تفاصيل مسؤول التشغيل

اسم تسجيل الدخول:

عبارة المرور:

تذكر اسم تسجيل الدخول الخاص بي

تفاصيل الجهاز

استخدام تفاصيل الجهاز الموجود

الرقم الداخلي:

تسجيل الدخول إلغاء تعليمات

تم تسجيل الخروج. غير جاهز.