



CHAPTER 4

Installing the MWTM Client on Windows

The MWTM client software can be downloaded from the MWTM server's web server on to a Windows XP Professional system. This chapter describes how to install the MWTM client software, how to verify installation, and how to uninstall and reinstall the MWTM on Windows.

This chapter includes the following sections:

- [Installing the MWTM Client for Windows Using the Web Server, page 4-1](#)
- [Verifying MWTM Client Installation, page 4-2](#)
- [Uninstalling the MWTM Client, page 4-2](#)

Installing the MWTM Client for Windows Using the Web Server

You can use the MWTM web server to access the client installation software to run the installation.



Note

Disable the Windows firewall before installing the MWTM client on Windows.

To install the MWTM client on a Windows system from the MWTM web server:

Step 1 From your browser, go to the URL for the MWTM web server:

```
http://your_MWTM_server:1774
```

where *your_MWTM_server* is the name or IP address of the MWTM web server and *1774* is the web port being using by the MWTM (**1774** is the default port number). If you do not know the name or web port of the MWTM web server, contact the system administrator who installed the MWTM server software.

The MWTM server home page appears.

If you are running a 6.1.7 server, you will have to download and use the 6.1.7 client.

Step 2 Click **Download Windows Client**.

The Download Instructions for MWTM Client on Windows page appears.

Step 3 Click **Download the Windows Client** to download the installation setup program for Windows XP Professional.

Step 4 When queried, specify the directory into which you want to download the installation software file.

- Step 5** Go to the download directory and double-click the **setup.exe** command to install the software. The installation files automatically uncompress into a temporary directory, and the Cisco MWTM Client Setup window appears, with the text, “Welcome to the InstallShield Wizard for the Cisco MWTM Client.”



Note It is recommended to temporarily disable any anti-virus and security software before installing the MWTM client on your computer.

- Step 6** Follow the prompts to install the software.

Verifying MWTM Client Installation

To verify the MWTM client installation:

- Step 1** Make sure the MWTM server is available.
- Step 2** Make sure the MWTM client icon appears on the desktop.
- Step 3** Make sure the following options are in the **Start > Programs > Cisco MWTM Client** menu:
- **Modify Default MWTM Server Name**
 - **MWTM Client**
 - **MWTM DOS Prompt**
 - **MWTM Event Editor**
 - **MWTM SSL Certificate Tool**
 - **Readme**
 - **Uninstall MWTM Client**
- Step 4** To start the MWTM client, use one of the following methods:
- Choose **Start > Programs > Cisco MWTM Client > MWTM Client**.
 - Double-click the MWTM Client icon on the Windows desktop.

The MWTM must discover your network during operation. If the MWTM server installation is successful, and if you do not now configure the MWTM server to automatically discover your network the first time the server starts after installation, the Discovery dialog box and the MWTM main window appear upon client startup. For details about these windows and the discovery process, see the [User Guide for the Cisco Mobile Wireless Transport Manager 6.1.7](#).

Uninstalling the MWTM Client

You can use the standard **Add/Remove Programs** icon in the Windows Control Panel to uninstall the MWTM, or you can uninstall the MWTM from the Windows Start menu.

To uninstall the MWTM:

-
- Step 1** Exit all open MWTM windows.
- Step 2** From the Windows Start menu, choose **Start > Programs > Cisco MWTM Client > Uninstall MWTM Client**.



Note You can also uninstall the MWTM from the Windows Control Panel by clicking **Add/Remove Programs**, selecting **MWTM Client**, and clicking **Change/Remove**, but using the Windows Start Menu is the recommended method.

- Step 3** Click **Yes (or Yes to All)** in the Remove Existing File window to remove the System.properties file or click **No (or No to All)** to restore the old System.properties file.

- Step 4** Click **Finish**.

The MWTM has been successfully uninstalled.
