



Creating Workers in Bulk

This chapter provides instructions for creating workers in bulk through the V2PC GUI.


Prerequisites

- The user has bootstrapped the V2PC cluster from the launcher node.
- The user has created the provider, network, and zone from the V2PC GUI.

Procedure

Step 1 From the navigation menu, choose **Application Deployment Manager > Resources > Nodes**. The Nodes page opens.

Figure 11-1 Nodes Page



Step 2 Click the **Add (+)** icon to add one or more worker nodes. The Bulk Nodes Creation dialog opens.

Figure 11-2 Bulk Nodes Creation Dialog

Bulk Nodes Creation

Number of Nodes* Description

Region* Image Tag*

Provider* Image Flavor*

Zone* Flavor Name*

Interfaces

Type	Network Name	IP Address Start Range
Management*	<input type="text" value="kinnetwork"/>	<input type="text" value="172.22.117.178"/>
Data In	<input type="text" value="kinnetwork"/>	<input type="text" value="172.22.117.188"/>
Data Out	<input type="text" value="kinnetwork"/>	<input type="text" value="172.22.117.199"/>

Step 3 Enter the number of nodes and other information as needed:

- **Number of nodes** – Enter number of nodes
- **Region** – Select Region Name
- **Provider** – Select Provider Name
- **Zone** – Select Zone
- **Description** – Enter Description
- **Image Tag** – Select Image
- **Image Flavor** – Select Image Flavor
- **Flavor Name** – Select Image Flavor Name

Step 4 Enter the IP addresses for the management and data interfaces:

- **Management** – Select Network and enter IP Address Start Range
- **Data In** – Select Network and enter IP Address Start Range
- **Data Out** – Select Network and enter IP Address Start Range

Step 5 Click **Create**. The GUI automatically configures each node and assigns a sequential IP address.



Note

All nodes are created in the configured zone.

A popup window displays the status of the node creation process.

Figure 11-3 Node Creation Status Window

Node Creation Status			
Node Name	Management IP Address	Status	Reason for Failure
worker-zone-1-178	172.22.117.178	Failure	Error creating object,objType nodes name worker-zone-1-178 Response code = 400, url = regions/region-0/nodes/worker-zone-1-178 error = {"errorCode":"Badrequest","error":"The ip 172.22.117.178 is Inuse"}
worker-zone-1-179	172.22.117.179	Failure	Error creating object,objType nodes name worker-zone-1-179 Response code = 400, url = regions/region-0/nodes/worker-zone-1-179 error = {"errorCode":"Badrequest","error":"The ip 172.22.117.179 is Inuse"}

OK

Limitations

- From the V2PC GUI navigation menu, choose **Application Deployment Manager > Resources > Nodes** to confirm that nodes are created as expected.
- There is a limit of up to 10 worker nodes maximum creation at a time.
- Bulk worker creation only supports contiguous IP address ranges.

